

AD722422


R-535-PR

March 1971

A MARKOVIAN FLOW MODEL: THE ANALYSIS OF MOVEMENT IN LARGE-SCALE (MILITARY) PERSONNEL SYSTEMS—PROGRAM LISTINGS

Kathleen Hall

A Report prepared for
UNITED STATES AIR FORCE PROJECT RAND



Reproduced by
**NATIONAL TECHNICAL
INFORMATION SERVICE**
Springfield, Va. 22151

Rand
SANTA MONICA, CA. 90406

DISTRIBUTION STATEMENT A

Approved for public release;
Distribution Unlimited

171

R-535-PR

March 1971

A MARKOVIAN FLOW MODEL: THE ANALYSIS OF MOVEMENT IN LARGE-SCALE (MILITARY) PERSONNEL SYSTEMS—PROGRAM LISTINGS

Kathleen Hall

A Report prepared for
UNITED STATES AIR FORCE PROJECT RAND

Rand
SANTA MONICA, CA. 90406

Rand maintains a number of special, subject bibliographies containing abstracts of Rand publications in fields of wide current interest. The following bibliographies are available upon request:

*Africa • Arms Control • Civil Defense • Combinatorics
Communication Satellites • Communication Systems • Communist China
Computing Technology • Decisionmaking • East-West Trade
Education • Foreign Aid • Health-related Research • Latin America
Linguistics • Long-range Forecasting • Maintenance
Mathematical Modeling of Physiological Processes • Middle East
Policy Sciences • Pollution • Procurement and R&D Strategy
Program Budgeting • SIMSCRIPT and Its Applications • Southeast Asia
Systems Analysis • Television • Urban Problems • USSR
Water Resources • Weather Forecasting and Control*

To obtain copies of these bibliographies, and to receive information on how to obtain copies of individual publications, write to: Communications Department, Rand, 1700 Main Street, Santa Monica, California 90406.

PREFACE

The movement of the military population through the USAF personnel system is an unusually well-defined example of social mobility. AF managers are constantly faced with the necessity for manipulating this process in order to alter the distribution of the personnel inventory. Accurate management of the system is extremely difficult with only periodic inventories and limited, primitive information about the patterns of transitional movement that produced those inventories; evaluation is principally based upon short-term effects.

The lack of statistics on transitional behavior is a result of (1) the difficulty of obtaining information on changes of status using personnel records designed on the basis of traditional inventory concepts; and (2) the difficulty of comprehending the net impact and significance of a huge number of transition paths upon future distributions of the population.

This report is the final volume in the series R-514-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems*; R-534-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems--Program Reference Manual*. This series of reports describes a model of social mobility that can be utilized to provide the manager or analyst with information about patterns of movement, projections of the existing population into the future, and the impact produced by changes in the rates of movement (the effect of policy changes, for example). The model, derived from the mathematical concepts of Markovian processes, is presented as a series of FORTRAN subroutines capable of being used on a wide variety of contemporary computers. This report provides documentation and illustrations for the programmer.

-v-

SUMMARY

This report is designed for use by a programmer/analyst in creating and maintaining a program library for the system of programs described in R-514-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems*, and R-534-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems--Program Reference Manual*.

All subroutines are written in FORTRAN. They have been compiled (under FORTRAN H) and executed on an IBM 360/65. Except for one utility subroutine (NUDATE), which assumes that hexadecimal characters are used for the internal representation of alphabetic data fields, these routines are not hardware dependent; they should run on any system for which an appropriate compiler is available.

The subroutine name, card label, number of cards, and storage required (in Hex bytes) are listed for each subroutine.

The FORTRAN source deck of each subroutine is listed and numerous comment cards are included. The comment cards contain a step-by-step natural-language description of the FORTRAN source-language statements.

-vii-

CONTENTS

PREFACE	iii
SUMMARY	v
Section	
I. INTRODUCTION	1
II. INFORMATION FOR NON-RAND USERS	3
System Implementation	3
Programs in Card Form	4
Programming Details	5
III. DESCRIPTION OF SOURCE-DECK FORMAT	7
IV. LIST OF SUBROUTINES	8
V. PROGRAM LISTINGS	9
VI. SAMPLE PROGRAM	159
REFERENCES	163

BLANK PAGE

I. INTRODUCTION

This report contains listings of the subroutines described in R-514-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems* [1], and R-534-PR, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems--Program Reference Manual* [2]. All subroutines are written in FORTRAN. They have been compiled and executed on an IBM 360/65; the FORTRAN H compiler was used.

In most instances, the average user of the Markovian Flow Model program package will not need to refer to this report. However, these program listings may be useful when:

1. The programs are to be compiled and run on another computer system.
2. A new operation using the Flow Model data has been defined and a subroutine implementing this operation is to be written.
3. There is the possibility of an error in the program. Before making this assumption, the following items should be very carefully checked--particularly if a System Completion Code is given for an abnormal end:
 - a. Does the Main program contain an IMPLICIT REAL*8(A-H,O-Z) statement?
 - b. Are all arrays in the argument lists dimensioned in the Main program? Is each dimension adequate for the data stored in the corresponding array?
 - c. Are all control cards required for each operation present? Is the information in these cards in the proper columns and of the proper type?

- d. Do the FORTRAN input/output units specified in the operation control cards correspond to the units specified in the IBM 360 Job Control Language Data Definition (JCL DD) cards?
- e. Does the information in each JCL DD card correctly describe the data file?

II. INFORMATION FOR NON-RAND USERS

SYSTEM IMPLEMENTATION

The exact procedure required to create a FLOMOD program library is determined by the operating system implemented for the available computer. The procedure described below, used by the systems programming staff at Rand, may be a useful guide.

Using the *multiple-load module-processing* capability of the level F linkage editor, an output module library called SYS1.FLOMOD is created on a 2314 direct-access device. By means of the SYSLIB DD statement, this library is easily accessible through concatenation with the SYS1.FORTRAN system library. The FORTCLG cataloged procedure makes this concatenation a trivial process. The library created is a partitioned data-set requiring approximately 16 tracks, with each object module comprising one member (of the same name).

The following JCL for the linkage editor creates SYS1.
FLOMOD:

```
//jobname JOB
// EXEC PGM=LINKEDIT,REGION=104K,PARM='LIST,MAP,XREF,NCAL'
//SYSLIB DD DSNAME=SYS1.FORTLIB,DISP=SHR
//      DD DSN=SYS1.PL1LIB,DISP=SHR
//SYSPRINT DD SYSOUT=A,DCB=BLKSIZE=1210
//SYSIMOD DD DSN=SYS1.FLOMOD,DISP=(,CATLG,DELETE),
//      UNIT=2314,VOL=SER=RAND05,SPACE=(CYL,(1,1,7),RLSE),
//      DCB=(BLKSIZE=800,LRECL=80,RECFM=FB),LABEL=EXPDT=99350
//SYSLIN DD DDNAME=SYSIN
//SYSUT1 DD UNIT=(SYSDA,SEP=(SYSLIB,SYSIMOD)),
//      SPACE=(1024,(50,20))
//SYSIN DD *
      (CARDSP object deck)
NAME CARDSP
:
      (TMT2 object deck)
NAME TMT2
/*
//
```

Only the JCL statements below are required to execute a FLOMOD program:

```
//jobname JOB  
// EXEC FORTCLG,LIBL='SYS1.FLOMOD'  
//FORT.SYSIN DD *  
      ...      (FLOMOD run deck)  
/*  
//
```

The above JCL invokes the following system-catalogued procedure (FORTCLG):

```
//FORTCLG  PROC LIB1='SYS1.NOTHING',LIB2='SYS1.NOTHING',  
//           LIB3='SYS1.NOTHING'  
//FORT EXEC PGM=IEYFORT,REGION=104K  
//SYSPRINT DD SYSOUT=A,DCB=BLKSIZE=1680  
//SYSPUNCH DD SYSOUT=B,DCB=BLKSIZE=800  
//SYSLIN DD DSN=&&LOADSET,SPACE=(1600,(10,5)),DISP=(MOD,PASS),  
//          DCB=(BLKSIZE=1600,RECFM=FB),UNIT=SYSDA  
//LKED EXEC PGM=LINKEDIT,COND=(5,LT,FORT),REGION=104K,  
//          PARM='LIST,MAP'  
//SYSLIB DD DSN=&LIB1,DISP=SHR  
// DD DSNAME=&LIB2,DISP=SHR  
// DD DSNAME=&LIB3,DISP=SHR  
// DD DSN=SYS1.FORTLIB,DISP=SHR  
// DD DSNAME=SYS1.CSDFNLIB,DISP=SHR  
//SYSPRINT DD SYSOUT=A,DCB=BLKSIZE=1210  
//SYSLMOD DD DSN=&&GOSET(GO),DISP=(MOD,PASS),  
//          SPACE=(3072,(17,7,1)),UNIT=SYSDA,DCB=BLKSIZE=3072  
//SYSLIN  DD DSNAME=&LOADSET,DISP=(OLD,DELETE)  
// DD DDNAME=SYSIN  
//SYSUT1 DD UNIT=(SYSDA,SEP=(SYSLIB,SYSLMOD)),  
//          SPACE=(1024,(50,20))  
//GO EXEC PGM=*.LKED.SYSLMOD,COND=((5,LT,FORT),(8,LT,LKED))  
//FT05F001 DD DDNAME=SYSIN  
//FT06F001 DD SYSOUT=A  
//FT07F001 DD SYSOUT=B  
//**NAME=SYSTEM,USE=FORTRAN G COMPILE, LINK EDIT, AND GO.
```

PROGRAMS IN CARD FORM

To operate with the program package in card form, include the Main program and the deck for each subroutine called. Also include the deck for each utility subroutine called, if any, by the operation subroutines. Each subroutine write-up in Ref. 2 lists the utility subroutines called.

PROGRAMMING DETAILS

A design objective of this program package was machine independence. The one known exception is subroutine NUDATE (a utility routine called by SXP), which assumes that alphanumeric data fields are represented in the computer in EBCDIC.[†]

The following programming details may be significant when this program package is used on other systems:

1. The standard FORTRAN convention in naming variables has been followed: all integer variables start with the letters I,J,K,L,M,N; all real variables start with the letters A through H, and O through Z. All literal or alphanumeric data are identified by integer-variable names. In each subroutine, all real variables are declared as REAL*8-type variables.

2. When a one-dimensional array is dimensioned in the Main program and included in a subroutine argument list, the array will have a dimension of one in the subroutine.

3. There are no COMMON statements in this program package.

4. All control cards (input-data cards) are read by a statement of the form

READ format, list

A statement of the form

PRINT format, list

is used for all printed output.

5. An A4 format is used for both input and output of alphanumeric fields.

6. Subroutine COPY may specify a read, backspace, and write sequence of operations for a single file. When this file has blocked variable-length records, the operating

[†]An abbreviation for "Extended Binary-Coded-Decimal Interchange Code"--an 8-bit code used by IBM System/360 computers.

system must execute a BACKSPACE statement as a logical rather than a physical backspace.

7. The maximum state number that may be processed by these programs is the maximum value that may be stored in a standard-length integer variable. For an IBM 360, this maximum integer value is $2^{31}-1$, or 2,147,483,647.

8. Certain inconsistencies in control-card or tape-file data detected by the FLOMOD programs cause program execution to cease. An error message is printed and a STOP statement is executed. This program package contains no CALL EXIT statements.

III. DESCRIPTION OF SOURCE-DECK FORMAT

The first card in each deck is a SUBROUTINE statement card. This is followed by comment cards containing a brief statement of the operation the subroutine will perform. The program statements and additional comment cards complete a deck.

There are no flow charts for the individual subroutines. Instead, the numerous comment cards in the program deck provide a step-by-step natural-language description of the operations performed when the statements are executed. The information in these cards defines variables and describes the data being read, written, computed, or tested at each step in the program.[†] A reference list of symbolic variable names is found at the end of each subroutine deck. The entries in the argument list are listed first, in the order of their appearance. These are followed by other variable names, in alphabetical order by the first letter only of the variable name.

Columns 73 through 80 of each subroutine deck contain a unique subroutine label of 3 to 5 characters and a sequential card number. The sequence numbers for each subroutine start at 10.

[†]D matrices, S vectors, and P matrices are typically referred to as "files" in these source decks; it should be clear from the context that we are not referring to system files.

IV. LIST OF SUBROUTINES

Subroutine Name	Subroutine Label in Cards	Number of Cards in Deck	Storage Required in Hexadecimal Bytes [†]	Page
CARDSP	CARD	259	BF6	10
CLLAPS	CLLA	318	AF6	15
COPY	COPY	200	878	21
DSPRNT	DSP1	492	12E8	25
DSPRN2	DSP2	669	1610	34
DXCOST	DXCO	294	9DA	46
FCHANG	FCH	1403	2BD6	52
FILE	FILE	64	1DE	77
FREQ1	FRQ1	211	7FA	79
FREQ2	FRQ2	226	85A	83
GENDSP	GEND	775	1C84	87
LSTPAT	LSTP	261	99A	101
NUDATE	NUDA	113	342	106
POSFWD	POSF	42	1F2	108
POSINP	POSI	101	3C0	109
PRINTD	PRNTD	64	1E4	111
PRINTP	PRNTP	73	2B6	113
PRINTS	PRNTS	51	218	115
READIN	RDIN	31	180	116
READSP	RDSP	141	404	117
SELPAT	SELP	388	B96	120
SMATXP	SMAT	300	C96	127
SMINUS	SMIN	301	B98	133
SPAIRS	SPAIR	67	272	139
STDES	STDE	227	7BA	141
STSORT	STSO	205	894	145
SXP	SXP	409	DEA	149
TMT	TMT	24	12E	157
TMT2	TMT2	29	144	158

[†]For FORTRAN IV H LEVEL 17 compiler on an IBM 360/65.

-9-

V. PROGRAM LISTINGS

SUBROUTINE CARDSP (ISN,ISVEC,P)	CARD0010		
C	CARD0020		
C	THIS ROUTINE WILL READ D, S AND/OR P ARRAYS PUNCHED IN CARDS AND WRITE THEM ON TAPE IN THE FLOMOD FORMAT.	CARD0030	
C	CARD0040		
C	CARD0050		
C	CARD0060		
C	IMPLICIT REAL*8(A-H,O-Z,\$)	CARD0070	
C	DIMENSION ISN(1),ISVEC(1),P(1),NAME(6),LABEL(30)	CARD0080	
C	CARD0090		
C	INITIALIZE RECORD TYPE VARIABLES.	CARD0100	
C	D BEGINNING LABEL.	CARD0110	
C	KDBEG=1	CARD0120	
C	D DATA RECORD.	CARD0130	
C	KDDAT=21	CARD0140	
C	D END LABEL.	CARD0150	
C	KDEND=31	CARD0160	
C	S BEGINNING LABEL.	CARD0170	
C	KSBEGL=2	CARD0180	
C	S DATA RECORD.	CARD0190	
C	KSDAT=22	CARD0200	
C	S END LABEL.	CARD0210	
C	KSEND=32	CARD0220	
C	P BEGINNING LABEL.	CARD0230	
C	KPBEG=3	CARD0240	
C	P LIST RECORD.	CARD0250	
C	KPLST=13	CARD0260	
C	P DATA RECORD.	CARD0270	
C	KPDAT=23	CARD0280	
C	P END LABEL.	CARD0290	
C	KPEND=33	CARD0300	
C	FLOMOD END OF FILE RECORD.	CARD0310	
C	KNEXT=40	CARD0320	
C	NL= NUMBER OF WORDS IN LABEL.	CARD0330	
C	NL=30	CARD0340	
C	FILLER VARIABLE.	CARD0350	
C	NFILL=1	CARD0360	
C	DATA KBLANK/4H	/	CARD0370
C	READ 5,KOUT	READ OUTPUT UNIT NUMBER.	CARD0380
C	REWIND KOUT	REWIND OUTPUT UNIT.	CARD0390
C	REWIND KOUT	SET COUNT OF FILES ON OUTPUT UNIT TO ZERO.	CARD0400
C	NFILES=0	CARD0410	
C	READ ARRAY TYPE.	CARD0420	
C	50 READ 5,KTYPE	CARD0430	
C	BRANCH ON ARRAY TYPE.	CARD0440	
C	GO TO (100,200,300,400),KTYPE	CARD0450	
C	CARD0460		
C	D MATRIX.	CARD0470	
C	100 CONTINUE	CARD0480	
C	READ MATRIX NAME AND LABEL.	CARD0490	
C	READ 10,NAME,LABEL	CARD0500	
C	PRINT TYPE AND NAME	CARD0510	
C	PRINT 2,KTYPE,NAME	CARD0520	
C	WRITE BEGINNING LABEL ON OUTPUT UNIT.	CARD0530	
C	WRITE(KOUT)KDBEG,NAME,NL,LABEL	CARD0540	
C	CARD0550		
C	CARD0560		

-11-

```
C          READ ARRAY ELEMENTS. THEY MUST BE IN ORDER BY      CARD0570
C          ROW AND BY COLUMN WITHIN ROW.                  CARD0580
C          INITIALIZE ELEMENT SUBSCRIPT FOR THIS ROW.      CARD0590
C          K=1                                              CARD0600
C          INITIALIZE NUMBER OF ELEMENTS COUNT FOR THE      CARD0610
C          MATRIX.                                         CARD0620
C          KSUM=0                                           CARD0630
C          ISCNT=0                                          CARD0640
C          ISCTN=0                                           CARD0650
C          READ FIRST ELEMENT CARD.                      CARD0660
C          READ 5,IROW,ISN(1),ISVEC(1)                   CARD0670
C          UPDATE ROW SUBSCRIPT.                         CARD0680
130 K=K+1          READ ADDITIONAL ELEMENT CARD.          CARD0690
C          READ 5,IROWX,ISN(K),ISVEC(K)                 CARD0700
C          WAS ROW NUMBER JUST READ SAME AS FOR PREVIOUS CARD0710
C          READ?                                         CARD0720
C          YES. GO TO READ NEXT CARD.                  CARD0730
C          IF(IROW.EQ.IROWX) GO TO 130                 CARD0740
C          THERE WAS A CHANGE IN ROW NUMBER. WRITE THE CARD0750
C          RECORD FOR THE ROW COMPLETED ON THE OUTPUT UNIT. CARD0770
C          LET ICNT = NUMBER OF ELEMENTS IN THE ROW.     CARD0780
C          ICNT=K-1                                       CARD0790
C          WRITE(KOUT)KDDAT,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) CARD0800
C          UPDATE MATRIX ROW COUNT.                     CARD0810
C          ISCNT=ISCNT+1                                CARD0820
C          ACCUMULATE COUNT OF D ELEMENTS FOR THIS MATRIX. CARD0830
C          KSUM=KSUM+ICNT                               CARD0840
C          HAVE ALL ELEMENTS FOR THIS MATRIX BEEN READ? CARD0850
C          YES - GO TO WRITE ARRAY END LABEL.          CARD0860
IF(IROWX.EQ.-1) GO TO 150          NO.                  CARD0870
C          DATA FROM LAST CARD READ IS TO BE SHOWN AS FIRST CARD0890
C          ENTRY IN A NEW ROW.                         CARD0900
C          IROW=IROWX                                     CARD0910
C          ISN(1)=ISN(K)                                 CARD0920
C          ISVEC(1)=ISVEC(K)                            CARD0930
C          K=1                                              CARD0940
C          GO TO READ NEXT CARD.                      CARD0950
GO TO 130          GO TO READ NEXT CARD.          CARD0960
C          ALL ELEMENTS FOR THE MATRIX HAVE BEEN READ. CARD0970
C          WRITE END LABEL.                           CARD0980
150 WRITE(KOUT) KDEND,NFILL,NFILL,ISCNT,KSUM          CARD0990
C          UPDATE NUMBER OF OUTPUT FILES.            CARD1000
C          NFILES=NFILES+1                            CARD1010
C          GO TO READ NEXT ARRAY TYPE CARD.          CARD1020
C          GO TO 50                                    CARD1030
C          GO TO 50                                    CARD1040
C          GO TO 50                                    CARD1050
***CARD1060
*CARD1070
C          S VECTOR.                                CARD1080
200 CONTINUE          READ VECTOR NAME AND LABEL. CARD1090
C          READ 10,NAME,LABEL                         CARD1100
C          PRINT TYPE AND NAME.                    CARD1110
PRINT 2,KTYPE,NAME          PRINT TYPE AND NAME. CARD1120
C          PRINT 2,KTYPE,NAME                         CARD1130
```

C WRITE(KOUT)KSBEGL,NAME,NL,LABEL CARD1140
C READ S VECTOR ELEMENTS. THEY MUST BE IN ORDER. CARD1150
C INITIALIZE S VECTOR SUBSCRIPT. CARD1160
C ISCNT=1 CARD1170
C ISUM=0 CARD1180
C READ AN ELEMENT. CARD1190
C 220 READ 15,ISN(ISCNT),ISVEC(ISCNT) CARD1200
C HAVE ALL ELEMENTS FOR THE VECTOR BEEN READ? CARD1210
C YES. GO TO WRITE ARRAY END LABEL. CARD1220
C IF(ISN(ISCNT).EQ.-1) GO TO 250 CARD1230
C NO. CARD1240
C ACCUMULATE S VECTOR SUM. CARD1250
C ISUM=ISUM+ISVEC(ISCNT) CARD1260
C UPDATE S VECTOR SUBSCRIPT. CARD1270
C ISCNT=ISCNT+1 CARD1280
C GO TO READ NEXT ELEMENT. CARD1290
C GO TO 220 CARD1300
C ALL ELEMENTS FOR THE S VECTOR HAVE BEEN READ. CARD1310
C SET ISCNT EQUAL THE NUMBER OF ELEMENTS IN S. CARD1320
C 250 ISCNT=ISCNT-1 CARD1330
C WRITE DATA RECORD. CARD1340
C WRITE(KOUT)KSDAT,NFILL,ISCNT,(ISN(I),I=1,ISCNT), CARD1350
C 1 (ISVEC(I),I=1,ISCNT) CARD1360
C WRITE END LABEL. CARD1370
C WRITE(KOUT)KSEND,NFILL,NFILL,ISUM,NFILL CARD1380
C UPDATE NUMBER OF OUTPUT FILES. CARD1390
C NFILES=NFILES+1 CARD1400
C GO TO READ NEXT TYPE CARD. CARD1410
C GO TO 50 CARD1420
C ***CARD1430
C ***CARD1440
C ***CARD1450
C ***CARD1460
C P MATRIX
C READ MATRIX NAME AND LABEL. CARD1470
C 300 READ 10,NAME,LABEL CARD1480
C PRINT 2,KTYPE,NAME CARD1490
C WRITE BEGINNING LABEL ON OUTPUT UNIT. CARD1500
C WRITE(KOUT)KPBEGL,NAME,NL,LABEL CARD1510
C READ LIST OF ROWS AND MODIFY SPECIFICATIONS. CARD1520
C READ 5,ISCNT,(ISN(I),I=1,ISCNT),MODSW,MODFAC CARD1530
C WRITE INFO JUST READ ON OUTPUT UNIT. CARD1540
C WRITE(KOUT)KPLST,ISCNT,(ISN(I),I=1,ISCNT),MODSW,MODFAC CARD1550
C READ LIST OF COLUMNS AND P MATRIX INCREMENT CARD1560
C VALUES. CARD1570
C READ 5,JCNT,(ISN(I),I=1,JCNT),NUMMO,NUMYR CARD1580
C WRITE INFO JUST READ ON OUTPUT UNIT. CARD1590
C WRITE(KOUT)KPLST,JCNT,(ISN(I),I=1,JCNT),NUMMO,NUMYR CARD1600
C READ ARRAY ELEMENTS. THEY MUST BE IN ORDER BY CARD1610
C ROW AND BY COLUMN WITHIN ROW. CARD1620
C INITIALIZE ELEMENT SUBSCRIPT FOR THIS ROW. CARD1630
C K=1 CARD1640
C INITIALIZE NUMBER OF ELEMENTS COUNT FOR THE CARD1650
C MATRIX. CARD1660
C CARD1670
C CARD1680
C CARD1690
C CARD1700

```
KSUM=0 CARD1710
C READ FIRST ELEMENT CARD. CARD1720
C READ 15,IROW,ISN(1),P(1) CARD1730
C UPDATE ROW SUBSCRIPT. CARD1740
330 K=K+1 CARD1750
C READ ADDITIONAL ELEMENT CARD. CARD1760
C READ 15,IROWX,ISN(K),P(K) CARD1770
C WAS ROW NUMBER JUST READ SAME AS THAT OF CARD1780
C PREVIOUS READ? CARD1790
C YES - GO TO READ NEXT CARD. CARD1800
C IF(IROW.EQ.IROWX) GO TO 330 CARD1810
C THERE WAS A CHANGE IN ROW NUMBER. WRITE THE CARD1820
C RECORD FOR THE ROW COMPLETED ON THE OUTPUT UNIT. CARD1830
C LET ICNT = NUMBER OF ELEMENTS IN THE ROW. CARD1840
C ICNT=K-1 CARD1850
C WRITE(KOUT)KPDAT,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT) CARD1860
C ACCUMULATE COUNT OF P ELEMENTS FOR THIS MATRIX. CARD1870
C KSUM=KSUM+ICNT CARD1880
C HAVE ALL ELEMENTS FOR THIS MATRIX BEEN READ? CARD1890
C YES - GO TO WRITE ARRAY END LABEL. CARD1900
C IF(IROWX.EQ.-1) GO TO 350 CARD1910
C NO. CARD1920
C DATA FROM LAST CARD READ IS TO BE SHOWN AS FIRSTCARD1930
C ENTRY IN A NEW ROW. CARD1940
C IROW=IROWX CARD1950
C ISN(1)=ISN(K) CARD1960
C P(1)=P(K) CARD1970
C K=1 CARD1980
C GO TO READ NEXT CARD. CARD1990
C GO TO 330 CARD2000
C C ALL ELEMENTS FOR THE MATRIX HAVE BEEN READ. CARD2020
C CHANGE COUNT OF ARRAY ELEMENTS TO A REAL VALUE. CARD2030
350 PN=KSUM CARD2040
C WRITE END LABEL. CARD2050
C WRITE(KOUT) KPEND,NFILL,NFILL,ISCNT,PN CARD2060
C UPDATE NUMBER OF OUTPUT FILES. CARD2070
C NFILES=NFILES+1 CARD2080
C GO TO READ NEXT ARRAY TYPE CARD. CARD2090
C GO TO 50 CARD2100
C C ALL ARRAYS HAVE BEEN PROCESSED. CARD2120
C C UPDATE NUMBER OF FILES FOR END OF FILE RECORD. CARD2140
C 400 NFILES=NFILES+1 CARD2150
C CREATE A BLANK FILE NAME. CARD2160
DO 410 I=1,6 CARD2170
410 NAME(I)=KBLANK CARD2180
C WRITE END LABEL. CARD2190
C WRITE(KOUT)KNEXT,NAME,NFILL,NFILES CARD2200
C REWIND OUTPUT UNIT. CARD2210
C REWIND KOUT CARD2220
C PRINT 2,KTYPE,NAME CARD2230
C PRINT 1,NFILES CARD2240
C PRINT END OF OPERATION MESSAGE. CARD2250
C RETURN CARD2260
C CARD2270
```

RETURN	CARD2280
C	CARD2290
1 FORMAT(46H CARDSP OPERATION COMPLETE. NUMBER OF FILES = I6)	CARD2300
2 FORMAT(1X,7HKTYPE =,I6,5X,6A4)	CARD2310
5 FORMAT(6I12)	CARD2320
10 FORMAT(6A4/20A4/10A4)	CARD2330
15 FORMAT(2I12,F12.6)	CARD2340
C	CARD2350
C REFERENCE LIST.	CARD2360
C	CARD2370
C SUBROUTINE ARGUMENTS.	CARD2380
C	CARD2390
C ISN - THIS ARRAY WILL BE USED FOR (1) P MATRIX LIST OF ROWS,	CARD2400
C LIST OF COLUMNS, AND LIST OF COLUMNS IN A ROW, (2) D	CARD2410
C MATRIX LIST OF COLUMNS IN A ROW, (3) S VECTOR LIST OF	CARD2420
C STATE NUMBERS.	CARD2430
C ISVEC - THIS ARRAY WILL BE USED FOR (1) D MATRIX ELEMENT VALUES	CARD2440
C IN A ROW, (2) S VECTOR STATE VALUES.	CARD2450
C P - THIS ARRAY WILL BE USED FOR THE P MATRIX ELEMENT VALUES	CARD2460
C IN A ROW.	CARD2470
C	CARD2480
C OTHER VARIABLES.	CARD2490
C	CARD2500
C KTYPE - 1.. D MATRIX.	CARD2510
C 2.. S VECTOR.	CARD2520
C 3.. P MATRIX.	CARD2530
C 4.. END OF INPUT DATA.	CARD2540
C MODSW - TRANSITION MODIFY SWITCH. SEE GENDSP FOR DETAILS.	CARD2550
C MODFAC - TRANSITION MODIFY FACTOR. SEE GENDSP FOR DETAILS.	CARD2560
C NUMMO - P MATRIX MONTH INCREMENT VALUE. SEE GENDSP FOR DETAILS.	CARD2570
C NUMYR - P MATRIX YEAR INCREMENT VALUE. SEE GENDSP FOR DETAILS.	CARD2580
C END	CARD2590

SUBROUTINE CLLAPS(KS,LSTCOD,LDIM) CLLA0010
C *CLLA0020
C THIS SUBROUTINE WILL COLLAPSE A GIVEN MODEL BY CLLA0030
C OMITTING OR RECODING ONE OR MORE VARIABLES IN CLLA0040
C THE STATE DEFINITION. CLLA0050
C THE COLLAPSE OPERATION CAN BE PERFORMED ON A CLLA0060
C STATE PATTERN FREQUENCY FILE ONLY. CLLA0070
C CLLA0080
C A DIMENSION OF 30 IS USED FOR THE VARIABLE CODE CLLA0090
C ARRAYS SINCE THIS IS THE MAXIMUM NUMBER OF VARI-CLLA0100
C ABLES THAT MAY BE USED IN DEFINING A MODEL. CLLA0110
C CLLA0120
C DIMENSION NCODEV(30),KS(1) CLLA0130
C DIMENSION NCODV2(30),NC(30),NC2(30),LOC(30),LSTCOD(1) CLLA0140
C DIMENSION LCODE(30) CLLA0150
C DIMENSION MULT(30) CLLA0160
C CLLA0170
C C INITIALIZE CONSTANT NFILL. CLLA0180
C NFILL=0 CLLA0190
C READ NV - NUMBER OF VARIABLES USED TO DEFINE CLLA0200
C INPUT STATE NUMBERS - AND NCODEV(1) THRU CLLA0210
C NCODEV(NV) - NUMBER OF CODES DEFINED PER VARI- CLLA0220
C ABLE FOR INPUT STATE NUMBERS. THE NCODEV VALUE CLLA0230
C WILL BE NEGATIVE FOR ANY VARIABLE BEING OMITTED CLLA0240
C IN OUTPUT STATE NUMBERS. CLLA0250
C READ 10,NV,(NCODEV(N),N=1,NV) CLLA0260
C READ 'NS' - NUMBER OF STATE NUMBERS PER PATTERN. CLLA0270
C READ 10,NS CLLA0280
C SET UP ARRAY OF POSITIVE NUMBER OF CODES PER CLLA0290
C VARIABLE FOR USE IN COMPUTING MULTIPLY FACTORS CLLA0300
C AND ARRAY SUBSCRIPTS. CLLA0310
C CLLA0320
C DO 20 N=1,NV CLLA0330
C 20 NC(N)=IABS(NCODEV(N)) CLLA0340
C INITIALIZE FOR LATER INDEX USE. CLLA0350
C NVMI=NV-1 CLLA0360
C GENERATE THE MULTIPLY FACTORS USED IN DECODING CLLA0370
C STATE NUMBERS. CLLA0380
C MULT(NV)=1 CLLA0390
C IF(NV.EQ.1) GO TO 24 CLLA0400
C H=NV CLLA0410
C DO 22 I=1,NVMI CLLA0420
C MULT(N-1)=MULT(N)*NC(N) CLLA0430
C 22 N=N-1 CLLA0440
C READ KOPT - SPECIFICATION OF COLLAPSE OPTION. CLLA0450
C 24 READ 10,KOPT CLLA0460
C BRANCH ON OPTION. CLLA0470
C IF(KOPT.EQ.2) GO TO 30 CLLA0480
C OPTION 1.
C VARIABLE OMISSION ONLY.
C THE NUMBER OF CODES DEFINED PER VARIABLE FOR CLLA0490
C OUTPUT STATE NUMBERS WILL BE THE SAME AS THE CLLA0500
C NUMBER OF CODES DEFINED FOR THE CORRESPONDING CLLA0510
C INPUT VARIABLE. CLLA0520
C CALL TMT(NV,NCODV2(1),NCODEV(1)) CLLA0530
C GO TO 60 CLLA0540
C CLLA0550

C OPTION 2. CLLA0560
C VARIABLE GROUPING ONLY OR VARIABLE GROUPING AND CLLA0570
C OMISSION. CLLA0580
C READ NV - NUMBER OF VARIABLES (MUST BE THE SAME CLLA0590
C AS NV IN THE FIRST READ) AND NCODV2(1) THRU CLLA0600
C NCODV2(NV) - THE NUMBER OF CODES PER VARIABLE CLLA0610
C FOR THE NEW MODEL. THE ENTRY WILL BE ZERO FOR A CLLA0620
C VARIABLE BEING OMITTED AND NEGATIVE FOR A CLLA0630
C VARIABLE BEING RECODED. CLLA0640
C
30 READ 10,NV,(NCODV2(N),N=1,NV) CLLA0650
C SET UP.. CLLA0660
C LSTCOD - ARRAY OF RECODE CODES FOR VARIABLES TO CLLA0670
C BE RECODED AND LOC - ARRAY OF SUBSCRIPTS - CLLA0680
C BEGINNING LOCATION IN LSTCOD OF RECODE VALUES CLLA0690
C FOR EACH VARIABLE. CLLA0700
C SET INITIAL SUBSCRIPT TO ONE. CLLA0710
C
LOCSUB=1 CLLA0720
C DO 50 N=1,NV CLLA0730
C IS THIS VARIABLE TO BE RECODED? CLLA0740
C IF(NCODV2(N).LT.0) GO TO 40 CLLA0750
C NO CLLA0760
C NO LOCATION IN LSTCOD WILL CONTAIN CODES FOR THE CLLA0780
C NTH VARIABLE. CLLA0790
C
LOC(N)=0 CLLA0800
C GO TO 50 CLLA0810
C
YES CLLA0820
C THE CODES FOR THIS VARIABLE ARE TO BE CHANGED. CLLA0830
C LOC(N)=FIRST LOCATION IN LSTCOD FOR CODES FOR CLLA0840
C THE NTH VARIABLE. CLLA0850
C
40 LOC(N)=LOCSUB CLLA0860
C NC(N) IS THE NUMBER OF CODES DEFINED FOR THE CLLA0870
C NTH VARIABLE IN THE INPUT MODEL. CLLA0880
C LTO IS THE LAST LOCATION IN LSTCOD FOR CODES FOR CLLA0890
C THE NTH VARIABLE. CLLA0900
C
LTO=LOCSUB+NC(N)-1 CLLA0910
C READ NX - VARIABLE NUMBER FOR FOLLOWING LIST OF CLLA0920
C RECODE VALUES, AND LSTCOD(LOCSUB) THRU LSTCOD CLLA0930
C (LTO) - A LIST OF NEW CODE VALUES, ONE FOR EACH CLLA0940
C ORIGINAL CODE VALUE. CLLA0950
C
READ 10,NX,(LSTCOD(L),L=LOCSUB,LTO) CLLA0960
C DOES THE VARIABLE NUMBER READ EQUAL THE CURRENT CLLA0970
C VARIABLE NUMBER OF THE DO LOOP CONTROLLING THE CLLA0980
C RECODE INPUT? CLLA0990
C NO. CONTROL CARD ERROR. CLLA1000
C
IF(NX.NE.N) GO TO 220 CLLA1010
C YES CLLA1020
C
LOCSUB=LTO+1 CLLA1030
C
CONTINUE CLLA1040
C
50 CONTINUE CLLA1050
C
IS FINAL SUBSCRIPT VALUE USED GREATER THAN THE CLLA1060
C DIMENSION OF THE ARRAY IN WHICH THESE NEW CODE CLLA1070
C VALUES WERE STORED? CLLA1080
C YES. DIMENSION ERROR. CLLA1090
C
IF(LOCSUB-1.GT.LDIM) GO TO 200 CLLA1100
C CLLA1110
C CLLA1120

C DECODE.
C DECODE THE ORIGINAL STATE NUMBER AND PLACE THE
C CODE VALUES IN LCODE. CLLA1700
C
C IF(NV.EQ.1) GO TO 1062 CLLA1710
DO 1060 N=1,NVM1 CLLA1720
LWK=(LK-1)/MULT(N)
LK=LK-LWK*MULT(N)
1060 LCODE(N)=LWK+1 CLLA1725
1062 LCODE(NV)=LK CLLA1730
C RECODE.
C RECODE THE NEW STATE NUMBER AND PUT IT IN KS(K).CLLA1790
C SET WORKING LOCATION FOR GENERATION OF NEW STATECLLA1800
C NUMBER TO ZERO. CLLA1810
C LWK=0 CLLA1820
C DO FOR ALL VARIABLES. CLLA1830
DO 1080 N=1,NV CLLA1840
C IS THIS VARIABLE BEING OMITTED?
C YES. GO TO NEXT VARIABLE. CLLA1850
IF(INCODEV(N).LT.0) GO TO 1080 CLLA1860
C NO CLLA1870
C IS THIS VARIABLE BEING RECODED?
C NO. KEEP CURRENT CODE FOR THIS VARIABLE. CLLA1880
IF(INCODV2(N).GT.0) GO TO 1075 CLLA1890
C YES CLLA1900
C PICK UP CODE SUBSCRIPT AND VALUE. PLACE NEW CODECLLA1930
C VALUE IN LCODE. CLLA1940
L=LOC(N)-1+LCODE(N)
LCODE(N)=LSTCOD(L)
C ACCUMULATE CONTRIBUTION OF THIS CODE TO STATE CLLA1950
NUMBER. CLLA1960
1075 LWK=LWK*NC2(N)+LCODE(N)-1 CLLA1970
C CONTINUE CLLA1980
1080 CONTINUE CLLA1990
C ADJUST FOR 1 SUBTRACTED FOR RTH VARIABLE. CLLA2000
KS(K)=LWK+1 CLLA2010
C CONTINUE CLLA2020
1100 CONTINUE CLLA2030
C *CLLA2040
C **CLLA2050
C WRITE: MODL,KS(1) THRU KS(NS),IFREQ. CLLA2060
WRITE(KOUT) MODL,(KS(N),N=1,NS),IFREQ CLLA2070
C GO TO READ AN INPUT RECORD. CLLA2080
C
C END OF FILE ON READ.
REWIND INPUT UNIT. CLLA2090
100 REWIND KINP CLLA2100
C PRINT 'OPERATION COMPLETE MESSAGE' FOR THIS CLLA2110
INPUT UNIT. CLLA2120
C PRINT 240,KINP CLLA2130
C GO TO READ A CONTROL CARD. CLLA2140
C GO TO 75 CLLA2150
C YES - A RETURN CARD WAS READ.
REWIND OUTPUT UNIT. CLLA2160
190 REWIND KOUT CLLA2170
C CLLA2180
C CLLA2190
C CLLA2200
C CLLA2210
C CLLA2220
C CLLA2230
C CLLA2240
C CLLA2250

C PRINT 'OPERATION COMPLETE MESSAGE' FOR THIS CLLA2260
C OUTPUT UNIT. CLLA2270
C PRINT 250,KOUT CLLA2280
C RETURN CLLA2290
C RETURN CLLA2300
C YES CLLA2310
C DIM ERROR FOR LSTCOD. CLLA2320
C PRINT ERROR MESSAGE. CLLA2330
C 200 PRINT 210,LDIM,LOCSub CLLA2340
C EXIT CLLA2350
C STOP CLLA2360
C NO - CONTROL CARD VARIABLE NUMBER DOES NOT EQUAL CLLA2380
C DO LOOP VARIABLE NUMBER. CLLA2390
C PRINT ERROR MESSAGE. CLLA2400
C 220 PRINT 230,NX,N CLLA2410
C EXIT CLLA2420
C STOP CLLA2430
C 10 FORMAT(6I12) CLLA2440
C 210 FORMAT(52H DIMENSION OF LSTCOD - CODE LIST VECTOR - TOO SMALL./ CLLA2450
C 1 30H VALUES OF LDIM AND LOCSub ARE,2I12) CLLA2460
C 230 FORMAT(52H CLLAPS...CONTROL CARD ERROR. CARD VARIABLE NUMBER = , CLLA2470
C 1112/27X,25HDO LOOP VARIABLE NUMBER = ,I12) CLLA2480
C 240 FORMAT(/45H CLLAPS...OPERATION COMPLETE FOR INPUT UNIT ,I6) CLLA2490
C 250 FORMAT(/45H CLLAPS...OPERATION COMPLETE FOR OUTPUT UNIT ,I6) CLLA2500
C
C REFERENCE LIST. CLLA2510
C
C SUBROUTINE ARGUMENTS. CLLA2520
C
C KS - ARRAY FOR NS STATES -- A STATE NUMBER PATTERN. CLLA2530
C CLLA2540
C CLLA2550
C CLLA2560
C
C LSTCOD - THE NEW CODE VALUES. THERE IS A NEW CODE FOR EACH OLD CLLA2600
C CODE IN THE OLD CODE SEQUENCE - FOR ONLY THOSE VARIABLES CLLA2610
C BEING CHANGED. CLLA2620
C LSTCOD(1) - NEW CODE VALUE FOR FIRST OLD CODE VALUE FOR FIRST CLLA2630
C VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2640
C LSTCOD(2) - NEW CODE VALUE FOR SECOND OLD CODE VALUE FOR FIRST CLLA2650
C VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2660
C . CLLA2670
C . CLLA2680
C . CLLA2690
C LSTCOD(NCODEV(I)) - NEW CODE VALUE FOR LAST OLD CODE VALUE FOR CLLA2700
C FIRST VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2710
C LSTCOD(NCODEV(I)+1) - NEW CODE VALUE FOR FIRST OLD CODE VALUE FOR CLLA2720
C SECOND VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2730
C LSTCOD(NCODEV(I)+2) - NEW CODE VALUE FOR SECOND OLD CODE VALUE FOR CLLA2740
C SECOND VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2750
C . CLLA2760
C . CLLA2770
C ; CLLA2780
C LSTCOD(NCODEV(I)+NCODEV(J)) - NEW CODE VALUE FOR LAST OLD CODE CLLA2790
C VALUE FOR SECOND VARIABLE THAT HAS A NEGATIVE ENTRY IN NCODV2. CLLA2800
C CLLA2810
C CLLA2820

C	.	CLLA2830
C	.	CLLA2840
C	LDIM - DIMENSION OF LSTCOD IN MAIN PROGRAM.	CLLA2850
C	.	CLLA2860
C	OTHER VARIABLES.	CLLA2870
C	KOPT - OPTION TYPE.	CLLA2880
C	1 IF VARIABLE OMISSION ONLY.	CLLA2890
C	2 IF (A) VARIABLE GROUPING ONLY, OR	CLLA2900
C	(B) VARIABLE GROUPING PLUS VARIABLE OMISSION.	CLLA2910
C	LOC - ARRAY CONTAINING FOR EACH VARIABLE, THE SUBSCRIPT VALUE	CLLA2920
C	FOR THE FIRST LOCATION IN LSTCOD CONTAINING THE CODES FOR	CLLA2930
C	THAT VARIABLE.	CLLA2940
C	THE VALUE WILL BE ZERO IF NCODV2(I) IS ZERO OR POSITIVE.	CLLA2950
C	THE VALUE WILL BE 1 + (NCODEV(K) FOR EACH NEGATIVE	CLLA2960
C	NCODV2(K), K=1 THRU I-1) IF NCODV2(I) IS NEGATIVE.	CLLA2970
C	LCODE - A WORK AREA USED FOR THE VARIABLE CODES AS EACH STATE	CLLA2980
C	NUMBER IS RECODED.	CLLA2990
C	MULT - ARRAY FOR STATE NUMBER MULTIPLY FACTORS.	CLLA3000
C	NC - ARRAY FOR ABSOLUTE VALUE OF NCODEV ENTRIES.	CLLA3010
C	NC2 - ARRAY FOR ABSOLUTE VALUE OF NCODV2 ENTRIES.	CLLA3020
C	NS - NUMBER OF STATES PER PATTERN.	CLLA3030
C	NV - NUMBER OF VARIABLES.	CLLA3040
C	NX - VARIABLE NUMBER ASSOCIATED WITH SET OF RECODE VALUES	CLLA3050
C	CURRENTLY BEING READ.	CLLA3060
C	NCODEV - ARRAY FOR NUMBER OF CODES PER VARIABLE. THE ENTRY WILL BE	CLLA3070
C	NEGATIVE IF THE VARIABLE IS BEING COLLAPSED OUT OF THE	CLLA3080
C	MODEL.	CLLA3090
C	NCODV2 - AN ARRAY FOR THE NUMBER OF CODES PER VARIABLE OF THE	CLLA3100
C	INPUT MODEL REQUIRED TO DEFINE THE OUTPUT MODEL. A ZERO	CLLA3110
C	SHOULD BE ENTERED FOR A VARIABLE BEING OMITTED.	CLLA3120
C	A NEGATIVE VALUE SHOULD BE ENTERED FOR A VARIABLE BEING	CLLA3130
C	RECODED.	CLLA3140
C	END	CLLA3150
C		CLLA3160

```

C SUBROUTINE COPY(ISN,ISVEC,P,LABEL) COPY0010
C
C THIS IS A GENERAL PURPOSE COPY ROUTINE FOR D COPY0020
C MATRICES, P MATRICES, AND S VECTORS. COPY0030
C
C THE FIRST CONTROL CARD IDENTIFIES THE OUTPUT COPY0040
C UNIT SPECIFICATIONS. THE CARD FIELDS ARE COPY0050
C KOUT - COL 1-6 (I6) FORTRAN UNIT NUMBER. COPY0060
C KPOS - COL 7-12 (I6) POSITIONING SPECIFICATION: COPY0070
C           0 - START AT BEGINNING OF FILE. COPY0080
C           1 - START AT FLOMOD END OF FILE RECORD. COPY0090
C
C ONE CONTROL CARD IS REQUIRED FOR EACH SET OF COPY0100
C CONSECUTIVE ARRAYS-ON AN INPUT UNIT-THE ARE TO COPY0110
C BE COPIED. COPY0120
C A BLANK CONTROL CARD IS USED TO RETURN CONTROL COPY0130
C TO THE CALLING PROGRAM. COPY0140
C THE CONTROL CARD FIELDS ARE COPY0150
C IDTAPE - COL 1-6 (I6) FORTRAN INPUT UNIT NUMBER. COPY0160
C NFILE - COL 7-30 (6A4) ARRAY NAME OF FIRST OF COPY0170
C           'NUMVC' FILES TO BE COPIED UNDER COPY0180
C           CONTROL OF THIS CARD. COPY0190
C NUMVC - COL 31-36 (I6) COPY0200
C           +N = THE NUMBER OF CONSECUTIVE ARRAYS COPY0210
C           TO BE COPIED FROM 'IDTAPE': COPY0220
C           STARTING WITH ARRAY 'NFILE'. COPY0230
C           0 = COPY OPERATION COMPLETED. RETURN. COPY0240
C           -1 = COPY ALL ARRAYS ON THE TAPE. COPY0250
C
C IMPLICIT REAL*8(A-H,O-Z,$) COPY0260
C DIMENSION ISN(1),ISVEC(1),P(1),LABEL(1),NFILE(6) COPY0270
C DATA KBLANK/4H   / COPY0280
C
C
C           INITIALIZATION COPY0290
C           RECORD TYPE FOR END OF FILE ARRAY. COPY0300
C
C K40=40 COPY0310
C
C NFILL=1 COPY0320
C
C NFILES=0 COPY0330
C
C PRINT 5 COPY0340
C
C 5 FORMAT(26H1 LIST OF FILES COPIED...) COPY0350
C           READ OUTPUT UNIT NUMBER AND POSITION TYPE. COPY0360
C
C READ 1,KOUT,KPOS COPY0370
C
C 1 FORMAT(2I6) COPY0380
C
C           REWIND OUTPUT UNIT. COPY0390
C
C REWIND KOUT COPY0400
C
C           IF OUTPUT IS TO START AT THE BEGINNING OF THE COPY0410
C TAPE, NO FURTHER POSITIONING IS REQUIRED. GO TO COPY0420
C READ INPUT SPECIFICATION. COPY0430
C
C IF(KPOS,EQ,0) GO TO 5 COPY0440
C
C           POSITION TO FLOMOD END OF FILE RECORD ON OUTPUT COPY0450
C UNIT. COPY0460
C
C 2 READ(KOUT)KTYPE COPY0470
C
C           IF THIS WAS NOT THE END OF FILE RECORD, READ THE COPY0480
C
C

```

C NEXT RECORD. COPY0570
C IF(KTYPE.NE.40) GO TO 2 COPY0580
C THE RECORD JUST READ WAS AN END OF FILE RECORD. COPY0590
C BACKSPACE THIS RECORD. COPY0600
C BACKSPACE KOUT COPY0610
C READ(KOUT)KTYPE,NFILE,NFILL,NFILES COPY0620
C SUBTRACT ONE FOR THE END OF FILE 'FILE' FROM THE COPY0630
C NUMBER OF FILES COUNT. COPY0640
C NFILES=NFILES-1 COPY0650
C BACKSPACE END OF FILE RECORD SO OUTPUT UNIT IS COPY0660
C IN PROPER POSITION FOR WRITING NEXT LABEL. COPY0670
C BACKSPACE KOUT COPY0680
C READ FIRST COPY SPECIFICATION CARD. COPY0690
C 6 READ 11, IDTAPE,NFILE,NUMVC COPY0700
C STORE TAPE NUMBER AS 'PREVIOUS' TAPE NUMBER. COPY0710
C THIS IS TO AVOID UNNECESSARY REWINDS. COPY0720
C !DTAPX=IDTAPE COPY0730
C REWIND IDTAPE COPY0740
C GO TO 12 COPY0750
C READ FOR ADDITIONAL COPY SPECIFICATION CARDS. COPY0760
C 10 READ 11, IDTAPE,NFILE,NUMVC COPY0770
C 11 FORMAT(16,6A4,I6) COPY0780
C IS THE COPY RUN COMPLETE? COPY0790
C YES, GO TO WRITE END RECORD. COPY0800
C 12 IF(NUMVC.EQ.0) GO TO 500 COPY0810
C NO COPY0820
C IS THE CURRENT INPUT UNIT THE SAME AS THE COPY0830
C PREVIOUS INPUT UNIT, AND IS THE FIRST INPUT FILE COPY0840
C TO BE LOCATED BY NAME? COPY0850
C YES, NO REWIND REQUIRED. GO TO POSITION INPUT BY COPY0860
C FILE NAME. COPY0870
C IF(IDTAPE.EQ.IDTAPX.AND.NUMVC.GT.0) GO TO 14 COPY0880
C NO COPY0890
C REWIND CURRENT INPUT UNIT. COPY0900
C REWIND IDTAPE COPY0910
C IS THE CURRENT INPUT UNIT THE SAME AS THE COPY0920
C PREVIOUS INPUT UNIT? COPY0930
C YES, ALL FILES ARE TO BE COPIED. GO TO READ COPY0940
C FIRST LABEL. COPY0950
C IF(IDTAPE.EQ.IDTAPX) GO TO 410 COPY0960
C THERE WAS AN INPUT UNIT CHANGE. REWIND PREVIOUS COPY0970
C INPUT UNIT. COPY0980
C REWIND IDTAPX COPY0990
C STORE CURRENT INPUT UNIT NUMBER AS PREVIOUS COPY1000
C INPUT UNIT NUMBER. COPY1010
C !DTAPX=IDTAPE COPY1020
C ARE ALL FILES ON CURRENT INPUT UNIT TO BE COPY1030
C COPIED? COPY1040
C YES, GO TO READ FIRST LABEL. COPY1050
C IF(NUMVC.EQ.(-1)) GO TO 410 COPY1060
C NO COPY1070
C CALL POSINP TO LOCATE NFILE. COPY1080
C IDTAPE,NFILE ARE INPUT ARGUMENTS. COPY1090
C NL,LABEL,KTYPE ARE RETURNED. COPY1100
C COPY1110
C COPY1120
C COPY1130

```
C 14 CALL POSINP(IDTAPE,KTYPE,NFILE,NL,LABEL)          COPY1140
      PRINT LABEL. WRITE LABEL ON OUTPUT UNIT.          COPY1150
C 15 PRINT 20,NFILE,(LABEL(I),I=1,NL)                  COPY1160
C 20 FORMAT(1H ,6A4/(1X,30A4))                      COPY1170
      WRITE(KOUT) KTYPE,NFILE,NL,(LABEL(I),I=1,NL)      COPY1180
C      ADD 1 TO NUMBER OF OUTPUT FILES.              COPY1190
C      NFILES=NFILES+1                                COPY1200
C      USE KTYPE FROM FILE LABEL TO BRANCH TO D, S, OR COPY1210
C      P COPY                                         COPY1220
C      GO TO (100,100,300),KTYPE                      COPY1230
C      D,S                                           COPY1240
C      READ A DATA RECORD FROM THE INPUT UNIT - INT*4 COPY1250
C      ELEMENT VALUES.                            COPY1260
C 100 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) COPY1270
C      WRITE THE DATA RECORD ON THE OUTPUT UNIT.      COPY1280
C      WRITE(KOUT) KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) COPY1290
C      WAS THIS A D,S,P END OF ARRAY RECORD?        COPY1300
C      YES. GO TO CHECK NUMBER OF FILES PROCESSED.   COPY1310
C      IF(KTYPE.GT.30) GO TO 400                     COPY1320
C          NO                                         CGPY1330
C          GO TO 100                                 COPY1340
C
C          P
C          READ AND WRITE ROW LIST RECORD.          COPY1350
C 300 READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR COPY1380
      WRITE(KOUT) KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR COPY1390
C          READ AND WRITE COLUMN LIST RECORD.       COPY1400
C          READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR COPY1410
      WRITE(KOUT) KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR COPY1420
          READ A DATA RECORD FROM THE INPUT UNIT - REAL*8 COPY1430
          ELEMENT VALUES.                            COPY1440
C 310 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT) COPY1450
C      WRITE THE DATA RECORD ON THE OUTPUT UNIT.      COPY1460
C      WRITE(KOUT) KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT) COPY1470
C      WAS THIS A D,S,P END OF ARRAY RECORD?        COPY1480
C      YES. GO TO CHECK NUMBER OF FILES PROCESSED.   COPY1490
C      IF(KTYPE.GT.30) GO TO 400                     COPY1500
C          NO                                         COPY1510
C          GO TO 310                                 COPY1520
C          YES                                         COPY1530
C          END OF ARRAY                           COPY1540
C          DECREASE NUMBER OF FILES TO BE COPIED BY 1. COPY1550
C 400 NUMVC=NUMVC-1                                  COPY1560
C          HAVE ALL SPECIFIED FILES BEEN COPIED?    COPY1570
C          YES. READ NEXT CONTROL CARD.             COPY1580
C          IF(NUMVC.EQ.0) GO TO 10                  COPY1590
C          NO                                         COPY1600
C          READ A D,S,P LABEL FROM THE INPUT UNIT.  COPY1610
C 410 READ(IDTAPE)KTYPE,NFILE,NL,(LABEL(I),I=1,NL)  COPY1620
C          WAS THIS A D,S,P END OF TAPE RECORD?     COPY1630
C          NO. GO TO LABEL PRINT.                   COPY1640
C          IF(KTYPE.NE.40) GO TO 15                COPY1650
C          YES                                         COPY1660
C          REWIND INPUT UNIT.                      COPY1670
C 430 REWIND IDTAPE                                COPY1680
C          GO TO READ A CONTROL CARD.            COPY1690
C          GO TO 10                                COPY1700
```

```
C           YES          COPY1710
C           BLANK CARD MEANS COPY OPERATION IS COMPLETE. COPY1720
C           ADD 1 TO THE OUTPUT UNIT NUMBER OF FILES COUNT. COPY1730
C
C   500 NFILES=NFILES+1          COPY1740
C     DD 501 I=1,6              COPY1750
C   501 NFILE(I)=KBLANK        COPY1760
C
C           WRITE A FLOMOD END RECORD ON THE OUTPUT TAPE. COPY1770
C           WRITE(KOUT) K40,NFILE,NFILL,NFILES            COPY1780
C           REWIND THE OUTPUT TAPE AND FINAL INPUT TAPE. COPY1790
C           REWIND KOUT                         COPY1800
C           REWIND IDTAPX                      COPY1810
C
C           RETURN                           COPY1820
C
C           RETURN                           COPY1830
C
C           REFERENCE LIST.                  COPY1840
C
C           SUBROUTINE ARGUMENTS.          COPY1850
C
C           ISN    - ARRAY FOR ROW OR COLUMN NUMBER LIST. COPY1890
C           ISVEC   - ARRAY FOR ROW OR COLUMN VALUES - INTEGER. COPY1900
C           P      - ARRAY FOR ROW OR COLUMN VALUES - REAL. COPY1910
C           LABEL   - ARRAY FOR FILE LABEL.          COPY1920
C
C
C           OTHER VARIABLES.             COPY1930
C
C           KPOS   - OUTPUT UNIT POSITIONING SPECIFICATION COPY1940
C             0 - START OUTPUT AT BEGINNING OF UNIT. COPY1950
C             1 - START OUTPUT AT END OF FILE RECORD. COPY1960
C
C           END                            COPY1970
C                                         COPY1980
C                                         COPY1990
C                                         COPY2000
```

SUBROUTINE DSPRNT(ISN,ISVEC,P,LABEL) DSP10010
C DSP10020
C D,S,P PRINT - FORMAT 1. DSP10030
C THIS IS A GENERAL PURPOSE PRINT FOR D AND P DSP10040
C MATRICES AND S VECTORS. ONLY THE ELEMENTS IN THE DSP10050
C TAPE RECORDS WILL BE PRINTED. THESE ELEMENTS DSP10060
C WILL USUALLY BE NON-ZERO, BUT ARRAYS GENERATED DSP10070
C BY CHANGE P OR SXP OPERATIONS MAY CONTAIN ZERO DSP10080
C ELEMENTS. DSP10090
C FOR EACH D OR P MATRIX ELEMENT PRESENT, THE ROW DSP10100
C NUMBER, COLUMN NUMBER, AND VALUE WILL BE PRINTED DSP10110
C FOR EACH S VECTOR ELEMENT PRESENT, THE STATE DSP10120
C NUMBER AND VALUE WILL BE PRINTED. DSP10130
C PRINTS 5 ELEMENTS PER LINE. DSP10140
C DSP10150
C DSP10160
C DSP10170
C ONE CONTROL CARD IS REQUIRED FOR EACH SET OF DSP10180
C CONSECUTIVE ARRAYS-ON AN INPUT UNIT-THE ARE TO DSP10190
C BE PRINTED. DSP10200
C A BLANK CONTROL CARD IS USED TO RETURN CONTROL DSP10210
C TO THE CALLING PROGRAM. DSP10220
C THE CONTROL CARD FIELDS ARE DSP10230
C IDTAPE - COL 1-6 (I6) FORTRAN INPUT UNIT NUMBER. DSP10240
C NFILE ~ COL 7-30 (6A4) ARRAY NAME OF FIRST OF DSP10250
C 'NUMVC' FILES TO BE PRINTED UNDER DSP10260
C CONTROL OF THIS CARD. DSP10270
C NUMVC - COL 31-36 (I6) DSP10280
C +N = THE NUMBER OF CONSECUTIVE ARRAYS DSP10290
C TO BE PRINTED FROM 'IDTAPE' DSP10300
C STARTING WITH ARRAY 'NFILE'. DSP10310
C 0 = PRINT OPERATION COMPLETED. RETURN. DSP10320
C -1 = PRINT ALL ARRAYS ON THE TAPE. DSP10330
C -2 = PRINT THE LABELS ONLY FOR ALL DSP10340
C ARRAYS ON THE TAPE. DSP10350
C DSP10360
C IMPLICIT REAL*8(A-H,O-Z,\$) DSP10370
C DIMENSION ISN(1),ISVEC(1),P(1),LABEL(1),NFILE(6) DSP10380
C DATA MBLANK/4H /,MCNT/4HC / DSP10390
C READ 11, IDTAPE,NFILE,NUMVC DFDSP10400
C RFAD INPUT UNIT NUMBER, ARRAY NAME AND NUMBER OF DSP10410
C ARRAYS FROM FIRST CONTROL CARD. DSP10420
C READ 11, IDTAPE,NFILE,NUMVC DFDSP10430
C STORE UNIT NUMBER IN IDSAVE. DSP10440
C IDSAVE=IDTAPE DSP10450
C GO TO 12
C READ INPUT UNIT NUMBER, ARRAY NAME AND NUMBER OF DF DSP10460
C ARRAYS FOR ALL CONTROL CARDS EXCEPT THE FIRST. DSP10470
C 10 READ 11, IDTAPE,NFILE,NUMVC DF DSP10480
C IF CARD IS BLANK, PRINT OPERATION IS COMPLETE. DSP10490
C 12 IF(NUMVC.EQ.0) RETURN DSP10500
C CONTINUE WITH PRINT OPERATION. DSP10510
C IS THE SAVED NUMBER EQUAL THE CURRENT UNIT DSP10520
C NUMBER? DSP10530
C IF(IDSAVE.EQ.IDTAPE) GO TO 13 DSP10540
C NO DSP10550

C	REWIND IDSAVE	REWIND UNIT IN PREVIOUS CARD.	DSP10560
C	IDSAVE=IDTAPE	STORE LATEST UNIT NUMBER IN IDSAVE.	DSP10570
C		YES - SAVED UNIT NUMBER EQUALS CURRENT UNIT NUMBER.	DSP10580
C		IS THE EXACT NUMBER OF ARRAYS TO BE PRINTED SPECIFIED?	DSP10590
C	13 IF(NUMVC.GT.0) GO TO 14		DSP10600
C		NO	DSP10610
C		ALL ARRAYS ON THE TAPE ARE TO BE PROCESSED.	DSP10620
C	REWIND IDTAPE	REWIND IDTAPE	DSP10630
C		ARE THE ARRAY DATA RECORDS TO BE PRINTED?	DSP10640
C		YES. GO TO READ FIRST LABEL.	DSP10650
C	IF(NUMVC.EQ.(-1)) GO TO 410		DSP10660
C		NO	DSP10670
C		PRINT LABELS ONLY.	DSP10680
C	GO TO 500		DSP10690
C		YES	DSP10700
C		EXACT NUMBER OF ARRAYS SPECIFIED.	DSP10710
C		CALL POSINP TO POSITION TO NAMED ARRAY.	DSP10720
C		IDTAPE,NFILE ARE INPUT ARGUMENTS.	DSP10730
C		NL,LABEL,KTYPE ARE RETURNED.	DSP10740
C	14 CALL POSINP(IDTAPE,KTYPE,NFILE,NL,LABEL)		DSP10750
C		USE KTYPE FROM FILE LABEL TO BRANCH TO D, S, OR P PRINT.	DSP10760
C		BRANCH ON ARRAY TYPE.	DSP10770
C	15 GO TO (100,200,300),KTYPE		DSP10780
C		D MATRIX.	DSP10790
C	100 CONTINUE	INITIALIZE KSKIP SO THAT THE FIRST DATA RECORD WILL BE READ.	DSP10800
C	KSKIP=1	COMPUTE NUMBER OF PRINT LINES USED FOR HEADING.	DSP10810
C	110 LCUR=NL/30+4	PRINT D MATRIX NAME AND LABEL.	DSP10820
C	112 PRINT 20,NFILE,(LABEL(I),I=1,NL)	PRINT HEADING FOR D ELEMENTS.	DSP10830
C	PRINT 101	BRANCH ON KSKIP.	DSP10840
C	GO TO (120,124,130),KSKIP		DSP10850
C	KSKIP=1		DSP10860
C		READ A RECORD.	DSP10870
C	120 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT)	IS THIS AN END RECORD?	DSP10880
C	IF(KTYPE.GT.30) GO TO 400		DSP10890
C		NO	DSP10900
C		SET CONTINUE FIELD TO A BLANK CHARACTER.	DSP10910
C	MPRINT=MBLANK	COMPUTE L, NUMBER OF LINES REQUIRED TO PRINT D ROW JUST READ.	DSP10920
C	L=(ICNT-1)/5+1	WILL THIS ROW REQUIRE MORE LINES THAN ARE AVAILABLE ON THE CURRENT PAGE?	DSP10930
C	124 IF(LCUR+L+1.GT.60) GO TO 140		DSP10940
			DSP10950
			DSP10960
			DSP10970
			DSP10980
			DSP10990
			DSP11000
			DSP11010
			DSP11020
			DSP11030
			DSP11040
			DSP11050
			DSP11060
			DSP11070
			DSP11080
			DSP11090
			DSP11100
			DSP11110
			DSP11120

C NO DSP11130
C SET INDEX VALUES FOR PRINT STATEMENT SO THAT ALL DSP11140
C ELEMENTS IN THE ROW WILL BE PRINTED. DSP11150
C
126 IFR=1 DSP11160
ITO=ICNT DSP11170
C UPDATE NUMBER OF PRINT LINES USED. DSP11180
LCUR=LCUR+L+1 DSP11190
C
PRINT ROW NUMBER, CONTINUE FIELD AND IFR THRU DSP11200
ITO ELEMENTS OF ROW. DSP11210
C
130 PRINT 102,IROW,MPRINT,(ISN(I),ISVEC(I),I=IFR,ITO) DSP11220
C
IF THE NUMBER OF ELEMENTS FOR A ROW ON A PAGE IS DSP11230
5, THE FORMAT FOR THE ROW PRINT WILL SPACE AFTER DSP11240
THIS LINE IS PRINTED. DSP11250
C
IF THE NUMBER OF ELEMENTS FOR A ROW ON A PAGE IS DSP11260
NOT 5, THE FORMAT FOR THE ROW PRINT WILL NOT DSP11270
SPACE AFTER THE LINE IS PRINTED. DSP11280
C
ADJUST THE NUMBER OF PRINT LINES USED IF DSP11290
NECESSARY. DSP11300
C
IF(IFCNT.EQ.5.OR.(ITO-IFR+1).EQ.5) LCUR=LCUR+1 DSP11310
C
ARE THERE ELEMENTS IN THIS ROW WHICH HAVE NOT DSP11320
YET BEEN PRINTED? DSP11330
C
IF(ITO.NE.ICNT) GO TO 150 DSP11340
NO - GO TO READ A RECORD.
C
GO TO 120
C
140 DSP11350
SPACE ON CURRENT PAGE NOT ADEQUATE FOR ENTIRE DSP11360
ROW. DSP11370
C
ROW FORMAT SPACES BEFORE FIRST PRINT LINE. DSP11380
THEREFORE IF ONLY ONE PRINT LINE IS AVAILABLE, DSP11390
NO DATA ELEMENTS FOR THE CURRENT ROW WILL BE DSP11400
PRINTED ON THE CURRENT PAGE. DSP11410
C
IS THERE SPACE ON THE CURRENT PAGE FOR ANY OF DSP11420
THE CURRENT ROW? DSP11430
C
140 IF(LCUR.GE.59) GO TO 160 DSP11440
C
YES DSP11450
C
SPLIT THE ROW. DSP11460
C
SET INDEX VALUES FOR PRINTING FIRST SEGMENT OF DSP11470
THE ROW SO THAT AS MANY ELEMENTS AS POSSIBLE DSP11480
WILL BE PRINTED ON THE CURRENT PAGE. DSP11490
C
IFR=1 DSP11500
ITO=(60-(LCUR+1))+5 DSP11510
C
GO TO 130 DSP11520
C
SET INDEX VALUES FOR ADDITIONAL SEGMENT. DSP11530
SET CONTINUE FIELD TO THE CHARACTER C. DSP11540
C
150 MPRINT=MCONT DSP11550
C
LCUR=NL/30+4 DSP11560
C
RESET LCUR TO NUMBER OF LINES HEADING REQUIRES. DSP11570
C
DSP11580
C
SET INDEX VALUES FOR PRINT STATEMENT SO THAT DSP11590
START WITH ELEMENT ITO + 1 AND CONTINUE THRU THE DSP11600
ELEMENT WHOSE SUBSCRIPT IS (1) THE MAXIMUM TO DSP11610
VALUE FOR A FULL PAGE OR (2) THE MAXIMUM DSP11620
SUBSCRIPT FOR THIS ROW - WHICHEVER IS SMALLER. DSP11630
C
IFR=ITO+1 DSP11640
C
DSP11650
C
DSP11660
C
DSP11670

```
ITO=IFR+(60-(LCUR+1))*5-1 DSP11680
IF(ITO.GT.ICNT) ITO=ICNT DSP11690
C SET LCUR = LAST PRINT LINE THAT WILL BE PRINTED DSP11700
C WITH INDEX VALUES JUST SET. DSP11710
C LCUR=LCUR+(ITO-IFR)/5+2 DSP11720
C SET KSKIP TO INDICATE CONTINUATION OF SPLIT ROW DSP11730
C BEING PRINTED. DSP11740
C KSKIP=3 DSP11750
C GO TO 112 DSP11760
C 160 DSP11770
C THERE IS NO SPACE ON THE CURRENT PAGE FOR ANY OF DSP11790
C THE CURRENT ROW. DSP11800
C SET KSKIP TO INDICATE START NEW PAGE AND NEW ROW DSP11810
C 160 KSKIP=2 DSP11820
C GO TO 110 DSP11830
C 160 DSP11840
C S VECTOR DSP11850
C L - NUMBER OF LINES REQUIRED TO PRINT ENTIRE S. DSP11860
C READ S DATA RECORD. DSP11870
C 200 READ(IDTAPE)KTYPE,NFILL,ICNT,(ISNM(I),I=1,ICNT),(ISVEC(I),I=1,ICNT)DSP11900
C COMPUTE LCUR, NUMBER OF LINES REQUIRED FOR LABEL DSP11910
C HEADING. DSP11920
C LCUR=NL/30+5 DSP11930
C COMPUTE NUMBER OF LINES REQUIRED FOR THIS S DSP11940
C VECTOR. DSP11950
C L=(ICNT-1)/5+1 DSP11960
C WILL THIS BE A MULTI-PAGE PRINT? DSP11970
C IF((LCUR+L).GT.60) GO TO 205 DSP11980
C NO DSP11990
C SET PRINT STATEMENT SUBSCRIPT RANGE FOR SINGLE DSP12000
C PAGE S. DSP12010
C IFR=1 DSP12020
C ITO=ICNT DSP12030
C SET LCUR = LAST PRINT LINE THAT WILL BE PRINTED DSP12040
C BY THESE INDEX VALUES. DSP12050
C LCUR=LCUR+L DSP12060
C GO TO 235 DSP12070
C 205 DSP12080
C YES DSP12090
C THIS WILL BE A MULTI-PAGE PRINT. DSP12100
C INITIALIZE SUBSCRIPT VALUE FOR FIRST PAGE OF DSP12110
C MULTI-PAGE S. DSP12120
C 205 ITO=0 DSP12130
C SET SUBSCRIPT RANGE FOR EACH PAGE OF A MULTI- DSP12140
C PAGE S. DSP12150
C 215 IFR=ITO+1 DSP12160
C ITO=(60-LCUR)*5+IFR-1 DSP12170
C IF(ITO.GT.ICNT) ITO=ICNT DSP12180
C SET LCUR = LAST PRINT LINE THAT WILL BE PRINTED DSP12190
C BY THESE INDEX VALUES. DSP12200
C LCUR=LCUR+(ITO-IFR)/5+1 DSP12210
C PRINT A PAGE. DSP12220
C PRINT S NAME, LABEL AND HEADING FOR ELEMENTS. DSP12230
C DSP12240
```

```
235 PRINT 20,NFILE,(LABEL(I),I=1,NL) DSP12250
      PRINT 210 DSP12260
C           PRINT ELEMENTS SPECIFIED BY CURRENT INDEX DSP12270
C           SETTINGS. DSP12280
C           PRINT 230,(ISN(I),ISVEC(I),I=IFR,ITO) DSP12290
C           WERE ALL ELEMENTS PRINTED? DSP12300
C           IF(ITO.EQ.ICNT) GO TO 245 DSP12310
C           NO DSP12320
C           RESET LCUR TO NUMBER OF LINES REQUIRED FOR LABEL DSP12330
C           AND HEADING. DSP12340
C           LCUR=NL/30+5 DSP12350
C           GO TO 215 DSP12360
C           YES - ALL ELEMENTS HAVE BEEN PRINTED FOR THIS S. DSP12380
C           READ S VECTOR SUM FROM END RECORD. DSP12390
245 READ(IDTAPE)KTYPE,NFILL,NFILL,ISUM DSP12400
C           IF THERE IS NO SPACE ON THE CURRENT PAGE FOR THE DSP12410
C           SUM, SKIP TO A NEW PAGE AND PRINT THE S NAME AND DSP12420
C           LABEL. DSP12430
C           IF(LCUR+3.GT.60) PRINT 20,NFILE,(LABEL(I),I=1,NL) DSP12440
C           PRINT THE S VECTOR SUM. DSP12450
C           PRINT 250,ISUM DSP12460
C           GO TO 400 DSP12470
C           P MATRIX DSP12480
C           ***DSP12490
C           *DSP12500
C           P MATRIX DSP12510
300 CONTINUE DSP12520
C           PRINT P MATRIX NAME, LABEL, ROW LIST, MODSW, DSP12530
C           MODFAC, COLUMN LIST, NUMMO, NUMYR. DSP12540
C           PRINT 20,NFILE,(LABEL(I),I=1,NL) DSP12550
C           READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),MODSW,MODFAC DSP12560
C           PRINT 303,ICNT,MODSW,MODFAC,(ISN(I),I=1,ICNT) DSP12570
C           READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR DSP12580
C           PRINT 304,ICNT,NUMMO,NUMYR ,(ISN(I),I=1,ICNT) DSP12590
C           PROCESS P ROW RECORDS. DSP12600
C           INITIALIZE KSKIP SO THAT THE FIRST DATA RECORD DSP12610
C           WILL BE READ. DSP12620
C           KSKIP=1 DSP12630
C           COMPUTE NUMBER OF PRINT LINES USED FOR HEADING. DSP12640
310 LCUR=NL/30+4 DSP12650
C           PRINT P MATRIX NAME AND LABEL. DSP12660
C           312 PRINT 20,NFILE,(LABEL(I),I=1,NL) DSP12670
C           PRINT HEADING FOR P ELEMENTS. DSP12680
C           PRINT 301 DSP12690
C           BRANCH ON KSKIP. DSP12700
C           GO TO (320,324,330),KSKIP DSP12710
C           KSKIP = 1 DSP12720
C           READ A RECORD DSP12730
C           320 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT) DSP12740
C           IS THIS AN END RECORD? DSP12750
C           IF(KTYPE.GT.30) GO TO 400 DSP12760
C           NO DSP12770
C           SET CONTINUE FIELD TO A BLANK CHARACTER. DSP12780
C           MPRINT=MBLANK DSP12790
C           COMPUTE L, NUMBER OF LINES REQUIRED TO PRINT P DSP12800
C
```

C ROW JUST READ. DSP12820
C L=(ICNT-1)/5+1 DSP12830
C WILL THIS ROW REQUIRE MORE LINES THAN ARE DSP12840
C AVAILABLE ON THE CURRENT PAGE? DSP12850
C 324 IF(LCUR+L+1.GT.60) GO TO 340 DSP12860
C NO DSP12870
C SET INDEX VALUES FOR PRINT STATEMENT SO THAT ALL DSP12880
C ELEMENTS IN THE ROW WILL BE PRINTED. DSP12890
C 326 IFR=1 DSP12900
C ITO=ICNT DSP12910
C UPDATE NUMBER OF PRINT LINES USED. DSP12920
C LCUR=LCUR+L+1 DSP12930
C PRINT ROW NUMBER, CONTINUE FIELD AND IFR THRU DSP12940
C ITO ELEMENTS OF ROW. DSP12950
C 330 PRINT 302,IROW,MPRINT,(ISN(I),P(I),I=IFR,IT0) DSP12960
C DSP12970
C IF THE NUMBER OF ELEMENTS FOR A ROW ON A PAGE IS DSP12990
C 5, THE FORMAT FOR THE ROW PRINT WILL SPACE AFTER DSP13000
C THIS LINE IS PRINTED. DSP13010
C IF THE NUMBER OF ELEMENTS FOR A ROW ON A PAGE IS DSP13020
C NOT 5, THE FORMAT FOR THE ROW PRINT WILL NOT DSP13030
C SPACE AFTER THE LINE IS PRINTED. DSP13040
C ADJUST THE NUMBER OF PRINT LINES USED IF DSP13050
C NECESSARY. DSP13060
C IF(ICNT.EQ.5.OR.(IT0-IFR+1).EQ.5) LCUR=LCUR+1 DSP13070
C DSP13080
C ARE THERE ELEMENTS IN THIS ROW WHICH HAVE NOT DSP13090
C YET BEEN PRINTED? DSP13100
C IF(IT0.NE.ICNT) GO TO 350 DSP13110
C NO DSP13120
C GO TO READ A RECORD. DSP13130
C GO TO 320 DSP13140
C DSP13150
C SPACE ON CURRENT PAGE NOT ADEQUATE FOR ENTIRE DSP13160
C ROW. DSP13170
C ROW FORMAT SPACES BEFORE FIRST PRINT LINE. DSP13180
C THEREFORE IF ONLY ONE PRINT LINE IS AVAILABLE, DSP13190
C NO DATA ELEMENTS FOR THE CURRENT ROW WILL BE DSP13200
C PRINTED ON THE CURRENT PAGE. DSP13210
C IS THERE SPACE ON THE CURRENT PAGE FOR ANY OF DSP13220
C THE CURRENT ROW... DSP13230
C 340 IF(LCUR.GE.59) GO TO 360 DSP13240
C YES DSP13250
C SPLIT THE ROW. DSP13260
C SET INDEX VALUES FOR PRINTING FIRST SEGMENT OF DSP13270
C THE ROW SO THAT AS MANY ELEMENTS AS POSSIBLE DSP13280
C WILL BE PRINTED ON THE CURRENT PAGE. DSP13290
C IFR=1 DSP13300
C ITO=(60-(LCUR+1))*5 DSP13310
C GO TO PRINT STATEMENT. DSP13320
C GO TO 330 DSP13330
C SET INDEX VALUES FOR ADDITIONAL SEGMENT. DSP13340
C SET CONTINUE FIELD TO THE CHARACTER C. DSP13350
C 350 MPRINT=MCONT DSP13360
C LCUR=N/30+4 DSP13362
C DSP13364

C SET INDEX VALUES FOR PRINT STATEMENT SO THAT DSP13370
C START WITH ELEMENT ITO + 1 AND CONTINUE THRU THEDSP13380
C ELEMENT WHOSE SUBSCRIPT IS (1) THE MAXIMUM TO DSP13390
C VALUE FOR A FULL PAGE OR (2) THE MAXIMUM DSP13400
C SUBSCRIPT FOR THIS ROW - WHICHEVER IS SMALLER. DSP13410
C
IFR=ITO+1 DSP13420
ITO=IFR+(60-(LCUR+1))*5-1 DSP13430
IF(ITO.GT.ICNT) ITO=ICNT DSP13440
C SET LCUR = LAST PRINT LINE THAT WILL BE PRINTED DSP13450
C WITH INDEX VALUES JUST SET. DSP13460
LCUR=LCUR+(ITO-IFR)/5+2 DSP13470
C SET KSKIP TO INDICATE CONTINUATION OF SPLIT ROW DSP13480
C BEING PRINTED. DSP13490
KSKIP=3 DSP13500
GO TO 312 DSP13510
C NO - THERE IS NO SPACE ON CURRENT PAGE FOR ANY DSP13530
C OF CURRENT ROW. DSP13540
SET KSKIP TO INDICATE START NEW PAGE AND NEW ROWDSP13550
360 KSKIP=2 DSP13560
GO TO 310 DSP13570
DSP13580
*DSP13590
***DSP13600
C
400 DSP13610
END OF ARRAY DSP13620
DECREASE NUMBER OF ARRAYS TO BE PROCESSED BY DSP13630
C ONE. DSP13640
DSP13650
400 NUMVC=NUMVC-1 DSP13660
HAVE ALL REQUESTED ARRAYS BEEN PROCESSED? DSP13670
YES. GO TO READ NEXT CONTROL CARD. DSP13680
IF(NUMVC.EQ.0) GO TO 10 DSP13690
NO. READ NEXT LABEL. DSP13700
410 READ(IDTAPE)KTYPE,NFILE,NL,(LABEL(I),I=1,NL) DSP13710
IS THIS A BEGINNING OF ARRAY LABEL? DSP13720
YES. GO TO BRANCH ON ARRAY TYPE. DSP13730
IF(KTYPE.NE.40) GO TO 15 DSP13740
NO DSP13750
REWIND TAPE. DSP13760
430 REWIND IDTAPE DSP13770
GO TO 10 DSP13780
C
PRINT ALL LABELS. DSP13790
SKIP TO A NEW PAGE. DSP13800
500 PRINT 505, IDTAPE DSP13810
DIMENSION MTYPE(4)
DATA MTYPE/16HD...S...P...END./ DSP13820
C INITIALIZE COUNT OF NUMBER OF LINES PRINTED. DSP13830
LCUR=0 DSP13840
READ A LABEL. DSP13850
510 READ(IDTAPE)KTYPE,NFILE,NL,(LABEL(I),I=1,NL) DSP13860
INITIALIZE RECORD COUNT FOR THIS ARRAY. DSP13870
NR=1 DSP13880
K=KTYPE DSP13890
SET K = KTYPE FOR SUBSCRIPT USE IN PRINT. DSP13900
DSP13910
DSP13920
DSP13930

C WAS THE LABEL JUST READ AN END OF FILE LABEL? DSP13940
C IF(KTYPE.EQ.40) GO TO 550 DSP13950
C NO DSP13960
C UPDATE NUMBER OF LINES COUNT. DSP13970
C LCUR=LCUR+NL/30+3 DSP13980
C IS THERE SPACE ON CURRENT PAGE FOR LABEL AND DSP13990
C RECORD COUNT... DSP14000
C IF(LCUR.LE.60) GO TO 518 DSP14010
C NO - START NEW PAGE. DSP14020
C PRINT 505,1DTAPE DSP14030
C RESET NUMBER OF LINES COUNT. DSP14040
C LCUR=NL/30+3 DSP14050
C YES. DSP14060
C THERE IS SPACE ON CURRENT PAGE FOR LABEL AND DSP14070
C RECORD COUNT. DSP14080
C PRINT LABEL. DSP14090
C 518 PRINT 506,MTYPE(K),NFILE,(LABEL(I),I=1,NL) DSP14100
C READ TYPE FIELD ONLY FROM NEXT RECORD. DSP14110
C 530 READ(1DTAPE)KTYPE DSP14120
C COUNT THIS RECORD. DSP14130
C NR=NR+1 DSP14140
C WAS THE RECORD JUST READ A DATA RECORD? DSP14150
C YES. GO TO READ NEXT RECORD. DSP14160
C IF(KTYPE.LT.31) GO TO 530 DSP14170
C NO DSP14180
C PRINT NR, NUMBER OF RECORDS FOR THIS ARRAY. DSP14190
C PRINT 540,NR DSP14200
C GO TO READ NEXT LABEL. DSP14210
C GO TO 510 DSP14220
C YES DSP14230
C END RECORD DSP14240
C SET K = 4 TO PRINT ARRAY TYPE 'END'. DSP14250
C 550 K=4 DSP14260
C PRINT ARRAY TYPE AND FILE NUMBER OF THIS END DSP14270
C RECORD. DSP14280
C PRINT 560,MTYPE(K),LABEL(1) DSP14290
C GO TO REWIND INPUT UNIT. DSP14300
C GO TO 430 DSP14310
C DSP14320
C 11 FORMAT(I6,6A4,I6) DSP14330
C 20 FORMAT(1H1,6A4/ (1X,30A4)) DSP14340
C 101 FORMAT(/132H FROM TO NUMBER TO TO NDSP14350
C NUMBER TO NUMBER TO NUMBER TO TO DSP14360
C 2 NUMBER / DSP14370
C 3 132H STATE STATE OF CASES STATE STATE OF DSP14380
C 4 CASES STATE OF CASES STATE OF CASES STATE DSP14390
C 5 OF CASES) DSP14400
C 102 FORMAT(/I12,A1,I11,9I12/ (12X,10I12)) DSP14410
C 210 FORMAT(/12X, 114H STATE NUMBER STATE NUMBER DSP14420
C 1 STATE NUMBER STATE NUMBER STATE NUMBER DSP14430
C 2/22X,8HOF CASES,16X,8HOF CASES,16X,8HOF CASES,16X, DSP14440
C 38HOF CASES/) DSP14450
C 230 FORMAT(6X,10I12) DSP14460
C 250 FORMAT(/105X,9H TOTAL = ,I12) DSP14470
C 301 FORMAT(/132H FROM TO PROBABILITY TO PROBADSP14480
C 1BILITY TO PROBABILITY TO PROBABILITY TO DSP14490
C 2 PROBABILITY/ DSP14500

3	132H	STATE	STATE	STATE	DSP14510
4		STATE	STATE	STATE	STATE DSP14520
5)				DSP14530
302	FORMAT(/I12,A1,I11,F12.6,4(I12,F12.6)/ (12X,5(I12,F12.6)))				DSP14540
303	FORMAT(/28H NUMBER OF ROW LIST·ENTRIES ,I12				DSP14550
1	/14H MODIFY SWITCH,I12				DSP14560
2	/14H MODIFY FACTOR,I12//12H ROW NUMBERS/				DSP14570
3	/(6X,10I12))				DSP14580
304	FORMAT(/30H NUMBER OF COLUMN LIST ENTRIES ,I12				DSP14590
1	/22H SXP INCREMENT MONTHS ,I12				DSP14600
2	/22H SXP INCREMENT YEARS ,I12//16H COLUMN NUMBERS /				DSP14610
3	/(6X,10I12))				DSP14620
505	FORMAT(24H1LIST OF LABELS ON UNIT ,I6)				DSP14630
506	FORMAT(/1X,A4,6A4/ (1X,30A4))				DSP14640
540	FORMAT(44H THE TOTAL NUMBER OF RECORDS IN THIS FILE = ,I12)				DSP14650
560	FORMAT(/1X,A4,12HFILE NUMBER ,I6)				DSP14660
C					DSP14670
C		REFERENCE LIST.			DSP14680
C					DSP14690
C		SUBROUTINE ARGUMENTS.			DSP14700
C					DSP14710
C	ISN	- ARRAY FOR COLUMN NUMBERS IN A D ROW. ELEMENT NUMBERS IN AN S VECTOR, P MATRIX ROW LIST, P MATRIX COLUMN LIST AND COLUMN NUMBERS IN A P ROW.			DSP14720
C					DSP14730
C					DSP14740
C	ISVEC	- ARRAY FOR COLUMN VALUES IN A D ROW - OR - ELEMENT VALUES IN AN S VECTOR.			DSP14750
C					DSP14760
C	P	- ARRAY FOR COLUMN VALUES IN A P ROW.			DSP14770
C	LABEL	- ARRAY FOR D, S, AND P LABELS.			DSP14780
C					DSP14790
C		OTHER VARIABLES.			DSP14800
C					DSP14810
C	LCUR	- NUMBER OF LINES PRINTED ON CURRENT PAGE.			DSP14820
C	60	- MAXIMUM NUMBER OF LINES TO BE PRINTED. ON LINES 4-63.			DSP14830
C	KSKIP	- 1...READ A RECORD. 2...DON'T READ. PRINT ENTIRE ROW OF LAST READ. 3...DON'T READ. CONTINUE PRINTING OF SPLIT ROW.			DSP14840
C					DSP14850
C					DSP14860
C					DSP14870
C	END				DSP14880

```
SUBROUTINE DSPRN2          DSP20010
1      (ISN,ISVEC,P,LABEL,   DSP20020
2      NAMEV,NAMEC,NCODE,LOC,ICODE,LIST)   DSP20030
C
C      IMPLICIT REAL*8(A-H,O-Z,$)   DSP20040
C
C      CALLS POSINP   DSP20050
C
C      D,S,P PRINT - FORMAT 2.   DSP20060
C
C      THIS IS A GENERAL PURPOSE PRINT FOR D AND P   DSP20070
C      MATRICES AND S VECTORS. ONLY THE NON-ZERO   DSP20080
C      ELEMENTS IN THE TAPE RECORDS WILL BE PRINTED.   DSP20090
C      FOR EACH D OR P MATRIX ELEMENT, THE ROW   DSP20100
C      NUMBER, COLUMN NUMBER, AND VALUE WILL BE PRINTED.   DSP20110
C      THE MEANING OF THE CODES USED IN GENERATING EACH   DSP20120
C      ROW NUMBER AND EACH COLUMN NUMBER WITHIN EACH   DSP20130
C      ROW WILL ALSO BE PRINTED.   DSP20140
C      FOR EACH S VECTOR ELEMENT, THE STATE   DSP20150
C      NUMBER, VALUE AND MEANING OF THE CODES USED IN   DSP20160
C      GENERATING THE STATE NUMBER WILL BE PRINTED.   DSP20170
C
C      REQUIRES ONE TO 5 PRINT LINES PER ELEMENT.   DSP20180
C
C      ONE CONTROL CARD IS REQUIRED FOR EACH SET OF   DSP20190
C      CONSECUTIVE ARRAYS-ON AN INPUT UNIT-THE ARE TO   DSP20200
C      BE PRINTED.   DSP20210
C      A BLANK CONTROL CARD IS USED TO RETURN CONTROL   DSP20220
C      TO THE CALLING PROGRAM.   DSP20230
C      THE CONTROL CARD FIELDS ARE   DSP20240
C      IDTAPE - COL 1-6 (I6) FORTRAN INPUT UNIT NUMBER.   DSP20250
C      NFILE - COL 7-30 (6A4) ARRAY NAME OF FIRST OF   DSP20260
C              'NUMVC' FILES TO BE PRINTED UNDER   DSP20270
C              CONTROL OF THIS CARD.   DSP20280
C      NUMVC - COL 31-36 (I6)
C              +N = THE NUMBER OF CONSECUTIVE ARRAYS   DSP20290
C              TO BE PRINTED FROM 'IDTAPE'   DSP20300
C              STARTING WITH ARRAY 'NFILE'.   DSP20310
C              0 = PRINT OPERATION COMPLETED. RETURN.   DSP20320
C              -1 = PRINT ALL ARRAYS ON THE TAPE.   DSP20330
C
C      DIMENSION NAMEV(3*NV),NAMEC(SUM OF NCODE(I)*3),NCODE(NV),LOC(NV+1)   DSP20340
C              ICODE(NV),LIST(3*NV)   DSP20350
C      DIMENSION NAMEV(1),NAMEC(1),NCODE(1),LOC(1),ICODE(1),LIST(1)   DSP20360
C      DIMENSION ISN(1),ISVEC(1),P(1),LABEL(1),NFILE(6)   DSP20370
C      DIMENSION MULT(30)   DSP20380
C      DATA NRROW/4HROW /,NCOL/4HCOL /   DSP20390
C
C      READ 90,NV           READ NUMBER OF VARIABLES.   DSP20400
C
C      INITIALIZE FOR LATER USE IN THE PROGRAM.   DSP20410
C      NUMBER OF VARIABLES MINUS ONE.   DSP20420
C
C      NVM1=NV-1           DSP20430
```

C NUMBER OF VARIABLES TIMES THREE. DSP20570
C NV3=NV*3 DSP20580
C ***DSP20590
C *DSP20600
C SET UP ARRAYS CONTAINING CODE DESCRIPTIONS OF THE DSP20610
C VARIABLES USED TO DEFINE THE MODEL. DSP20620
C SET CODE NAME ARRAY SUBSCRIPT FOR FIRST VARIABLE DSP20630
C LOC(1)=1 DSP20640
C FOR EACH VARIABLE.. DSP20650
C DO 2 I=1,NV DSP20660
C COMPUTE SUBSCRIPTS FOR I'TH VARIABLE IN NAME OF DSP20670
C VARIABLE VECTOR. DSP20680
C IFR=(I-1)*3+1 DSP20690
C ITO=IFR+2 DSP20700
C READ VARIABLE NUMBER, VARIABLE NAME AND NUMBER DSP20710
C OF CODES DEFINED FOR THIS VARIABLE. DSP20720
C READ 90,INV,(NAMEV(I)),II=IFR,ITO),NCODE(I) DSP20730
C IS THE VARIABLE NUMBER READ EQUAL THE DO LOOP DSP20740
C VARIABLE NUMBER? DSP20750
C IF(INV.EQ.I) GO TO 4 DSP20760
C NO DSP20770
C PRINT 92,I,INV DSP20780
C EXIT. DSP20790
C STOP DSP20800
C YES DSP20810
C 4 NCI=NCODE(I) DSP20820
C STORE IN ARRAY 'LOC' THE BEGINNING LOCATION IN DSP20830
C NAME OF CODES ARRAY OF THE CODE NAMES FOR THE DSP20840
C NEXT VARIABLE. DSP20850
C LOC(I+1)=LOC(I)+NCI*3 DSP20860
C INITIALIZE SUBSCRIPT FOR READING I'TH VARIABLE DSP20870
C CODE NAMES. DSP20880
C JFR=LOC(I)-3 DSP20890
C **DSP20900
C *DSP20930
C DO 1 J=1,NCI DSP20940
C COMPUTE SUBSCRIPTS FOR NAME OF CODE VECTOR. DSP20950
C JFR=JFR+3 DSP20960
C JTO=JFR+2 DSP20970
C READ CODE NUMBER AND NAME. DSP20980
C READ 90,INC,(NAMEC(JJ),JJ=JFR,JTO) DSP20990
C IS THE CODE NUMBER READ EQUAL TO DO LOOP CODE DSP21000
C NUMBER? DSP21010
C IF(INC.EQ.J) GO TO 1 DSP21020
C NO DSP21030
C PRINT 92,I,INV,J,INC DSP21040
C EXIT. DSP21050
C STOP DSP21060
C 1 DSP21070
C YES DSP21080
C CONTINUE DSP21090
C 1 CONTINUE DSP21100
C DSP21110
C DSP21120
C DSP21130

```
C *DSP21140
C **DSP21150
C DSP21160
C DSP21170
C DSP21180
C *DSP21190
C ***DSP21200
C DSP21210
C GENERATE THE MULTIPLY FACTORS USED IN DECODING ADSP21220
C STATE NUMBER INTO ITS ORIGINAL CODE VALUES. DSP21230
C MULT(NV)=1 DSP21240
C IF(NV.EQ.1) GO TO 5 DSP21245
C NV=NV
C DO 3 I=1,NVM1 DSP21250
C MULT(N-1)=MULT(N)*NCODE(N) DSP21260
C 3 N=N-1 DSP21270
C COMPUTE NUMBER OF PRINT LINES REQUIRED PER DSP21290
C DESCRIPTION FOR THE CURRENT MODEL. THIS VALUE IS DSP21310
C A FUNCTION OF THE NUMBER OF VARIABLES USED TO DSP21320
C DEFINE THE MODEL. THIS VALUE WILL BE USED FOR D,DSP21330
C S AND P ARRAYS. DSP21340
C 5 NLINES=(NV-1)/7+1 DSP21350
C IF THE NUMBER OF VARIABLES IS EXACTLY SEVEN, DSP21360
C THERE WILL BE AN EXTRA SPACE AFTER THE DSP21370
C PRINT HEADING AND AFTER EACH STATE NUMBER DSP21380
C DESCRIPTION. DSP21390
C ADJUST THE NUMBER OF LINES PER DESCRIPTION IF DSP21400
C NECESSARY. DSP21410
C IF(NV.EQ.7) NLINES=NLINES+1 DSP21420
C *****DSP21440
C *DSP21450
C PRINT. DSP21460
C READ FIRST PRINT CONTROL CARD. DSP21470
C READ INPUT UNIT NUMBER, ARRAY NAME, AND NUMBER DSP21480
C OF ARRAYS TO BE PRINTED. DSP21490
C READ 91, IDTAPE, NFILE, NUMVC DSP21500
C STORE INITIAL INPUT UNIT NUMBER IN IDTAPX. DSP21510
C IDTAPX=IDTAPE DSP21520
C REWIND INPUT UNIT. DSP21530
C REWIND IDTAPE DSP21540
C GO TO TEST NUMVC. DSP21550
C GO TO 12 DSP21560
C READ ADDITIONAL CONTROL CARD. DSP21570
C READ INPUT UNIT NUMBER, ARRAY NAME, AND NUMBER DSP21580
C OF ARRAYS TO BE PRINTED. DSP21590
C 10 READ 91, IDTAPE, NFILE, NUMVC DSP21600
C IF CARD IS BLANK, PRINT OPERATION IS COMPLETE. DSP21610
C 12 IF(NUMVC.EQ.0) GO TO 500 DSP21620
C ADDITIONAL ARRAYS ARE TO BE PRINTED. DSP21630
C WAS THERE A CHANGE IN THE INPUT UNIT NUMBER? DSP21640
C IF(IDTAPX.NE.IDTAPE) GO TO 13 DSP21650
C NO DSP21660
C ARE ALL ARRAYS ON THE TAPE TO BE PRINTED? DSP21670
C IF(NUMVC.GT.0) GO TO 14 DSP21680
C YES DSP21690
```

C REWIND IDTAPE REWIND THE INPUT UNIT. DSP21700
C GO TO 410 GO TO READ THE FIRST LABEL RECORD. DSP21710
C YES THERE WAS A CHANGE IN THE INPUT UNIT NUMBER. DSP21720
C REWIND PREVIOUS INPUT UNIT. DSP21730
C 13 REWIND IDTAPX STORE CURRENT INPUT UNIT NUMBER IN IDTAPX. DSP21740
C IDTAPX=IDTAPE DSP21750
C REWIND IDTAPE DSP21760
C IF(NUMVC.EQ.(-1)) GO TO 410 IF NUMVC IS NEGATIVE, PRINT THE ENTIRE TAPE. DSP21770
C THE FIRST ARRAY TO BE PRINTED UNDER CONTROL OF THIS CARD MUST BE LOCATED BY NAME. DSP21780
C POSITION INPUT FILE TO ARRAY NAMED IN 'NFILE'. DSP21790
C IDTAPE,NFILE ARE INPUT ARGUMENTS. DSP21800
C NL,LABEL,KTYPE ARE RETURNED. DSP21810
C 14 CALL POSINP(IDTAPE,KTYPE,NFILE,NL,LABEL) DSP21820
C USE KTYPE FROM FILE LABEL TO BRANCH TO D, S, OR P PRINT. DSP21830
C 15 GO TO (1000,2000,3000),KTYPE DSP21840
C ***DSP21950
C *DSP21960
C D DSP21970
C 1000 CONTINUE DSP21980
C THIS SEGMENT OF THE PROGRAM WILL DSP21990
C (1) READ THE D MATRIX DATA RECORDS. PRINT THE ROW NUMBER AND THE VARIABLE DEFINITIONS DESCRIB-_DSP22000
C ING THIS NUMBER. FOR EACH NON-ZERO ELEMENT IN THE ROW, PRINT THE COLUMN NUMBER, FREQUENCY AND VARIABLE DEFINITIONS DESCRIBING THIS NUMBER. DSP22010
C (2) READ THE D MATRIX END LABEL. DSP22020
C DSP22030
C COMPUTE NUMBER OF PRINT LINES REQUIRED FOR HEAD-DSP22040
C ING. DSP22050
C NLHEAD=NL/30+2+NLINE\$+1 DSP22060
C SET INITIAL VALUE OF NUMBER OF PRINT LINES USED TO 60 SO THAT PRINT HEADING BRANCH WILL BE TAKENDSP22070
C PRECEDING THE PRINT OF THE FIRST STATE NUMBER. DSP22080
C NLCUR=60 DSP22090
C READ A D MATRIX RECORD. DSP22100
C 1010 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) WAS THIS THE D MATRIX END LABEL. DSP22110
C YES. GO TO END OF ARRAY PROCESSING. DSP22120
C IF(KTYPE.GT.30) GO TO 400 RECORD JUST READ WAS A DATA RECORD. DSP22130
C PRINT DESCRIPTION FOR EACH NON-ZERO ENTRY IN THE DSP22140
C ROW. DSP22150
C SET ISW TO 1 TO INDICATE THAT THE INITIAL PRINT DSP22160

C OF THE DESCRIPTION OF THIS ROW HAS NOT YET DSP22270
C OCCURRED. DSP22280
C ISW=1 DSP22290
C
C DO FOR EACH COLUMN ENTRY IN A ROW. DSP22320
C DO 1210 IC=1,ICNT DSP22330
C IS THE COLUMN VALUE ZERO? DSP22340
C YES. GO TO INCREMENT COLUMN INDEX. DSP22350
C IF(ISVEC(IC).EQ.0) GO TO 1210 DSP22360
C NO. DSP22370
C HAS THE INITIAL PRINT OF THE DESCRIPTION OF THIS DSP22380
C ROW BEEN EXECUTED? DSP22390
C YES. GO TO CHECK SPACE AVAILABLE FOR A COLUMN DSP22400
C DESCRIPTION. DSP22410
C IF(ISW.EQ.0) GO TO 1050 DSP22420
C INITIAL ROW DESCRIPTION HAS NOT BEEN PRINTED. DSP22430
C RESET INITIAL PRINT DESCRIPTION SWITCH AND DSP22440
C EXECUTE PRINT-ROW-DESCRIPTION PROCEDURE. DSP22450
C ISW=0 DSP22460
C IS THERE SPACE ON THE CURRENT PAGE FOR THE ROW DSP22470
C DESCRIPTION AND AT LEAST ONE COLUMN DESCRIPTION DSP22480
C FOR THAT ROW? DSP22490
C NO. GO TO SKIP TO A NEW PAGE. DSP22500
C IF(NLCUR+2*NLINES+1.GT.60) GO TO 1060 DSP22510
C YES. SKIP A LINE BEFORE PRINTING THE ROW NUMBER. DSP22520
C PRINT 1002 DSP22530
C ADD 1 TO NUMBER OF PRINT LINES CURRENTLY USED. DSP22540
C NLCUR=NLCUR+1 DSP22550
C GO TO 1080 DSP22560
C IS SPACE AVAILABLE FOR A COLUMN DESCRIPTION? DSP22580
C YES. GO TO DECODE COLUMN NUMBER. DSP22590
C 1050 IF(NLCUR+NLINES.LE.60) GO TO 1160 DSP22600
C NO. DSP22610
C SKIP TO A NEW PAGE AND PRINT HEADING. DSP22620
C 1060 PRINT 97,NFILE,(LABEL(I),I=1,NL) DSP22630
C PRINT 1001,(NAMEV(I),I=1,NV3) DSP22640
C PRINT 1002 DSP22650
C NLCUR=NLHEAD RESET NUMBER OF PRINT LINES USED ON CURRENT PAGE DSP22660
C COMPUTE VARIABLE CODE VALUES FOR ROW NUMBER. DSP22670
C IS THIS ROW ZERO? DSP22680
C YES. BYPASS DECODE PROCEDURE. DSP22690
C 1080 IF(IROW.EQ.0) GO TO 1140 DSP22700
C THIS IS NOT ROW ZERO. DSP22710
C SET IRSW TO INDICATE A ROW NUMBER IS BEING DE- DSP22720
C CODED. DSP22730
C IRSW=1 DSP22740
C I2=IROW SET I2 EQUAL THE ROW NUMBER TO BE DECODED. DSP22750
C TRANSFER HERE FOR DECODING OF BOTH ROW AND DSP22760
C COLUMN NUMBERS. DSP22770
C 1090 IF(NV.EQ.1) GO TO 1102 DSP22780
C DO 1100 I3=1,NVM1 DSP22790
C I1=(I2-1)/MULT(I3) DSP22800
C I2=I2-I1*MULT(I3) DSP22810
C DSP22820

```
1100 ICODE(I3)=I1+1 DSP22830
1102 ICODE(NV)=I2 DSP22840
C TRANSFER CODE DESCRIPTIONS TO LIST ARRAY FOR
C PRINTING. DSP22850
C DSP22860
L2=1 DSP22870
DO 1120 I=1,NV DSP22880
L=LOC(I)+(ICODE(I)-1)*3 DSP22890
LIST(L2)=NAMEC(L) DSP22900
LIST(L2+1)=NAMEC(L+1) DSP22910
LIST(L2+2)=NAMEC(L+2) DSP22920
L2=L2+3 DSP22930
1120 CONTINUE DSP22940
C IF THE NUMBER JUST DECODED HAS A COLUMN, GO TO DSP22950
C COLUMN PRINT. DSP22960
C IF(IRSW.EQ.2) GO TO 1180 DSP22970
C PRINT ROW NUMBER AND DESCRIPTION. DSP22980
C PRINT 1002,NROW,IROW,(LIST(I),I=1,NV3) DSP22990
C INCREMENT NUMBER OF PRINT LINES USED. DSP23000
NLCUR=NLCUR+NLLINES DSP23010
C GO TO PROCESS COLUMN ENTRY. DSP23020
C GO TO 1160 DSP23030
C PRINT ROW NUMBER FOR ROW ZERO. DSP23040
1140 PRINT 1002,NROW,IROW DSP23050
C INCREMENT NUMBER OF PRINT LINES USED. DSP23060
NLCUR=NLCUR+1 DSP23070
C THERE IS SPACE FOR A COLUMN DESCRIPTION. DSP23080
C IS THIS COLUMN ZERO? DSP23090
C YES. GO DIRECTLY TO PRINT STATEMENT. DSP23100
1160 IF(ISN(IC).EQ.0) GO TO 1190 DSP23110
C THIS IS NOT COLUMN ZERO. DSP23120
C SET IRSW TO INDICATE A COLUMN NUMBER IS BEING
C DECODED. DSP23130
C IRSW=2 DSP23140
C SET I2 EQUAL THE COLUMN NUMBER TO BE DECODED. DSP23150
C I2=ISN(IC) DSP23160
C GO TO 1090 DSP23170
C GO TO 1090 DSP23180
C RETURN TO 1180 FROM DECODE LOOP. DSP23190
C COLUMN PRINT. DSP23200
C 1180 PRINT 1003,NCOL,ISN(IC),ISVEC(IC),(LIST(I),I=1,NV3) DSP23210
C INCREMENT NUMBER OF PRINT LINES USED. DSP23220
NLCUR=NLCUR+NLLINES DSP23230
C GO TO COLUMN DO LOOP CONTINUE STATEMENT. DSP23240
C GO TO 1210 DSP23250
C COLUMN PRINT FOR ZERO COLUMN. DSP23260
C 1190 PRINT 1003,NCOL,ISN(IC),ISVEC(IC) DSP23270
C INCREMENT NUMBER OF PRINT LINES USED. DSP23280
NLCUR=NLCUR+1 DSP23290
C CONTINUE FOR DO FOR EACH COLUMN IN A ROW. DSP23300
1210 CONTINUE DSP23310
C *DSP23320
C **DSP23330
C GO TO READ NEXT D DATA RECORD. DSP23340
C GO TO 1010 DSP23350
C DSP23360
C *DSP23370
C ***DSP23380
C ***DSP23390
```

```
C          DSP23400
C          ***DSP23410
C          *DSP23420
C          S          DSP23430
C 2000 CONTINUE          DSP23440
C          DSP23450
C          THIS IS THE PRINT S SEGMENT OF THE PROGRAM. IT          DSP23460
C          WILL          DSP23470
C          (1) READ THE S VECTOR DATA RECORD,          DSP23480
C          (2) READ THE S VECTOR END LABEL, AND          DSP23490
C          (3) FOR EACH ELEMENT IN THE S VECTOR, PRINT          DSP23500
C          (A) THE STATE NUMBER,          DSP23510
C          (B) THE FREQUENCY, AND          DSP23520
C          (C) THE VARIABLE DEFINITIONS THAT DESCRIBE          DSP23530
C          THE CASES IN THIS STATE.          DSP23540
C          DSP23550
C          DSP23560
C          FOR CURRENT ARRAY COMPUTE NUMBER OF DESCRIPTIONS          DSP23570
C          THAT CAN BE PRINTED PER PAGE.          DSP23580
C          NDPAGE=(60-(NL/30+1)-1)/NLINES-1          DSP23590
C          SET INITIAL VALUE OF NUMBER-OF-DESCRIPTIONS-          DSP23600
C          CURRENTLY-PRINTED-ON-THE-PAGE TO THE MAXIMUM          DSP23610
C          VALUE SO THAT THE PRINT HEADING BRANCH WILL BE          DSP23620
C          TAKEN IMMEDIATELY PRECEDING THE PRINT OF THE          DSP23630
C          FIRST STATE NUMBER.          DSP23640
C          NDCUR=NDPAGE          DSP23650
C          DSP23660
C          READ S DATA RECORD          DSP23670
C          READ(IDTAPE)KTYPE,NFILL,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT)          DSP23680
C          READ S END LABEL          DSP23690
C          READ(IDTAPE)KTYPE,NFILL,NFILL,ISUM,NFILL          DSP23700
C          DSP23710
C          **DSP23720
C          *DSP23730
C          PROCESS EACH S VECTOR ENTRY.          DSP23740
C          DO 2090 IC=1,ICNT          DSP23750
C          IS THE VALUE OF THE ELEMENT EQUAL ZERO?          DSP23760
C          YES. DO NOT PRINT.          DSP23770
C          IF(ISVEC(IC).EQ.0) GO TO 2090          DSP23780
C          ELEMENT IS NON-ZERO.          DSP23790
C          I2=ISN(IC)          DSP23800
C          IS THERE SPACE ON THE CURRENT PAGE FOR THIS          DSP23810
C          STATE NUMBER DESCRIPTION?          DSP23820
C          2025 IF(NDCUR.LT.NDPAGE) GO TO 2030          DSP23830
C          NO          DSP23840
C          RESET NUMBER OF DESCRIPTIONS ON CURRENT PAGE.          DSP23850
C          NDCUR=0          DSP23860
C          PRINT PAGE HEADING          DSP23870
C          PRINT 97,NFILE,(LABEL(I),I=1,NL)          DSP23880
C          PRINT 2001,(NAMEV(II),II=1,NV3)          DSP23890
C          PRINT 2002          DSP23900
C          INCREMENT COUNT OF NUMBER OF DESCRIPTIONS ON          DSP23910
C          THIS PAGE.          DSP23920
C          2030 NDCUR=NDCUR+1          DSP23930
C          IS STATE ZERO THE STATE BEING PRINTED?          DSP23940
C          YES. BYPASS DECODE PROCEDURE.          DSP23950
C          IF(I2.EQ.0) GO TO 2080          DSP23960
```

C NO. DSP23970
C COMPUTE CODE NUMBER FOR EACH VARIABLE. DSP23980
C IF(NV.EQ.1) GO TO 2042 DSP23985
DO 2040 I3=1,NVM1 DSP23990
I1=(I2~1)/MULT(I3) DSP24000
I2=I2-I1*MULT(I3) DSP24010
2040 ICODE(I3)=I1+1 DSP24020
2042 ICODE(NV)=I2 DSP24030
C TRANSFER CODE DESCRIPTIONS TO 'LIST' ARRAY FOR DSP24040
C PRINTING. DSP24050
L2=1 DSP24060
DO 2050 I=1,NV DSP24070
L=LOC(I)+(ICODE(I)-1)*3 DSP24080
LIST(L2)=NAMEC(L) DSP24090
LIST(L2+1)=NAMEC(L+1) DSP24100
LIST(L2+2)=NAMEC(L+2) DSP24110
L2=L2+3 DSP24120
2050 CONTINUE DSP24130
C PRINT STATE NUMBER AND DESCRIPTION DSP24140
PRINT 2002,ISN(IC),ISVEC(IC),(LIST(II),II=1,NV3) DSP24150
GO TO 2090 DSP24160
C PRINT STATEMENT FOR STATE ZERO. THE STATE NUMBER DSP24170
AND FREQUENCY WILL BE PRINTED BUT NO DESCRIPTION DSP24180
2080 PRINT 2002,ISN(IC),ISVEC(IC) DSP24190
C CONTINUE. DSP24200
2090 CONTINUE DSP24210
C *DSP24220
C **DSP24230
C ALL STATE NUMBERS IN S VECTOR HAVE BEEN PRINTED. DSP24240
PRINT S VECTOR SUM. DSP24250
C END OF PROCESSING FOR THIS ARRAY. DSP24260
C GO TO 400 DSP24270
C DSP24280
C *DSP24290
C ***DSP24300
C DSP24310
C ***DSP24320
C *DSP24330
C P DSP24340
3000 CONTINUE DSP24350
C DSP24360
C THIS SEGMENT OF THE PROGRAM WILL DSP24370
(1) PASS THE P MATRIX LIST OF ROWS AND LIST OF DSP24380
COLUMNS RECORDS. DSP24390
(2) READ THE P MATRIX DATA RECORDS. PRINT THE DSP24400
C ROW NUMBER AND THE VARIABLE DEFINITIONS DFSCRIB-DSP24410
C ING THIS NUMBER. FOR EACH NON-ZERO ELEMENT IN DSP24420
C THE ROW, PRINT THE COLUMN NUMBER, PROBABILITY DSP24430
C AND VARIABLE DEFINITIONS DESCRIBING THIS NUMBER.DSP24440
(3) READ THE P MATRIX END LABEL. DSP24450
C DSP24460
C COMPUTE NUMBER OF PRINT LINES REQUIRED FOR HEAD-DSP24470
C ING. DSP24480
NLHEAD=NL/30+2+NLINE+1 DSP24490
C SET INITIAL VALUE OF NUMBER OF PRINT LINES USED DSP24500
C TO 60 SO THAT PRINT HEADING BRANCH WILL BE TAKENDSP24510
C PRECEDING THE PRINT OF THE FIRST STATE NUMBER. DSP24520

```
NLCUR=60 DSP24530
C
C          READ(IUTAPE) PASS THE P MATRIX ROW LIST RECORD. DSP24540
C          READ(IUTAPE) PASS THE P MATRIX COL LIST RECORD. DSP24550
C
C          READ A P MATRIX RECORD. DSP24560
C 3010 READ(IUTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT) DSP24570
C          WAS THIS THE P MATRIX END LABEL. DSP24580
C          YES. GO TO END OF ARRAY PROCESSING. DSP24590
C
C          IF(KTYPE.GT.30) GO TO 400 DSP24600
C          RECORD JUST READ WAS A DATA RECORD. DSP24610
C          PRINT DESCRIPTION FOR EACH NON-ZERO ENTRY IN THE DSP24620
C          ROW. DSP24630
C          SET ISW TO 1 TO INDICATE THAT THE INITIAL PRINT DSP24640
C          OF THE DESCRIPTION OF THIS ROW HAS NOT YET DSP24650
C          OCCURRED. DSP24660
C
C          ISW=1 DSP24670
C
C          DO 3210 IC=1,ICNT DSP24680
C          DO FOR EACH COLUMN ENTRY IN A ROW. DSP24690
C          IS THE COLUMN VALUE ZERO? DSP2470
C          YES. GO TO INCREMENT COLUMN INDEX. DSP24710
C
C          IF(P(IC).EQ.0.0D0) GO TO 3210 DSP24720
C          NO. DSP24730
C          HAS THE INITIAL PRINT OF THE DESCRIPTION OF THIS DSP24740
C          ROW BEEN EXECUTED? DSP24750
C          YES. GO TO CHECK SPACE AVAILABLE FOR A COLUMN DSP24760
C          DESCRIPTION. DSP24770
C
C          IF(ISW.EQ.0) GO TO 3050 DSP24780
C          INITIAL ROW DESCRIPTION HAS NOT BEEN PRINTED. DSP24790
C          RESET INITIAL PRINT DESCRIPTION SWITCH AND DSP24800
C          EXECUTE PRINT-ROW-DESCRIPTION PROCEDURE. DSP24810
C
C          ISW=0 DSP24820
C          IS THERE SPACE ON THE CURRENT PAGE FOR THE ROW DSP24830
C          DESCRIPTION AND AT LEAST ONE COLUMN DESCRIPTION DSP24840
C          FOR THAT ROW? DSP24850
C          NO. GO TO SKIP TO A NEW PAGE. DSP24860
C
C          IF(NLCUR+2*NLINES+2.GT.60) GO TO 3060 DSP24870
C          YES. SKIP A LINE BEFORE PRINTING THE ROW NUMBER. DSP24880
C
C          PRINT 1002 DSP24890
C          ADD 1 TO NUMBER OF PRINT LINES CURRENTLY USED. DSP24900
C
C          NLCUR=NLCUR+1 DSP24910
C
C          GO TO 3060 DSP24920
C
C          IS SPACE AVAILABLE FOR A COLUMN DESCRIPTION? DSP24930
C          YES. GO TO DECODE COLUMN NUMBER. DSP24940
C
C 3050 IF(NLCUR+NLINES.LE.60) GO TO 3160 DSP24950
C          NO. DSP24960
C          SKIP TO A NEW PAGE AND PRINT HEADING. DSP24970
C
C 3060 PRINT 97,NFILE,(LABEL(I),I=1,NL) DSP24980
C          PRINT 3001,(NAMEV(I),I=1,NV3) DSP24990
C          PRINT 1002 DSP25000
C
C          NLCUR=NLHEAD RESET NUMBER OF PRINT LINES USED ON CURRENT PAGE DSP25010
C
C
C
C
```

C COMPUTE VARIABLE CODE VALUES FOR ROW NUMBER. DSP25100
C IS THIS ROW ZERO? DSP25110
C YES. BYPASS DECODE PROCEDURE. DSP25120
3080 IF(IROW.EQ.0) GO TO 3140 DSP25130
C THIS IS NOT ROW ZERO. DSP25140
C SET IRSW TO INDICATE A ROW NUMBER IS BEING DE- DSP25150
C CODED. DSP25160
C IRSW=1 DSP25170
C I2=IROW DSP25180
C TRANSFER HERE FOR DECODING OF BOTH ROW AND DSP25200
C COLUMN NUMBERS. DSP25210
3090 IF(NV.EQ.1) GO TO 3102 DSP25215
DO 3100 I3=1,NV1
I1=(I2-1)/MULT(I3)
I2=I2-I1*MULT(I3)
3100 ICODE(I3)=I1+1
3102 ICODE(NV)=I2
C TRANSFER CODE DESCRIPTIONS TO LIST ARRAY FOR DSP25220
C PRINTING. DSP25230
L2=1 DSP25240
DO 3120 I=1,NV DSP25250
L=LOC(I)+(ICODE(I)-1)*3 DSP25260
LIST(L2)=NAMEC(L)
LIST(L2+1)=NAMEC(L+1)
LIST(L2+2)=NAMEC(L+2)
L2=L2+3 DSP25270
3120 CONTINUE DSP25280
C IF THE NUMBER JUST DECODED WAS A COLUMN, GO TO DSP25290
C COLUMN PRINT. DSP25300
IF(IRSW.EQ.2) GO TO 3180 DSP25310
C PRINT ROW NUMBER AND DESCRIPTION. DSP25320
PRINT 1002,NROW,IROW,(LIST(I),I=1,NV3)
C INCREMENT NUMBER OF PRINT LINES USED. DSP25330
NLCUR=NLCUR+NLINES DSP25340
C GO TO PROCESS COLUMN ENTRY. DSP25350
GO TO 3160 DSP25360
C PRINT ROW NUMBER FOR ROW ZERO. DSP25370
3140 PRINT 1002,NROW,IROW DSP25380
C INCREMENT NUMBER OF PRINT LINES USED. DSP25390
NLCUR=NLCUR+1 DSP25400
C THERE IS SPACE FOR A COLUMN DESCRIPTION. DSP25410
C IS THIS COLUMN ZERO? DSP25420
C YES. GO DIRECTLY TO PRINT STATEMENT. DSP25430
3160 IF(ISN(IC).EQ.0) GO TO 3190 DSP25440
C THIS IS NOT COLUMN ZERO. DSP25450
C SET IRSW TO INDICATE A COLUMN NUMBER IS BEING DSP25460
C DECODED. DSP25470
C IRSW=2 DSP25480
C I2=ISN(IC) DSP25490
C GO TO 3090 DSP25500
C RETURN TO 3180 FROM DECODE LOOP. DSP25510
C COLUMN PRINT. DSP25520
3180 PRINT 3003,NCOL,ISN(IC),P(IC) ,:(LIST(I),I=1,NV3) DSP25530
C INCREMENT NUMBER OF PRINT LINES USED. DSP25540

NLCUR=NLCUR+NLLINES	DSP25660
C GO TO 3210	DSP25670
C COLUMN PRINT FOR ZERO COLUMN.	DSP25680
3190 PRINT 3003,NCOL,ISN(IC),P(IC)	DSP25690
C INCREMENT NUMBER OF PRINT LINES USED.	DSP25700
NLCUR=NLCUR+1	DSP25710
C CONTINUE FOR DO FOR EACH COLUMN IN A ROW.	DSP25720
3210 CONTINUE	DSP25730
C	DSP25740
C	*DSP25750
C	**DSP25760
C GO TO 3010	DSP25770
C	DSP25780
C	*DSP25790
C	***DSP25800
C	DSP25810
C END OF ARRAY LABEL WAS READ.	DSP25820
C DECREASE NUMBER OF ARRAYS PROCESSED BY ONE.	DSP25830
400 NUMVC=NUMVC-1	DSP25840
C HAVE ALL SPECIFIED ARRAYS BEEN PRINTED?	DSP25850
C YES. READ NEXT CONTROL CARD.	DSP25860
IF(NUMVC.EQ.0) GO TO 10	DSP25870
C NO. READ NEXT LABEL.	DSP25880
410 READ(IDTAPE)KTYPE,NFILE,NL,(LABEL(I),I=1,NL)	DSP25890
C IS THIS A BEGINNING OF ARRAY RECORD?	DSP25900
C YES - GO TO BRANCH ON ARRAY TYPE.	DSP25910
IF(KTYPE.NE.40) GO TO 15	DSP25920
C NO	DSP25930
C THIS IS AN END OF FILE LABEL.	DSP25940
C REWIND INPUT UNIT.	DSP25950
430 REWIND IDTAPE	DSP25960
C GO TO READ NEXT CONTROL CARD.	DSP25970
C GO TO 10	DSP25980
C	DSP25990
C	DSP26000
C ALL PRINT CARDS PROCESSED.	DSP26010
C REWIND LAST INPUT UNIT.	DSP26020
500 REWIND IDTAPX	DSP26030
C SKIP TO A NEW PAGE.	DSP26040
C PRINT 510	DSP26050
C RETURN	DSP26060
C	DSP26070
C	DSP26080
C	*DSP26090
C	***DSP26100
C	DSP26110
C	DSP26120
90 FORMAT(16,3A4,16)	DSP26130
91 FORMAT(16,6A4,216)	DSP26140
92 FORMAT(48H DSPRN2 - ERROR IN STATE DESCRIPTION DATA CARDS.	DSP26150
1 /1X,I6,30H = VARIABLE NUMBER IN DO LOOP.	DSP26160
2 /1X,I6,28H = VARIABLE NUMBER IN CARD.	DSP26170
3 /1X,I6,26H = CODE NUMBER IN DO LOOP.	DSP26180
4 /1X,I6,24H = CODE NUMBER IN CARD.)	DSP26190
97 FORMAT(1H1, 6A4/ (1X,30A4))	DSP26200
510 FORMAT(1H1)	DSP26210
1001 FORMAT(27H0 STATE NUMBER FREQUENCY,7(3X,3A4)/(27X,7(3X,3A4)))	DSP26220

1002	FORMAT(1X,A3,I11,12X,7(3X,3A4)/(27X,7(3X,3A4)))	DSP26230
1003	FORMAT(1X,A3,I11,I12,7(3X,3A4)/(27X,7(3X,3A4)))	DSP26240
2001	FORMAT(25H0STATE NUMBER FREQUENCY,7(3X,3A4)/(25X,7(3X,3A4)))	DSP26250
2002	FORMAT(1X,2I12,7(3X,3A4)/(25X,7(3X,3A4)))	DSP26260
2003	FORMAT(// 4X,9H TOTAL = ,I12)	DSP26270
3001	FORMAT(27H0 STATE NUMBER PROBABILITY,7(3X,3A4)/(27X,7(3X,3A4)))	DSP26280
3003	FORMAT(1X,A3,I11,F12.6,7(3X,3A4)/(27X,7(3X,3A4)))	DSP26290

C

REFERENCE LIST.

C

ARGUMENT LIST

C

ISN	- ARRAY FOR COLUMN NUMBERS IN A D ROW, ELEMENT NUMBERS IN AN S VECTOR AND COLUMN NUMBERS IN A P ROW.	DSP26350
ISVEC	- ARRAY FOR COLUMN VALUES IN A D ROW - OR - ELEMENT VALUES IN AN S VECTOR.	DSP26360

P	- ARRAY FOR COLUMN VALUES IN A P ROW.	DSP26370
LABEL	- ARRAY FOR D, S, AND P LABELS.	DSP26380

NAMEV(3*NV)	- VARIABLE NAMES.	DSP26390
NAMEC(SUM OF NCODE(I)*3)	- CODE NAMES.	DSP26400

NCODE(NV)	- NUMBER OF CODES FOR EACH VARIABLE.	DSP26410
LOC(NV+1)	- BEGINNING LOCATION IN NAMEC VECTOR OF CODE NAMES FOR EACH VARIABLE.	DSP26420

ICODE(NV)	- CURRENT CODE VALUE BEING PRINTED FOR EACH VARIABLE.	DSP26430
LIST(3*NV)	- PRINT LINE(S).	DSP26440

		DSP26450
		DSP26460

		DSP26470
		DSP26480

		DSP26490
		DSP26500

		DSP26510
IDTAPE	- THE UNIT ON WHICH THE CURRENT ARRAY IS LOCATED.	DSP26520

ISW	- 1 - THERE HAS NOT BEEN AN INITIAL ROW DESCRIPTION PRINT.	DSP26530
	0 - THERE HAS BEEN AN INITIAL ROW DESCRIPTION PRINT.	DSP26540

IRSW	- 1 - A ROW NUMBER IS BEING DECODED.	DSP26550
	2 - A COL NUMBER IS BEING DECODED.	DSP26560

MULT	- ARRAY FOR STATE NUMBER MULTIPLY FACTORS.	DSP26570
------	--	----------

NFILE	- THE NAME OF THE INITIAL ARRAY TO BE LOCATED. OR, THE NAME OF THE ARRAY CURRENTLY BEING PRINTED.	DSP26580
-------	---	----------

NL	- THE NUMBER OF INT*4 WORDS IN THE LABEL.	DSP26590
----	---	----------

NLINES	- NUMBER PRINT LINES REQUIRED PER DESCRIPTION.	DSP26600
--------	--	----------

NDPAGE	- NUMBER OF DESCRIPTIONS THAT CAN BE PRINTED PER PAGE.	DSP26610
--------	--	----------

NDCUR	- NUMBER OF DESCRIPTIONS CURRENTLY PRINTED ON THE PAGE.	DSP26620
-------	---	----------

		DSP26630
--	--	----------

		DSP26640
--	--	----------

END		DSP26650
-----	--	----------

SUBROUTINE DXCOST	DXC00010
1 (ISN,ISVEC,JCOL,P,LABELD,LABELC)	DXC00020
C	DXC00030
C ELEMENT BY ELEMENT MULTIPLICATION OF D MATRIX	DXC00040
C TIMES COST PER UNIT MATRIX.	DXC00050
C DXC=X	DXC00060
C THERE WILL BE A ROW IN THE OUTPUT MATRIX ONLY	DXC00070
C WHEN THERE ARE CORRESPONDING ROWS IN THE INPUT	DXC00080
C ARRAYS.	DXC00090
C	DXC00100
IMPLICIT REAL*8(A-H,O-Z,S)	DXC00110
DIMENSION ISN(1),ISVEC(1),JCOL(1),P(1),LABELD(1),LABELC(1)	DXC00120
DIMENSION NAMED(6),NAMEC(6)	DXC00130
C	DXC00140
C INITIALIZATION FOR THIS CALL.	DXC00150
C P RECORD TYPE VARIABLES. THESE ARE USED FOR X	DXC00160
C MATRIX.	DXC00170
KPBEG=3	DXC00180
KPLST=13	DXC00190
KPDAT=23	DXC00200
KPEND=33	DXC00210
C	DXC00220
KNEXT=40	DXC00230
C	DXC00240
NFILL=1	DXC00250
DATA KBLANK/4H	DXC00260
C	DXC00270
PRINT 2	DXC00280
C	DXC00290
READ 5,IOUT	DXC00300
REWIND IOUT	DXC00310
C	DXC00320
NFILES=0	DXC00330
C	DXC00340
READ A CONTROL CARD.	DXC00350
C	DXC00360
D AND C MAY NOT BE ON THE SAME INPUT FILE.	DXC00370
10 READ 11,NAMFD,INP1,NAMEC,INP2	DXC00380
C	DXC00390
IF(INP1 .NE.0) GO TO 25	DXC00400
C	DXC00410
HAVE ALL ARRAYS BEEN PROCESSED?	DXC00420
C	DXC00430
YES. MULTIPLICATIONS COMPLETE FOR THIS CALL.	DXC00440
C	DXC00450
ADD 1 TO COUNT OF OUTPUT FILES.	DXC00460
12 NFILEFS=NFILES+1	DXC00470
C	DXC00480
PLACE BLANKS IN FILE NAME.	DXC00490
DO 15 I=1,6	DXC00500
15 NAMED(I)=KBLANK	DXC00510
C	DXC00520
WRITE(IOUT) KNEXT,NAMED,NFILL,NFILES	DXC00530
C	DXC00540
REWIND IOUT	DXC00550
C	DXC00560
DID AN ERROR IN THE UNITS SPECIFIED CAUSE THE	
C	
TRANSFER TO THE END OF FILE PROCESSING?	
C	
YES. CALL EXIT.	
IF(INP1.NE.0) STOP	
C	
NO.	
C	
RETURN	

C THERE ARE STILL ARRAYS TO BE PROCESSED. DXC00570
C ARE D AND C ON THE SAME UNIT? DXC00580
C NO. GO TO PROCESS THIS CARD. DXC00590
C
25 IF(INP1.NE.INP2) GO TO 30 DXC00600
C YES. PRINT ERROR MESSAGE AND EXIT. DXC00610
C PRINT 7,INP1 DXC00620
7 FORMAT(44H DXCOST ERROR. BOTH INPUT ARRAYS ARE ON UNIT,I6) DXC00630
C GO TO CLOSE OUTPUT FILE. DXC00640
C GO TO 12 DXC00650
C PROCESS THE CONTROL CARD JUST READ. DXC00660
C LOCATE D MATRIX. DXC00670
C 30 CALL POSINP(INP1,KTYPE,NAMED,NLD,LABELD) DXC00680
C LOCATE C MATRIX. DXC00690
C CALL POSINP(INP2,KTYPE,NAMEC,NLC,LABELC) DXC00700
C PASS C MATRIX ROW LIST RECORD. DXC00710
C READ(INP2) DXC00720
C PASS C MATRIX COL LIST RECORD. DXC00730
C READ(INP2) DXC00740
C
C READ NAME FOR OUTPUT ARRAY. DXC00750
C READ 11,NAMED DXC00760
C SET UP DXCOST ID LINE FOR OUTPUT LABEL. DXC00770
C DATA LABELX/120HTOTAL COST MATRIX RESULTING FROM ELEMENT BY ELEMENT
1T MULTIPLICATION OF D MATRIX AND COST PER UNIT MATRIX DXC00780
2 / DXC00810
C COMPUTE OUTPUT LABEL LENGTH. DXC00820
C NLX=60+NLD DXC00830
C
C WRITE OUTPUT ARRAY BEGINNING LABEL. DXC00840
C WRITE(IOUT)KPBEG,NAMED,NLX,LABELX,(LABELD(I),I=1,NLD),(LABELC(I), I=1,30) DXC00850
1
C
C WRITE DUMMY LIST RECORDS FOR X ARRAY TO MAINTAIN COMPATIBILITY WITH P ARRAY FORMAT. DXC00860
C
C WRITE(IOUT) KPLST,NFILL,NFILL,NFILL,NFILL DXC00870
C WRITE(IOUT) KPLST,NFILL,NFILL,NFILL,NFILL DXC00880
C INITIAL VALUE OF NUMBER OF ROWS IN X IS ZERO. DXC00890
C NDROWS=0 DXC00900
C INITIAL VALUE OF NUMBER OF ELEMENTS IN X = ZERO. DXC00910
C NDLMTS=0 DXC00920
C INITIAL VALUE OF ARRAY SUM IS ZERO. DXC00930
C SUM=0 DXC00940
C ***DXC01010
C *DXC01020
C D MATRIX - C MATRIX ELEMENT BY ELEMENT MULTIPLICATION. DXC01030
C
C I = SUBSCRIPT FOR ISN,ISVEC, LIST OF COLUMNS AND VALUES IN D MATRIX ROW. DXC01040
C J = SUBSCRIPT FOR JCOL,P, LIST OF COLUMNS AND VALUES IN C MATRIX ROW. DXC01050
C KPASS 1 - READ D AND C RECORDS. DXC01060
C 2 - READ D RECORD ONLY. DXC01070
C
C INITIAL SETTING OF KPASS WILL BE 1. DXC01080

C KPASS=1 DXC01140
C READ A D RECORD. DXC01150
C 85 READ(INP1)KTYPE,KROW1,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) DXC01160
C WAS RECORD JUST READ THE D END LABEL? DXC01170
C YES. GO TO READ REMAINING C RECORDS. DXC01180
C IF(KTYPE.EQ.31) GO TO 140 DXC01190
C RECORD JUST READ WAS A D DATA RECORD. DXC01200
C IS A C RECORD TO BE READ? DXC01210
C NO. GO TO COMPARE ROW NUMBERS. DXC01220
C IF(KPASS.EQ.2) GO TO 95 DXC01230
C READ A C RECORD. DXC01240
C 90 READ(INP2)KTYPE,KROW2,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) DXC01250
C WAS RECORD JUST READ THE C END LABEL? DXC01260
C YES. GO TO READ REMAINING D RECORDS. DXC01270
C IF(KTYPF.EQ.33) GO TO 145 DXC01280
C RECORD JUST READ WAS A C DATA RECORD. DXC01290
C DOES CURRENT D ROW NUMBER EQUAL CURRENT C ROW DXC01300
C NUMBER? DXC01310
C YES. GO TO MULTIPLY. DXC01320
C 95 IF(KROW1.EQ.KROW2) GO TO 100 DXC01330
C NO. DXC01340
C SET KPASS TO INDICATE A SINGLE READ IS REQUIRED DXC01350
C BECAUSE OF UNMATCHING ROWS. DXC01360
C KPASS=2 DXC01370
C IF D ROW NUMBER IS LESS THAN C ROW NUMBER, GO TO 100 DXC01380
C READ D RECORD. DXC01390
C IF(KROW1.LT.KROW2) GO TO 85 DXC01400
C C ROW NUMBER IS LESS THAN D ROW NUMBER. DXC01410
C GO TO READ NEXT C RECORD. DXC01420
C GO TO 90 DXC01430
C D ROW AND C ROW MATCH. DXC01440
C SET KPASS TO INDICATE MATCHING ROWS. DXC01450
C 100 KPASS=1 DXC01460
C I=1 DXC01470
C J=1 DXC01480
C K=0 DXC01490
C NOW MULTIPLY THE CORRESPONDING COLUMN ELEMENTS DXC01500
C OF MATCHING ROW. DXC01510
C DO THE CURRENT COLUMN ELEMENTS WITHIN THE ROW DXC01520
C MATCH? DXC01530
C 105 IF(ISN(I)-JCOL(J)) 120,110,125 DXC01540
C COLUMN ELEMENTS MATCH. DXC01550

C INCREMENT K, SUBSCRIPT FOR OUTPUT ROW. DXCO1710
C 110 K=K+1 DXCO1720
C MOVE COLUMN NUMBER TO KTH LOCATION IN JCOL TO DXCO1730
C CREATE OUTPUT COLUMN LIST. K WILL ALWAYS BE LESSDXCO1740
C THAN OR EQUAL J. DXCO1750
C JCOL(K)=ISN(I) DXCO1760
C COMPUTE KTH ENTRY IN OUTPUT ROW. STORE IN P. DXCO1770
C P(K)=ISVEC(I)*P(J) DXCO1780
C ACCUMULATE ARRAY SUM. DXCO1790
C SUM=SUM+P(K) DXCO1800
C HAVE ALL ELEMENTS OF D ROW BEEN PROCESSED? DXCO1810
C YES. GO TO WRITE CURRENT ROW OF OUTPUT. DXCO1820
C IF(I.EQ.ICNT) GO TO 128 DXCO1830
C NO. DXCO1840
C INCREMENT I, SUBSCRIPT FOR D ROW. DXCO1850
C I=I+1 DXCO1860
C HAVE ALL ELEMENTS OF C ROW BEEN PROCESSED? DXCO1870
C YES. GO TO WRITE CURRENT ROW OF OUTPUT. DXCO1880
C IF(J.EQ.JCNT) GO TO 128 DXCO1890
C NO. DXCO1900
C INCREMENT J, SUBSCRIPT FOR C ROW. DXCO1910
C J=J+1 DXCO1920
C GO TO COMPARE COLUMN NUMBERS. DXCO1930
C GO TO 105 DXCO1940
C D COLUMN NUMBER IS LESS THAN C COLUMN NUMBER. DXCO1950
C HAVE ALL ELEMENTS OF D ROW BEEN PROCESSED? DXCO1960
C YES. GO TO WRITE CURRENT OUTPUT ROW. DXCO1970
C 120 IF(I.EQ.ICNT) GO TO 128 DXCO1980
C NO DXCO1990
C ADDITIONAL ELEMENTS IN THIS ROW ARE TO BE DXCO2000
C PROCESSED. DXCO2010
C INCREMENT COLUMN LIST SUBSCRIPT FOR D ROW. DXCO2020
C I=I+1 DXCO2030
C GO TO COMPARE COLUMN NUMBERS. DXCO2040
C GO TO 105 DXCO2050
C C COLUMN NUMBER IS LESS THAN D COLUMN NUMBER. DXCO2060
C HAVE ALL ELEMENTS IN THIS C ROW BEEN PROCESSED. DXCO2070
C YES. GO TO WRITE CURRENT OUTPUT ROW. DXCO2080
C 125 IF(J.EQ.JCNT) GO TO 128 DXCO2090
C NO DXCO2100
C ADDITIONAL ELEMENTS IN THIS ROW ARE TO BE DXCO2110
C PROCESSED. DXCO2120
C INCREMENT J, SUBSCRIPT FOR C ROW. DXCO2130
C J=J+1 DXCO2140
C GO TO COMPARE COLUMN NUMBERS. DXCO2150
C GO TO 105 DXCO2160
C ALL MATCHING COLUMN ELEMENTS, IF ANY, IN MATCH- DXCO2170
C ING D AND C ROWS HAVE BEEN MULTIPLIED. DXCO2180
C 128 CONTINUE DXCO2190
C IF THERE ARE NO ENTRIES IN THE OUTPUT ROW, GO TO DXCO2200
C READ NEXT RECORDS. DXCO2210
C IF(K.EQ.0) GO TO 85 DXCO2220
C THERE ARE ENTRIES IN THE OUTPUT ROW. DXCO2230
C WRITE A ROW RECORD FOR THE OUTPUT MATRIX. DXCO2240
C DXCO2250
C DXCO2260
C DXCO2270

C WRITE(IOUT)KPDAT,KROW1,K,(JCOL(KK),KK=1,K),(P(KK),KK=1,K) DXC02280
C INCREMENT COUNT OF ROWS IN X MATRIX. DXC02290
C NDROWS=NDROWS+1 INCREMENT COUNT OF ELEMENTS IN X MATRIX. DXC02300
C NDLMTS=NDLMTS+K MATCHING ROWS JUST PROCESSED. DXC02320
C *DXC02340
C **DXC02350
C DXC02360
C DXC02370
C DXC02380
C GO TO 85
C READ REMAINING D OR C RECORDS. DXC02390
C THIS IS JUST SO TAPE WILL ALWAYS BE POSITIONED DXC02400
C AFTER AN END-OF-ARRAY RECORD AT THE COMPLETION DXC02410
C OF A MULTIPLY OPERATION. DXC02420
140 READ(INP2)KTYPE DXC02430
 IF(KTYPE.EQ.33) GO TO 150 DXC02440
 GO TO 140 DXC02450
145 READ(INP1)KTYPE DXC02460
 IF(KTYPE.EQ.31) GO TO 150 DXC02470
 GO TO 145 DXC02480
C INPUT TAPE IS POSITIONED FOR NEXT BEGINNING OF DXC02490
C ARRAY LABEL. DXC02500
C 150 CONTINUE DXC02510
C PRINT 6,NAMED,SUM DXC02520
C CHANGE NUMBER OF ELEMENTS TO A REAL VALUE. DXC02530
C DLMTS=NDLMTS DXC02540
C WRITE X MATRIX END LABEL. DXC02550
C WRITE(IOUT)KPEND,NFILL,NFILL,NDROWS,DLMTS DXC02560
C ADD 1 TO COUNT OF FILES ON OUTPUT UNIT. DXC02570
C NFILES=NFILES+1 DXC02580
C *DXC02610
C ***DXC02620
C GO TO READ NEXT CONTROL CARD. DXC02630
C GO TO 10 DXC02640
C 2 FORMAT (1H1) DXC02650
5 FORMAT(I6) DXC02660
6 FORMAT(24H TOTAL C MATRIX - SUM...,6A4,F12.2) DXC02670
11 FORMAT(6A4,I6,6A4,I6) DXC02680
C DXC02690
C DXC02700
C REFERENCE LIST. DXC02710
C SUBROUTINE ARGUMENTS. DXC02720
C DXC02730
C DXC02740
C ISN - ELEMENT LIST FOR D ROW. DXC02750
C ISVEC - ELEMENT VALUE FOR D ROW. DXC02760
C JCOL - ELEMENT LIST FOR C ROW AND X ROW. DXC02770
C P - ELEMENT VALUE FOR C ROW AND X ROW. DXC02780
C LABELD - ARRAY FOR INPUT D LABEL AND OUTPUT X LABEL. DXC02790
C LABELC - ARRAY FOR INPUT C LABEL. DXC02800
C DXC02810
C DXC02820
C OTHER VARIABLES. DXC02830
C DXC02840

-51-

C	IOUT	- OUTPUT UNIT.	DXC02850
C	INP1	- INPUT UNIT FOR D.	DXC02860
C	INP2	- INPUT UNIT FOR C. MAY NOT BE THE SAME AS INP1.	DXC02870
C	SUM	- SUM OF ENTRIES IN THE OUTPUT MATRIX.	DXC02880
C	NFILES	- NUMBER OF FILES ON OUTPUT UNIT.	DXC02890
C	NLD	- LENGTH OF D LABEL.	DXC02900
C	NLC	- LENGTH OF C LABEL.	DXC02910
C	NLX	- LENGTH OF X LABEL.	DXC02920
C	END		DXC02930
			DXC02940

SUBROUTINE FCHANG (NDIM,ISN,LSTCOL,JCOL,P,LABELP,NUROWS,/IT. , FCH0010
C C C P MATRIX - FAMILY CHANGE AND SPECIFIC CHANGE. FCH0020
C C C IMPLICIT REAL*8(A-H,O-Z,\$) FCH0030
C C C DIMENSION ISN(1),LSTCOL(1),JCOL(1),P(1),LABELP(1),NUROWS(1) FCH0040
C C C DIMENSION NAMEP(6),UNAME(6),NULABL(30) FCH0050
C C C DIMENSION IFR(30),IRTO(30),ICFR(30),ICTO(30),IFCR(30),ICCR(30), FCH0060
C C C 1 IFR(30),IRV(30),ICSW(30),IFSW(30),MULT(30),IACT(30) FCH0070
C C C * FCH0080
C C C ***** THE DIRECT ACCESS DATA FILE MUST BE DEFINED FOR FCH0090
C C C ***** EACH MODEL. A DEFINE FILE STATEMENT MUST BE FCH00100
C C C * INCLUDED IN THE CALLING PROGRAM. THE GENERAL FORM FCH00110
C C C OF THE STATEMENT IN THE CALLING PROGRAM IS: FCH00120
C C C DEFINE FILE KDISK(NO. RECORDS,RECORD SIZE,FCH00130
C C C FMT,ITRACK) FCH00140
C C C REPLACE KDISK BY AN INTEGER CONSTANT THAT IS THE FCH00150
C C C DATA SET REFERENCE NUMBER. FCH00160
C C C REPLACE NO. RECORDS BY AN INTEGER CONSTANT THAT FCH00170
C C C SPECIFIES THE NUMBER OF RECORDS IN FCH00180
C C C THE DATA SET. FCH00190
C C C REPLACE RECORD SIZE BY AN INTEGER CONSTANT THAT FCH00200
C C C SPECIFIES THE MAXIMUM RECORD SIZE FCH00210
C C C (IN FOUR BYTE WORDS) OF EACH RECORD. FCH00220
C C C FCH00230
C C C INITIALIZATION FOR TOTAL RUN. FCH00240
C C C SKIP TO NEW PAGE FOR PRINTED OUTPUT. FCH00250
C C C FCH00260
C C C PRINT 1 FCH00270
C C C 1 FORMAT(1H1) FCH00280
C C C FCH00290
C C C SET ARRAY TYPE CONSTANTS. FCH00300
C C C BEGINNING LABEL FOR P MATRIX. FCH00310
C C C FCH00320
C C C KPBEG=3 FCH00330
C C C FCH00340
C C C KPI,ST=23 FCH00350
C C C FCH00360
C C C KNEXT=40 FCH00370
C C C FCH00380
C C C NFILL=1 FCH00390
C C C FCH00400
C C C NFILES=0 FCH00410
C C C FCH00420
C C C READ FORTRAN UNIT NUMBERS FOR INPUT UNIT, OUTPUT FCH00430
C C C UNIT, DIRECT ACCESS DISK UNIT. FCH00440
C C C FCH00450
C C C READ 15,KINP,KOUTP,KDISK FCH00460
C C C FCH00470
C C C 15 FORMAT(3I6) FCH00480
C C C REWIND KOUTP FCH00490
C C C FCH00500
C C C READ TYPE 1 OR TYPE 2 CONTROL CARD. FCH00510
C C C TYPE 1 - CHANGE A P MATRIX. FCH00520
C C C TYPE 2 - END OF CHANGES. FCH00530
C C C READ: CARD TYPE - LTYPE, NAME OF P MATRIX, FCH00540
C C C SWITCH FOR TYPE OF P POSITIONING, NAME FOR NEW FCH00550
C C C P. FCH00560

```
20 READ 25,LTYPE,NAMEP,INPSW,NUNAME FCH00570
25 FORMAT(16,6A4,16,6A4) FCH00580
C DID THE CARD JUST READ IDENTIFY A P MATRIX TO BEFCH00590
C CHANGED? FCH00600
C NO. GO TO END OF CHANGE PROCESSING. FCH00610
C IF(LTYPE.NE.1) GO TO 700 FCH00620
C C YES FCH00630
C C LTYPE=1. CHANGE A P MATRIX. FCH00640
C C READ TRANSITION MODIFY CHANGE SWITCH, CURRENT FCH00650
C C MODIFY SWITCH, AND CURRENT MODIFY FACTOR. FCH00660
C C READ 490,MODCHG,KURSW,KURFAC FCH00670
C C READ: NULABL - LABEL INFO FOR NEW P, NV - NUMBERFCH00680
C C OF VARIABLES, IVL - NUMBER OF CODES DEFINED PER FCH00690
C C VARIABLE. FCH00700
C C READ 30,NULABL,NV,(IVL(I),I=1,NV) FCH00710
C 30 FORMAT(20A4/10A4/I6/(6I12)) FCH00720
C C COMPUTE NUMBER VARIABLES MINUS ONE FOR LATER DO FCH00730
C C LOOP USE. FCH00740
C C NVMI=NV-1 FCH00750
C C BRANCH ON TYPE OF P POSITIONING. FCH00760
C C IF(INPSW.EQ.1) GO TO 40 FCH00770
C C CALL POSITION INPUT TO LOCATE NAMED FILE. FCH00780
C C CALL POSINP(KINP,KTYPE,NAMEP,NL,LABELP) FCH00790
C C GO TO 45 FCH00800
C C 40 SET KTYPE = 3. CALL POSITION FORWARD TO LOCATE FCH00810
C C NEXT P MATRIX REGARDLESS OF NAME. FCH00820
C C 40 KTYPE=3 FCH00830
C C CALL POSFWD(KINP,KTYPE,NAMEP,NL,LABELP) FCH00840
C C READ P ROW LIST RECORD. FCH00850
C C 45 READ(KINP) KTYPE,ISCNT,(ISNI(I),I=1,ISCNT),MODSW,MODFAC FCH00860
C C READ P COLUMN LIST RECORD. FCH00870
C C READ(KINP) KTYPE,JCOUNT,(LSTCOL(I),I=1,JCOUNT),NUMMO,NUMYR FCH00880
C C PRINT INPUT VALUES OF MODIFY SWITCH SETTINGS ANDFCH00890
C C ROW AND COLUMN COUNTS. FCH00900
C C PRINT 46,MODSW,MODFAC,MODCHG,KURSW,KURFAC,ISCNT,JCOUNT FCH00910
C 46 FORMAT(18H INPUT VALUES FOR / FCH00920
C 18X,5HMODSW,6X,6HMODFAC,6X,6HMODCHG,7X,5HKURSW,6X,6HKURFAC, FCH00930
C 27X,14HNUMBER OF ROWS,6X,17HNUMBER OF COLUMNS/ FCH00940
C 31X,5I12,9X,I12,11X,I12) FCH00950
C C TRANSFER TAPE MODIFY INFO TO CURRENT MODIFY FCH00960
C C FIELDS IF NECESSARY. FCH00970
C C DID THE MODIFY CHANGE CONTROL CARD CONTAIN FCH00980
C C CURRENT MODIFY SWITCH AND FACTOR VALUES? FCH00990
C C IF(MODCHG.EQ.2) GO TO 47 FCH01000
C C NO FCH01010
C C TRANSFER MODIFY SWITCH AND FACTOR VALUES FROM P FCH01020
C C ROW LIST RECORD TO CURRENT MODIFY SWITCH AND FCH01030
C C FACTOR VARIABLES. FCH01040
C C KURSW=MODSW FCH01050
C C KURFAC=MODFAC FCH01060
C C INITIALIZE COUNTERS FOR THIS P MATRIX. FCH01070
C C NUMBER OF COLUMN ELEMENTS SEARCHED FOR. FCH01080
C C FCH01090
C C FCH01100
C C FCH01110
C C FCH01120
C C FCH01130
```

C	47 NSERCH=0	FCH01140
C	NFOUND=0	FCH01150
C	NDCODE=0	FCH01160
C		FCH01170
C		FCH01180
C		FCH01190
C		FCH01200
C		FCH01210
C		FCH01220
C		FCH01230
C		FCH01240
C	II=0	FCH01250
C		FCH01260
C	NN=0	FCH01270
C		FCH01280
C	KCHGSW=0	FCH01290
C		FCH01300
C	MULT(NV)=1	FCH01310
	IF(NV.EQ.1) GO TO 52	FCH01320
	N=NV	FCH01325
	DO 50 I=1,NVM1	FCH01330
	MULT(N-1)=MULT(N)*IVL(N)	FCH01340
50	N=N-1	FCH01350
C		FCH01360
C		FCH01370
C		**FCH01380
C		*FCH01390
C		FCH01400
C	52 ITK=1	FCH01410
C		FCH01420
C	2100 READ(KINP)	FCH01430
1	KTYPE,IROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT)	FCH01440
C	WRITE P RECORD IN NEXT DIRECT ACCESS DATA FILE	FCH01450
C	RECORD.	FCH01460
	WRITE(KDISK,ITK)	FCH01470
1	KTYPE,IROW,JCN1,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT)	FCH01480
C	WAS THIS A P END RECORD?	FCH01490
C	NO	FCH01500
C	GO TO READ NEXT RECORD.	FCH01510
C	IF(KTYPE.NE.33) GO TO 2100	FCH01520
C	YES	FCH01530
C	SET DIRECT ACCESS DATA FILE RECORD NUMBER TO	FCH01540
C	LOCATION OF P END RECORD.	FCH01550
C	ITK=ITK-1	FCH01560
C		FCH01570
C		FCH01580
C	DOES THE NUMBER OF DISK RECORDS WRITTEN AGREE	FCH01590
C	WITH THE NUMBER OF ROWS COUNT IN THE ISN RECORD?	FCH01600
C	IF(ISCNT+1.EQ.ITK) GO TO 140	FCH01610
C		FCH01620
C	NO	FCH01630
C	PRINT ERROR MESSAGE.	FCH01640
C	PRINT 80,ISCNT,ITK	FCH01650
80	FORMAT(42H ERROR IN DISK COPY RECORD COUNT. ISCNT = ,I12,6H ITK = ,	FCH01660
1	I12)	FCH01670
C	EXIT	FCH01680
C	STOP	FCH01690

C LTYPE 3 (SPECIFIC CHANGE) AND FCH02250
C LTYPE 4 (FAMILY CHANGE) BOTH TRANSFER HERE. FCH02260
C
C ROW SEARCH. FCH02270
C IS THERE A ROW RECORD CURRENTLY IN CORE? FCH02280
C NO. SEARCH FOR ROW. FCH02290
170 IF(II.EQ.0) GO TO 172 FCH02300
C YES FCH02310
C IS THE ROW CURRENTLY IN CORE THE SAME AS THE ROW FCH02330
C SPECIFIED FOR THE CHANGE BEING PROCESSED? FCH02340
C YES. GO TO BRANCH ON TYPE OF CHANGE. FCH02350
C IF(ISN(II).EQ.IDROW) GO TO 195 FCH02360
C NO FCH02370
C IS THERE A CHANGED ROW THAT NEEDS TO BE WRITTEN. FCH02380
C NO. SEARCH FOR LATEST ROW SPECIFIED. FCH02390
C IF(KCHGSH.EQ.0) GO TO 172 FCH02400
C YES, FCH02410
C CHANGES HAVE BEEN MADE IN THE ROW RECORD IN FCH02420
C CORE. WRITE THE CHANGED RECORD ON DISK. FCH02430
C SET RANDOM ACCESS RECORD NUMBER EQUAL ROW NUMBER FCH02440
C SUBSCRIPT. FCH02450
C ITK=II FCH02460
C WRITE ROW RECORD ON DISK. FCH02470
1 WRITE(KDISK,ITK) FCH02480
C KTYPE,ISN(II),JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH02490
C
C SET KCHGSH TO ZERO TO INDICATE NO CHANGES IN FCH02510
C CORE RECORD THAT ARE NOT ON DISK. FCH02520
C KCHGSH=0 FCH02530
C CHECK ROW LIST FOR PRESENCE OF ROW FOR WHICH FCH02540
C CHANGE IS SPECIFIED. FCH02550
172 DO 175 II=1,ISCNT FCH02560
IF(ISN(II).LT.IDROW) GO TO 175 FCH02570
IF(ISN(II).EQ.IDROW) GO TO 190 FCH02580
GO TO 176 FCH02590
175 CONTINUE FCH02600
C
C ROW DOES NOT EXIST. FCH02620
C II IS UNDEFINED FOLLOWING NORMAL EXIT FROM THE FCH02630
C DO 175 LOOP. FCH02640
C SET II TO ZERO TO INDICATE NO ROW RECORD IN CORE FCH02650
176 II=0 FCH02660
C GO TO NEXT CHANGE. FCH02670
C IS THIS A SPECIFIC CHANGE? FCH02680
C YES. GO TO READ NEXT CARD. FCH02690
C IF(KPSS.EQ.1) GO TO 140 FCH02700
C NO FCH02710
C FAMILY CHANGE. FCH02720
C GO TO CODE NEXT ROW NUMBER. FCH02730
C GO TO 500 FCH02740
C
C 190 FCH02750
C YES FCH02760
C ROW EXISTS. FCH02770
C SET TRACK NUMBER EQUAL ISN SUBSCRIPT. FCH02780
190 ITK=II FCH02790
C READ DATA RECORD FOR IDROW FROM DISK. FCH02800
C FCH02810

```
READ(KDISK'ITK) FCH02820
I KTY,E,IROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH02830
C SFT NUMBER OF CHANGES MADE IN THIS RECORD TO FCH02840
C ZERO. FCH02850
C KCHGSW=0 FCH02860
C IS THIS A FAMILY CHANGE ROW? FCH02870
C YES. GO TO INITIALIZE NON-FREE COL CODES FOR ROW FCH02880
195 IF(KPASS.EQ.3) GO TO 510 FCH02890
C * FCH02900
C * FCH02910
C **** FCH02920
C NO FCH02930
C THIS IS THE SPFCIFIC CHANGE PATH. THE ELEMENT TO FCH02940
C BE LOCATED NEXT IS THE NONFREE COLUMN. FCH02950
200 ICOL=IDCOL FCH02960
C FCH02970
C **** FCH02980
C * FCH02990
C * FCH03000
C SEARCH THE ROW RECORD IN CORE FOR A SPECIFIC FCH03010
C COLUMN NUMBER. FCH03020
C THE VARIABLE 'ICOL' CONTAINS THF COLUMN NUMBER FCH03030
C TO BE LOCATED. FCH03040
C FCH03050
C 210 FCH03060
C PROGRAM PATHS FOR KPASS=1,2,3 AND 4 ALL TRANSFER FCH03070
C TO THIS POINT IN THE PROGRAM. FCH03080
C KPASS 1 - SPECIFIC CHANGE NON FREE COLUMN. FCH03090
C KPASS 2 - SPECIFIC CHANGE FREE COLUMN. FCH03100
C KPASS 3 - FAMILY CHANGE NON FREE COLUMN. FCH03110
C KPASS 4 - FAMILY CHANGE FREE COLUMN. FCH03120
C FCH03130
C IS THE SPECIFIED COLUMN PRESENT? FCH03140
210 DO 220 IJ=1,JCNT FCH03150
IF(JCOL(IJ).LT.ICOL) GO TO 220 FCH03160
C YES. GO TO BRANCH ON TYPE OF PASS. FCH03170
IF(JCOL(IJ).EQ.ICOL) GO TO 275 FCH03180
C NO FCH03190
C ICOL NOT PRESENT. GT THAN CURRENT JCOL ENTRY. FCH03200
C ICOL IS LESS THAN THE LARGEST COLUMN NUMBER IN FCH03210
C THE ROW. THE PRESENT IJ SETTING IS THE POSITION FCH03220
C WHERE THIS COLUMN WOULD BE STORED IF IT WERE FCH03230
C ADDED TO THE ROW. FCH03240
C GO TO BRANCH ON TYPE OF PASS. FCH03250
C FCH03260
C GO TO 225 FCH03270
C CONTINUF. FCH03280
220 CONTINUE FCH03290
C NO FCH03300
C ICOL NOT PRESENT. FCH03310
C ICOL IS GREATER THAN LARGEST COLUMN NUMBER IN FCH03320
C THE ROW. FCH03330
C SET SUBSCRIPT TO POSITION WHERE ICOL ELEMENT FCH03340
C WOULD BE STORED IF IT WERE ADDED TO THE ROW. FCH03350
C FCH03360
IJ=JCNT+1 IF THE ELEMENT NOT PRESENT IS A NON-FREE ELEMENT FCH03370
C GO TO THE NEXT CHANGE. FCH03380
C IS THIS A NON-FREE ELEMENT (SPECIFIC CHANGE)? FCH03380
```

C YES. GO TO READ NEXT CARD. FCH03390
C 225 IF(KPASS.EQ.1) GO TO 140 FCH03400
C NO FCH03410
C IS THIS A NON-FREE ELEMENT (FAMILY CHANGE)? FCH03420
C YES. GO TO CODE NEXT COLUMN NUMBER. FCH03430
C IF(KPASS.EQ.3) GO TO 530 FCH03440
C NO FCH03450
C THE ELEMENT NOT PRESENT IS A FREE ELEMENT. FCH03460
C DO NOT ADD FREE ELEMENT TIL CHANGE OF A NON-FREE FCH03470
C ELEMENT REQUIRES IT. FCH03480
C SET SWITCH TO INDICATE FREE ELEMENT IS NOT FCH03490
C PRESENT. FCH03500
C KFRSW=1 FCH03510
C FREE AMOUNT IS THEREFORE EQUAL 0. FCH03520
C AMTFR=0.0 FCH03530
C GO TO 300 FCH03540
C
C YES - SPECIFIED COLUMN IS PRESENT. FCH03550
C BRANCH ON ELEMENT TYPE AND TYPE OF CHANGE. FCH03560
C 275 GO TO(280,295,280,295),KPASS FCH03570
C 280 FCH03580
C KPASS=1,3 FCH03590
C NON FREE ELEMENT. FCH03600
C SET NON FREE AMOUNT AND SUBSCRIPT. FCH03610
C
C 280 AMTNF=P(IJ) FCH03620
C IJNF=IJ FCH03630
C IS THIS A SPECIFIC CHANGE? FCH03640
C IF(KPASS.NE.3) GO TO 285 FCH03650
C NO FCH03660
C THIS IS A FAMILY CHANGE. FCH03680
C ADD 1 TO COUNT OF NUMBER OF ELEMENTS FOUND. FCH03690
C NFOUND=NFOUND+1 FCH03700
C GO TO MAKE CHANGE. FCH03710
C GO TO 317 FCH03720
C
C 285 ICOL=IFRCOL FCH03730
C KPASS=2 FCH03740
C GO TO 210 FCH03750
C
C 295 KPASS=2,4 FCH03760
C FREE ELEMENT IS PRESENT. FCH03770
C SET FREE AMOUNT. FCH03780
C
C 295 AMTFR=P(IJ) FCH03790
C
C 300 FCH03800
C FREE ELEMENT NOT PRESENT ALSO TRANSFERS HERE. FCH03810
C SET FREE ELEMENT SUBSCRIPT. FCH03820
C WHEN KFRSW=0, IJFR IS THE LOCATION IN JCOL OF FCH03830
C THE FREE ELEMENT. FCH03840
C WHEN KFRSW=1, IJFR IS THE LOCATION IN JCOL WHERE FCH03920
C THE FREE ELEMENT IS TO BE ADDED. FCH03930
C 300 IJFR=IJ FCH03940
C IS THIS A FAMILY CHANGE. FCH03950

C YES. GO TO NON-FREE COLUMN PROCESSING. FCH03960
C IF(KPASS.EQ.4) GO TO 524 FCH03970
C NO FCH03980
C * FCH03990
C * FCH04000
C **** FCH04010
C FCH04020
C **** FCH04030
C * FCH04040
C * FCH04050
C FCH04060
C FCH04070
C AMTFR IS RESET AT THIS POINT BECAUSE FAMILY FCH04080
C CHANGE CAN MAKE SEVERAL CHANGES IN THE SAME ROW. FCH04090
C RESET THE FREE ELEMENT WORKING VALUE IF THE FCH04100
C ELEMENT IS PRESENT. FCH04110
317 IF(KFRSW.EQ.0) AMTFR=P(IJFR) FCH04120
C COMPUTE AMOUNT OF CHANGE REQUESTED. FCH04130
AAMTC=PCCHG*AMTNF FCH04140
C IS THE TOTAL CHANGE REQUESTED POSSIBLE... FCH04150
C ALL CHANGES DECREASING THE NON-FREE ELEMENT WILL FCH04160
C BE POSSIBLE. FCH04170
C YES. GO TO PROCESS CHANGE. FCH04180
IF(AMTFR-AMTC.GE.0.000) GO TO 330 FCH04190
NO FCH04200
PRINT MESSAGE SAYING TOTAL CHANGE NOT POSSIBLE FCH04210
FOR CURRENT ROW AND COLUMN. FCH04220
319 PRINT 320, IDROW, IDCOL, AMTNF, IFRCOL, AMTFR, AMTC FCH04230
320 FORMAT(4H ROW, I12, 4H COL, I12, 6H VALUE, F9.5, 9H FREE COL, I12, 6H VALUFCH04240
1E, F9.5/15H DESIRED CHANGE, F9.5, 17H IS NOT POSSIBLE.) FCH04250
C IS ANY CHANGE POSSIBLE? FCH04260
C YES. GO TO RESET AMOUNT OF CHANGE. FCH04270
IF(AMTFR.NE.0.000) GO TO 325 FCH04280
C NO. GO TO NEXT SPECIFIC CHANGE -- OR - NEXT ROW. FCH04290
IF(KPASS.EQ.2) GO TO 140 FCH04300
GO TO 500 FCH04310
FCH04320
325 325 FCH04330
C YES. SOME CHANGE IS POSSIBLE. FCH04340
C SET AMOUNT OF CHANGE TO BE MADE EQUAL AMOUNT OF FCH04350
C CHANGE POSSIBLE. FCH04360
325 AMTC=AMTFR FCH04370
C PROCESS CHANGE - BOTH ALL OR PART. FCH04380
C CHANGE NON-FREE ELEMENT. FCH04390
330 AMTNF=AMTNF+AMTC FCH04400
P(IJNF)=AMTNF FCH04410
C AMTFR=AMTFR-AMTC FCH04420
C CHANGE WORKING VALUE OF FREE ELEMENT. FCH04430
C BRANCH ON FREE ELEMENT PRESENT SWITCH. IS FREE FCH04440
C ELEMENT TO BE ADDED?
YES. GO TO ADD ELEMENT. FCH04450
IF(KFRSW.NE.0) GO TO 340 FCH04460
NO. FCH04470
CHANGE VALUE OF FREE ELEMENT. FCH04480
P(IJFR)=AMTFR FCH04490
GO TO UPDATE CHANGE COUNTS. FCH04500
GO TO 380 FCH04510
FCH04520

C ***FCH04530
C *FCH04540
C FCH04550
C FCH04560
C FCH04570
C FCH04580
C FCH04590
C FCH04600
C FCH04610
C FCH04620
C FCH04630
C FCH04640
C FCH04650
C FCH04660
C FCH04670
C FCH04680
C FCH04690
C FCH04700
C FCH04710
C FCH04720
C FCH04730
C FCH04740
C FCH04750
C FCH04760
C FCH04770
C FCH04780
C FCH04790
C FCH04800
C FCH04810
C FCH04820
C FCH04830
C FCH04840
C FCH04850
C FCH04860
C FCH04870
C FCH04880
C FCH04890
C FCH04900
C FCH04910
C FCH04920
C FCH04930
C **FCH04940
C *FCH04950
C FCH04960
C FCH04970
C FCH04980
C FCH04990
C FCH05000
C FCH05010
C FCH05020
C FCH05030
C FCH05040
C FCH05050
C FCH05060
C FCH05070
C FCH05080
C FCH05090

C 340
C YES
C FREE ELEMENT MUST BE ADDED TO A ROW.
C IS FREE ELEMENT TO BE ADDED AT END OF ROW?
C 340 IF(IJFR.GT.JCNT) GO TO 345
C NO
C CALL TMT2 TO PUSH DOWN COLUMN NUMBER ARRAY AND
C COLUMN VALUE ARRAY SO THAT THE FREE ELEMENT MAY
C BE ADDED IN THE MIDDLE OF THE ROW.
C CALL TMT2(JCOL(IJFR),JCOL(IJFR+1),JCNT-IJFR+1)
C CALL TMT2(P(IJFR),P(IJFR+1),2*(JCNT-IJFR+1))
C ADD 1 TO NUMBER OF ELEMENTS IN THE ROW.
C 345 JCNT=JCNT+1
C DOES NUMBER OF ELEMENTS PRESENT NOW EXCEED ARRAY
C DIMENSION?
C YES. GO TO PRINT ERROR MESSAGE AND EXIT.
C IF(JCNT.GT.NDIM) GO TO 730
C NO
C PLACE FREE COLUMN NUMBER IN COLUMN LIST.
C JCOL(IJFR)=IFRCOL
C PLACE FREE COLUMN VALUE IN VALUE LIST.
C P(IJFR)=AMTR
C CHANGE FREE ELEMENT PRESENT SWITCH TO SHOW
C ELEMENT IS PRESENT.
C KFRSW=0
C IS THIS A DECODE PROCEDURE FAMILY CHANGE?
C IF(KPASS.NE.5) GO TO 346
C YES
C SET DO LOOP CONTROLS TO MAINTAIN PROPER
C POSITION IN DECODE LOOP.
C JFR=J+1
C IF(IJFR.LE.J) JFR=JFR+1
C JTO=JCNT
C 346
C IS TRANS MODIFY BEING BYPASSED...
C YES. ADD FREE COLUMN TO MATRIX LIST OF COLUMNS,
C IF NECESSARY.
C 346 IF(KURSW.LT.0) GO TO 358
C NO
C TRANSITION MODIFY OPERATION.
C ADD THE COLUMN OF THE FREE ELEMENT TO THE NEW
C ROWS ARRAY IF NECESSARY.
C IS THERE A ROW IN THE ISN LIST CORRESPONDING TO
C THE COLUMN OF THE FREE ELEMENT JUST ADDED.
C YES. GO TO CHECK THE COLUMN LIST.
C DO 348 I=1,ISCNT
C IF(ISN(I).GE.IFRCOL) GO TO 354
C 348 CONTINUE
C 349
C NO
C COL OF NEW ELEMENT NOT IN ISN.
C NN IS NUMBER OF ENTRIES IN NUROWS.

C IS THE ADDED ELEMENT IN THE NUROWS ARRAY? FCH05100
349 IF(NN.EQ.0) GO TO 356 FCH05110
DO 350 N=1,NN FCH05120
IF(NUROWS(N).GE.IFRCOL) GO TO 352 FCH05130
350 CONTINUE FCH05140
C NO FCH05150
C ADD ELEMENT AT END OF NEW ROWS ARRAY. FCH05160
NN=NN+1 FCH05170
NUROWS(NN)=IFRCOL FCH05180
GO TO 358 FCH05190
C FCH05200
352 IF(IFRCOL.EQ.NUROWS(N)) GO TO 358 FCH05210
C FILE ADDED ELEMENT IN NUROWS ARRAY AT POSITION NFCH05220
CALL TMT2(NUROWS(N),NUROWS(N+1),NN-N+1) FCH05230
NUROWS(N)=IFRCOL FCH05240
NN=NN+1 FCH05250
GO TO 358 FCH05260
C FCH05270
354 IF(IFRCOL.EQ.ISN(I)) GO TO 358 FCH05280
GO TO 349 FCH05290
C FCH05300
C FIRST ENTRY IN NEW ROWS ARRAY. FCH05310
356 NN=1 FCH05320
NUROWS(NN)=IFRCOL FCH05330
GO TO 358 FCH05340
C *FCH05350
C **FCH05360
C IS THERE A COLUMN IN LSTCOL CORRESPONDING TO THEFCH05370
C ... --- COLUMN OF THE FREE ELEMENT JUST ADDED... FCH05380
C ADD ELEMENT TO LSTCOL IF NECESSARY. FCH05390
358 DO 360 I=1,JCOUNT FCH05400
IF(LSTCOL(I).GE.IFRCOL) GO TO 364 FCH05410
360 CONTINUE FCH05420
C FREE COL JUST ADDED NOT IN LSTCOL. ADD AT END. FCH05430
JCOUNT=JCOUNT+1 FCH05440
LSTCOL(JCOUNT)=IFRCOL FCH05450
GO TO 380 FCH05460
C FCH05470
364 IF(IFRCOL.EQ.LSTCOL(I)) GO TO 380 FCH05480
C ADD COL AT POSITION I. FCH05490
CALL TMT2(LSTCOL(I),LSTCOL(I+1),JCOUNT-I+1) FCH05500
LSTCOL(I)=IFRCOL FCH05510
JCOUNT=JCOUNT+1 FCH05520
C *FCH05530
C ***FCH05540
C 380 FCH05550
C TRANSFER HERE FCH05560
C (1) WHEN CHANGE HAS BEEN MADE AND FREE ELEMENT FCH05570
C WAS PRESENT, AND FCH05580
C (2) WHEN CHANGE HAS BEEN MADE, FREE ELEMENT HAS FCH05590
C BEEN ADDED, AND NECESSARY ROW LIST AND COLUMN FCH05600
C LIST ADDITIONS HAVE BEEN PROCESSED. FCH05610
C FCH05620
C ADD 1 TO MATRIX CHANGE COUNT. FCH05630
380 NCHG=NCHG+1 FCH05640
C ADD 1 TO ROW CHANGE COUNT. FCH05650
KCHGSW=KCHGSW+1 FCH05660

C GO TO NEXT CHANGE BY TYPE OF CHANGE JUST FCH05670
C PROCESSED. FCH05680
C WAS THIS A FAMILY CODE PROCEDURE CHANGE? FCH05690
C YES. GO TO CODE NEXT COLUMN. FCH05700
C IF(KPASS.EQ.3) GO TO 530 FCH05710
C NO FCH05720
C WAS THIS A FAMILY DECODE PROCEDURE CHANGE? FCH05730
C YES. GO TO LOCATION IN DECODE SEGMENT OF PROGRAM FCH05740
C AS DETERMINED BY CURRENT VALUES OF J DO LOOP FCH05750
C INDICES. FCH05760
C IF(KPASS.EQ.5.AND.JFR.LE.J) GO TO 550 FCH05770
C IF(KPASS.EQ.5.AND.JFR.GT.J) GO TO 541 FCH05780
C NO FCH05790
C THIS WAS A SPECIFIC CHANGE. FCH05800
C GO TO READ NEXT CHANGE CARD. FCH05810
C GO TO 140 FCH05820
C * FCH05830
C * FCH05840
C * FCH05850
C **** FCH05860
C FCH05870
C CARD TYPE 4 - FAMILY CHANGE. FCH05880
C PICK UP PROCEDURE CODE FROM CARD FIELD IDROW. FCH05890
C 480 KPROC=IDROW FCH05900
C READ THE VARIABLE CODE RANGES FOR THE FAMILY FCH05910
C CHANGE. FCH05920
C FOR EACH VARIABLE, READ INDEX VALUES INTO THE FCH05930
C FOLLOWING ARRAYS:
C IRFR-ROW FROM VALUE. FCH05940
C IRT0-ROW TO VALUE. FCH05950
C ICFR-NON FREE COLUMN FROM VALUE. FCH05960
C ICTO-NON FREE COLUMN TO VALUE. FCH05970
C IFR-FREE COLUMN VALUE. FCH05980
C READ 490,(IRFR(I),I=1,NV) FCH05990
C READ 490,(IRT0(I),I=1,NV)
C READ 490,(ICFR(I),I=1,NV)
C READ 490,(ICTO(I),I=1,NV)
C READ 490,(IFR (I),I=1,NV)
C 490 FORMAT(6I12) FCH06000
C SET NON-FREE COLUMN SWITCH AND FREE COLUMN FCH06010
C SWITCH ARRAYS TO ZERO. FCH06020
C ICSW(1)=0 FCH06030
C IF(NVM1.NE.0) CALL TMT(NVM1,ICSW(2),ICSW(1)) FCH06040
C CALL TMT (NV,IFSW(1),ICSW(1)) FCH06050
C SET A SWITCH FOR EACH -9 (INDICATING CURRENT FCH06060
C VALUE OF ROW INDF. IS TO BE USED AS THE COLUMN FCH06070
C INDEX) IN FREE COL AND NON-FREE COL RANGES. FCH06080
C DO 495 I=1,NV FCH06090
C IF (ICFR(I).EQ.(-9)) ICSW(I)=1 FCH06100
C IF (IFR(I).EQ.(-9)) IFSW(I)=1 FCH06110
C 495 CONTINUE FCH06120
C SET ROW CURRENT INDEX VALUES EQUAL ROW FROM FCH06130
C INDEX VALUES. FCH06140
C CALL TMT (NV,IRCR(1),IRFR(1)) FCH06150
C SUBTRACT ONE FROM CURRENT ROW FROM-INDEX VALUE FCH06160
C FOR LAST VARIABLE. FCH06170
C ICR(NV)=IRFR(NV)-1 FCH06180
C FCH06190
C FCH06200
C FCH06210
C FCH06220
C FCH06230

C INITIAL SETTING FOR ROW VARIABLE CURRENTLY BEING FCH06240
C NCR=NV FCH06250
C INCREMENTED IS THE LAST VARIABLE. FCH06260
C
C 500 **FCH06270
C CODE A ROW NUMBER. FCH06280
C
C 500 CONTINUE FCH06290
C 1001 FCH06300
C IS CURRENT VALUE OF VARIABLE BEING INCREMENTED FCH06310
C EQUAL TO-VALUE OF THAT VARIABLE? FCH06320
C YES. GO TO STEP VARIABLE NUMBER. FCH06330
C
1001 IF(IRCR(NCR).EQ.IRTO(NCR)) GO TO 1019 FCH06340
C NO FCH06350
C ADD 1 TO CURRENT VALUE OF VARIABLE BEING INCRE- FCH06360
C MENTED. FCH06370
C
C ICR(NCR)=ICR(NCR)+1 FCH06380
C IS THE VARIABLE BEING INCREMENTED THE LAST VARI- FCH06390
C ABLE? FCH06400
C YES. GO TO COMPUTE ROW NUMBER. FCH06410
C
C IF(NCR.EQ.NV) GO TO 1008 FCH06420
C NO FCH06430
C RESET ALL 'INNER DO'S' TO THEIR BEGINNING VALUE. FCH06440
C
C NC1=NCR+1 FCH06450
C DO 1006 I=NC1,NV FCH06460
C ICR(I)=IRFR(I) FCH06470
C VARIABLE TO BE INCREMENTED NEXT WILL BE THE FCH06480
C INNERMOST DO. FCH06490
C
C NCR=NV FCH06500
C 1008 1008 FCH06510
C COMPUTE STATE NUMBER. FCH06520
C SET IDROW=0 FCH06530
C
C 1008 IDROW=0 FCH06540
C IS CURRENT VALUE OF VARIABLE 1.EQ.0? FCH06550
C YES. ROW WILL BE ROW ZERO. FCH06560
C
C IF(ICR(I).EQ.0) GO TO 1024 FCH06570
C NO FCH06580
C
C IF(NV.EQ.1) GO TO 1012 FCH06590
C DO 1010 I=1,NVM1 FCH06600
C IDROW=IDROW+(ICR(I)-1)*MULT(I) FCH06610
C 1010 IDROW=IDROW+ICR(NV) FCH06620
C
C 1012 END OF CODE A ROW NUMBER. FCH06630
C
C GO TO 1024 FCH06640
C
C 1019 1019 FCH06650
C YES FCH06660
C FOR VARIABLE BEING INCREMENTED, CURRENT VALUE IS FCH06670
C EQUAL TO-VALUE. FCH06680
C
C 1019 IF(INCR.EQ.1) GO TO 1022 FCH06690
C NO FCH06700
C DECREASE NUMBER OF VARIABLE BEING INCREMENTED BY FCH06710
C ONE. FCH06720
C
C NCR=NCR-1 FCH06730
C GO TO 1001 FCH06740
C
C YES FCH06750
C ALL INDEX VALUES FOR ALL VARIABLES HAVE BEEN FCH06760
C PROCESSED. FCH06770
C FCH06780
C FCH06790

C PLACE -1 IN ROW NUMBER VARIABLE. FCH06800
C 1022 IDROW=-1 FCH06810
C 1024 CONTINUE FCH06820
C END OF CODE A ROW NUMBER. FCH06830
C *FCH06840
C **FCH06850
C HAVE ALL ROW NUMBERS BEEN GENERATED? FCH06860
C YES FCH06880
C GO TO READ NEXT CONTROL CARD. FCH06890
C IF(IDROW.LT.0) GO TO 140 FCH06900
C NO FCH06910
C SET KPASS=3. GO TO ROW SEARCH. FCH06920
C AT THE COMPLETION OF THE ROW SEARCH, THERE WILL FCH06930
C BE A TRANSFER TO (1) 510 IF THE ROW IS PRESENT FCH06940
C AND (2) 500 IF THE ROW IS NOT PRESENT. FCH06950
C FCH06960
C KPASS=3 FCH06970
C GO TO 170 FCH06980
C FCH06990
C FCH07000
C 510 FCH07010
C FAMILY CHANGE: ROW IS PRESENT AND HAS BEEN READ. FCH07020
C 510 CONTINUE FCH07030
C 1025 FCH07040
C **FCH07050
C *FCH07060
C INITIALIZE COLUMN CODE VALUES TO BE USED IN PRO- FCH07070
C cessing the row just read. FCH07080
C FCH07090
C SET ARRAY FOR CURRENT CODE VALUES FOR COLUMN FCH07100
C (ICCR) EQUAL INITIAL CODE VALUES FOR COLUMN FCH07110
C (ICFR). FCH07120
C 1025 CALL TMT(NV,ICCR(1),ICFR(1)) FCH07130
C SUBTRACT 1 FROM NVTH ENTRY IN ICCR. FCH07140
C ICCR(NV)=ICFR(NV)-1 FCH07150
C INITIAL SETTING FOR COLUMN VARIABLE CURRENTLY FCH07160
C BEING INCREMENTED IS LAST VARIABLE. FCH07170
C MCR=NV FCH07180
C 1026 FCH07190
C DO 1028 I=1,NV FCH07200
C IS SWITCH SET INDICATING THAT CURRENT ROW CODES FCH07210
C ARE TO BE USED FOR NON FREE COLUMN CODES? FCH07220
C 1027 FCH07230
C IF(ICSW(I).EQ.0) GO TO 1027 FCH07240
C YES FCH07250
C FOR THIS VARIABLE SET CURRENT INDEX, FROM INDEX FCH07260
C AND TO INDEX FOR THIS COLUMN EQUAL THE VALUE OF FCH07270
C THIS CODE FOR THE CURRENT ROW. FCH07280
C FCH07290
C FCH07300
C ICCR(I)=IRCR(I) FCH07310
C ICFR(I)=IRCR(I) FCH07320
C ICTD(I)=IRCR(I) FCH07330
C 1027 FCH07340
C IS SWITCH SET INDICATING THAT CURRENT ROW CODES FCH07350
C ARE TO BE USED FOR NON FREE COLUMN CODES? FCH07360

1027	IF(IFSW(I).EQ.0) GO TO 1028	FCH07370
C	YES	FCH07380
C	SET FREE COLUMN CODE EQUAL CURRENT CODE FOR ROW.	FCH07390
C	IFR(I)=ICCR(I)	FCH07400
C	1028	FCH07410
C	CONTINUE	FCH07420
1028	CONTINUE	FCH07430
C	1029	FCH07440
C	IF THE CURRENT ROW VALUE IS TO BE USED FOR THE	FCH07450
C	NVTH COLUMN VALUE, DECREASE THIS VALUF BY 1.	FCH07460
1029	IF(ICSW(NV).EQ.1) ICCR(NV)=ICFR(NV)-1	FCH07470
C	END OF INITIALIZE COLUMN CODE VALUES.	FCH07480
C	*	FCH07490
C	**	FCH07500
C	1030	FCH07510
C	GENERATE FREE COLUMN NUMBER.	FCH07520
C	INITIALIZE IFRCOL TO ZERO.	FCH07530
1030	IFRCOL=0	FCH07540
C	IS THE CURRENT VALUE OF VARIABLE 1 EQUAL 0?	FCH07550
C	YES. FREE COLUMN WILL BE COLUMN ZERO.	FCH07560
C	IF(IFR(I).EQ.0) GO TO 1034	FCH07570
C	NO	FCH07580
C	COMPUTE STATE NUMBER.	FCH07590
C	IF(NV.EQ.1) GO TO 1033	FCH07595
C	DO 1032 I=1,NVM1	FCH07600
1032	IFRCOL=IFRCOL+(IFR(I)-1)*MULT(I)	FCH07610
1033	IFRCOL=IFRCOL+IFR(NV)	FCH07620
C	1034	FCH07630
C	CONTINUE	FCH07640
1034	CONTINUE	FCH07650
C	END OF GENERATE FREE COLUMN NUMBER.	FCH07660
C	SET KPASS, ICOL, AND KFRSW FOR USE IN FREE	FCH07670
C	COLUMN SEARCH.	FCH07680
KPASS=4		FCH07690
ICOL=IFRCOL		FCH07700
KFRSW=0		FCH07710
C	GO TO COLUMN SEARCH SEGMENT OF PROGRAM.	FCH07720
C	AT THE COMPLETION OF THE COLUMN SEARCH, THE	FCH07730
C	PROGRAM WILL TRANSFER TO 524.	FCH07740
C	GO TO 210	FCH07750
C	FREE ELEMENT SEARCH COMPLETE AND SWITCH SET.	FCH07760
C	IF FREE ELEMENT IS NOT PRESENT AND PERCENT	FCH07770
C	CHANGE IS POSITIVE, NO CHANGE IS POSSIBLE FOR	FCH07780
C	THIS ROW. GO TO NEXT ROW.	FCH07790
524	IF(KFRSW.GT.0.AND.PCCHG.GT.0.0) GO TO 500	FCH07800
C	CONTINUE WITH CHANGES FOR THIS ROW.	FCH07810
C	BRANCH ON PROCEDURE CODE.	FCH07820
C	525 GO TO (530,540),KPROC	FCH07830
C		FCH07840
C		FCH07850
C	CODE	**FCH07860
C	PROCEDURE 1 - CODE NON FREE COLUMN NUMBERS.	*FCH07870
C	530 CONTINUE	FCH07880
C	1040	FCH07890
C	CODE A NON FREE COLUMN NUMBER.	FCH07900
C		FCH07910
C		FCH07920

C IS CURRENT VALUE OF VARIABLE BEING INCREMENTED FCH07930
C EQUAL TO VALUE OF THAT VARIABLE? FCH07940
C YES. GO TO STEP VARIABLE NUMBER. FCH07950
1040 IF(ICCR(MCR).EQ.ICTO(MCR)) GO TO 1056 FCH07960
C NO FCH07970
C ADD 1 TO CURRENT VALUE OF VARIABLE BEING INCRE- FCH07980
C MENTED. FCH07990
ICCR(MCR)=ICCR(MCR)+1 FCH08000
C IS THE VARIABLE BEING INCREMENTED THE LAST VARI- FCH08010
C ABLE? FCH08020
C YES. GO TO COMPUTE COLUMN NUMBER. FCH08030
IF(MCR.EQ.NV) GO TO 1048 FCH08040
C NO FCH08050
C RESET ALL 'INNER DO'S' TO THEIR BEGINNING VALUE. FCH08060
MC1=MCR+1 FCH08070
DO 1046 I=MC1,NV FCH08080
ICCR(I)=ICFR(I) FCH08090
C VARIABLE TO BE INCREMENTED NEXT WILL BE THE FCH08100
C INNERMOST DO. FCH08110
MCR=NV FCH08120
1048 FCH08130
COMPUTE STATE NUMBER. FCH08140
INITIALIZE COLUMN NUMBER VARIABLE TO ZERO FCH08150
IDCOL=0 FCH08160
IS CURRENT VALUE OF VARIABLE 1.EQ.0? FCH08170
YES. COLUMN WILL BE COLUMN ZERO. FCH08180
IF(ICCR(1).EQ.0) GO TO 1062 FCH08190
C NO FCH08200
IF(NV.EQ.1) GO TO 1053 FCH08205
DO 1052 I=1,NVM1 FCH08210
IDCOL=IDCOL+(ICCR(I)-1)*MULT(I) FCH08220
1053 IDCOL=IDCOL+ICCR(NV) FCH08230
C CONTINUE FCH08240
GO TO 1062 FCH08250
1056 FCH08260
IS THE VARIABLE BEING INCREMENTED THE FIRST ONE? FCH08270
IF(MCR.EQ.1) GO TO 1060 FCH08280
C NO FCH08290
DECREASE VARIABLE BEING INCREMENTED BY ONE. FCH08300
MCR=MCR-1 FCH08310
GO TO 1040 FCH08320
C YES FCH08330
ALL INDEX VALUES FOR ALL VARIABLES HAVE BEEN FCH08340
C PROCESSED. FCH08350
PLACE -1 IN COLUMN NUMBER VARIABLE. FCH08360
1040 IDCOL=-1 FCH08370
C 1062 FCH08380
C CONTINUE FCH08390
END OF CODE A COL NUMBER. FCH08400
C HAVE ALL COLUMNS IN CURRENT ROW BEEN PROCESSED? FCH08410
C YES - GO TO NEXT ROW. FCH08420
IF(IDCOL.LT.0) GO TO 500 FCH08430
C NO - PROCESS NEXT COLUMN. FCH08440
ADD 1 TO COUNT OF NUMBER OF SEARCHES MADE. FCH08450
NSFRCH=NSERCH+1 FCH08460
FCH08470
FCH08480

C SET KPASS AND ICOL FOR USE IN COLUMN SEARCH. FCH08490
C KPASS=3 FCH08500
C ICOL=IDCOL FCH08510
C *FCH08520
C **FCH08530
C GO TO 210 FCH08540
C FCH08550
C GO TO COLUMN SEARCH SEGMENT OF PROGRAM. FCH08560
C IF THE ELEMENT IS PRESENT, PROGRAM WILL TRANSFER FCH08570
C TO 317 TO MAKE A CHANGE. FCH08580
C IF THE ELEMENT IS NOT PRESENT, PROGRAM WILL FCH08590
C TRANSFER TO 530 TO CODE NEXT COLUMN NUMBER. FCH08600
C FCH08610
C **FCH08620
C DECODE FCH08630
C PROCEDURE 2 - DECODE EACH COLUMN PRESENT. FCH08640
C SET INITIAL VALUES FOR THE DO LOOP FOR THE LIST FCH08650
C OF COLUMNS IN A ROW. FCH08660
C 540 JFR=1 FCH08670
C JTO=JCNT FCH08680
C GO TO 542 FCH08690
C FCH08700
C TRANSFER HERE FOLLOWING A CHANGE THAT CAUSED THE FCH08710
C FREE ELEMENT TO BE ADDED TO THE ROW. FCH08720
C HAVE ALL COLUMN ELEMENTS BEEN PROCESSED? FCH08730
C YES. GO TO CODE NEXT ROW NUMBER. FCH08740
C 541 IF(JFR.GT.JCNT) GO TO 500 FCH08750
C 542 FCH08760
C NO FCH08770
C FCH08780
C DECODE A COLUMN NUMBER. COMPARE CODES WITH FCH08790
C FAMILY CHANGE SPECIFICATIONS. FCH08800
C FCH08810
C DO FOR EACH ELEMENT IN THE ROW. FCH08820
C FCH08830
C 542 DO 550 J=JFR,JTO FCH08840
C FCH08850
C NDCODE=NDCODE+1 FCH08860
C FCH08870
C DECODE JTH ELEMENT IN ROW AND COMPARE WITH FCH08880
C FAMILY CHANGE SPECIFICATION. FCH08890
C 1071 IS COLUMN NUMBER ZERO... FCH08900
C 1071 IF(JCOL(J).NE.0) GO TO 1074 FCH08910
C YES. SET ALL VARIABLE CODE VALUES TO ZER0. FCH08920
C DO 1072 I=1,NV FCH08930
C 1072 IACT(I)=0 FCH08940
C GO TO 1086 FCH08950
C 1074 FCH08960
C NON-ZERO COLUMN NUMBER. DECODE TO OBTAIN FCH08970
C ORIG'NAL VARIABLE CODES. FCH08980
C 1074 I2=JCOL(J) FCH08990
C IF(NV.EQ.1) GO TO 1085 FCH08995
C DO 1084 I=1,NVM1 FCH09000
C I1=(I2-1)/MULT(I) FCH09010
C I2=I2-I1*MULT(I) FCH09020
C 1084 IACT(I)=I1+1 FCH09030
C 1085 IACT(NV)=I2 FCH090 ')

C 1086 1086 FCH09050
C ARE ALL CODES FOR THIS COLUMN NUMBER IN THE FCH09060
C SPECIFIED RANGE? FCH09070
1086 DO 1088 I=1,NV FCH09080
IIFIAC(I).LT.ICFR(I).OR.IACT(I).GT.ICTO(I) GO TO 1092 FCH09090
1088 CONTINUE FCH09100
C YES. THIS COLUMN NUMBER IS IN THE SPECIFIED FCH09110
C CHANGE RANGE. FCH09120
C SET IDCOL EQUAL THE COLUMN NUMBER JUST DECODED. FCH09130
IDCOL=JCOL(J) FCH09140
GO TO 1094 FCH09150
C NO FCH09160
C SET IDCOL=-1 TO INDICATE COLUMN NUMBER NOT IN FCH09170
C RANGE. FCH09180
1092 IDCOL=-1 FCH09190
C 1094 FCH09200
C CONTINUE FCH09210
1094 CONTINUE FCH09220
C END OF DECODE A COLUMN NUMBER. FCH09230
C FCH09240
C WAS COLUMN IN RANGE? FCH09250
C NO. GO TO DECODE NEXT COLUMN. FCH09260
C IF(IDCOL.LT.0) GO TO 550 FCH09270
C YES FCH09280
C ADD 1 TO COUNT OF NUMBER OF COLUMNS IN RANGE. FCH09290
NINRNG=NINRNG+1 FCH09300
C SET NON-FREE AMOUNT, LOCATION OF NON-FREE FCH09310
C ELEMENT AND TYPE OF PASS FOR USE OF PROGRAM SEG-FCH09320
C MENT THAT ACTUALLY CHANGES THE ELEMENT VALUES. FCH09330
AMTNF=P(J) FCH09340
IJNF=J FCH09350
KPASS=5 FCH09360
C GO TO 317 FCH09370
C RETURN WILL BE TO 541 OR 550 TO DECODE NEXT COL. FCH09380
C GO TO 317 FCH09390
C CONTINUE FCH09400
550 CONTINUE FCH09410
*FCH09420
**FCH09430
C ALL COLUMNS IN THIS ROW HAVE BEEN PROCESSED. FCH09440
C GO TO NEXT ROW. FCH09450
C GO TO 500 FCH09460
C FCH09470
***FCH09480
C *FCH09490
C A TYPE 5 CARD - END OF CHANGES FOR CURRENT P FCH09500
C MATRIX - WILL CAUSE A TRANSFER TO THIS SEGMENT FCH09510
C OF THE PROGRAM. FCH09520
C IS THERE A CHANGED ROW RECORD IN CORE THAT HAS FCH09530
C NOT BEEN WRITTEN. FCH09540
C NO. GO TO PRINT COUNTS. FCH09550
567 IF(II.EQ.0.OR.KCHGSW.EQ.0) GO TO 568 FCH09560
C YES FCH09570
C SET RANDOM ACCESS RECORD NUMBER EQUAL ROW NUMBER FCH09580
C SUBSCRIPT. FCH09590
ITK=II FCH09600
C WRITE ROW RECORD ON DISK. FCH09610

```
      WRITE(KDISK,ITK)          FCH09620
      1      KTYPE,ISN(I),JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH09630
      C      FCH09640
      C      568 FCH09650
      C      PRINT COUNTS FOR THIS MATRIX: NUMBER OF ELEMENTSFCH09660
      C      SEARCHED FOR, NUMBER OF ELEMENTS FOUND, NUMBER FCH09670
      C      OF COLUMNS DECODED, NUMBER OF COLUMNS IN RANGE, FCH09680
      C      NUMBER OF NON FREE COLUMNS CHANGED. FCH09690
      C      568 PRINT 569,NSERCH,NFOUND,NDCODE,NINRNG FCH09700
      C      569 FORMAT(1/2)H FAMILY CHANGE COUNTS FCH09710
      1      /35H NUMBER OF ELEMENTS SEARCHED FOR = ,I10 FCH09720
      2      /35H NUMBER OF ELEMENTS FOUND      = ,I10 FCH09730
      3      /35H NUMBER OF COLUMNS DECODED    = ,I10 FCH09740
      4      /35H NUMBER OF COLUMNS IN RANGE   = ,I10 FCH09750
      577 PRINT 578,NCHG FCH09760
      578 FORMAT(1/4)H SPECIFIC CHANGE AND FAMILY CHANGE COUNT FCH09770
      1      /38H NUMBER OF NON-FREE ELEMENTS CHANGED = ,I10) FCH09780
      C      FCH09790
      C      WERE ANY CHANGES ACTUALLY MADE IN THIS MATRIX? FCH09800
      C      YES. GO TO WRITE OUTPUT MATRIX. FCH09810
      C      IF(NCHG.NE.0) GO TO 590 FCH09820
      C      FCH09830
      C      NO. SHOULD THE MATRIX BE COPIED ONTO THE OUTPUTFCH09840
      C      FILE ANYWAY... FCH09850
      C      IF NOT, READ NEXT TYPE 1 CARD. FCH09860
      C      THE IDROW FIELD IN A TYPE 5 CARD IS THE WRITE P FCH09870
      C      SWITCH. FCH09880
      C      IF(IDROW.EQ.0) GO TO 20 FCH09890
      C      FCH09900
      C      590 FCH09910
      C      TRANSFER HERE (1) TO COPY CHANGED MATRIX AND FCH09920
      C      (2) TO COPY MATRIX WITH NO CHANGES IF SWITCH SO FCH09930
      C      SPECIFIES. FCH09940
      C      WRITE OUTPUT LABEL FOR CHANGED P. FCH09950
      C      590 NLP=60 FCH09960
      C      WRITE(KOUTP)KPBEG,NUNAMF,NLP,(LABELP(I),I=1,30),NULABL FCH09970
      C      **FCH09980
      C      *FCH09990
      C      UPDATE ISN LIST IF NEW ROWS HAS ANY ENTRIES FCH10000
      C      ISN CANNOT BE UPDATED UNTIL THE CHANGE OPERATIONFCH10010
      C      FOR THE MATRIX IS COMPLETE SINCE IT IS USED TO FCH10020
      C      DETERMINE ROW RECORD TRACK NUMBERS. FCH10030
      C      IF NN.EQ.0, THERE ARE NO ROWS TO ADD TO ISN. FCH10040
      C      FCH10050
      C      IS THE NEW ROW LIST EMPTY? FCH10060
      C      YES. GO TO WRITE ROW LIST AND COLUMN LIST FCH10070
      C      RECORDS. FCH10080
      C      IF(NN.EQ.0) GO TO 610 FCH10090
      C      NO FCH10100
      C      THERE ARE ENTRIES IN THE NEW ROW LIST. ARE ALL FCH10110
      C      ELEMENTS BEING ADDED DIAGONAL ELEMENTS? FCH10120
      C      YES. GO TO FILE NEW ROWS FNTRIES INTO TOTAL ROW FCH10130
      C      LIST. FCH10140
      C      IF(KURSW.EQ.0) GO TO 591 FCH10150
      C      ***FCH10160
      C      *FCH10170
      C      NO FCH10180
```

C OFF DIAGONAL ELEMENTS MAY BE ADDED. FCH10190
C GENERATE ADDITIONAL ROWS AND COLUMNS, IF ANY, FCH10200
C FROM MODIFY SPECIFICATIONS. FCH10210
C FCH10220
C EXECUTE THIS SEGMENT OF PROGRAM WHEN FCH10230
C KURSW=+N AND NN.GT.0 FCH10240
C FCH10250
C COMPUTE COLUMN IN WHICH ENTRY WILL BE PLACED FOR FCH10260
C EACH NEW ROW. ADD THE COLUMN TO LSTCOL AND/OR FCH10270
C NUROWS AS REQUIRED. FCH10280
C FCH10290
C INITIALIZE SUBSCRIPT FOR NEW ROW LIST. FCH10300
C FCH10310
1500 N=1
C WILL THE COLUMN ELEMENT FOR THE NTH ENTRY IN THE FCH10320
C NEW ROW LIST BE A DIAGONAL ELEMENT? FCH10330
C YES. GO TO CHECK NEXT ELEMENT. FCH10340
1505 IF(MOD(NUROWS(N),KURFAC).EQ.0) GO TO 1570 FCH10350
C NO FCH10360
C COMPUTE THE COLUMN NUMBER OF THE ELEMENT THAT FCH10370
C WILL BE ADDED. FCH10380
C ICOL=NUROWS(N)+KUF SW FCH10390
C IS THE COLUMN NUMBER JUST COMPUTED IN LSTCOL? FCH10400
DO 1515 J=1,JCOUNT FCH10410
IF(LSTCOL(J).GE.ICOL) GO TO 1525 FCH10420
1515 CONTINUE FCH10430
C NO FCH10440
C ADD AT END OF LSTCOL. FCH10450
JCOUNT=JCOUNT+1 FCH10460
LSTCOL(JCOUNT)=ICOL FCH10470
GO TO 1540 FCH10480
C WAS THIS AN EQUAL BRANCH... FCH10490
1525 IF(ICOL.EQ.LSTCOL(J)) GO TO 1540 FCH10500
C NO. FILE NEW COL AT POSITION J. FCH10510
CALL TMT2(LSTCOL(J),LSTCOL(J+1),JCOUNT-J+1) FCH10520
LSTCOL(J)=ICOL FCH10530
JCOUNT=JCOUNT+1 FCH10540
C IS THE COLUMN NUMBER JUST COMPUTED IN ISN? FCH10550
1540 DO 1545 I=1,ISCNT FCH10560
IF(ISN(I).LT.ICOL) GO TO 1545 FCH10570
IF(ICOL.EQ.ISN(I)) GO TO 1570 FCH10580
GO TO 1550 FCH10590
1545 CONTINUE FCH10600
C 1550 FCH10610
C NO FCH10620
C IS THE COLUMN NUMBER JUST COMPUTED IN NUROWS? FCH10630
1550 DO 1555 I=N,NN FCH10640
IF(NUROWS(I).GE.ICOL) GO TO 1560 FCH10650
1555 CONTINUE FCH10660
C ADD COL AT END OF NUROWS. FCH10670
NN=NN+1 FCH10680
NUROWS(NN)=ICOL FCH10690
GO TO 1570 FCH10700
C WAS THIS AN EQUAL BRANCH... FCH10710
1560 IF(NUROWS(I).EQ.ICOL) GO TO 1570 FCH10720
C NO. FILE NEW COL AT POSITION I. FCH10730
CALL TMT2(NUROWS(I),NUROWS(I+1),NN-I+1) FCH10740
NUROWS(I)=ICOL FCH10750

NN=NN+1 FCH10760
C CONTINUE. FCH10770
C HAVE ALL ENTRIES IN THE NUROWS LIST BEEN PROCES- FCH10780
C SED? FCH10790
C YES. GO TO FILE NEW ROWS ENTRIES INTO TOTAL ROW FCH10800
C LIST. FCH10810
1570 IF(N.EQ.NN) GO TO 591 FCH10820
C NO FCH10830
C INCREMENT SUBSCRIPT FOR NEW ROW LIST. FCH10840
C N=N+1 FCH10850
C PROCESS NEXT ENTRY IN NUROWS LIST. FCH10860
C GO TO 1505 FCH10870
C *FCH10880
C ***FCH10890
C FCH10900
C **FCH10910
C *FCH10920
C FILE NEW ROW ENTRIES INTO TOTAL ROW LIST AND UP-FCH10930
C DATE COUNT OF ELEMENTS IN ROW LIST. FCH10940
C USE N FOR NUROWS SUBSCRIPT AND I FOR ISN SUB- FCH10950
C SCRIPT. INITIALIZE. FCH10960
591 N=1 FCH10970
I=1 FCH10980
C 592 IS ISN ENTRY GREATER THAN NUROWS ENTRY? FCH10990
C 592 IF(ISN(I).GE.NUROWS(N)) GO TO 598 FCH11000
C NO FCH11010
C UPDATE I. FCH11020
C I=I+1 FCH11030
C ARE THERE STILL ELEMENTS IN ISN TO BE PROCESSED? FCH11050
C IF(I.LE.ISCNT) GO TO 592 FCH11060
C 594 FCH11070
C NO FCH11080
C ADD REMAINING NEW ROW NUMBERS AT END OF ISN. FCH11090
594 ISN(I)=NUROWS(N) FCH11100
C UPDATE N. FCH11110
C N=N+1 FCH11120
C HAVE ALL NUROWS ENTRIES BEEN PROCESSED? FCH11130
C IF(N.GT.NN) GO TO 602 FCH11140
C NO FCH11150
C UPDATE I. FCH11160
C I=I+1 FCH11170
C GO TO 594 FCH11180
C 598 FCH11190
C YES FCH11200
C NUROWS ENTRY IS GREATER THAN ISN ENTRY. FCH11210
C FILE NUROWS ENTRY HERE. FCH11220
C PUSH DOWN ISN ARRAY, POSITION I THRU ISCNT. FCH11230
598 CALL TMT2(ISN(I),ISN(I+1),ISCNT-I+1) FCH11240
C ISN(I)=NUROWS(N) FCH11250
C ADD 1 TO COUNT OF ISN ENTRIES. FCH11260
C ISCNT=ISCNT+1 FCH11270
C UPDATE SUBSCRIPTS. FCH11280
C I=I+1 FCH11290
C N=N+1 FCH11300
C HAVE ALL NUROWS ENTRIES BEEN PROCESSED? FCH11310
C IF(N.GT.NN) GO TO 602 FCH11320

C NO FCH11330
C ARE THERE STILL ISN ENTRIES TO BE PROCESSED? FCH11340
C IF(I.GT.ISCNT) GO TO 594 FCH11350
S YES FCH11360
C GO TO 592 FCH11370
C
C 602 FCH11380
C ALL NEW ROW ENTRIES HAVE BEEN PROCESSED. FCH11390
C RESET COUNT OF NUMBER OF ENTRIES IN ROW LIST. FCH11400
C 602 ISCNT=I FCH11410
C
C WRITE P ROW LIST RECORD. FCH11420
C 610 WRITE(KOUTP)KPLST,ISCNT,(ISN(I),I=1,ISCNT),MODSW,MODFAC *FCH11430
C WRITE P COLUMN LIST RECORD. **FCH11440
C WRITE(KOUTP)KPLST,JCOUNT,(LSTCOL(I),I=1,JCOUNT),NUMMO,NUMYR FCH11450
C PRINT OUTPUT MATRIX ROW AND COLUMN COUNTS. FCH11460
C FCH11470
C FCH11480
C FCH11490
C PRINT 612,ISCNT,JCOUNT FCH11500
C 612 FORMAT(/38H FOR OUTPUT P MATRIX, NUMBER OF ROWS = ,I12,5X, FCH11510
1 20HNUMBER OF COLUMNS = ,I12) FCH11520
C
C COPY P MATRIX FROM DIRECT ACCESS FILE TO FCH11530
C SEQUENTIAL ACCESS FILE. GENERATE A RECORD FOR FCH11540
C EACH ENTRY IN NUROWS. FCH11550
C PLACE A -1 FOLLOWING THE LAST ENTRY IN NUROWS FCH11560
C AND SET INITIAL DIRECT ACCESS RECORD NUMBER TO FCH11570
C 1. FCH11580
C FCH11590
C NUROWS(NN+1)=-1 FCH11600
C ITK=1 FCH11610
C
C SET RECORD TYPE AND ELEMENT VALUE FOR USE IN FCH11620
C ADDED ROW ENTRIES. FCH11630
2400 KPDAT=23 FCH11640
PVALUE=1.0 FCH11650
C
C INITIALIZE SUBSCRIPT FOR PICKING UP ELEMENTS OF FCH11660
NUROWS. FCH11670
C I=1 FCH11680
C
C PICK UP NEXT NEW ROW NUMBER. FCH11690
NADD=NUROWS(I) FCH11700
C
C READ A RECORD FROM DISK. FCH11710
2410 READ(KDISK'ITK) FCH11720
1 KTYPE,IROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH11730
C
C WAS THIS A P END LABEL? FCH11740
C YES. ALL DISK RECORDS READ. FCH11750
C
C !F(KTYPE.EQ.33) GO TO 2435 FCH11760
C
C NO FCH11770
C
C HAVE ALL NEW ROWS BEEN ADDED? FCH11780
C YES. GO TO WRITE RECORD JUST READ. FCH11790
2420
C
C IF(NADD.LE.0) GO TO 2430 FCH11800
C
C NO FCH11810
C
C IS NEXT NEW ROW GREATER THAN ROW OF RECORD JUST FCH11820
C READ? FCH11830
C
C YES. GO TO WRITE RECORD JUST READ. FCH11840
C
C IF(NADD.GT.IROW) GO TO 2430 FCH11850
C
C NO FCH11860
C
C WRITE AN OUTPUT RECORD FOR THE NEXT NEW ROW. FCH11870
C COMPUTE COLUMN NUMBER FROM ROW NUMBER AND FCH11880
C CURRENT TRANSITION MODIFY SPECIFICATIONS. FCH11890

```
ICOL=NADD FCH11900
IF(KURSW.EQ.0) GO TO 2426 FCH11910
IF(MOD(ICOL,KURFAC).NE.0) ICOL=ICOL+KURSW FCH11920
2426 WRITE(KOUTP) KPDAT,NADD,NFILL,ICOL,PVALUE FCH11930
C UPDATE NUROWS SUBSCRIPT AND PICK UP NEXT NEW ROW FCH11940
C ELEMENT. FCH11950
I=I+1 FCH11960
NADD=NUROWS(I) FCH11970
GO TO 2420 FCH11980
C 2430 FCH11990
C WRITE THE RECORD READ FROM DISK ONTO THE OUTPUT FCH12000
C FILE. FCH12010
2430 WRITE(KOUTP) FCH12020
1 KTYPE,IROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH12030
C GO TO READ NEXT DISK RFCORD. FCH12040
C GO TO 2410 FCH12050
C 2435 FCH12060
C ALL DISK RECORDS HAVE BEEN COPIED. FCH12070
C HAVE ALL NEW ROWS BEEN ADDED? FCH12080
C YES. WRITE END LABEL. FCH12090
2435 IF(NADD.LE.0) GO TO 2450 FCH12100
C 2440 FCH12110
C NO FCH12120
C WRITE AN OUTPUT RECORD FOR THE NEXT NEW ROW. FCH12130
C COMPUTE COLUMN NUMBER FROM ROW NUMBER AND CUR- FCH12140
C REN. TRANSITION MODIFY SPECIFICATIONS. FCH12150
2440 ICOL=NADD FCH12160
IF(KURSW.EQ.0) GO TO 2446 FCH12170
IF(MOD(ICOL,KURFAC).NE.0) ICOL=ICOL+KURSW FCH12180
2446 WRITE(KOUTP) KPDAT,NADD,NFILL,ICOL,PVALUE FCH12190
C UPDATE NUROWS SUBSCRIPT AND PICK UP NEXT NEW ROW FCH12200
C ELEMENT. FCH12210
I=I+1 FCH12220
NADD=NUROWS(I) FCH12230
GO TO 2435 FCH12240
C 2450 FCH12250
C YES FCH12260
C ALL DISK DATA RECORDS HAVE BEEN COPIED AND FCH12270
C ALL NEW ROWS HAVE BEEN ADDED. FCH12280
C UPDATE P MATRIX ROW AND ELEMENT COUNT FOR END FCH12290
C LABEL. FCH12300
2450 JCOL(1)=JCOL(1)+I-1 FCH12310
P(1)=P(1)+DFLOAT(I-1) FCH12320
C WRITE END LABEL ON OUTPUT FILE. FCH12330
C WRITE(KOUTP) FCH12340
1 KTYPE,IROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) FCH12350
C UPDATE COUNT OF OUTPUT FILES. FCH12360
C NFILES=NFILES+1 FCH12370
C GO TO READ NEXT CONTROL CARD. FCH12380
C GO TO 20 FCH12390
C *FCH12400
C ***FCH12410
C FCH12420
C LTYPE=2 FOR END OF CHANGES. FCH12430
C ADD 1 TO NUMBER OF FILES. FCH12440
C 700 NFILES=NFILES+1 FCH12450
C PLACE BLANKS IN NAME FIELD FOR END OF FILE FCH12460
```

C RECORD. FCH12470
C DATA KBLANK/4H FCH12480
C DO 701 I=1,6 FCH12490
C 701 NAMEP(I)=KBLANK FCH12500
C WRITE(KOUTP),NEXT,NAMEP,NFILL,NFILES FCH12510
C REWIND KOUTP FCH12520
C WAS THE CARD WHICH CAUSED THE BRANCH TO THIS FCH12530
C SEGMENT OF THE PROGRAM A TYPE 2 CARD? FCH12540
C IFILTYPE.NE.2) GO TO 710 FCH12550
C YES FCH12560
C PRINT A MESSAGE: END OF F CHANGE DATA CARDS. FCH12570
C FCH12580
C PRINT 705 FCH12590
C 705 FORMAT(//30H END OF F CHANGE DATA CARDS.) FCH12600
C RETURN FCH12610
C FCH12620
C RETURN FCH12630
C NO FCH12640
C PRINT MESSAGE: F CHANGE CONTROL CARD ERROR AND FCH12650
C CARD TYPE. FCH12660
C 710 PRINT 715,LTYPE FCH12670
C 715 FORMAT(//36H F CHANGE CONTROL CARD ERROR. TYPE =,16) FCH12680
C EXIT FCH12690
C STOP FCH12700
C YES FCH12710
C NUMBER OF ELEMENTS PRESENT EXCEEDS ARRAY FCH12720
C DIMENSION. FCH12730
C PRINT ERROR MESSAGE. FCH12740
C FCH12750
C 730 PRINT 735,NDIM,JCNT FCH12760
C 735 FORMAT(56H NUMBER OF ELEMENTS IN A ROW EXCEEDS VARIABLE DIMENSION. FCH12770
C 1 /16H NDIM AND JCNT = ,2I12) FCH12780
C EXIT FCH12790
C STOP FCH12800
C PRINT MESSAGE: DATA CARD ERROR IN PERCENT CHANGEFCH12810
C FIELD. FCH12820
C FCH12830
C 750 PRINT 755 FCH12840
C 755 FORMAT(52H PCHANGE DATA CARD ERROR. NEGATIVE CHANGE CANNOT BE FCH12850
C 1 /28H GREATER THAN 100 PER CENT.) FCH12860
C PRINT CONTENTS OF DATA CARD. FCH12870
C PRINT 145,LTYPE,PCCHG,IDROW,IDCOL,IFRCOL FCH12880
C EXIT FCH12890
C STOP FCH12900
C REFERENCE LIST. FCH12910
C SUBROUTINE ARGUMENTS. FCH12920
C FCH12930
C FCH12940
C NDIM - DIMENSION OF JCOL AND P IN THE CALLING PROGRAM. FCH12950
C ISN - ARRAY FOR LIST OF ROWS IN P MATRIX. FCH12960
C LSTCOL - ARRAY FOR LIST OF COLUMNS IN P MATRIX. FCH12970
C JCOL - ARRAY FOR LIST OF COLUMNS IN A SINGLE ROW OF THE P MATRIX FCH12980
C P - ARRAY FOR ELEMENT VALUES IN A SINGLE ROW OF THE P MATRIX. FCH12990
C LABELP - ARRAY FOR LABEL OF INPUT P MATRIX. FCH13000
C NUROWS - ARRAY FOR LIST OF ROWS NOT PRESENT IN INPUT P FOR WHICH FCH13010
C COLUMN ELEMENTS HAVE BEEN ADDED BY THE CHANGE OPERATION. FCH13020
C ITK - DIRECT ACCESS DISK ASSOCIATED VARIABLE. AT THE CONCLUSION FCH13030

OF EACH READ OR WRITE OPERATION, ITK IS SET TO A VALUE FCH13040
THAT POINTS TO THE RECORD THAT IMMEDIATELY FOLLOWS THE FCH13050
LAST RECORD TRANSMITTED. FCH13060
FCH13070
FCH13080
FCH13090
FCH13100
FCH13110

OTHER VARIABLES.

C AMTC	- AMOUNT OF CHANGE POSSIBLE. THIS MAY ALSO BE THE AMOUNT OFF	FCH13120
C CHANGE DESIRED.		FCH13130
C AMTNF	- NON FREE ELEMENT PROBABILITY.	FCH13140
C AMTR	- FREE ELEMENT PROBABILITY.	FCH13150
C IDROW	- ROW TO BE CHANGED.	FCH13160
C IDCOL	- NON-FREE COLUMN ELEMENT TO BE CHANGED.	FCH13170
C IFRCOL	- FREE COLUMN ELEMENT.	FCH13180
C ICOL	- COLUMN CURRENTLY SEARCHING FOR. THIS WILL EQUAL IDCOL OR FCH13190	
C IFRCOL.		FCH13200
C IROW	- ROW NUMBER IN P MATRIX RECORD READ FROM TAPE OR DISK.	FCH13210
C INPSW	- 0 IF POSITION INPUT FOR P IS REQUIRED.	FCH13220
C	1 IF POSITION FORWARD ONLY IS APPROPRIATE.	FCH13230
C		FCH13240
C ISCNT	- NUMBER OF ENTRIES IN ISN.	FCH13250
C IVL	- VECTOR OF NUMBER OF CODES DEFINED FOR EACH VARIABLE.	FCH13260
C IRFR	- VARIABLE CODES FOR ROW FROM VALUES.	FCH13270
C IRTG	- VARIABLE CODES FOR ROW TO.	FCH13280
C IFR	- VARIABLE CODES FOR FREE COLUMN.	FCH13290
C ICFR	- VARIABLE CODES FOR NON-FREE COLUMN FROM.	FCH13300
C ICTO	- VARIABLE CODES FOR NON-FREE COLUMN TO.	FCH13310
C IACT	- ARRAY FOR VARIABLE VALUES OF THE COLUMN NUMBER BEING FCH13320	
C	DECODED.	FCH13330
C		FCH13340
C	IRCR - CURRENT VARIABLE VALUE FOR ROW GENERATION.	FCH13350
C	ICCR - CURRENT VARIABLE VALUE FOR COLUMN GENERATION.	FCH13360
C	ICSW - SWITCH FOR NON-FREE COL VAR VALUE SAME AS ROW VAR VALUE.	FCH13370
C	IFSW - SWITCH FOR FREE COL VAR VAL SAME AS ROW VAR VALUE.	FCH13380
C		FCH13390
C	JCNT - NUMBER OF COLUMNS IN CURRENT P MATRIX ROW.	FCH13400
C	JCOUNT - NUMBER OF ENTRIES IN LSTCOL.	FCH13410
C	KINP - UNIT ON WHICH INPUT P IS LOCATED.	FCH13420
C	KOUT - UNIT ON WHICH CHANGED P IS TO BE WRITTEN.	FCH13430
C	KDISK - DIRECT ACCESS SCRATCH DISK.	FCH13440
C	KTYPE - D,S,P ARRAY RECORD TYPE.	FCH13450
C	KCHGSW - 0 IF NO CHANGES HAVE BEEN MADE IN THE NEW RECORD IN CORE.	FCH13460
C	NONZERO - NUMBER OF CHANGES MADE IN THE NEW RECORD.	FCH13470
C	KFRSW - FREE ELEMENT SWITCH.	FCH13480
C	0.. FREE ELEMENT PRESENT.	FCH13490
C	1.. FREE ELEMENT NOT PRESENT.	FCH13500
C	KPASS - 1.. NON-FREE ELEMENT PASS, SPECIFIC CHANGE.	FCH13510
C	2.. FREE ELEMENT PASS, SPECIFIC CHANGE.	FCH13520
C	3.. NON-FREE ELEMENT PASS, FAMILY CHANGE.	FCH13530
C	3.. ALSO USED FOR ROW SEARCH, FAMILY CHANGF.	FCH13540
C	4.. FREE ELEMENT PASS, FAMILY CHANGE.	FCH13550
C	5.. CHANGE PASS, FAMILY CHANGE DECODE PROCEDURE.	FCH13560
C	KPROC - NON-FREE COLUMN PROCEDURE SWITCH.	FCH13570
C	1.. CODE EACH ELEMENT IN CHANGE RANGE AND SEARCH THE ROW FCH13580	
C	FOR THESE ELEMENTS.	FCH13590
C	2.. DECODE EACH COLUMN PRESENT. SEE IF ELLMENT IS IN FCH13600	
C	RANGE OF COLUMNS TO BE CHANGED.	

C	KURSW - TRANSITION MODIFY SWITCH FOR THIS RUN.	FCH13610
C	KURFAC - TRANSITION MODIFY FACTOR FOR THIS RUN.	FCH13620
C		FCH13630
C	' TYPE - CONTROL CARD TYPE.	FCH13640
C	1.. CHANGE A P MATRIX.	FCH13650
C	2.. THE JOB IS FINISHED.	FCH13660
C	3.. SPECIFIC CHANGE.	FCH13670
C	4.. FAMILY CHANGE.	FCH13680
C	5.. END OF CHANGES FOR CURRENT P.	FCH13690
C	MCR - NUMBER OF COLUMN VARIABLE CURRENTLY BEING INCREMENTED.	FCH13700
C	MODSW - ORIGINAL TRANSITION MODIFY SWITCH.	FCH13710
C	MODFAC - ORIGINAL TRANSITION MODIFY FACTOR.	FCH13720
C	MODCHG - SWITCH INDICATING (1) USE ORIGINAL MODIFY VALUES, (2) USE VALUES IN FCHANG CONTROL CARD.	FCH13730
C	MULT - ARRAY FOR PRODUCTS USED IN GENERATING THE STATE NUMBERS.	FCH13740
C		FCH13750
C		FCH13760
C	NAMEP - NAME OF INPUT P.	FCH13770
C	NUNAME - NAME OF OUTPUT P.	FCH13780
C	NULABL - LABEL INFORMATION FOR SECOND 120 CHARACTERS OF OUTPUT P MATRIX.	FCH13790
C	NFILES - NUMBER OF FILES ON OUTPUT UNIT.	FCH13800
C	NCR - NUMBER OF ROW VARIABLE CURRENTLY BEING INCREMENTED.	FCH13810
C	NCHG - NUMBER OF CHANGES MADE IN THE MATRIX.	FCH13820
C	NSERCH - NUMBER OF COLUMN ELEMENTS SEARCHED FOR IN CODE PROCEDURE FAMILY CHANGE.	FCH13830
C	NFOUND - NUMBER OF COLUMN ELEMENTS FOUND IN FAMILY CHANGE SEARCH.	FCH13840
C	NDCODE - NUMBER OF COLUMN ELEMENTS DECODED IN FAMILY CHANGE DECODE PROCEDURE SEARCH.	FCH13850
C	NINRNG - NUMBER OF DECODED COLUMN ELEMENTS THAT WERE IN FAMILY CHANGE RANGE.	FCH13860
C	NN - NUMBER OF ELEMENTS IN LIST OF NEW ROWS.	FCH13870
C	NV - NUMBER OF VARIABLES IN STATE NUMBER DEFINITION.	FCH13880
C	NVM1 - NUMBER OF VARIABLES MINUS ONE.	FCH13890
C	PCCHG - PER CENT CHANGE TO BE MADE IN NON-FREE ELEMENT. MAY BE POSITIVE OR NEGATIVE.	FCH13940
C	END	FCH13950
		FCH13960

```
SUBROUTINE FILE(LEMENT,LARRAY,LENGTH,LASTN)          FILE 010
C
C           FILE AN ELEMENT INTO AN ARRAY. THE ELEMENT      FILE 020
C           PASSED IS GREATER THAN THE FIRST ELEMENT IN THE FILE 030
C           INPUT ARRAY. THE ELEMENTS IN THE INPUT ARRAY AREFILE 040
C           ASSUMED TO BE IN ASCENDING SEQUENCE.            FILE 050
C
C           DIMENSION LARRAY(1)                         FILE 060
C           IS THERE JUST ONE ELEMENT IN THE INPUT ARRAY? FILE 070
C           YES.                                         FILE 080
C           GO TO ADD ELEMENT AT END OF ARRAY.          FILE 090
C
C           IF(LENGTH.EQ.1) GO TO 25                   FILE 100
C           NO.                                         FILE 110
C           THERE IS MORE THAN ONE ELEMENT IN THE INPUT FILE 120
C           ARRAY.                                       FILE 130
C           COMPARE THE ELEMENT TO BE FILED WITH THE FILE 140
C           ELEMENTS CURRENTLY IN THE ARRAY.             FILE 150
C           START WITH THE SECOND ELEMENT IN THE ARRAY FILE 160
C           SINCE, BY DEFINITION OF THIS FILE OPERATION, FILE 170
C           'LEMENT' IS GREATER THAN THE FIRST ENTRY IN FILE 180
C           'LARRAY'.                                     FILE 190
C
C           DO 20 L=2,LENGTH                           FILE 200
C           IF THE ELEMENT IS ALREADY IN THE ARRAY, LEAVE FILE 210
C           ALL ARGUMENTS AS IS AND RETURN.            FILE 220
C
C           IF(LEMENT.EQ.LARRAY(L)) RETURN             FILE 230
C           IF(LEMENT.GT.LARRAY(L)) GO TO 20          FILE 240
C               ADD ELEMENT AT AN INTERMEDIATE POSITION IN THE FILE 250
C               ARRAY.                                 FILE 260
C               PUSH DOWN ELEMENTS GREATER THAN THE ELEMENT FILE 270
C               BEING ADDED.                            FILE 280
C
C           CALL TMT2(LARRAY(L),LARRAY(L+1),LENGTH-L+1) FILE 290
C               STORE ELEMENT IN ARRAY.                FILE 300
C
C           LARRAY(L)=LEMENT                         FILE 310
C               ADD ONE TO COUNT OF ENTRIES IN THE TOTAL ARRAY. FILE 320
C
C           LASTN=LASTN+1                           FILE 330
C               RETURN.                                FILE 340
C
C               RETURN.                                FILE 350
C
C               CONTINUE.                               FILE 360
C               'LEMENT' IS GREATER THAN L'TH ENTRY IN 'LARRAY'. FILE 370
C
C           20 CONTINUE                                FILE 380
C               25
C               ADD ELEMENT AT END OF ARRAY.          FILE 390
C               ADD ONE TO COUNT OF ENTRIES IN THE TOTAL ARRAY. FILE 400
C
C           25 LASTN=LASTN+1                          FILE 410
C               STORE ELEMENT IN ARRAY.                FILE 420
C
C               LARRAY(LENGTH+1)=LEMENT                FILE 430
C               RETURN.                                FILE 440
C
C               RETURN.                                FILE 450
C
C               REFERENCE LIST.                      FILE 460
C               SUBROUTINE ARGUMENTS.                 FILE 470
C
C               LEMENT - ELEMENT TO BE FILED.        FILE 480
C               LARRAY - ARRAY INTO WHICH ELEMENT IS TO BE FILED. FILE 490
C               LENGTH - NUMBER OF ENTRIES IN LARRAY. FILE 500
C               LASTN - THE NUMBER OF ENTRIES IN THE CALLING PROGRAM IN THE ARRAYFILE 510
C                                         FILE 520
C                                         FILE 530
C                                         FILE 540
C                                         FILE 550
C                                         FILE 560
```

C SHOWN IN THE 'LARRAY' ARGUMENT. IF THE CALL STATEMENT FILE 570
C SPECIFIES ARRAY NAME(1), THE INPUT ARGUMENTS 'LENGTH' ANDFILE 580
C 'LASTN' WILL BE EQUAL. IF THE CALL STATEMENT SPECIFIES FILE 590
C ARRAY NAME(N), 'LASTN' WILL BE GREATER THAN 'LENGTH'. FILE 600
C LASTN = LENGTH +N -1 ON INPUT. THE OUTPUT VALUE OF FILE 610
C 'LASTN' WILL BE INCREASED BY ONE IF AN ELEMENT IS ADDED FILE 620
C TO 'LARRAY'. FILE 630
C
END FILE 640

```

SUBROUTINE FREQ1(KS,KSNEW,KDISTF,KDISTN,NDIM)          FRQ10010
C
C           FREQ1                                     FRQ10020
C           THIS ROUTINE WILL COUNT THE NUMBER OF LIKE   FRQ10030
C           PATTERNS ON A SORTED STATE NUMBER TAPE.       FRQ10040
C           THERE MAY BE ONLY ONE MODEL ON ANY INPUT TAPE. FRQ10050
C           ALL STATE NUMBERS FOR A MODEL ARE ASSUMED TO BE FRQ10060
C           ON ONE TAPE.                                FRQ10070
C           THE OUTPUT WILL BE A STATE PATTERN DISTRIBUTION FRQ10080
C           TAPE PLUS A PRINT OF THE FREQUENCY DISTRIBUTION. FRQ10090
C
C           DIMENSION KS(1),KSNEW(1),KDISTF(1),KDISTN(1)    FRQ10100
C
C           READ ID OF OUTPUT UNIT AND REWIND.             FRQ10110
C
C           READ 10,KOUT                                     FRQ10120
10  FORMAT(4I12)                                       FRQ10130
      REWIND KOUT                                      FRQ10140
C
C           READ ID OF INPUT UNIT, NUMBER OF TIMES PER   FRQ10150
C           PATTERN, NUMBER CASES, MODEL NUMBER.         FRQ10160
C
20  READ 10,KINP,NTIMES,KCASES,MODNUM                 FRQ10170
C
C           HAVE ALL INPUT FILES BEEN PROCESSED?        FRQ10180
C           YES. GO TO REWIND OUTPUT UNIT.               FRQ10190
C
      IF(KINP.EQ.0) GO TO 250                         FRQ10200
C
C           NO                                         FRQ10210
C
C           REWIND INPUT UNIT.                         FRQ10220
C
      REWIND KINP                                     FRQ10230
C
C           READ FIRST STATE NUMBER RECORD FOR THIS MODEL. FRQ10240
C
      READ(KINP)(KS(I),I=1,NTIMES)                   FRQ10250
C
C           INITIALIZATION FOR THIS MODEL:              FRQ10260
C           NUMBER OF RECORDS READ.                   FRQ10270
C
      NCASES=1                                       FRQ10280
C
C           NUMBER ENTRIES IN FREQ. DISTR.            FRQ10290
C
      KD=0                                           FRQ10300
C
C           FREQ FOR CURRENT PATTERN.                FRQ10310
C
      KOUNT=1                                         FRQ10320
C
C           NUMBER OF UNIQUE PATTERNS.               FRQ10330
C
      KPAT=0                                         FRQ10340
C
C
C           READ AND COMPARE PATTERNS.               FRQ10350
C
C           READ A DATA RECORD INTO KSNEW.          FRQ10360
C
52  READ(KINP,END=169)(KSNEW(I),I=1,NTIMES)          FRQ10370
C
C           NO EOF.                                 ***FRQ10380
C
C           ADD 1 TO NUMBER OF CASES READ.          *FRQ10390
C
      NCASES=NCASES+1                               FRQ10400
C
C           IS THIS PATTERN SAME AS PREVIOUS PATTERN... FRQ10410
C           COMPARE KS AND KSNEW.                  FRQ10420
C
      DO 60 I=1,NTIMES                            FRQ10430
      IF(KS(I).EQ.KSNEW(I)) GO TO 60              FRQ10440
      IF(KS(I).GT.KSNEW(I)) GO TO 300             FRQ10450
      GO TO 70                                     FRQ10460
C
60  CONTINUE                                     FRQ10470
C
C           KS EQUAL KSNEW.                        FRQ10480
C
C           ADD 1 TO FREQ FOR CURRENT PATTERN.     FRQ10490
C
      KOUNT=KOUNT+1                               FRQ10500
C
C           GO TO READ NEXT RECORD.               FRQ10510
C

```

C	GO TO 52	FRQ10570
C	70	FRQ10580
C	KS LESS THAN KNEW	FRQ10590
C	SET KSW TO INDICATE THERE WAS A PATTERN CHANGE.	FRQ10600
C	70 KSW=1	FRQ10610
C	GO TO UPDATE FREQ AND WRITE OUTPUT.	FRQ10620
C	RETURN TO 140.	FRQ10630
C	GO TO 170	FRQ10640
C	140	FRQ10650
C	RESET COMPARE FIELD AND COUNT.	FRQ10660
C	140 DO 142 I=1,NTIMES	FRQ10670
C	142 KS(I)=KNEW(I)	FRQ10680
C	KOUNT=1	FRQ10690
C	GO TO READ NEXT RECORD.	FRQ10700
C	GO TO 52	FRQ10710
C	*	FRQ10720
C	***	FRQ10730
C	169	FRQ10740
C	EOF BRANCH	FRQ10750
C	KSW SET TO INDICATE EOF ON INPUT UNIT.	FRQ10760
C	169 KSW=2	FRQ10770
C	REWIND KINP.	FRQ10780
C		FRQ10790
C		FRQ10800
C		***FRQ10810
C		*FRQ10820
C	170	FRQ10830
C	UPDATE FREQ DISTRIBUTION.	FRQ10840
C	FILF KOUNT INTO FREQ DISTRIBUTION.	FRQ10850
C	ARE THERE ANY ENTRIES IN KDISTF AND KDISTN?	FRQ10860
C	170 IF(KD.GT.0) GO TO 80	FRQ10870
C	NO	FRQ10880
C	STORE CURRENT FREQUENCY IN THE FIRST LOCATION.	FRQ10890
C	KDIS/F(1)=KOUNT	FRQ10900
C	KDISTN(1)=1	FRQ10910
C	KD=1	FRQ10920
C	GO TO 130	FRQ10930
C	80	FRQ10940
C	YES - THERE ARE ENTRIES IN THE FREQ DISTRIBUTION	FRQ10950
C	ARRAY.	FRQ10960
C	IS CURRENT KOUNT VALUE IN KDISTF?	FRQ10970
C	80 DO 90 II=1,KD	FRQ10980
C	IF(KDISTF(II).LT.KOUNT) GO TO 90	FRQ10990
C	IF(KDISTF(II).GT.KOUNT) GO TO 110	FRQ11000
C	YES	FRQ11010
C	CURRENT KOUNT VALUE IS IN KDISTF. UPDATE	FRQ11020
C	FREQUENCY COUNT AND GO TO WRITE OUTPUT RECORD.	FRQ11030
C	KDISTN(II)=KDSTN(II)+1	FRQ11040
C	GO TO 130	FRQ11050
C	90 CONTINUE	FRQ11060
C	NO	FRQ11070
C	CURRENT FREQUENCY GREATER THAN ANY IN L'ST. ADD	FRQ11080
C	AT END.	FRQ11090
C	KD=KD+1	FRQ11100
C	KDISTF(KD)=KOUNT	FRQ11110
C	KDISTN(KD)=1	FRQ11120
C	HAVE NDIM ENTRIES BEEN PLACED IN DISTR ARRAY?	FRQ11130

C	THE DIMENSION OF THE DISTR ARRAY IS NDIM.	FRQ11140
C	IF(KD.GE.NDIM) GO TO 175	FRQ11150
C	NO	FRQ11160
C	GO TO 130	FRQ11170
C	110	FRQ11180
C	KOUNT GREATER THAN KDISTF(II).	FRQ11190
C	FILE FREQ IN HERE. PUSH DOWN KDISTF AND KDISTN	FRQ11200
C	USING TMT2.	FRQ11210
C	110 CALL TMT2(KDISTF(II),KDISTF(II+1),KD-II+1)	FRQ11220
C	CALL TMT2(KDISTN(II),KDISTN(II+1),KD-II+1)	FRQ11230
C	KDISTF(II)=KOUNT	FRQ11240
C	KDISTN(II)=1	FRQ11250
C	KD=KD+1	FRQ11260
C	HAVE NDIM ENTRIES BEEN PLACED IN DISTR ARRAY?	FRQ11270
C	THE DIMENSION OF THE DISTR ARRAY IS NDIM.	FRQ11280
C	IF(KD.GE.NDIM) GO TO 175	FRQ11290
C	NO	FRQ11300
C	GO TO 130	FRQ11310
C	NDIM DISTR ARRAY ENTRIES HAVE BEEN PRINTED.	FRQ11320
C	RESET NUMBER OF ENTRIES IN FREQ ARRAY.	FRQ11330
C	128 KD=0	FRQ11340
C	RESET KSW TO SHOW NORMAL PATH	FRQ11350
C	KSW=1	FRQ11360
C	130	FRQ11370
C	WRITE OUTPUT RECORD.	FRQ11380
C	WRITE THE MODEL NUMBER, PATTERN AND FREQUENCY	FRQ11390
C	FOR THAT PATTERN.	FRQ11400
C	130 WRITE(KOUT)MODNUM,(KS(I),I=1,NTIMES),KOUNT	FRQ11410
C	UPDATE OUTPUT RECORD COUNT.	FRQ11420
C	KPAT=KPAT+1	FRQ11430
C	BRANCH ON KSW.	FRQ11440
C	GO TO (140,180),KSW	FRQ11450
C		FRQ11460
C		*FRQ11470
C	SET KSW TO INDICATE THAT BRANCH TO PRINT SEGMENT	***FRQ11480
C	OF PROGRAM WAS DUE TO NDIM ENTRIES IN DISTRIBUTION ARRAY.	FRQ11490
C	175 KSW=3	FRQ11500
C	PRINT FREQUENCY DISTRIBUTION.	FRQ11510
C	PRINT NUMBER CASES READ AND EXPECTED, NUMBER	FRQ11520
C	UNIQUE PATTERNS AND NUMBER UNIQUE FREQUENCIES.	FRQ11530
C	180 PRINT 190,MODNUM,(KDISTF(I),KDISTN(I),I=1,KD)	FRQ11540
C	PRINT 195,NCASES,KCASES	FRQ11550
C	PRINT 200,KPAT,KD	FRQ11560
C	BRANCH ON KSW.	FRQ11570
C	GO TO NEXT CARD IF KSW =1 OR 2.	FRQ11580
C	(WILL NEVER EQUAL 1 ON THIS BRANCH.)	FRQ11590
C	GO TO (20,20,128),KSW	FRQ11600
C		FRQ11610
C		FRQ11620
C	250	FRQ11630
C	YES	FRQ11640
C	END OF FREQ1 RUN.	FRQ11650
C	REWIND OUTPUT UNIT.	FRQ11660
C	250 REWIND KOUT	FRQ11670
C	RETURN	FRQ11680
C	RETURN	FRQ11690
C		FRQ11700

```

C          300
C          KS GREATER THAN KSNEW.
C          ERROR IN INPUT DATA.
C          PRINT SEQUENCE ERROR MESSAGE.
C
300 PRINT 310,(KS(I),I=1,NTIMES)           FRQ11760
PRINT 320,(KSNEW(I),I=1,NTIMES)           FRQ11770
PRINT 330,MODNUM,NCASES                  FRQ11780
C          EXIT.                         FRQ11790
C          STOP                          FRQ11800
C
C
190 FORMAT(34H1FREQUENCY DISTRIBUTION FOR MODEL ,I12//1X, 5(6X,4HFREQ,FRQ11830
   19X,1HN)/(1X,10I10))                   FRQ11840
195 FORMAT(1/54H CURRENT NUMBER OF INPUT RECORDS FOR THIS MODEL      = ,FRQ11850
   1I12/54H EXPECTED NUMBER OF CASES FOR THIS MODEL (IF KNOWN) = ,I12)FRQ11860
200 FORMAT(54H CURRENT NUMBER OF OUTPUT RECORDS FOR THIS MODEL     = , FRQ11870
   1I12/54H NUMBER OF ENTRIES IN FREQ DIST TABLE JUST PRINTED = ,I12)FRQ11880
310 FORMAT(35H INPUT TAPE NOT IN ASCENDING ORDER./
   1      10H KS      = ,10I12/(10X,10I12))                      FRQ11890
320 FORMAT(10H KSNEW = ,10I12/(10X,10I12))                      FRQ11910
330 FORMAT(10H MODNUM = ,I12/10H CASE NO= ,I12)                  FRQ11920
C
C          REFERENCE LIST.                    FRQ11930
C
C          SUBROUTINE ARGUMENTS.            FRQ11940
C
C          KS AND                         FRQ11950
C          KSNEW - ARRAYS FOR STATE NUMBER PATTERNS.        FRQ11960
C          KDISTF - ARRAY OF UNIQUE FREQUENCIES.          FRQ11970
C          KDISTN - ARRAY OF NUMBER OF PATTERNS HAVING THAT FREQUENCY. FRQ11980
C          NDIM - DIMENSION OF KDISTF AND KDISTN.         FRQ11990
C
C          OTHER VARIABLES                 FRQ12000
C
C          KD      - NUMBER OF ENTRIES CURRENTLY IN KDISTF AND KDISTN. FRQ12010
C          KPAT    - NUMBER OF UNIQUE PATTERNS.               FRQ12020
C          KOUNT   - FREQ FOR CURRENT PATTERN.              FRQ12030
C          KSH   - 1. BRANCH TO WRITE PATTERN BECAUSE OF A PATTERN CHANGE. FRQ12040
C                     2. BRANCH TO WRITE PATTERN BECAUSE OF END OF DATA.  FRQ12050
C                     3. BRANCH TO PRINT FREQ BECAUSE KDISTF HAS NDIM ENTRIES. FRQ12060
C
C          END                           FRQ12070
C
C

```

```

C SUBROUTINE FREQ2(KS,KSNEW,KDISTF,KDISTN,NDIM) FRQ20010
C
C     FREO2 FRQ20020
C     INPUT - A STATE PATTERN TAPE PRODUCED BY SORTING FRQ20030
C             THE OUTPUT FROM A COLLAPSE RUN. THERE FRQ20040
C             MAY BE MORE THAN ONE RECORD PER UNIQUE FRQ20050
C             PATTERN. ANY GIVEN MODEL IS ASSUMED TO FRQ20060
C             BE ON ONLY ONE TAPE. FRQ20070
C             THERE MAY BE MORE THAN ONE MODEL ON THE FRQ20080
C             INPUT TAPE. FRQ20090
C             FRQ20100
C             OUTPUT - A STATE PATTERN TAPE WITH ONLY ONE FRQ20110
C             RECORD PER UNIQUE PATTERN. FRQ20120
C             OUTPUT - PRINTED - FREQUENCY DISTRIBUTION. FRQ20130
C             FRQ20140
C
C             DIMENSION KS(1),KSNEW(1),KDISTF(1),KDISTN(1) FRQ20150
C             READ ID OF OUTPUT UNIT AND REWIND. FRQ20160
C
C             READ 10,KOUT FRQ20170
C 10 FORMAT(4I12) FRQ20180
C             REWIND KOUT FRQ20190
C
C             READ ID OF INPUT UNIT, NUMBER OF TIMES PER PAT- FRQ20200
C             TERN AND NUMBER CASES. FRQ20210
C 20 READ 10,KINP,NTIMES,KCASES FRQ20220
C             HAVE ALL INPUT FILES BEEN PROCESSED? FRQ20230
C             IF(KINP.EQ.0) GO TO 250 FRQ20240
C             NO FRQ20250
C             REWIND INPUT UNIT. FRQ20260
C
C             REWIND KINP FRQ20270
C             READ FIRST DATA RECORD INTO MODL, KS, KIN. FRQ20280
C             READ(KINP)MODL,(KS(I),I=1,NTIMES),KIN FRQ20290
C             40 FRQ20300
C             INITIALIZATION FOR THIS MODEL: FRQ20310
C             NUMBER OF RECORDS READ. FRQ20320
C 40 NCASES=1 FRQ20330
C             NUMBER ENTRIES IN FREQ. DIST. FRQ20340
C             KD=0 FRQ20350
C             KOUNT=KIN FRQ20360
C             KPAT=0 FRQ20370
C             FRQ20380
C             FRQ20390
C
C             ***FRQ20400
C             *FRQ20410
C             READ A DATA RECORD INTO MODNU, KSNEW, KIN. FRQ20420
C 52 READ(KINP,END=169)MODNU,(KSNEW(I),I=1,NTIMES),KIN FRQ20430
C             NO EOF FRQ20440
C             WAS THERE A MODEL CHANGE? FRQ20450
C             IF(MODL.NE.MODNU) GO TO 160 FRQ20460
C             NO FRQ20470
C             ADD 1 TO NUMBER OF CASES READ. FRQ20480
C             NCASES=NCASES+1 FRQ20490
C             COMPARE KS AND KSNEW. FRQ20500
C             DO 60 I=1,NTIMES FRQ20510
C             IF(KS(I).EQ.KSNEW(I)) GO TO 60 FRQ20520
C             IF(KS(I).GT.KSNEW(I)) GO TO 300 FRQ20530
C             GO TO 70 FRQ20540
C 60 CONTINUE FRQ20550
C             KS EQUAL KSNEW FRQ20560

```

C ADD FREQ FOR PATTERN JUST READ TO CUMULATIVE FREQ FOR THAT PATTERN. FRQ20570
C FRQ20580
C KOUNT=KOUNT+KIN FRQ20590
C GO TO 52 FRQ20600
C 70 FRQ20610
C KS LESS THAN KSNEW FRQ20620
C KSW SETTING INDICATES A PATTERN CHANGE CONDITION FRQ20630
C HAS OCCURED. FRQ20640
C 70 KSW=1 FRQ20650
C GO TO UPDATE FREQ AND WRITE OUTPUT. FRQ20660
C RETURN TO 140. FRQ20670
C GO TO 170 FRQ20680
C 140 RESET COMPARE FIELD AND COUNT. FRQ20690
C DO 142 I=1,NTIMES FRQ20700
C 142 KS(I)=KSNEW(I) FRQ20710
C KOUNT=KIN FRQ20720
C GO TO READ NEXT PATTERN RECORD. FRQ20730
C GO TO 52 FRQ20740
C *FRQ20750
C **FRQ20760
C 160 FRQ20770
C YES FRQ20780
C THERE WAS A MODEL CHANGE. FRQ20790
C KSW SETTING INDICATES A MODEL CHANGE OCCURED. FRQ20800
C 160 KSW=4 FRQ20810
C GO TO 170 FRQ20820
C 169 FRQ20830
C EOF BRANCH FRQ20840
C KSW SETTING INDICATES EOF ON INPUT. FRQ20850
C 169 KSW=2 FRQ20860
C REWIND KINP FRQ20870
C ***FRQ20880
C REWIND KINP FRQ20890
C FRQ20900
C 170 ***FRQ20910
C FILE KOUNT INTO FREQ DISTRIBUTION. *FRQ20920
C ARE THERE ANY ENTRIES IN KDISTF AND KDISTN? FRQ20930
C 170 IF(KD.GT.0) GO TO 80 FRQ20940
C NO FRQ20950
C FIRST ENTRY IN LIST. FRQ20960
C STORE CURRENT FREQUENCY IN THE FIRST LOCATION. FRQ20970
C KDISTF(1)=KOUNT FRQ20980
C KDISTN(1)=1 FRQ20990
C KD=1 FRQ21000
C GO TO 130 FRQ21010
C 80 80 FRQ21020
C YES FRQ21030
C THERE ARE ENTRIES IN DISTRIBUTION ARRAYS. FRQ21040
C IS CURRENT KOUNT VALUE IN KDISTF? FRQ21050
C 80 DO 90 II=1,KD FRQ21060
C IF(KDISTF(II).LT.KOUNT) GO TO 90 FRQ21070
C IF(KDISTF(II).GT.KOUNT) GO TO 110 FRQ21080
C YES FRQ21090
C ADD 1 TO FREQUENCY OF THE FREQUENCY. FRQ21100
C KDISTN(II)=KDISTN(II)+1 FRQ21110
C FRQ21120
C FRQ21130

```
GO TO 130 FRQ21140
90 CONTINUE FRQ21150
C NO FRQ21160
C CURRENT FREQUENCY IS GREATER THAN ANY IN LIST. FRQ21170
C ADD AT END. FRQ21180
C : KD=KD+1 FRQ21190
KDISTF(KD)=KOUNT FRQ21200
KDISTN(KD)=1 FRQ21210
C IS FREQUENCY ARRAY FULL? FRQ21220
IF(KD.GE.NDIM) GO TO 175 FRQ21230
C NO FRQ21240
GO TO 130 FRQ21250
C 110 FRQ21260
ADD FREQ IN MIDDLE OF LIST. FRQ21270
110 CALL TMT2(KDISTF(II),KDISTF(II+1),KD-II+1) FRQ21280
CALL TMT2(KDISTN(II),KDISTN(II+1),KD-II+1) FRQ21290
KDISTF(II)=KOUNT FRQ21300
KDISTN(II)=1 FRQ21310
KD=KD+1 FRQ21320
C IS FREQUENCY ARRAY FULL? FRQ21330
IF(KD.GE.NDIM) GO TO 175 FRQ21340
C NO FRQ21350
GO TO 130 FRQ21360
C RESET NUMBER ENTRIES IN DISTRIBUTION ARRAY AFTER FRQ21370
C PRINTING NDIM ELEMENT SEGMENT. FRQ21380
128 KD=0 FRQ21390
C KSW=1 FRQ21400
C 130 FRQ21410
WRITE OUTPUT RECORD. FRQ21420
C WRITE THE MODEL NUMBER, PATTERN AND FREQUENCY FRQ21430
C FOR THAT PATTERN. FRQ21440
130 WRITE(KOUT)MODL,(KS(I),I=1,NTIMES),KOUNT FRQ21450
C UPDATE OUTPUT RECORD COUNT. FRQ21460
KPAT=KPAT+1 FRQ21470
C BRANCH ON KSW FRQ21480
IF(KSW.EQ.1) GO TO 140 FRQ21490
C KSW=2,4 FRQ21500
GO TO 180 FRQ21510
C ***FRQ21520
C KDISTF IS FULL. PRINT FIRST NDIM ENTRIES. FRQ21530
175 KSW=3 FRQ21540
C 180 FRQ21550
PRINT FREQUENCY DISTRIBUTION. FRQ21560
C 180 PRINT 190,MODL,(KDISTF(I),KDISTN(I),I=1,KD) FRQ21570
190 FORMAT(34H1FREQUENCY DISTRIBUTION FOR MODEL ,I12//1X, 5(6X,4HFREQ,FRQ21580
19X,1HN)/(1X,10I10)) FRQ21590
C PRINT NUMBER CASES READ AND EXPECTED, NUMBER FRQ21600
C UNIQUE PATTERNS AND NUMBER UNIQUE FREQUENCIES. FRQ21610
C PRINT 195,NCASES,KCASES FRQ21620
195 FORMAT(/54H CURRENT NUMBER OF INPUT RECORDS FOR THIS MODEL = ,FRQ21630
1112/54H EXPECTED NUMBER OF CASES FOR THIS MODEL (IF KNOWN) = ,I12)FRQ21640
PRINT 200,KPAT,KD FRQ21650
C 200 FORMAT(54H CURRENT NUMBER OF OUTPUT RECORDS FOR THIS MODEL = ,FRQ21660
1112/54H NUMBER OF ENTRIES IN FREQ DIST TABLE JUST PRINTED = ,I12)FRQ21670
C BRANCH ON KSW. (WILL NEVER EQUAL 1 HERE.) FRQ21680
C GO TO (20,20,128,205),KSW FRQ21690
C FRQ21700
```

C MODEL CHANGE ON THE CURRENT INPUT UNIT. FRQ21710
C RESET COMPARE FIELD AND MODEL NUMBER FIELD FOR FRQ21720
C NEW MODEL. FRQ21730
C
205 DO 210 I=1,NTIMES FRQ21740
210 KS(I)=KSNEW(I) FRQ21750
MODL=MODNU FRQ21760
GO TO 40 FRQ21770
C
250 YES FRQ21780
C ALL INPUT FILES HAVE BEEN PROCESSED. FRQ21790
C REWIND OUTPUT UNIT. FRQ21800
C
250 REWIND KOUT FRQ21810
C RETURN FRQ21820
C
300 300 FRQ21830
C ERROR IN INPUT DATA. FRQ21840
C PRINT SEQUENCE ERROR MESSAGE FRQ21850
C
300 PRINT 310,(KSII),I=1,NTIMES FRQ21860
PRINT 320,(KSNEW(I),I=1,NTIMES) FRQ21870
PRINT 330,MODL,NCASES FRQ21880
C EXIT FRQ21890
C STOP FRQ21900
C
310 FORMAT(35H INPUT TAPE NOT IN ASCENDING ORDER./
1 10H KS = ,10I12/(10X,10I12)) FRQ21910
320 FORMAT(10H KSNEW = ,10I12/(10X,10I12)) FRQ21920
330 FORMAT(10H MODL = ,I12/I0H CASE NO= ,I12) FRQ21930
C
REFERENCE LIST. FRQ21940
C
SUBROUTINE ARGUMENTS. FRQ21950
C
KS - ARRAY FOR A STATE NUMBER PATTERN. FRQ21960
KSNEW - ARRAY FOR A STATE NUMBER PATTERN. FRQ21970
KDISTF - ARRAY OF UNIQUE FREQUENCIES. FRQ21980
KDISTN - ARRAY OF NUMBER OF PATTERNS HAVING THAT FREQUENCY. FRQ21990
NDIM - DIMENSION OF KDISTF AND KDISTN. FRQ22000
C
OTHER VARIABLES. FRQ22010
C
KD - NUMBER OF ENTRIES CURRENTLY IN KDISTF AND KDISTN. FRQ22020
KPAT - NUMBER OF UNIQUE PATTERNS. FRQ22030
KOUNT - FREQ FOR CURRENT PATTERN. FRQ22040
KIN - FREQ FOR RECORD JUST READ. FRQ22050
KSW - 1. BRANCH TO WRITE PATTERN BECAUSE OF A PATTERN CHANGE. FRQ22060
2. BRANCH TO WRITE PATTERN BECAUSE OF END OF DATA. FRQ22070
3. BRANCH TO PRINT FREQ BECAUSE KDISTF HAS NDIM ENTRIES. FRQ22080
4. BRANCH TO WRITE PATTERN AND PRINT FREQ ON MODEL CHANGEFRQ22090
C
KOUT - OUTPUT UNIT NUMBER. FRQ22100
C
KINP - INPUT UNIT NUMBER. FRQ22110
KCASES - EXPECTED CASE N. FRQ22120
C
MODL - MODEL NUMBER BEING PROCESSED. FRQ22130
MODNU - MODEL NUMBER JUST READ. FRQ22140
C
NTIMES - NUMBER OF TIMES FOR WHICH STATE NUMBERS WERE GENERATED. FRQ22150
END FRQ22160

SUBROUTINE GENDSP(ISN,ISVEC,JCOL,JVAL,P,LSTCOL,LSVEC) GEND0010
C GEND0020
C GENFRATF D MATRIX, FROM-S VECTOR, TO-S VECTOR GEND0030
C AND P MATRIX. GEND0040
C GEND0050
C IMPLICIT REAL*8(A-H,O-Z,\$) GEND0060
C DIMENSION ISN(1),ISVEC(1),JCOL(1),JVAL(1),P(1),LSTCOL(1) GEND0070
1 ,LSVEC(1) GEND0080
C FROM-S ARRAYS: ISN,ISVEC. GEND0090
C D OR P ROW ARRAYS: JCOL,JVAL,P. GEND0100
C TO-S ARRAYS: LSTCOL,LSVEC. GEND0110
C DIMENSION NDFILE(6),LABELD(30),NSFILE(6),LABELS(30),NPFILE(6), GEND0120
1 LABELP(30),NAMES2(6),LABLS2(30),LSTCNT(10) GEND0130
C THE CALLING PROGRAM MAY EQUIVALENCE JVAL AND P. GEND0140
C EQUIVALENCE (NDFILE(1),NSFILE(1)),(LABELD(1),LABELS(1)). GEND0150
1 (NPFILE(1),NAMES2(1)),(LABELP(1),LABLS2(1)) GEND0160
DATA KBLANK/4H / GEND0170
C INITIALIZE RECORD-TYPE VARIABLES. GEND0180
C D MATRIX BEGINNING LABEL, DATA RECORD, END LABEL GEND0200
C KDBEG=1 GEND0210
KDDAT=21 GEND0220
KDEND=31 GEND0230
C S VECTOR BEGINNING LABEL, DATA RECORD, END LABEL GEND0240
KSHEG=2 GEND0250
KSDAT=22 GEND0260
KSEND=32 GEND0270
C P MATRIX BEGINNING LABEL, LIST RECORD, DATA GEND0280
RECORD, END LABEL. GEND0290
KPREG=3 GEND0300
KPLST=13 GEND0310
KPDAT=23 GEND0320
KPEnd=33 GEND0330
C FLOMOD END OF FILE RECORD. GEND0340
KNEXT=40 GEND0350
C
1 FORMAT(5I6) GEND0370
2 FORMAT(3I12) GEND0380
5 FORMAT(1H1) GEND0390
25 FORMAT(6A4/20A4/10A4) GEND0400
30 FORMAT(//1X,30A4) GEND0410
C
INITIALIZE GEND0420
READ: I/O UNITS ID, NUMBER SETS OF DATA TO BE GEND0430
PROCESSED, PRINT SWITCH. GEND0440
C READ 1,ITAPE1,ITAPE2,ITAPE3,NTIMES,KPRINT GEND0450
REWIND INPUT UNIT AND OUTPUT UNIT. GEND0460
C REWIND ITAPE1 GEND0470
REWIND ITAPE3 GEND0480
C SET INPSW TO INDICATE NO EOF CONDITION ON DATA GEND0500
RECORD READ. GEND0510
C
INPSW=0 GEND0520
C
INITIALIZE NUMBER OF FILES ON OUTPUT UNIT TO GEND0530
ZERO. GEND0540
C
NFILES=0 GEND0550
C SKIP TO NEW PAGE ON PRINT UNIT. GEND0560

```
PRINT 5 GEND0570
C READ: GEND0580
C NZERO - ZERO STATE N. GEND0590
C MODSW - TRANSITION MODIFY SWITCH. GEND0600
C MODFAC - NUMBER CODES FOR LAST VARIABLE. GEND0610
C READ 2,NZERO,MODSW,MODFAC GEND0620
C READ FOR INITIAL DATA RECORD ONLY. GEND0630
C MODEL NUMBER, FROM-STATE NUMBER, TO-STATE NUMBER GEND0640
C AND FREQUENCY FOR THIS STATE NUMBER PAIR ARE GEND0650
C RETURNED. GEND0660
C CALL READIN (ITAPE1,ID,IS1,IS2,KNT,INPSW) GEND0670
C WAS THERE AN END OF FILE ON THIS READ? GEND0680
C YES. GO TO PRINT ERROR MESSAGE. GEND0690
C IF(INPSW.NE.0) GO TO 400 GEND0700
C 10 GEND0710
C NO GEND0720
C INITIALIZATION FOR EACH MODEL. GEND0730
C INITIALIZE LSTCOL BY INDICATING FIRST ELEMENT IS GEND0740
C COLUMN ZERO. GEND0750
C 10 LSTCOL(1)=0 GEND0760
C LSVEC(1)=0 GEND0770
C JCOUNT=1 GEND0780
C NPELE=0 GEND0790
C NFILL=1 GEND0800
C ISUM=0 GEND0810
C NL=30 GEND0820
C LST#1 GEND0830
C READ D AND P NAMES AND LABELS. GEND0840
C READ 25,NDFILE,LABELD,NPFILE,LABELP GEND0850
C PRINT D LABEL. GEND0860
C PRINT 30,LABELD GEND0870
C IF KPRINT.NE.0) GO TO 34 GEND0880
C PRINT 32 GEND0890
C 32 FORMAT(44H LIST OF NUMBER OF NON-ZERO ENTRIES PER ROW.) GEND0900
C REWIND TEMPORARY STORAGE UNIT. GEND0910
C 34 REWIND ITAPE2 GEND0920
C WRITE(ITAPE3)KDBEG,NDFILE,NL,LABELD GEND0930
C WRITE(ITAPE2)KPBEG,NPFILE,NL,LABELP GEND0940
C READ 25,NSFILE,LABELS,NAMES2,LABLS2 GEND0950
C READ P MATRIX INCREMENT FACTORS. GEND0960
C READ 1,NUMMO,NUMYR GEND0970
C SET NUMBER ENTRIES IN FROM-S EQUAL ZERO. THIS IS GEND1100
C ALSO THE NUMBER OF D MATRIX ROWS. GEND1110
C ISCNT=0 GEND1120
C FOR FIRST ROW OF DISTRIBUTION MATRIX, SET NUMBER GEND1130
```

C OF ROW ENTRIES EQUAL ONE. GEND1140
C ICOUNT=1 GEND1150
C C GEND1160
C C ***GEND1170
C GENERATE A ROW OF DISTRIBUTION MATRIX. *GEND1180
C C 40 GEND1190
C STORE COL NUMBER AND INITIAL COL COUNT IN ROW. GEND1200
C C 40 JCOL(ICOUNT)=IS2 GEND1210
C JVAL(ICOUNT)=KNT GEND1220
C C 42 GEND1230
C READ FOR ALL EXCEPT FIRST DATA RECORD. GEND1240
C MODEL NUMBER, FROM-STATE NUMBER, TO-STATE NUMBER GEND1250
C AND FREQUENCY FOR THIS STATE NUMBER PAIR ARE GEND1260
C RETURNED. GEND1270
C 42 CALL READIN (ITAPE1, ID2, IS12, IS22, KNT, INPSW) GEND1280
C WAS THERE AN END OF FILE ON THIS READ? GEND1290
C GO TO SUM ROW ON EOF. GEND1300
C IF(INPSW.NE.0) GO TO 60 GEND1310
C NO EOF. GEND1320
C WAS MODEL NUMBER JUST READ SAME AS MODEL NUMBER GEND1330
C OF PREVIOUS READ? GEND1340
C GO TO SUM ROW ON ID CHANGE. GEND1350
C IF(ID2.NE.ID) GO TO 60 GEND1360
C GEND1370
C YES. THIS IS THE SAME MODEL. GEND1380
C WAS ROW JUST READ SAME AS ROW OF PREVIOUS READ? GEND1390
C NO. GO TO SUM ROW. GEND1400
C IF (IS12.NE.IS1) GO TO 60 GEND1410
C YES. THIS IS THE SAME ROW AND MODEL. GEND1420
C WAS COL JUST READ SAME AS COL OF PREVIOUS READ? GEND1430
C NO. GO TO INCREMENT COUNT OF COLUMN ELEMENTS IN GEND1440
C THE ROW. GEND1450
C IF(IS22.NE.IS2) GO TO 45 GEND1460
C YES. THIS IS THE SAME COLUMN AND ROW AND MODEL. GEND1470
C ADD FREQUENCY FOR THIS DATA RECORD TO CUMULATIVE GEND1480
C FREQUENCY IN JVAL. GEND1490
C JVAL(ICOUNT)=JVAL(ICOUNT)+KNT GEND1500
C GO TO READ NEXT PAIR RECORD. GEND1510
C GO TO 42 GEND1520
C 45 ICOUNT=ICOUNT+1 GEND1530
C MOVE COL NUMBER JUST READ TO PREVIOUS COL VARIABLE. GEND1540
C GEND1550
C ADD 1 TO NUMBER OF COLUMN ELEMENTS. GEND1560
C GEND1570
C IS2=IS22 GEND1580
C GO TO STORE COLUMN NUMBER AND COUNT. GEND1590
C GEND1600
C GO TO 40 GEND1610
C GEND1620
C GEND1630
C 60 GEND1640
C TRANSFER HERE AT END OF A ROW. GEND1650
C CONDITIONS WHICH WILL SIGNAL THE END OF A ROW GEND1660
C ARE (1) AN EOF ON THE READ OF A PAIR RECORD, GEND1670
C (2) A MODEL CHANGE IN THE PAIR RECORDS, AND GEND1680
C (3) A CHANGE IN THE ROW NUMBER IN A PAIR RECORD. GEND1690
C 4 SUM ELEMENTS OF ROW OF D MATRIX TO OBTAIN FROM-SGEND1700

C ENTRY. GEND1710
60 KSUM=0 GEND1720
DO 62 I=1,ICOUNT GEND1730
62 KSUM=KSUM+JVAL(I) GEND1740
C UPDATE ROW COUNT. GEND1750
ISCNT=ISCNT+1 GEND1760
C STORE ROW NUMBER AND SUM IN FROM-S VECTOR. GEND1770
ISN(ISCNT)=IS1 GEND1780
ISVEC(ISCNT)=KSUM GEND1790
C IS THIS ROW ZERO? GEND1800
C NO. GO TO UPDATE COLUMN LIST. GEND1810
C IF(IS1.NE.0) GO TO 68 GEND1820
C YES GEND1830
C IS COL ZERO PRESENT? GEND1840
C IF(JCOL(1).EQ.0) GO TO 66 GEND1850
C NO GEND1860
C PUSH DOWN ENTRIES IN COL AND ELEMENT LIST. GEND1870
DO 64 I=1,ICOUNT GEND1880
IFR=ICOUNT-I+2 GEND1890
JCOL(IFR)=JCOL(IFR-1) GEND1900
64 JVAL(IFR)=JVAL(IFR-1) GEND1910
C ADD ZERO, ZERO WITH VALUE OF ZERO. GEND1920
ICOUNT=ICOUNT+1 GEND1930
JCOL(1)=0 GEND1940
JVAL(1)=0 GEND1950
C 66 GEND1960
C MAKE NZERO ADJUSTMENT TO FROM-S STATE ZERO ELEMENT. GEND1970
C IF(NZERO.EQ.0) GO TO 68 GEND1980
C IF(NZERO.LT.KSUM) GO TO 67 GEND1990
C IF NZERO IS GREATER THAN KSUM, GEND2000
C ADJUST (ZERO,ZERO) ELEMENT. GEND2010
C JVAL(1)=NZERO-KSUM+JVAL(1) GEND2020
C ADJUST ROW-ZERO SUM. GEND2030
C KSUM=NZERO GEND2040
C ISVEC(ISCNT)=KSUM GEND2050
C GO TO 68 GEND2060
C PRINT MESSAGE IF NZERO ADJUSTMENT IS BYPASSED. GEND2070
67 PRINT 410,NZERO,KSUM GEND2080
410 FORMAT(55H NZERO VALUE IN CONTROL CARD IS LESS THAN ZERO ROW SUM./GEND2110
136H NZERO ADJUSTMENT HAS BEEN BYPASSED./ GEND2120
2 9H NZERO = ,I12,5X,16H ZERO ROW SUM = ,I12) GEND2130
C 68 *GEND2140
C ***GEND2150
C GEND2160
C ***GEND2170
C *GEND2180
C GEND2190
C GEND2200
C FOR D ROW JUST COMPLETED, FILE COL NUMBERS IN LSTCOL AND ACCUMULATE FREQUENCIES IN TO-S. GEND2210
C INITIAL J FROM VALUE FOR LSTCOL INDEX USE. GEND2220
C GEND2230
C GEND2240
68 JFR=1 GEND2250
C DO FOR EACH ENTRY IN ROW. GEND2260
DO 76 I=1,ICOUNT GEND2270

C COMPUTE ICOL TO AVOID GENERATING SUBSCRIPTED GEND2280
C VALUE MANY TIMES IN INNER DO. GEND2290
C ICOL=JCOL(I) GEND2300
C DO FOR EACH ENTRY IN LSTCOL. GEND2310
C DO 70 J=JFR,JCOUNT GEND2320
C COMPARE COLUMN IN ROW WITH COLUMN IN LIST OF GEND2330
C COLUMNS. GEND2340
C IF(ICOL.GT.LSTCOL(J)) GO TO 70 GEND2350
C IF(ICOL.LT.LSTCOL(J)) GO TO 72 GEND2360
C ICOL.EQ.LSTCOL(J) GEND2370
C ACCUMULATE FREQ FOR THIS ELEMENT IN TO-S. GEND2380
C LSVEC(J)=LSVEC(J)+JVAL(I) GEND2390
C GO TO INCREMENT LSTCOL FROM-INDEX. GEND2400
C GO TO 74 GEND2410
C 70 70 GEND2420
C J CONTINUE GEND2430
C 70 CONTINUE GEND2440
C END OF J LOOP. GEND2450
C IF FALL THRU LOOP, 'ICOL' AND ALL ADDITIONAL GEND2460
C CNTRIES IN THE ROW LIST OF COLUMNS DO NOT MATCH GEND2470
C LSTCOL ENTRIES. THEY WILL BE ADDED TO THE END OF GEND2480
C THE COLUMN LIST FOR THE MATRIX. GEND2490
C GO TO 80 GEND2500
C 72 GEND2510
C ICOL IS LT LSTCOL(J) SO FILE IN ICOL HERE. GEND2520
C PUSH DOWN LSTCOL AND LSVEC ENTRIES. GEND2530
C 72 CALL TMT2(LSTCOL(J),LSTCOL(J+1),JCOUNT-J+1) GEND2540
C CALL TMT2(LSVEC(J),LSVEC(J+1),JCOUNT-J+1) GEND2550
C UPDATE J COUNT. GEND2560
C JCOUNT=JCOUNT+1 GEND2570
C FILE COL NUMBER AND COL VALUE IN LSTCOL AND GEND2580
C LSVEC. GEND2590
C LSTCOL(J)=ICOL GEND2600
C LSVEC(J)=JVAL(I) GEND2610
C 74 GEND2620
C INCREMENT INITIAL COLUMN LIST SUBSCRIPT VALUE GEND2630
C FOR NEXT COMPARE. GEND2640
C 74 JFR=J+1 GEND2650
C HAVE ALL J'S BEEN PROCESSED? GEND2660
C NO. GO TO INCREMENT SUBSCRIPT FOR COLUMN ENTRY GEND2670
C IN A ROW. GEND2680
C IF(JFR.LE.JCOUNT) GO TO 76 GEND2690
C YES GEND2700
C HAVE ALL I'S BEEN PROCESSED? GEND2710
C YES. COLUMN LIST UPDATE IS COMPLETE. GEND2720
C IF(I.EQ.ICOUNT) GO TO 83 GEND2730
C NO GEND2740
C GO TO 78 GEND2750
C 76 GEND2760
C CONTINUE - DO I FOR EACH ROW. GEND2770
C 76 GEND2780
C GO TO 83 GEND2790
C 78 GEND2800
C UPDATE I INDEX GEND2810
C 78 I=I+1 GEND2820
C GEND2830
C GEND2840

C 80 ADD REMAINING I THRU ICOUNT ENTRIES IN ROW TO LSVEC AND LSTCOL. UPDATE ELEMENT COUNT (J COUNT) GEND2850
C JCOUNT=JCOUNT+1 GEND2860
C LSVEC(JCOUNT)=JVAL(K) GEND2870
C 82 LSTCOL(JCOUNT)=JCOL(K) GEND2880
C END OF UPDATE LSTCOL SEGMENT *GEND2890
C ***GEND2900
C 83 ADD COUNT OF D ELEMENTS IN ROW JUST COMPLETED TO COUNT OF D ELEMENTS IN THE MATRIX. GEND2910
C GEND2920
C GEND2930
C 83 NPELE=NPELE+ICOUNT GEND2940
C WRITE D ROW NUMBER AND DATA. GEND2950
C WRITE(ITAPE3)KDDAT,IS1,ICOUNT,(JCOL(I),I=1,ICOUNT), GEND2960
C 1 (JVAL(I),I=1,ICOUNT) GEND2970
C IS PRINT SWITCH ON? GEND2980
C IF(KPRINT.NE.0) GO TO 88 GEND2990
C YES GEND3000
C SAVE ICOUNT. PRINT ICOUNT PRINT LINE IF ONE LINE GEND3010
C ARRAY IS FULL. GEND3020
C LSTCNT(LST)=ICOUNT GEND3030
C LST=LST+1 GEND3040
C IF(LST.LT.11) GO TO 88 GEND3050
C PRINT 86,LSTCNT GEND3060
C 86 FORMAT(1X,10I12) GEND3070
C LST=1 GEND3080
C 88 DIVIDE EACH D ELEMENT BY ROW SUM TO GET P ROW. GEND3090
C GEND3100
C 88 S=KSUM GEND3110
C DO 90 I=1,ICOUNT GEND3120
C D=JVAL(I) GEND3130
C 90 P(I)=D/S GEND3140
C WRITE P ROW ON ITAPE 2. GEND3150
C WRITE(ITAPE2)KPDAT,IS1,ICOUNT,(JCOL(I),I=1,ICOUNT), GEND3160
C 1 (P(I),I=1,ICOUNT) GEND3170
C END-OF-ROW HOUSEKEEPING. GEND3180
C ACCUMULATE ROW SUM INTO S SUM. GEND3190
C ISUM=ISUM+KSUM GEND3200
C SET 'PREVIOUS' ROW AND COL EQUAL ROW AND COL OF GEND3210
C LAST RECORD READ. GEND3220
C IS1=IS12 GEND3230
C IS2=IS22 GEND3240
C ICOUNT=1 SET NUMBER OF ENTRIES IN ROW TO ONE. GEND3250
C ARE THERE ADDITIONAL DATA RECORDS TO BE PROCESSED FOR THE CURRENT MODEL? GEND3260
C YES, GO TO STORE LATEST PAIR COLUMN AND FREQ IN A NEW ROW. GEND3270
C IF(ID2.EQ.ID.AND.INPSW.EQ.0) GO TO 40 GEND3280
C NO GEND3290
C THERE WAS A MODEL CHANGE OR READ EOF. GEND3300
C SET CURRENT MODEL ID TO ID OF RECORD LAST READ. GEND3310
C ID=ID2 GEND3320
C IF PRINT SWITCH IS ON AND THERE ARE ANY ICOUNT GEND3330
C GEND3340
C GEND3350
C GEND3360
C NO GEND3370
C GEND3380
C GEND3390
C GEND3400
C GEND3410

C ELEMENTS LEFT IN PRINT LINE, PRINT. GEND3420
C IF(KPRINT.NE.0) GO TO 93 GEND3430
C IF(LST.EQ.1) GO TO 93 GEND3440
LST=LST-1 GEND3450
C PRINT 86,(LSTCNT(I),I=1,LST) GEND3460
C 93 GEND3470
C WRITE FILE END LABELS FOR D AND P. GEND3480
C 93 WRITE(ITAPE3)KDEND,NFILL,NFILL,ISCNT,NPELE GEND3490
PELE=NPELE GEND3500
WRITE(ITAPE2)KPEND,NFILL,NFILL,ISCNT,PELE GEND3510
FOR FROM-S, WRITE BEGINNING LABEL, DATA RECORD, GEND3520
END LABEL. GEND3530
WRITE(ITAPE3)KSBEGL,NSFILE,NL,LABELS GEND3540
WRITE(ITAPE3)KSDAT,NFILL,ISCNT,(ISN(I),I=1,ISCNT), GEND3550
1 (ISVEC(I),I=1,ISCNT) GEND3560
WRITE(ITAPE3)KSEND,NFILL,NFILL,ISUM,NFILL GEND3570
C FOR TO-S, WRITE BEGINNING LABEL, DATA RECORD, GEND3580
END LABEL. GEND3590
WRITE(ITAPE3)KSBEGL,NAMES2,NL,LABLS2 GEND3600
WRITE(ITAPE3)KSDAT,NFILL,JCOUNT,(LSTCOL(I),I=1,JCOUNT), GEND3610
1 (LSVEC(I),I=1,JCOUNT) GEND3620
WRITE(ITAPE3)KSEND,NFILL,NFILL,ISUM,NFILL GEND3630
C PRINT NUMBER OF NON-ZERO ELEMENTS AND NON-ZERO GEND3640
ROWS AND COLUMNS IN D MATRIX. GEND3650
C PRINT 95,NPELE GEND3660
PRINT 96,ISCNT,JCOUNT GEND3670
95 FORMAT(42H THE NUMBER OF ELEMENTS IN THE D MATRIX IS ,I12) GEND3680
96 FORMAT(42H THE NUMBER OF ROWS IN THE D MATRIX IS ,I12/ GEND3690
1 42H THE NUMBER OF COLUMNS IN THE D MATRIX IS ,I12) GEND3700
C IS TRANSITION MODIFY TO BE EXECUTED? GEND3710
C NO, GO TO COPY P MATRIX. GEND3720
C IF(IMODSW.LT.0) GO TO 340 GEND3730
C ***GEND3740
C *GEND3750
C YES. GEND3760
C TRANSITION MODIFY IS TO BE EXECUTED. GEND3770
C TRANSITION MODIFY WILL ADD A ROW TO THE P MATRIX GEND3780
C FOR EACH COLUMN WHICH DOES NOT HAVE A CORRE- GEND3790
C SPONDING ROW PRESENT. GEND3800
C GEND3810
C IN THIS SEGMENT OF THE PROGRAM, COMPARE THE P GEND3820
C MATRIX LIST OF ROWS AND LIST OF COLUMNS. MAKE GEND3830
C ADDITIONS TO THESE LISTS AS REQUIRED BY THE GEND3840
C MODIFY OPERATION FOR THE CURRENT MODIFY SWITCH GEND3850
C SETTINGS. GEND3860
C GEND3870
C DETERMINE ROWS TO BE ADDED BY TRANSITION MODIFY. GEND3880
C UPDATE ISN. GEND3890
C THIS IS CONCEPTUALLY A PAIR OF PARALLEL DO LOOPS GEND3900
C DO LOOPS ARE NOT USED BECAUSE THE INDEX VALUES GEND3910
C ARE CHANGING WITHIN THE RANGE OF THE LOOP. GEND3920
C GEND3930
C INITIALIZE INDICES. GEND3940

C JADD = NUMBER OF ELEMENTS ADDED TO THE ROW LIST.GEND3990
C JADD=0 GEND4000
C I=1 I IS SUBSCRIPT FOR LIST OF ROWS - ISN. GEND4010
C J=1 J IS SUBSCRIPT FOR LIST OF COLUMNS - LSTCOL. GEND4020
C 100 COMPARE COLUMN LIST ELEMENT AND ROW LIST ELEMENTGEND4030
C 100 IF(LSTCOL(J),EQ.ISN(I)) GO TO 105 GEND4040
C GO TO 120 GEND4050
C 105 THE COLUMN NUMBER EQUALS THE ROW NUMBER. GEND4060
C ARE THERE ANYMORE ENTRIES IN THE ROW LIST? GEND4070
C YES. GO TO INCREMENT ROW SUBSCRIPT. GEND4080
C 105 IF(I.LT.ISCNT) GO TO 135 GEND4090
C NO GEND4100
C ARE THERE ANYMORE ENTRIES IN LSTCOL? GEND4110
C NO. DETERMINATION OF ROWS TO BE ADDED COMPLETE. GEND4120
C IF(J.EQ.JCOUNT) GO TO 175 GEND4130
C YES GEND4140
C ADD REMAINING ELEMENTS IN COLUMN LIST TO ROW GEND4150
C LIST. GEND4160
C SUBSCRIPT OF FIRST COLUMN LIST ELEMENT TO BE GEND4170
C ADDED IS J+1. GEND4180
C K=J+1 GEND4190
C **GEND4200
C *GEND4210
C 110 PROGRAM SEGMENT TO ADD COLUMN LIST ENTRIES TO GEND4220
C ROW LIST. GEND4230
C UPDATE COUNT OF ROW ELEMENTS ADDED. GEND4240
C 110 JADD=JADD+1 GEND4250
C UPDATE ROW LIST SUBSCRIPT. GEND4260
C ISCNT=ISCNT+1 GEND4270
C MOVE COLUMN LIST ELEMENT TO ROW LIST. GEND4280
C ISN(ISCNT)=LSTCOL(K) GEND4290
C ARE ALL ELEMENTS TO BE ADDED BY THE MODIFY GEND4300
C OPERATION DIAGONAL ELEMENTS? GEND4310
C YES. GO TO INCREMENT COLUMN LIST SUBSCRIPT. GEND4320
C IF(MODSW.EQ.0) GO TO 114 GEND4330
C NO GEND4340
C WAS THE STATE NUMBER JUST ADDED TO THE ROW LIST GEND4350
C GENERATED FROM THE LAST CODE OF THE LAST GEND4360
C VARIABLE? GEND4370
C YES. GO TO INCREMENT COLUMN LIST SUBSCRIPT. GEND4380
C IF(MOD(LSTCOL(K),MODFAC).EQ.0) GO TO 114 GEND4390
C NO GEND4400
C THEREFORE AN OFF DIAGONAL ELEMENT WILL BE ADDED.GEND4410
C GENERATE THE COLUMN NUMBER OF THIS ELEMENT. GEND4420
C ICOL=LSTCOL(K)+MODSW GEND4430
C GEND4440
C THIS OFF DIAGONAL ELEMENT WILL ALWAYS BE GREATERGEND4450
C THAN THE COLUMN NUMBER JUST PLACED IN THE ROW GEND4460
C LIST. GEND4470
C ADD THIS ELEMENT TO THE COLUMN LIST IF NECESSARYGEND4480
C CALL FILE(ICOL,LSTCOL(K),JCOUNT-K+1,JCOUNT) GEND4490
C THE FILE SUBROUTINE WILL UPDATE JCOUNT IF AN GEND4500

C ADDITION IS MADE TO THE COLUMN LIST. GEND4560
C 114 ARE THERE ANY MORE LSTCOL (JCOUNT) ELEMENTS? GEND4570
C NO. LIST COMPARE COMPLETE. GEND4580
C 114 IF(K.EQ.JCOUNT) GO TO 175 GEND4590
C YES GEND4600
C INCREMENT SUBSCRIPT FOR LSTCOL ELEMENT TO BE GEND4610
C ADDED. GEND4620
C K=K+1 GEND4630
C GO TO 110 *GEND4640
C **GEND4650
C 120 THE CURRENT COLUMN AND ROW NUMBERS ARE NOT EQUAL GEND4660
C IF THERE IS A ROW PRESENT FOR WHICH THERE IS NO GEND4670
C CORRESPONDING COLUMN, GO TO INCREMENT ROW SUB- GEND4680
C SCRIPT. GEND4690
C 120 IF(LSTCOL(J).GT.ISN(I)) GO TO 125 GEND4700
C 121 THE CURRENT COLUMN NUMBER IS LESS THAN THE ROW GEND4710
C NUMBER. ADD THIS ONE ELEMENT TO THE ROW LIST. GEND4720
C UPDATE COUNT OF ROW ELEMENTS ADDED. GEND4730
C 121 JADD=JADD+1 GEND4740
C CALL TMT2 TO PUSH DOWN ROW LIST. GEND4750
C CALL TMT2(ISN(I),ISN(I+1),ISCNT-I+1) GEND4760
C PLACE COLUMN ELEMENT IN ROW LIST. GEND4770
C ISN(I)=LSTCOL(J) GEND4780
C ISCNT=ISCNT+1 GEND4790
C ARE ALL ELEMENTS TO BE ADDED BY THE MODIFY GEND4800
C OPERATION DIAGONAL ELEMENTS? GEND4810
C YES. GO TO INCREMENT BOTH ROW AND COLUMN LIST GEND4820
C SUBSCRIPTS. GEND4830
C IF(MODSW.EQ.0) GO TO 135 GEND4840
C NO GEND4850
C WAS THIS STATE NUMBER GENERATED FROM THE LAST GEND4860
C CODE OF THE LAST VARIABLE? GEND4870
C YES. GO TO INCREMENT BOTH ROW AND COLUMN LIST GEND4880
C SUBSCRIPTS. GEND4890
C IF(MOD(LSTCOL(J),MODFAC).EQ.0) GO TO 135 GEND4900
C NO GEND4910
C THEREFORE AN OFF DIAGONAL ELEMENT WILL BE ADDED. GEND4920
C GENERATE THE COLUMN NUMBER OF THIS ELEMENT. GEND4930
C ICOL=LSTCOL(J)+MODSW GEND4940
C ADD THIS ELEMENT TO THE COLUMN LIST IF NECESSARY GEND4950
C CALL FILE(ICOL,LSTCOL(J),JCOUNT-J+1,JCOUNT) GEND4960
C THE FILE SUBROUTINE WILL UPDATE JCOUNT IF AN GEND4970
C ADDITION IS MADE TO THE COLUMN LIST. GEND4980
C GO TO INCREMENT SUBSCRIPTS. GEND4990
C GO TO 135 GEND5000
C 125 CURRENT COLUMN ELEMENT IS GT CURRENT ROW ELEMENT GEND5010
C ARE THERE ANYMORE ENTRIES IN ISN LIST? GEND5020
C NO. ADD REMAINING COLUMN ENTRIES TO ROW LIST. GEND5030
C 125 IF(I.EQ.ISCNT) GO TO 130 GEND5040
C YES GEND5050
C INCREMENT I. GEND5060
C GEND5070
C GEND5080
C GEND5090
C GEND5100
C GEND5110
C GEND5120

I=I+1 GEND5130
C GO TO 100 GEND5140
C 130 GEND5150
C THERE ARE NO MORE ENTRIES IN THE ROW LIST. GEND5160
C THERE ARE ENTRIES IN THE COLUMN LIST. ADD GEND5170
C REMAINING COLUMN LIST ENTRIES TO THE ROW LIST. GEND5180
C SUBSCRIPT OF FIRST LSTCOL ELEMENT TO BE ADDED GEND5190
C IS J. GEND5200
C 130 K=J GEND5210
C GO TO 110 GEND5220
C 135 GEND5230
C YES GEND5240
C THERE ARE ADDITIONAL ENTRIES IN THE ROW LIST. GEND5250
C INCREMENT ROW LIST SUBSCRIPT. GEND5260
C 135 I=I+1 GEND5270
C ARE THERE ANYMORE ENTRIES IN LSTCOL? GEND5280
C NO. LIST COMPARE COMPLETE. GEND5290
C 140 IF(J.EQ.JCOUNT) GO TO 175 GEND5300
C YES GEND5310
C INCREMENT J. GEND5320
C J=J+1 GEND5330
C GO TO COMPARE COLUMN LIST ELEMENT AND ROW LIST GEND5340
C ELEMENT. GEND5350
C GO TO 100 GEND5360
C *GEND5370
C ***GEND5380
C 175 GEND5390
C WERE ANY ADDITIONS MADE TO THE ROW LIST BY THE GEND5400
C MODIFY OPERATION? GEND5410
C 175 IF(JADD.GT.0) GO TO 185 GEND5420
C NO GEND5430
C PRINT MESSAGE THAT NO ROWS ARE BEING ADDED. GEND5440
C PRINT 180 GEND5450
C 180 FORMAT(68H NO ROWS OR COLUMNS WERE ADDED TO THE P MATRIX BY TRANSI- GEND5460
C TION MODIFY.) GEND5470
C GO TO COPY P MATRIX. GEND5480
C GO TO 350 GEND5490
C 185 GEND5500
C 185 GEND5510
C YES GEND5520
C ADDITIONS WERE MADE TO THE ROW LIST BY TRANSI- GEND5530
C TION MODIFY. GEND5540
C UPDATE COUNT OF NUMBER OF P ELEMENTS. GEND5550
C 185 NPELE=NPELE+JADD GEND5560
C PRINT NUMBER ELEMENTS AND NUMBER ROWS IN P GEND5570
C MATRIX. GEND5580
C PRINT 194 GEND5590
C PRINT 195,NPELE GEND5600
C PRINT 196,ISCNT,JCOUNT GEND5610
C 194 FORMAT(56H CHANGES WERE MADE IN THE P MATRIX BY TRANSITION MODIFY. GEND5620
C 1) GEND5630
C 195 FORMAT(42H THE NUMBER OF ELEMENTS IN THE P MATRIX IS ,I12) GEND5640
C 196 FORMAT(42H THE NUMBER OF ROWS IN THE P MATRIX IS ,I12/ GEND5650
C 1 42H THE NUMBER OF COLUMNS IN THE P MATRIX IS ,I12) GEND5660
C ***GEND5670
C GEND5680
C ***GEND5690

C MODIFY LOOP
 C TRANS MODIFY MAKES CHANGES TO P MATRIX ONLY.
 C D AND S ARE NOT CHANGED.
 C ISW=0 FOR READ ANOTHER P RECORD.
 C ISW =1 FOR BY PASS READ P RECORD.
 C COPY P MATRIX. ADD NEW ROWS AS REQUIRED.
 C
 C REWIND ITAPE 2 COPY P BEGINNING RECORD FROM
 C ITAPE 2 TO ITAPE 3.
 C
 C READ (ITAPE2)KTYPE,NPFILE,N,LABELP
 C WRITE(ITAPE3)KTYPE,NPFILE,N,LABELP
 C WRITE P ISN RECORDS ON ITAPE 3.
 C WRITE(ITAPE3)KPLST,ISCNT,(ISN(I),I=1,ISCNT),MODSW,MODFAC
 C WRITE(ITAPE3)KPLST,JCOUNT,(LSTCOL(I),I=1,JCOUNT),NUMMD,NUMYR
 C
 C 200
 C SET ISW TO INDICATE A P DATA RECORD IS TO BE
 C READ.
 200 ISW=0
 C SET P VALUE=1.0
 C PVALUE=1.000
 C DO FOR EACH ENTRY IN LIST OF ROWS.
 C DO 260 I=1,ISCNT
 C BRANCH ON ISW.
 C IF(ISW.NE.0) GO TO 210
 C ISW=0
 C READ A P DATA RECORD FOR ROW 1ROW.
 C READ(ITAPE2)KPROW,IROW,ICOUNT,(JCOL(M),M=1,ICOUNT),
 1 (P(M),M=1,ICOUNT)
 C WAS A P END RECORD READ?
 C YES. GO TO PROCESS REMAINING ENTRIES IN ROW LIST
 C IF(KPROW.EQ.KPEND) GO TO 280
 C 210
 C NO
 C IS P MATRIX ROW JUST READ EQUAL I'TH ENTRY IN
 C LIST OF ROWS?
 C YES. GO TO WRITE P RECORD.
 210 IF(IROW.EQ.ISN(I)) GO TO 250
 C 225
 C NO
 C ROW NUMBER JUST READ IS GREATER THAN ROW LIST
 C ENTRY.
 C ADD A ROW RECORD TO P MATRIX.
 C DETERMINE COLUMN NUMBER FOR ROW BEING ADDED.
 225 ICOL=ISN(I)
 C IF(MODSW.EQ.0) GO TO 245
 C IF(MOD(ICOL,MODFAC).NE.0) ICOL=ICOL+MODSW
 C 245
 C WRITE GENERATED P RECORD.
 C 245 WRITE(ITAPE3)KPDAT,ISN(I),NFILL,ICOL,PVALUE
 C SET ISW TO INDICATE BYPASS READ P RECORD SINCE
 C LAST RECORD READ HAS NOT BEEN WRITTEN.
 C
 C ISW=1
 C GO TO 260

```
C           WRITE AN ORIGINAL ROW.          GEND6270
250 WRITE(ITAPE3)KPROW,IROW,ICOUNT,(JCOL(M),M=1,ICOUNT),
      1          (P(M),M=1,ICOUNT)          GEND6280
C           SET ISW=0          GEND6290
C           ISW=0          GEND6300
C           260          GEND6310
C           CONTINUE          GEND6320
260 CONTINUE          GEND6330
C           270          GEND6340
C           ALL ROW LIST ELEMENTS HAVE BEEN PROCESSED.          GEND6350
C           WRITE UPDATED P END RECORD.          GEND6360
C           270 PELE=NPELE          GEND6370
      WRITE(ITAPE3)KPEND,NFILL,NFILL,ISCNT,PELE          GEND6380
      GO TO 320          GEND6390
C           280          GEND6400
C           YES          GEND6410
C           ALL ORIG P RECORDS COPIED BUT ITEMS REMAINING          GEND6420
C           IN ISN TO BE PROCESSED.          GEND6430
C           FOR REMAINING ENTRIES IN ISN GENERATE AND WRITE          GEND6440
C           A P DATA RECORD.          GEND6450
C           280 DO 290 K=I,ISCNT          GEND6460
      ICOL=ISN(K)          GEND6470
      IF(MODSW.EQ.0) GO TO 290          GEND6480
      IF(MOD(ICOL,MODFAC).NE.0) ICOL=ICOL+MODSW          GEND6490
290 WRITE(ITAPE3)KPDAT,ISN(K),NFILL,ICOL,PVALUE          GEND6500
      GO TO 270          GEND6510
C           *GEND6520
C           ***GEND6530
C           320          GEND6540
C           TRANS MOD OF THIS MATRIX COMPLETE.          GEND6550
C           UPDATE COUNT OF OUTPUT TAPE FILES.          GEND6560
C           320 NFILES=NFILES+4          GEND6570
      HAVE ALL INPUT DATA RECORDS BEEN READ?          GEND6580
C           YES - RETURN.          GEND6590
      IF(INPSW.EQ.1) GO TO 330          GEND6600
      NO - PROCESS NEXT MODEL.          GEND6610
      IF THERE IS ONE.          GEND6620
      HAVE THE NUMBER OF MODELS SPECIFIED BEEN PROCESSED?
      SED?          GEND6630
      NTIMES=NTIMES-1          GEND6640
      IF(NTIMES.EQ.0) GO TO 330          GEND6650
C           NO          GEND6660
C           READ NZERO, MODSW, MODFAC FOR NEXT MODEL.          GEND6670
      READ 2,NZERO,MODSW,MODFAC          GEND6680
C           GO TO INITIALIZE FOR NEW MODEL.          GEND6690
      GO TO 10          GEND6700
C           330          GEND6710
C           YES          GEND6720
C           SET FILE NAME TO BLANK. ADD 1 TO NUMBER OF          GEND6730
C           FILES.          GEND6740
      330 DO 331 M=1,6          GEND6750
      331 NSFILE(M)=KBLANK          GEND6760
      NFILES=NFILES+1          GEND6770
C           WRITE END POSITIONING RECORD.          GEND6780
      WRITE(ITAPE3)KNEXT,NSFILE,NFILL,NFILES          GEND6790
      REWIND OUTPUT UNIT.          GEND6800
C           GEND6810
C           GEND6820
C           GEND6830
```

REWIND ITAPE3 GEND6840
C RETURN GEND6850
C RETURN GEND6860
C NO. GEND6870
C BY PASS TRANS MODIFY GEND6880
C BECAUSE MODSW SPECIFIES BYPASS. GEND6900
340 PRINT 345 GEND6910
345 FORMAT(28H TRANSITION MODIFY BYPASSED.) GEND6920
C BECAUSE NO ELEMENTS NEED TO BE ADDED. GEND6930
C COPY ORIG P FROM TEMPORARY TO PERMANENT STORAGE. GEND6940
350 REWIND ITAPE2 GEND6950
C READ AND WRITE BEGINNING LABEL. GEND6960
READ(ITAPE2)KTYPE,NPFILE,N,LABELP GEND6970
WRITE(ITAPE3)KTYPE,NPFILE,N,LABELP GEND6980
C WRITE ROW AND COLUMN LIST RECORDS GEND6990
WRITE(ITAPE3)KPLST,ISCNT,(ISN(I),I=1,ISCNT),MODSW,MODFAC GEND7000
WRITE(ITAPE3)KPLST,JCOUNT,(LSTCOL(I),I=1,JCOUNT),NUMMD,NUMYR GEND7010
C COPY DATA RECORDS. GEND7020
357 ITO=ISCNT+1 GEND7030
DO 360 I=1,ITO GEND7040
READ (ITAPE2)KTYPE,IROW,IC,(JCOL(M),M=1,IC),(P(M),M=1,IC) GEND7050
360 WRITE(ITAPE3)KTYPE,IROW,IC,(JCOL(M),M=1,IC),(P(M),M=1,IC) GEND7060
C GO TO INCREMENT OUTPUT FILE COUNT. GEND7070
GO TO 320 GEND7080
C
C 400 PRINT 405 GEND7090
C PRINT ERROR MESSAGE. GEND7100
405 FORMAT(38H EOF ON FIRST READ OF INPUT DATA TAPE.) GEND7110
C EXIT GEND7120
STOP GEND7130
C
C REFERENCE LIST. GEND7140
C
C SUBROUTINE ARGUMENTS. GEND7150
C
C ISN - ROW NUMBER ARRAY. GEND7160
C ISVEC - ROW SUM ARRAY. GEND7170
C JCOL - COL NUMBER ARRAY FOR A ROW. GEND7180
C JVAL - COL ELEMENT ARRAY FOR A ROW. GEND7190
C P - ARRAY OF PROBABILITY ELEMENTS IN A ROW. GEND7200
C JVAL AND P MAY SHARE THE SAME CORE LOCATIONS. GEND7210
C LSTCOL - ARRAY CONTAINING LIST OF COLUMNS PRESENT. GEND7220
C LSVEC - ARRAY CONTAINING COLUMN SUMS - TO S. GEND7230
C
C OTHER VARIABLES. GEND7240
C
C ICOUNT - NUMBER ENTRIES IN JCOL AND JVAL. AND P. GEND7250
C ISCNT - NUMBER ENTRIES IN ISN AND ISVEC. GEND7260
C ISUM - S VECTOR SUM. GEND7270
C ITAPE1 - INPUT. STATE NUMBER PAIRS PLUS FREQUENCY. GEND7280
C ITAPE2 - UNIT USED FOR TEMPORARY STORAGE OF UNMODIFIED P MATRIX. GEND7290
C THE BEGINNING LABEL, DATA RECORDS FOR ROWS EXISTING IN GEND7300
C THE D MATRIX AND END LABEL WILL BE WRITTEN ON THIS UNIT. GEND7310
C ROW AND COLUMN LIST RECORDS AND DATA RECORDS FOR ROWS GEND7320

-100-

C	ADDED BY TRANSITION MODIFY WILL NOT BE WRITTEN ON THIS	GEND7410
C	UNIT.	GEND7420
C	ITAPE3 - D MATRIX, FROM-S, TO-S, FINAL P MATRIX.	GEND7430
C	INPSW - 0 IF RECORD ON ITAPE1 READ.	GEND7440
C	1 IF EOF ON ITAPE1 READ.	GEND7450
C	JADD - NUMBER OF ELEMENTS ADDED TO THE ROW LIST BY TRANSITION	GEND7460
C	MODIFY.	GEND7470
C	JCOUNT - NUMBER OF ENTRIES IN LSTCOL AND LSVEC.	GEND7480
C	KPRINT - A SWITCH TO CONTROL THE LISTING OF THE NUMBER OF NON-ZERO	GEND7500
C	ELEMENTS IN EACH NON-ZERO ROW OF THE D MATRIX.	GEND7510
C	0 - PRINT.	GEND7520
C	1 - DO NOT PRINT.	GEND7530
C	LSTCNT - ARRAY FOR 1 PRINT LINE OF ICOUNT VALUES.	GEND7540
C	LST - SUBSCRIPT FOR LSTCNT.	GEND7550
C	MODSW - TRANSITION MODIFY SWITCH.	GEND7560
C	-1 BYPASS	GEND7570
C	0 EXECUTE. ADD DIAG ELEMENT.	GEND7580
C	+N EXECUTE. ADD ELEMENT TO DIAG POSITION + N.	GEND7590
C	MODFAC - ENTERED WHEN MODSW=+N. THE IS THE LAST CODE FOR THE LAST	GEND7600
C	VARIABLE IN THE STATE DEFINITION.	GEND7610
C	NFILL - FILLER VARIABLE CONTAINING A ONE.	GEND7620
C	NL - LENGTH OF ALL LABEL ARRAYS.	GEND7630
C	NTIMES - NUMBER OF TIME PERIODS FOR WHICH D S AND P ARE TO BE	GEND7640
C	GENERATED. MAY BE LESS THAN THE NUMBER OF TIME PERIODS ON	GEND7650
C	THE INPUT TAPE, BUT NO POSITIONING IS PROVIDED FOR. THE	GEND7660
C	FIRST NTIMES DATA SETS WILL BE PROCESSED.	GEND7670
C	NPELE - NUMBER OF NON-ZERO ELEMENTS IN THE MATRIX.	GEND7680
C	NFILES - COUNT OF NUMBER OF FILES WRITTEN ON ITAPE3 - FINAL OUTPUT	GEND7690
C	TAPE ON WHICH D, S, AND P ARRAYS ARE WRITTEN.	GEND7700
C	NZERO - ADJUSTMENT FOR STATE ZERO SO THAT 'OUTSIDE WORLD' IS	GEND7710
C	LARGE.	GEND7720
C	END	GEND7730
C		GEND7740
C		GEND7750

SUBROUTINE LSTPAT(IYRS,ISTATE) LSTP0010
C LSTP0020
C SUBROUTINE TO LIST STATE NUMBER PATTERNS. LSTP0030
C THE MODEL NUMBER AND FREQUENCY RANGE SPECIFICA- LSTP0040
C TIONS FOR THE PATTERNS TO BE LISTED WILL BE READLSTP0050
C FROM CONTROL CARDS. LSTP0060
C LSTP0070
C IMPLICIT REAL*8 (A-H,O-Z) LSTP0080
C DIMENSION IDENT(30),IYRS(1),ISTATE(1) LSTP0090
C READ INPUT UNIT ID, NYRS - NUMBER OF TIME LSTP0100
C PERIODS, NFREQ - TOTAL NUMBER OF CASES. LSTP0110
C READ 20,ITAF - NYRS,NFREQ LSTP0120
20 FORMAT(3I12) LSTP0130
C REWIND ITAPE LSTP0140
C FREQ=NFREQ LSTP0150
C READ ARRAY IYRS - A DATE FOR EACH TIME PERIOD. LSTP0160
C READ 30,(IYRS(I),I=1,NYRS) LSTP0170
30 FORMAT(20A4) LSTP0180
C SET SWITCH INDICATING NO UNPROCESSED DATA RECORDLSTP0190
C IN CORE. LSTP0200
C KSKIP=0 LSTP0210
C COMPUTE NUMBER OF PRINT LINES PER PATTERN AND LSTP0220
C NUMBER OF PATTERNS PER PAGE. WHEN NYRS IS 9, AN LSTP0230
C EXTRA LINE WILL BE SPACED AFTER EACH PATTERN LSTP0240
C PRINT. THE HEADING REQUIRES ONE SET OF LINES. LSTP0250
C NLPAT=(NYRS-1)/9+1 LSTP0260
C IF(NYRS.EQ.9) NLPAT=NLPAT+1 LSTP0270
C NPPAGE=53/NLPAT-1 LSTP0275
C READ FROM-FREQUENCY VALUE, TO-FREQUENCY VALUE LSTP0280
C AND MODEL NUMBER. LSTP0290
40 READ 20,NFROM,NTO,MODEL N LSTP0300
C IS THIS A RETURN CARD? LSTP0310
C IF(NFROM.GE.0) GO TO 45 LSTP0320
C YES LSTP0330
C REWIND INPUT. LSTP0340
C REWIND ITAPE LSTP0350
C SPACE PRINTED OUTPUT TO A NEW PAGE. LSTP0360
C PRINT 50 LSTP0370
50 FORMAT(1H1) LSTP0380
C RETURN. LSTP0390
C RETURN LSTP0400
C NO - THE CARD JUST READ DID NOT SPECIFY A RETURNLSTP0410
C TO THE CALLING PROGRAM. LSTP0420
C READ HEADING FOR LIST INTO ARRAY IDENT. LSTP0430
C LSTP0440
45 READ 30,IDENT LSTP0450
C INITIALIZE TYPE OF FREQUENCY RANGE SPECIFICATIONLSTP0460
C SWITCH. LSTP0470
C LSTP0480
60 NSW=0 LSTP0490
C IF ALL PATTERNS ARE TO BE PRINTED, SET NSW =1. LSTP0500
C IF(NFROM.EQ.0.AND.NTO.EQ.0) NSW=1 LSTP0510
C IF ALL PATTERNS WITH A FREQUENCY GREATER THAN LSTP0520
C NFROM ARE TO BE PRINTED, SET NSW = 2. LSTP0530
C IF(NFROM.GT.0.AND.NTO.EQ.0) NSW=2 LSTP0540

C IF ALL PATTERNS WITH A FREQUENCY IN THE LSTP0550
C SPECIFIED NFROM - NTO RANGE ARE TO BE PRINTED, LSTP0560
C SET NSW = 3. LSTP0570
C IF((NFROM.GT.0.AND.NTO.GT.0).AND.(NTO.GE.NFROM)) NSW=3 LSTP0580
C IS THE TYPE OF RANGE SWITCH STILL ZERO? LSTP0590
C YES. GO TO PRINT ERROR MESSAGE. LSTP0600
C IF(NSW.EQ.0) GO TO 300 LSTP0610
C NO - THE RANGE SPECIFICATION IS LEGAL. LSTP0620
C C INITIALIZATION FOR THIS LIST. LSTP0630
C NUMBER OF PATTERNS LISTED. LSTP0640
C C LISTN=0 LSTP0650
C LSTSUM=0 LSTP0660
C NPAT = 0 LSTP0670
C NPCUR=0 LSTP0680
C C 80 PRINT 90,IDENT LSTP0690
C 90 FORMAT(1H1,30A4) LSTP0700
C C BRANCH ON NSW AND PRINT TYPE OF FREQUENCY LSTP0710
C SELECTION. LSTP0720
C GO TO (100,110,120),NSW LSTP0730
C NSW = 1 ALL PATTERNS. LSTP0740
C C 100 PRINT 105 LSTP0750
C 105 FORMAT(/36H LIST OF ALL STATE NUMBER PATTERNS) LSTP0760
C GO TO 140 LSTP0770
C NSW = 2 PATTERNS WITH FREQ GE NFROM. LSTP0780
C C 110 PRINT 115,NFROM LSTP0790
C 115 FORMAT(/68H LIST OF STATE NUMBER PATTERNS WITH FREQUENCY GREATER TLSTP0800
C THAN OR EQUAL ,18) LSTP0810
C GO TO 140 LSTP0820
C NSW = 3 PATTERNS IN NFROM - NTO RANGE. LSTP0830
C C 120 PRINT 125,NFROM,NTO LSTP0840
C 125 FORMAT(/55H LIST OF STATE NUMBER PATTERNS WITH FREQUENCY IN RANGE LSTP0850
C 1,18,6H THRU ,18) LSTP0860
C C 140 LSTP0870
C PRINT COLUMN HEADING INCLUDING THE DATE ARRAY LSTP0880
C IYRS. LSTP0890
C C 140 PRINT 145,(IYRS(I),I=1,NYRS) LSTP0900
C 145 FORMAT(/13X,8HPER CENT,3X,21H STATE NUMBER PATTERN/6X,18HFREQ OFLSTP1000
C 1 TOTAL ,9(8X,A4)/ (24X,9(8X,A4))) LSTP1010
C PRINT 150 LSTP1020
C 150 FORMAT(/) LSTP1030
C C AT THIS POINT IN THE PROGRAM, NPCUR WILL BE ZERO LSTP1040
C WHEN THE HEADING JUST PRINTED IS FOR THE FIRST LSTP1050
C PAGE OF OUTPUT FOR A MODEL. NPCUR WILL BE EQUAL LSTP1060
C NPPAGE WHEN THE HEADING JUST PRINTED IS FOR AN LSTP1070
C ADDITIONAL PAGE FOR THE MODEL. THE SELECTED LSTP1080
C PATTERN WHICH COULD NOT BE PRINTED ON THE PRE- LSTP1090
C CEDING PAGE IS READY TO BE PRINTED. LSTP1100
C C LSTP1110

C IS THERE A PATTERN READY TO BE PRINTED? LSTP1120
C IF(NPCUR.EQ.0) GO TO 160 LSTP1130
C YES LSTP1140
C SET NUMBER OF PATTERNS ON THIS PAGE TO ZERO. LSTP1150
C NPCUR=0 LSTP1160
C GO TO PRINT A PATTERN. LSTP1170
C GO TO 215 LSTP1180
C ***LSTP1190
C READ PATTERNS AND PRINT IF IN RANGE. LSTP1200
C IS A RECORD TO BE READ? LSTP1210
C 160 IF(KSKIP.EQ.0) GO TO 170 LSTP1220
C NO. LSTP1230
C SET KSKIP TO 0. LSTP1240
C KSKIP=0 LSTP1250
C GO TO 175 LSTP1260
C 170 LSTP1270
C YES. LSTP1280
C READ A RECORD. LSTP1290
C 170 READ(ITAPE,END=254)MODL,(ISTATE(N),N=1,NYRS),IFREQ LSTP1300
C NO EOF. LSTP1320
C IS THE MODEL NUMBER READ FROM THE INPUT FILE LSTP1330
C EQUAL THE MODEL NUMBER IN THE CONTROL CARD? LSTP1340
C NO. GO TO END OF MODEL PROCESSING. LSTP1350
C 175 IF(MODL.NE.MODELN) GO TO 250 LSTP1360
C YES LSTP1370
C COUNT RECORD READ. LSTP1380
C NPAT=NPAT+1 LSTP1390
C IS THE FREQUENCY OF THE CURRENT PATTERN RECORD LSTP1400
C IN THE SPECIFIED FREQUENCY RANGE? LSTP1410
C BRANCH ON NSW (TYPE OF FREQUENCY SELECTION.) LSTP1420
C GO TO (210,200,190),NSW LSTP1430
C 190 LSTP1440
C IS FREQUENCY GREATER THAN NTO? LSTP1450
C 190 IF(IFREQ.GT.NTO) GO TO 240 LSTP1460
C 200 LSTP1470
C NO LSTP1480
C IS FREQUENCY LESS THAN NFROM? LSTP1490
C 200 IF(IFREQ.LT.NFROM) GO TO 240 LSTP1500
C NO LSTP1510
C FREQUENCY IS IN SPECIFIED RANGE. LSTP1520
C LSTP1530
C IS THERE SPACE ON THE CURRENT PAGE TO PRINT THIS LSTP1540
C PATTERN? LSTP1550
C NO. GO TO SKIP TO A NEW PAGE. RETURN TO 215. LSTP1560
C 210 IF(NPCUR.EQ.NPPAGE) GO TO 80 LSTP1570
C YES LSTP1580
C ADD 1 TO PATTERNS LISTED. LSTP1590
C 215 LISTN=LISTN+1 LSTP1600
C ADD FREQUENCY OF THIS PATTERN TO FREQ-SUM FOR LSTP1610
C THIS LIST. LSTP1620
C LSTSUM=LSTSUM+IFREQ LSTP1630
C LSTP1640
C LSTP1650
C ADD FREQUENCY OF THIS PATTERN TO FREQ-SUM FOR LSTP1660
C THIS LIST. LSTP1670
C LSTP1680

C COMPUTE PERCENT FOR THE FREQUENCY OF THIS LSTP1690
C PATTERN. LSTP1700
C PERCNT=(DFLOAT(IFREQ)/FREQ)*100.000 LSTP1710
C PRINT THIS PATTERN AND THE PERCENT VALUE JUST LSTP1720
C COMPUTED. LSTP1730
C PRINT 220,IFREQ,PERCNT,(ISTATE(N),N=1,NYRS) LSTP1740
220 FORMAT(2X,I8,F11.4,3X,9I12/ 124X,9I12)) LSTP1750
C ADD 1 TO THE NUMBER OF PATTERNS PRINTED ON THIS LSTP1760
C PAGE. LSTP1770
C NPCUR=NPCUR+1 LSTP1780
C CONTINUE LSTP1790
C 240 CONTINUE LSTP1800
C GO TO READ A RECORD. LSTP1810
C GO TO 170 LSTP1820
C *LSTP1830
C ***LSTP1850
C LSTP1860
C THE MODEL NUMBER IN THE RECORD JUST READ FROM LSTP1870
C THE INPUT FILE DOES NOT EQUAL THE MODEL NUMBER LSTP1880
C IN THE CONTROL CARD. LSTP1890
C HAVE ANY PATTERNS FOR THE MODEL SPECIFIED IN THE LSTP1900
C CONTROL CARD BEEN READ? LSTP1910
250 IF(NPAT.EQ.0) GO TO 350 LSTP1920
C YES LSTP1930
C SET UNPROCESSED RECORD IN CORE SWITCH. LSTP1940
C KSKIP=1 LSTP1950
C GO TO 255 LSTP1960
C 254 LSTP1970
C EOF ON READ LSTP1980
C REWIND INPUT UNIT. LSTP1990
254 REWIND ITAPE LSTP2000
C PRINT SUMMARY INFO. LSTP2010
C COMPUTE PERCENT FOR SUM FOR THIS LIST. LSTP2020
255 PFRCNT=(DFLOAT(LSTSUM)/FREQ)*100.000 LSTP2030
C PRINT SUMMARY DATA FOR THIS LIST. LSTP2040
C SKIP TO A NEW PAGE IF NECESSARY. LSTP2050
C IF((NPAT*NLPAT+4).GT.(NPPAGE*NLPAT)) PRINT 90,IDENT LSTP2060
PRINT 260,LSTSUM,PERCNT,LISTN LSTP2070
260 FORMAT(//1X ,I9,F11.4,3X,I12,17H PATTERNS LISTED.) LSTP2080
PFRCNT=100.0 LSTP2090
PRINT 270,NFREQ,PERCNT,NPAT LSTP2100
270 FORMAT(2X,I8,F11.4,3X,I12,16H PATTERNS TOTAL.) LSTP2110
C GO TO READ NEXT CONTROL CARD. LSTP2120
C GO TO 40 LSTP2130
C 300 LSTP2140
C YES - THE RANGE SPECIFICATION IS ILLEGAL. LSTP2150
C PRINT ERROR IN CONTROL CARDS MESSAGE. LSTP2160
300 PRINT 310,NFROM,NTO LSTP2170
310 FORMAT(37H1LSTPAT..CONTROL CARD ERROR. NFROM = ,I12,5Y,7H NTO = , LSTP2180
1112) LSTP2190
C EXIT LSTP2200
C STOP LSTP2210
C 350 LSTP2220
C NO - MODEL NUMBER IN CONTROL CARD DOES NOT MATCH LSTP2230
C TAPE MODEL NUMBER. LSTP2240
C LSTP2250

C	PRINT ERROR MESSAGE.	LSTP2260
C	350 PRINT 360,MODELN,MODL	LSTP2270
C	360 FORMAT(22H1LSTPAT,CARD MODEL NO,I12,5X,14H TAPE MODEL NO,I12)	LSTP2280
C	EXIT	LSTP2290
C	STOP	LSTP2300
C	REFERENCE LIST.	LSTP2310
C	SUBROUTINE ARGUMENTS.	LSTP2320
C	IYRS - ARRAY FOR LIST OF YEARS. EACH ELEMENT IS READ AND PRINTED AS AN A4 FIELD. THEREFORE THE DATE MAY BE YEAR ONLY- 1969 OR MONTH AND YEAR- 6-69.	LSTP2330
C	ISTATE - ARRAY FOR LIST OF STATE NUMBERS.	LSTP2340
C	OTHER VARIABLES.	LSTP2350
C	IDENT - ARRAY FOR HEADING TO IDENTIFY MODEL. (30A4).	LSTP2360
C	ITAPE - INPUT UNIT.	LSTP2370
C	KSKIP - 0 NO UNPROCESSED DATA RECORD IN CORE.	LSTP2380
C	1 AN UNPROCESSED DATA RECORD IS IN CORE- THIS WILL OCCUR WHEN THERE IS A MODEL CHANGE IN THE INPUT RECORDS.	LSTP2390
C	LISTN - NUMBER OF PATTERNS LISTED.	LSTP2400
C	LSTSUM - SUM OF FREQ FOR PATTERNS LISTED.	LSTP2410
C	NYRS - NUMBER OF TIME PERIODS AND STATE NUMBERS.	LSTP2420
C	NPAT - NUMBER OF UNIQUE PATTERN, READ FOR A MODEL.	LSTP2430
C	NFREQ - NUMBER OF CASES IN THE MODEL.	LSTP2440
C	NFROMK - FROM AND TO VALUES FOR FREQUENCY	LSTP2450
C	NTO - RANGE TO BE PRINTED.	LSTP2460
C	NSW - SET ON BASIS OF NFROM AND NT0 VALUES.	LSTP2470
C	1=PRINT ALL PATTERNS.	LSTP2480
C	2=PRINT ALL PATTERNS WHOSE FREQ.GE.NFROM.	LSTP2490
C	3=PRINT ALL PATTERNS WHERE NFROM.LE.FREQ.LE.NTO.	LSTP2500
C	END	LSTP2510
C		LSTP2520
C		LSTP2530
C		LSTP2540
C		LSTP2550
C		LSTP2560
C		LSTP2570
C		LSTP2580
C		LSTP2590

SUBROUTINE NUDATE(MONTH,MYEAR,NUMMO,NUMYR) NUDA0010
C NUDA0020
C THE NEW DATE ROUTINE WILL INCREMENT THE DATE IN NUDA0030
C THE S VECTOR NAME BY THE MONTH AND YEAR FACTORS NUDA0040
C OF THE P MATRIX BEING USED IN THE SXP OPERATION. NUDA0050
C NUDA0060
C DATA STATEMENT SETTING UP MLIST-AN ARRAY NUDA0070
C CONTAINING 12 MONTH NAMES 3 CHARACTERS EACH. NUDA0080
C
C DIMENSION MLIST(12) NUDA0090
C DATA MLIST/48HJAN FEB MAR APR MAY JUN JUL AUG SEP OCT NOV DEC / NUDA0100
C DATA STATEMENT SETTING UP LITERAL ZERO WORD FOR NUDA0110
C USE IN BINARY-HEX CONVERSION. NUDA0120
C DATA NZERO/4H0000/ NUDA0130
C ***NUDA0140
C *NUDA0150
C
C INCREMENT MONTH NUDA0160
C SET MONTH INCREMENT CARRY OVER VARIABLE TO ZERO. NUDA0170
C NADD=0 NUDA0180
C IS THE MONTH INCREMENT VALUE EQUAL ZERO? NUDA0190
C YES. MONTH WILL NOT CHANGE. GO TO INCREMENT YR. NUDA0200
C IF(NUMMO.EQ.0) GO TO 50 NUDA0210
C NO NUDA0220
C IS THE ENTRY PASSED IN THE MONTH FIELD IN THE NUDA0230
C MONTH LIST? NUDA0240
C DO 20 I=1,12 NUDA0250
C IF(MONTH.EQ.MLIST(I)) GO TO 30 NUDA0260
C 20 CONTINUE NUDA0270
C NO NUDA0280
C PRINT 25,MONTH NUDA0290
C 25 FORMAT(50H NAME IN MONTH DOES NOT MATCH ANY NAME IN MLIST. ,A4) NUDA0310
C CONTINUE. NUDA0320
C GO TO 50 NUDA0330
C YES NUDA0340
C MONTH MATCH. NUDA0350
C NEW MONTH POSITION EQUALS OLD MONTH POSITION NUDA0360
C PLUS MONTH INCREMENT. NUDA0370
C 30 I=I+NUMMO NUDA0380
C IS THE SUBSCRIPT LESS THAN OR EQ 12? NUDA0390
C YES. CURRENT SUBSCRIPT VALUE IS NEW MONTH NUMBER NUDA0400
C IF(I.LE.12) GO TO 40 NUDA0410
C NO NUDA0420
C SET CARRY OVER VALUE FOR YEAR. NUDA0430
C NADD=1 NUDA0440
C I=MOD(I,12) NUDA0450
C
C 40 MONTH=MLIST(I) NUDA0460
C REPLACE INPUT MONTH ENTRY BY NEW MONTH. NUDA0470
C NUDA0480
C ***NUDA0490
C *NUDA0500
C *NUDA0510
C
C INCREMENT YEAR NUDA0520
C TOTAL YEAR INCREMENT EQUALS MONTH CARRY OVER NUDA0530
C PLUS INPUT YEAR INCREMENT. NUDA0540
C 50 NADD=NADD+NUMYR NUDA0550
C IS THE TOTAL YEAR INCREMENT ZERO? NUDA0560

C YES NUDA0570
C RETURN NUDA0580
C IF(NADD.EQ.0) RETURN NUDA0590
C NO NUDA0600
C CONVERT EACH CHARACTER IN THE INPUT YEAR NUDA0610
C ARGUMENT FROM A HEXADECIMAL TO A BINARY NUDA0620
C CHARACTER. NUDA0630
C
C NYR=MYEAR-NZERO NUDA0640
C N1=NYR/2**24 NUDA0650
C NYR=NYR-N1*2**24 NUDA0660
C N2=NYR/2**16 NUDA0670
C NYR=NYR-N2*2**16 NUDA0680
C N3=NYR/2**8 NUDA0690
C N4=NYR-N3*2**8 NUDA0700
C
C COMBINE THESE BINARY CHARACTERS INTO A TOTAL NUDA0710
C BINARY YEAR VALUE AND ADD THE TOTAL YEAR INCRE- NUDA0720
C MENT. NUDA0730
C NYR=N1*1000+N2*100+N3*10+N4+NADD NUDA0740
C
C CONVERT THE INCREMENTED YEAR FROM A BINARY VALUE NUDA0750
C TO BINARY CHARACTERS. NUDA0760
C
C N1=NYR/1000 NUDA0770
C NYR=NYR-N1*1000 NUDA0780
C N2=NYR/100 NUDA0790
C NYR=NYR-N2*100 NUDA0800
C N3=NYR/10 NUDA0810
C N4=NYR-N3*10 NUDA0820
C
C COMBINE THESE BINARY CHARACTERS AND THE WORD NUDA0830
C CONTAINING ZERO CHARACTERS TO FORM THE HEXADECIMAL NUDA0840
C VALUE OF THE NEW YEAR. NUDA0850
C
C MYEAR=N1*2**24+N2*2**16+N3*2**8+N4+NZERO NUDA0860
C
C RETURN NUDA0870
C
C NOTE: *NUDA0880
C THE HEXADECIMAL CHARACTER FOR A SINGLE DIGIT 0-9 NUDA0890
C MINUS THE HEXADECIMAL CHARACTER FOR 0 GIVES THE NUDA0900
C BINARY VALUE OF THE DIGIT. NUDA0910
C
C HEXADECIMAL BINARY NUDA0920
C 0 11110000 00000000
C 1 11110001 00000001
C 2 11110010 00000010
C . . .
C . . .
C . . .
C 9 11111001 00001001
C
C
C REFERENCE LIST.
C SUBROUTINE ARGUMENTS.
C
C MONTH - THE S VECTOR NAME MONTH FIELD. THIS WILL BE THREE NUDA1080
C CHARACTERS, LEFT JUSTIFIED. NUDA1090
C
C MYEAR - THE S VECTOR NAME YEAR FIELD. THIS WILL BE 4 CHARACTERS. NUDA1100
C
C NUMMO - P MATRIX MONTH INCREMENT. NUDA1110
C
C NUMYR - P MATRIX YEAR INCREMENT. NUDA1120
C
C END NUDA1130

```
SUBROUTINE POSFWD(IDTAPE,KTYPE,NAMEX,NLX,LABELX)          POSF 010
C
C           THIS POSITION FORWARD SUBROUTINE WILL READ THE      POSF 020
C           LABEL OF THE SECOND S OR THE FIRST P DEPENDING      POSF 030
C           ON THE KTYPE INPUT VALUE. FOR AN S CALL THE        POSF 040
C           INPUT IS EXPECTED TO BE GENDSP OUTPUT.            POSF 050
C
C           DIMENSION NAMEX(6),LABELX(1)                      POSF 060
C           SET NUMBER OF S'S COUNTER.                      POSF 070
C
C           NS=1
C           READ TYPE WORD ONLY FROM NEXT RECORD OF IDTAPE. POSF 110
C 10 READ(IDTAPE)MTYPE          IS TYPE READ EQUAL TYPE REQUESTED? POSF 120
C           IF(MTYPE,NE.,KTYPE) GO TO 10
C           YES
C           IS THIS A P MATRIX LABEL?                  POSF 150
C           IF(MTYPE.EQ.3) GO TO 20
C           NO
C           IS S COUNTER EQUAL 2?                     POSF 190
C           IF(NS.EQ.2)    GO TO 20
C           NO
C           ADD 1 TO S COUNTER.                      POSF 220
C
C           NS=2
C           GO TO 10
C           YES
C           FILE LOCATED.
C           BACKSPACE IDTAPE,                         POSF 270
C
C 20 BACKSPACE IDTAPE          READ ENTIRE LABEL RECORD.      POSF 280
C           READ(IDTAPE)MTYPE,NAMEX,NLX,(LABELX(I),I=1,NLX) POSF 290
C           RETURN
C
C           REFERENCE LIST.                          POSF 330
C           SUBROUTINE ARGUMENTS.                   POSF 340
C
C           IDTAPE - THE INPUT UNIT NUMBER.          INPUT ARGUMENT.POSF 370
C           KTYPE - THE ARRAY TYPE TO BE POSITIONED TO. INPUT ARGUMENT.POSF 380
C           NAMEX - THE NAME OF THE ARRAY.          VALUE RETURNED.POSF 390
C           NLX - THE NUMBER OF WORDS IN THE LABEL. VALUE RETURNED.POSF 400
C           LABELX - THE LABEL OF THE ARRAY.        VALUE RETURNED.POSF 410
C
C           END                                     POSF 420
```

SUBROUTINE POSINP(IDTAPE,KTYPE,KFILE,NL,LABEL) POSI0010
C POSI0020
C POSI0030
C POSI0040 THIS ROUTINE WILL POSITION AN INPUT TAPE(WRITTENPOSI0040
C IN THE FLOW MODEL FORMAT) TO THE FILE NAMED POSI0050
C KFILE. THE FILE TYPE AND LABEL INFORMATION WILL POSI0060
C BE RETURNED FOR POSSIBLE USE BY THE CALLING POSI0070
C ROUTINE. THE TAPE WILL BE IN POSITION FOR A READPOSI0080
C OF THE FIRST DATA RECORD. POSI0090
C POSI0100
C POSI0110 THIS ROUTINE WILL POSITION FROM THE RECORD READYPOSI0110
C TO BE READ AT THE TIME THE ROUTINE IS CALLED. POSI0120
C THERE WILL BE A TAPE REWIND ONLY WHEN A TYPE 40 POSI0130
C RECORD IS READ. THIS PROCEDURE WILL AVOID POSI0140
C EXCESSIVE REWINDS WHEN SEQUENTIAL ARRAYS ARE POSI0150
C BEING USED IN SUCH A WAY AS TO REQUIRE POSINP POSI0160
C CALLS TO LOCATE THEM BY NAME. POSI0170
C POSI0180
C DIMENSION KFILE(6),NFILE(6),LABEL(1) POSI0190
C SET NUMBER OF FILES ON TAPE AND NUMBER OF FILES POSI0200
C READ TO ZERO. POSI0210
C NFILES=0 POSI0220
C KNT=0 POSI0230
C HAS NFILES BEEN READ FROM TYPE 40 RECORD? POSI0240
C 5 IF(NFILES.EQ.0) GO TO 10 POSI0250
C YES POSI0260
C HAVE ALL FILES BEEN READ IN THIS CALL OF THE POSI0270
C POSITION INPUT OPERATION. POSI0280
C 8 IF(KNT.GE.NFILES) GO TO 60 POSI0290
C NO POSI0300
C ALL FILES HAVE NOT BEEN READ. POSI0310
C READ A LABEL RECORD. POSI0320
C 10 READ(IDTAPE,END=40,ERR=50)KTYPE,NFILE,NL,(LABEL(I),I=1,NL) POSI0330
C ADD 1 TO NUMBER OF FILES READ. POSI0340
C KNT=KNT+1 POSI0350
C IS THIS A TYPE 40 RECORD? POSI0360
C IF(KTYPE.EQ.40) GO TO 70 POSI0370
C NO POSI0380
C IS THIS THE FILE REQUESTED... POSI0390
C DO 20 K=1,6 POSI0400
C IF(NFILE(K).NE.KFILE(K)) GO TO 30 POSI0410
C 20 CONTINUE POSI0420
C YES. POSI0430
C RETURN POSI0440
C NO. POSI0450
C THIS IS NOT THE FILE REQUESTED. POSI0460
C PASS DATA RECORDS FOR THIS FILE. POSI0470
C READ TYPE FIELD ONLY FROM A RECORD. POSI0480
C 30 READ(IDTAPE,END=40,ERR=50)KTYPE POSI0490
C IS TYPE CODE AN ARRAY END CODE? POSI0500
C YES. GO TO CHECK NUMBER OF FILES READ. POSI0510
C IF(KTYPE.GT.23) GO TO 5 POSI0520
C NO POSI0530
C POSI0540
C POSI0550
C POSI0560

GO TO 30	POSI0570
C END BRANCH ON READ.	POSI0580
C PRINT MESSAGE.	POSI0590
40 PRINT 41, IDTAPE, KFILE	POSI0600
41 FORMAT(46H TAPE MARK READ BY POSINP FOR TAPE AND FILE = ,I4,4X,6A4)	POSI0610
1) EXIT	POSI0620
C STOP	POSI0630
C ERR BRANCH ON READ.	POSI0640
C PRINT MESSAGE.	POSI0650
50 PRINT 51, IDTAPE, KFILE	POSI0660
51 FORMAT(42H ERROR READ BY POSINP FOR TAPE AND FILE = ,I4,4X,6A4)	POSI0680
C EXIT	POSI0690
C STOP	POSI0700
C YES	POSI0710
C ALL FILES ON THIS TAPE HAVE BEEN READ.	POSI0720
C PRINT MESSAGE: REQUESTED FILE IS NOT ON THIS	POSI0730
C TAPE.	POSI0740
60 PRINT 61, KFILE, IDTAPE	POSI0750
61 FORMAT(6H FILE ,6A4,13H NOT ON TAPE ,I4)	POSI0760
C EXIT	POSI0770
C STOP	POSI0780
C TYPE 40 RECORD WAS JUST READ.	POSI0790
C SAVE FILE COUNT FROM TYPE 40 RECORD.	POSI0800
70 NFILES=LABEL(1)	POSI0810
C REWIND IDTAPE	POSI0820
C GO TO 8	POSI0830
C	POSI0840
C REFERENCE LIST.	POSI0850
C SUBROUTINE ARGUMENTS.	POSI0860
C	POSI0870
C	POSI0880
IDTAPE - THE INPUT UNIT NUMBER.	INPUT ARGUMENT. POSI0890
KTYPE - THE TYPE OF ARRAY POSITIONED TO.	VALUE RETURNED. POSI0900
KFILE - THE ARRAY NAME TO BE POSITIONED TO.	INPUT ARGUMENT. POSI0910
NL - THE NUMBER OF WORDS IN THE LABEL.	POSI0920
LABEL - THE LABEL OF THE ARRAY.	VALUE RETURNED. POSI0930
C OTHER VARIABLES.	POSI0940
C	POSI0950
C	POSI0960
C NFILES - NUMBER OF FILES ON TAPE. TO BE READ FROM TYPE 40 RECORD.	POSI0970
C VALUE WILL BE ZERO IF TYPE 40 RECORD HAS NOT BEEN READ.	POSI0980
C KNT - NUMBER OF FILES READ	POSI0990
C NFILE - NAME OF ARRAY JUST READ.	POSI1000
C END	POSI1010

SUBROUTINE PRINTD (NFILE,NL,LABEL,ISN,ISVEC,IDTAPE,KSW) PRNTD010
C CALLED BY SUBROUTINE READSP. PRNTD020
C THIS IS THE STANDARD 'PRINTD' SUBROUTINE WHICH PRNTD030
C WILL BE FOUND IN THE 'FLOMOD' LIBRARY. IT WILL PRNTD040
C (1) READ THE D MATRIX DATA RECORDS, PRNTD050
C (2) READ THE D MATRIX END LABEL, AND PRNTD060
C (3) RETURN TO THE READSP SUBROUTINE. PRNTD070
C PRNTD080
C PRNTD090
C PRNTD100
C IN ORDER TO PRINT THE D MATRICES FOR A GIVEN PRNTD110
C MODEL IN ONE OR MORE SPECIFIC FORMATS, A 'PRINTD' PRNTD120
C SUBROUTINE FOR THAT MODEL MUST BE WRITTEN. THIS PRNTD130
C NON-STANDARD 'PRINTD' SUBROUTINE MUST DUPLICATE PRNTD140
C ALL STATEMENTS IN THE STANDARD SUBROUTINE. THE PRNTD150
C 'CONTINUE' STATEMENTS INDICATE THE POSITIONS IN PRNTD160
C THE PROGRAM WHERE THE STATEMENTS REQUIRED TO PRNTD170
C PRODUCE THE DESIRED PRINTED OUTPUT MUST BE PRNTD180
C INSERTED. PRNTD190
C PRNTD200
C DO NOT REPLACE THE STANDARD 'PRINTD' SUBROUTINE PRNTD210
C IN THE 'FLOMOD' LIBRARY. USE THE CARD DECK OR A PRNTD220
C PRIVATE LIBRARY FOR THE SPECIAL 'PRINTD' PRNTD230
C SUBROUTINE. PRNTD240
C PRNTD250
C IMPLICIT REAL*8(A-H,O-Z,\$) PRNTD260
C DIMENSION ISN(1),ISVEC(1),LABEL(1),NFILE(6) PRNTD270
C PLACE HEADING PRINT INSTRUCTIONS HERE. *PRNTD280
C CONTINUE PRNTD290
C C READ A D MATRIX RECORD. PRNTD300
C 10 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT) PRNTD310
C C WAS THIS THE D MATRIX END LABEL. PRNTD320
C C IF(KTYPE.GT.30) GO TO 20 PRNTD330
C C RECORD JUST READ WAS A DATA RECORD. PRNTD340
C C PLACE PRINT INSTRUCTIONS HERE FOR A ROW OF THE *PRNTD350
C C MATRIX. *PRNTD360
C C CONTINUE PRNTD370
C C GO TO 10 PRNTD380
C C RECORD JUST READ WAS THE D MATRIX END LABEL. PRNTD390
C C 20 CONTINUE PRNTD400
C C PLACE ANY END OF ARRAY PRINT INSTRUCTIONS HERE. *PRNTD410
C C CONTINUE PRNTD420
C C RETURN PRNTD430
C C PRNTD440
C C PRNTD450
C C PRNTD460
C C PRNTD470
C C PRNTD480
C C PRNTD490
C C REFERENCE LIST. PRNTD500
C C SUBROUTINE ARGUMENTS. PRNTD510
C C NFILE - AN ARRAY FOR THE NAME OF THE D MATRIX. PRNTD520
C C NL - THE NUMBER OF INT*4 WORDS IN THE LABEL. PRNTD530
C C LABEL - AN ARRAY FOR THE LABEL OF THE D MATRIX. PRNTD540
C C ISN - THE ARRAY FOR THE LIST OF NON-ZERO COLUMNS IN A D MATRIX PRNTD550
C C PRNTD560

C ROW. PRNTD570
C ISVEC - THE ARRAY FOR THE NON-ZERO ELEMENTS IN A D MATRIX ROW. PRNTD580
C IDTAPE - THE UNIT FROM WHICH THE D MATRIX IS TO BE READ. PRNTD590
C KSW - A PRINT OPTION SWITCH INCLUDED IN THE READSP CONTROL CARDPRNTD600
C C IT IS USED TO SPECIFY A PRINT OPTION WITHIN A NON- PRNTD610
C STANDARD 'PRINTD' SUBROUTINE. PRNTD620
C END PRNTD630
C PRNTD640

SUBROUTINE PRINP (NFILE,NL,LABEL,ISN,P,IDLTAPE,KSW) PRNTP010
CALLED BY SUBROUTINE READSP. PRNTP020
PRNTP030
PRNTP040
PRNTP050
PRNTP060
PRNTP070
PRNTP080
PRNTP090
PRNTP100
PRNTP110
PRNTP120
PRNTP130
PRNTP140
PRNTP150
PRNTP160
PRNTP170
PRNTP180
PRNTP190
PRNTP200
PRNTP210
PRNTP220
PRNTP230
PRNTP240
PRNTP250
PRNTP260
PRNTP270
PRNTP280
PRNTP290
PRNTP300
PRNTP310
PRNTP320
PRNTP330
PRNTP340
PRNTP350
PRNTP360
PRNTP370
PRNTP380
PRNTP390
PRNTP400
PRNTP410
PRNTP420
PRNTP430
PRNTP440
PRNTP450
PRNTP460
PRNTP470
PRNTP480
PRNTP490
PRNTP500
PRNTP510
PRNTP520
PRNTP530
PRNTP540
PRNTP550
PRNTP560

THIS IS THE STANDARD 'PRINP' SUBROUTINE WHICH WILL BE FOUND IN THE 'FLOMOD' LIBRARY. IT WILL (1) READ THE P MATRIX LIST OF ROWS PRESENT, (2) READ THE P MATRIX LIST OF COLUMNS PRESENT, (3) READ THE P MATRIX DATA RECORDS, (4) READ THE P MATRIX END LABEL, AND (5) RETURN TO THE READSP SUBROUTINE.

IN ORDER TO PRINT THE P MATRICES FOR A GIVEN MODEL IN ONE OR MORE SPECIFIC FORMATS, A 'PRINP' SUBROUTINE FOR THAT MODEL MUST BE WRITTEN. THIS NON-STANDARD 'PRINP' SUBROUTINE MUST DUPLICATE ALL STATEMENTS IN THE STANDARD SUBROUTINE. THE 'CONTINUE' STATEMENTS INDICATE THE POSITIONS IN THE PROGRAM WHERE THE STATEMENTS REQUIRED TO PRODUCE THE DESIRED PRINTED OUTPUT MUST BE INSERTED.

DO NOT REPLACE THE STANDARD 'PRINP' SUBROUTINE IN THE 'FLOMOD' LIBRARY. USE THE CARD DECK OR A PRIVATE LIBRARY FOR THE SPECIAL 'PRINP' SUBROUTINE.

IMPLICIT REAL*8(A-H,O-Z,\$)
DIMENSION ISN(1),P(1),LABEL(1),NFILE(6)
READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),MODSH,MODFAC
PLACE HEADING / ROW LIST PRINT STATEMENTS HERE.*
CONTINUE
*PRNTP340
READ THE P MATRIX LIST OF COLUMNS PRESENT RECORD
READ(IDTAPE)KTYPE,ICNT,(ISN(I),I=1,ICNT),NUMMO,NUMYR
PLACE COLUMN LIST PRINT STATEMENTS HERE.
CONTINUE
*PRNTP370
READ A P MATRIX RECORD.
10 READ(IDTAPE)KTYPE,IROW,ICNT,(ISN(I),I=1,ICNT),(P(I),I=1,ICNT)
WAS THIS THE P MATRIX END LABEL.
IF(KTYPE.GT.30) GO TO 20
RECORD JUST READ WAS A DATA RECORD.
PLACE PRINT INSTRUCTIONS HERE FOR A ROW OF THE MATRIX.
CONTINUE
*PRNTP460
GO TO READ THE NEXT RECORD.
20 CONTINUE
RECORD JUST READ WAS THE P MATRIX END LABEL.
PLACE ANY END OF ARRAY PRINT INSTRUCTIONS HERE.*
CONTINUE
RETURN

PCTURN	PRNTP570
C	PRNTP580
SUBROUTINE ARGUMENTS.	PRNTP590
C	ARGUMENT LIST.
C	PRNTP600
NFILE	PRNTP610
C	PRNTP620
NL	PRNTP630
C	PRNTP640
LABEL	PRNTP650
C	PRNTP660
ISN	PRNTP670
C	PRNTP680
P	PRNTP690
IDTAPE	PRNTP700
C	PRNTP710
KSW	PRNTP720
C	PRNTP730
END	

SUBROUTINE PRINTS (NFILE,NL,LABEL,ISN,ISVEC,IDTAPE,KSW) PRNTS010
C
C CALLED BY SUBROUTINE READSP. PRNTS020
C
C THIS IS THE STANDARD 'PRINTS' SUBROUTINE WHICH PRNTS030
C WILL BE FOUND IN THE 'FLOMOD' LIBRARY. IT WILL PRNTS040
C (1) READ THE S VECTOR DATA RECORD, PRNTS050
C (2) READ THE S VECTOR END LABEL, AND PRNTS060
C (3) RETURN TO THE READSP SUBROUTINE. PRNTS070
C
C IN ORDER TO PRINT THE S VECTORS FOR A GIVEN PRNTS080
C MODEL IN ONE OR MORE SPECIFIC FORMATS, A 'PRINTS' PRNTS090
C SUBROUTINE FOR THAT MODEL MUST BE WRITTEN. THIS PRNTS100
C NON-STANDARD 'PRINTS' SUBROUTINE MUST DUPLICATE PRNTS110
C ALL STATEMENTS IN THE STANDARD SUBROUTINE. THE PRNTS120
C 'CONTINUE' STATEMENT INDICATES THE POSITION IN PRNTS130
C THE PROGRAM WHERE THE STATEMENTS REQUIRED TO PRNTS140
C PRODUCE THE DESIRED PRINTED OUTPUT MUST BE PRNTS150
C INSERTED. PRNTS160
C
C DO NOT REPLACE THE STANDARD 'PRINTS' SUBROUTINE PRNTS170
C IN THE 'FLOMOD' LIBRARY. USE THE CARD DECK OR A PRNTS180
C PRIVATE LIBRARY FOR THE SPECIAL 'PRINTS' PRNTS190
C SUBROUTINE. PRNTS200
C
C IMPLICIT REAL*8(A-H,O-Z,\$) PRNTS210
C DIMENSION ISN(1),ISVEC(1),LABEL(1),NFILE(6) PRNTS220
C READ S DATA RECORD PRNTS230
C READ(IDTAPE)KTYPE,NFILL,ICNT,(ISN(I),I=1,ICNT),(ISVEC(I),I=1,ICNT)PRNTS240
C READ S END LABEL PRNTS250
C READ(IDTAPE)KTYPE,NFILL,NFILL,ISUM,NFILL PRNTS260
C PLACE PRINT INSTRUCTIONS HERE. *PRNTS270
C CONTINUE PRNTS280
C
C RETURN PRNTS290
C
C REFERENCE LIST. PRNTS300
C SUBROUTINE ARGUMENTS. PRNTS310
C
C NFILE - AN ARRAY FOR THE NAME OF THE S VECTOR. PRNTS320
C NL - THE NUMBER OF INT*4 WORDS IN THE LABEL. PRNTS330
C LABEL - AN ARRAY FOR THE LABEL OF THE S VECTOR. PRNTS340
C ISN - THE ARRAY FOR THE LIST OF STATES IN THE S VECTOR. PRNTS350
C ISVEC - THE ARRAY FOR THE ELEMENTS IN THE S VECTOR. PRNTS360
C IDTAPE - THE UNIT FROM WHICH THE S VECTOR IS TO BE READ. PRNTS370
C KSW - THIS IS A PRINT OPTION SWITCH INCLUDED IN THE READSP PRNTS380
C CONTROL CARD. IT IS USED TO SPECIFY A PRINT OPTION WITHINPRNTS390
C A NON-STANDARD 'PRINTS' SUBROUTINE. PRNTS400
C
C END PRNTS410

```
SUBROUTINE READIN(IDTAPE,IDENT,IROW,ICOL,KOUNT,INPSW) RDIN 010
C RDIN 020
C THIS ROUTINE WILL READ STATE NUMBER PAIRS IN THE RDIN 030
C STANDARD FORMAT. RDIN 040
C IF THE SOURCE DATA EXISTS IN A DIFFERENT FORMAT, RDIN 050
C A SPECIAL READIN SUBROUTINE MAY BE WRITTEN. DO RDIN 060
C NOT REPLACE THE STANDARD READIN SUBROUTINE IN RDIN 070
C THE 'FLOMOD' LIBRARY. USE THE CARD DECK OR A RDIN 080
C PRIVATE LIBRARY FOR THE SPECIAL READIN RDIN 090
C SUBROUTINE. RDIN 100
C INPSW HAS BEEN SET TO ZERO IN GENDSP. RDIN 110
C RDIN 120
C READ(IDTAPE, END=20)IDENT,IROW,ICOL,KOUNT RDIN 130
C RETURN RDIN 140
C EOF READ ON INPUT TAPE. RDIN 150
20 INPSW=1 RDIN 160
C RETURN RDIN 170
C RDIN 180
C REFERENCE LIST. RDIN 190
C SUBROUTINE ARGUMENTS. RDIN 200
C RDIN 210
C IDTAPE - INPUT ARGUMENT. FORTRAN UNIT NUMBER WHERE STATE PAIR RDIN 220
C RECORDS ARE LOCATED. RDIN 230
C IDENT - PAIR MODEL NUMBER. THIS VALUE IS RETURNED. RDIN 240
C IROW - ROW NUMBER OF STATE NUMBER PAIR. THIS VALUE IS RETURNED. RDIN 250
C ICOL - COL NUMBER OF STATE NUMBER PAIR. THIS VALUE IS RETURNED. RDIN 260
C KOUNT - FREQUENCY FOR STATE NUMBER PAIR. THIS VALUE IS RETURNED. RDIN 270
C INPSW - INPUT VALUE WILL BE ZERO. IF A DATA RECORD IS READ, THE RDIN 280
C OUTPUT VALUE WILL BE ZERO. IF AN END OF FILE CONDITION RDIN 290
C OCCURS ON THE INPUT UNIT, THE VALUE RETURNED WILL BE ONE. RDIN 300
C END RDIN 310
```

SUBROUTINE READSP(ISN,ISVEC,P,LABEL) RDSP0010
C CALLS POSINP, PRINTD, PRINTS, PRINTP RDSP0020
C THIS IS A GENERAL PURPOSE D-S-P READ ROUTINE. RDSP0030
C THIS ROUTINE WILL BE CALLED WHEN SPECIAL PURPOSE RDSP0040
C PRINTS FOR A GIVEN MODEL ARE REQUIRED. RDSP0050
C ONE CONTROL CARD IS REQUIRED FOR EACH SET OF RDSP0060
C CONSECUTIVE ARRAYS-ON AN INPUT UNIT-THE ARE TO RDSP0070
C BE PRINTED. RDSP0080
C A BLANK CONTROL CARD IS USED TO RETURN CONTROL RDSP0090
C TO THE CALLING PROGRAM. RDSP0100
C THE CONTROL CARD FIELDS ARE RDSP0110
C IDTAPE - COL 1-6 (I6) FORTRAN INPUT UNIT NUMBER. RDSP0120
C NFILE - COL 7-30 (6A4) ARRAY NAME OF FIRST OF RDSP0130
C 'NUMVC' FILES TO BE PRINTED UNDER RDSP0140
C CONTROL OF THIS CARD. RDSP0150
C NUMVC - COL 31-36 (I6) RDSP0160
C +N = THE NUMBER OF CONSECUTIVE ARRAYS RDSP0170
C TO BE PRINTED FROM 'IDTAPE' RDSP0180
C STARTING WITH ARRAY 'NFILE'. RDSP0190
C 0 = PRINT OPERATION COMPLETED. RETURN. RDSP0200
C -1 = PRINT ALL ARRAYS ON THE TAPE. RDSP0210
C KSW - 1,2,...,N USED IN PRINTD, PRINTS, RDSP0220
C PRINTP IF MULTI-PRINT OPTIONS ARE RDSP0230
C PROVIDED. RDSP0240
C RDSP0250
C RDSP0260
C RDSP0270
C RDSP0280
C IMPLICIT REAL*8(A-H,O-Z,\$) RDSP0290
C DIMENSION ISN(1),ISVEC(1),P(1),LABEL(1),NFILE(6) RDSP0300
C READ FIRST PRINT CONTROL CARD. RDSP0310
C READ 11, IDTAPE,NFILE,NUMVC,KSW RDSP0320
C SAVE INPUT UNIT NUMBER. RDSP0330
C IDTAPX=IDTAPE RDSP0340
C REWIND IDTAPE RDSP0350
C GO TO 12 RDSP0360
C RDSP0370
C RDSP0380
C READ FOR ALL ADDITIONAL CONTROL CARDS. RDSP0390
C 10 READ 11, IDTAPE,NFILE,NUMVC,KSW RDSP0400
C 11 FORMAT(I6,6A4,2I6)
C HAVE ALL PRINT CARDS BEEN PROCESSED? RDSP0410
C IF CARD IS BLANK, PRINT OPERATION IS COMPLETE. RDSP0420
C 12 IF(NUMVC.EQ.0) GO TO 500 RDSP0430
C NO RDSP0440
C IS TAPE FOR CURRENT CONTROL CARD A DIFFERENT RDSP0450
C TAPE FROM ONE IN PREVIOUS CONTROL CARD? RDSP0460
C IF(IDTAPX.NE.IDTAPE) GO TO 13 RDSP0470
C NO RDSP0480
C IS POSITIONING TO A NAMED FILE ON IDTAPE RE- RDSP0490
C QUIRED? RDSP0500
C IF(NUMVC.NE.(-1)) GO TO 14 RDSP0510
C NO RDSP0520
C ALL FILES ON THE INPUT TAPE WILL BE PROCESSED. RDSP0530
C REWIND IDTAPE RDSP0540
C GO TO READ FIRST LABEL. RDSP0550
C RDSP0560

GO TO 410 RDSP0570
C 13 YES - THERE WAS AN INPUT UNIT CHANGE. RDSP0580
C REWIND PREVIOUS INPUT UNIT. RDSP0590
C 13 REWIND IDTAPX RDSP0600
C IDTAPX=IDTAPE RDSP0610
C REWIND CURRENT INPUT UNIT. RDSP0620
C REWIND IDTAPE RDSP0630
C ARE ALL FILES ON THIS TAPE TO BE COPIED? RDSP0640
C YES. GO TO READ FIRST LABEL. RDSP0650
C IF(NUMVC.EQ.(-1)) GO TO 410 RDSP0660
C NO RDSP0670
C CALL POSINP TO LOCATE ARRAY NFILE ON UNIT RDSP0680
C IDTAPE. RDSP0690
C IDTAPE,NFILE ARE INPUT ARGUMENTS. RDSP0700
C NL,LABEL,KTYPE ARE RETURNED. RDSP0710
C 14 CALL POSINP(IDTAPE,KTYPE,NFILE,NL,LABEL) RDSP0720
C USE KTYPE FROM FILE LABEL TO BRANCH TO D, S, OR RDSP0730
C P PRINT. RDSP0740
C 15 GO TO (100,200,300),KTYPE RDSP0750
C 100 RDSP0760
C D RDSP0770
C 100 CONTINUE RDSP0780
C CALL PRINTD RDSP0790
C CALL PRINTD(NFILE,NL,LABEL,ISN,ISVEC,IDTAPE,KSW) RDSP0800
C GO TO 400 RDSP0810
C 200 RDSP0820
C S RDSP0830
C 200 CONTINUE RDSP0840
C CALL PRINTS RDSP0850
C CALL PRINTS(NFILE,NL,LABEL,ISN,ISVEC,IDTAPE,KSW) RDSP0860
C GO TO 400 RDSP0870
C 300 RDSP0880
C P RDSP0890
C 300 CONTINUE RDSP0900
C CALL PRINTP RDSP0910
C CALL PRINTP(NFILE,NL,LABEL,ISN,P ,IDTAPE,KSW) RDSP0920
C GO TO 400 RDSP0930
C END OF ARRAY RDSP0940
C DECREASE NUMBER OF ARRAYS TO BE PROCESSED BY RDSP0950
C ONE. RDSP0960
C 400 NUMVC=NUMVC-1 RDSP0970
C HAVE ALL ARRAYS BEEN PRINTED? RDSP0980
C YES. READ NEXT CONTROL CARD. RDSP0990
C IF(NUMVC.EQ.0) GO TO 10 RDSP1000
C NO RDSP1010
C READ NEXT LABEL FROM IDTAPE. RDSP1020
C 410 READ(IDTAPE)KTYPE,NFILE,NL,(LABEL(I),I=1,NL) RDSP1030
C IS THIS A D,S, OR P BEGINNING LABEL? RDSP1040
C YES. GO TO BRANCH ON ARRAY TYPE. RDSP1050
C IF(KTYPE.NE.40) GO TO 15 RDSP1060
C NO RDSP1070
C THIS IS A TYPE 40 RECORD. THIS MEANS ALL FILES RDSP1080
C FOR THIS CARD HAVE BEEN PROCESSED. A TYPE 40 RDSP1090
C RDSP1100
C RDSP1110
C RDSP1120
C RDSP1130

-119-

C	RECORD IS A FLOMOD END OF FILE RECORD.	RDSP1140
C	REWIND IDTAPE.	RDSP1150
C	GO TO 10	RDSP1160
C	500	RDSP1170
C	YES	RDSP1180
C	ALL PRINT CARDS PROCESSED.	RDSP1190
C	REWIND IDTAPE - LAST TAPE PRINTED FROM.	RDSP1200
C	500 REWIND IDTAPX	RDSP1210
C	PRINT 510	RDSP1220
C	510 FORMAT(1H1)	RDSP1230
C	RETURN	RDSP1240
C	REFERENCE LIST.	RDSP1250
C	SUBROUTINE ARGUMENTS.	RDSP1260
C	ISN - ARRAY FOR COLUMN NUMBERS IN A D ROW, ELEMENT NUMBERS IN AN S VECTOR, P MATRIX ROW LIST, P MATRIX COLUMN LIST AND COLUMN NUMBERS IN A P ROW.	RDSP1270
C	ISVEC - ARRAY FOR COLUMN VALUES IN A D ROW - OR - ELEMENT VALUES IN AN S VECTOR.	RDSP1280
C	P - ARRAY FOR COLUMN VALUES IN A P ROW.	RDSP1290
C	LABEL - ARRAY FOR D, S, AND P LABELS.	RDSP1300
C	END	RDSP1310
C		RDSP1320
C		RDSP1330
C		RDSP1340
C		RDSP1350
C		RDSP1360
C		RDSP1370
C		RDSP1380
C		RDSP1390
C		RDSP1400
C		RDSP1410

```
SUBROUTINE SELPAT          SELP0010
1   (IFROM,ITO,ICURR,MULT,NVCODE,      SELP0020
2   KSEL,KSELX,NI,NJ,                  SELP0030
3   KS)                               SELP0040
C   SELPAT                           SELP0050
C   THIS SUBROUTINE WILL SELECT SPECIFIED PATTERNS SELP0060
C   FROM A STATE PATTERN DISTRIBUTION TAPE AND WRITESEL0070
C   THE SELECTED PATTERNS ON AN OUTPUT TAPE.      SELP0080
C   THE PATTERNS NOT SELECTED WILL BE WRITTEN ON A SELP0090
C   SEPARATE OUTPUT TAPE IF THIS OPTION IS SPECIFIEDSELP0100
C                                         SELP0110
C   DIMENSION IFROM(1),ITO(1),ICURR(1),MULT(1),KSEL(1),KS(1)      SELP0120
1   ,NVCODE(1)                         SELP0130
DIMENSION KSELX(NI,NJ)                 SELP0140
C   READ OUTPUT UNIT ID. KOUT1 FOR SELECTED PATTERNSSELP0150
C   KOUT2 FOR PATTERNS NOT SELECTED.      SELP0160
READ 10,KOUT1,KOUT2                  SELP0170
C   REWIND KOUT 1.                      SELP0180
REWIND KOUT1                         SELP0190
C   IF PATTERNS NOT SELECTED ARE TO BE WRITTEN, RE- SELP0200
C   WIND KOUT 2.                         SELP0210
IF(KOUT2.NE.0) REWIND KOUT2          SELP0220
C   SET KRDSW2 TO INDICATE THERE IS NO PATTERN SEL- SELP0230
C   ECTION DATA IN CORE.                SELP0240
KRDSW2=1                            SELP0250
C   READ ID OF INPUT UNIT, INITIAL MODEL NO, MODEL SELP0260
C   NUMBER INCREMENTS FOR OUTPUT, NUMBER OF MODELS SELP0270
C   TO BE PROCESSED, LOCATION OF SELECTION DATA, ANDSELP0280
C   NS-NUMBER OF STATE NUMBERS PER PATTERN.      SELP0290
100 READ 10,KINP,MODL1,INC1,INC2,NMOD,KRDSW1,NS      SELP0300
C   HAVE ALL MODELS BEEN SPECIFIED...      SELP0310
C   YES. GO TO REWIND OUTPUT UNITS.      SELP0320
IF(KINP.EQ.0) GO TO 600              SELP0330
NO.                                SELP0340
C   REWIND INPUT UNIT.                  SELP0350
REWIND KINP                         SELP0360
C   SET OUTPUT MODEL NUMBERS.        SELP0370
MOUT1=MODL1+INC1                   SELP0380
MOUT2=MODL1+INC2                   SELP0390
C   IS PREVIOUS PATTERN INFO TO BE USED...      SELP0400
C   NO. GO TO READ PATTERN SELECTION DATA.      SELP0410
IF(KRDSW1.EQ.1) GO TO 150          SELP0420
YES.                                SELP0430
C   HAS A SET OF PATTERN SELECTION DATA BEEN READ SELP0440
C   DURING THIS SELPAT CALL?            SELP0450
C   YES. GO TO PROCESS INPUT TAPE.      SELP0460
IF(KRDSW2.EQ.2) GO TO 200          SELP0470
NO.                                SELP0480
C   PRINT ERROR MESSAGE.             SELP0490
PRINT 90,KINP,MODL1                SELP0500
C   EXIT                             SELP0510
STOP                               SELP0520
C                                         SELP0530
****SELP0540
*SELP0550
SELP0560
```

C READ PATTERN SELECTION DATA. SELP0570
C READ KOPT - OPTION TYPE. SELP0580
C NTFR - FROM TIME TO BE COMPARED. SELP0590
C NTTO - TO TIME TO BE COMPARED. SELP0600
C 150 READ 10,KOPT,NTFR,NTTO SELP0610
C BRANCH ON OPTION TYPE - KOPT. SELP0620
C GO TO (152,156,178), KOPT SELP0630
C 152 OPTION 1. SELP0640
C READ A LIST OF SINGLE TIME STATE NUMBERS. SELP0650
C READ LISTN - LENGTH OF LIST AND KSEL(1) - KSEL SELP0660
C (LISTN) - LIST OF STATE NUMBERS. SELP0670
C 152 READ 20,LISTN,(KSEL(I),I=1,LISTN) SELP0680
C GO TO 190 SELP0690
C 156 OPTION 2. SELP0700
C READ A FAMILY SPECIFICATION AND GENERATE A LIST SELP0710
C OF SINGLE TIME STATE NUMBERS. SELP0720
C READ NV - NUMBER OF VARIABLES AND NVCODE(1) - SELP0730
C NVCODE(NV) - NUMBER OF CODES DEFINED FOR EACH SELP0740
C VARIABLE. SELP0750
C 156 READ 20,NV,(NVCODE(I),I=1,NV) SELP0760
C LET NVM EQUAL NUMBER VARIABLES MINUS 1 FOR LATERSEL P0770
C INDEX USE. SELP0780
C NVM=NV-1 SELP0790
C COMPUTE MULT ARRAY FOR USE IN STATE NUMBER GEN- SELP0800
C ERATION. SELP0810
C MULT(NV)=1 SELP0820
C MULT(NV-1)=NVCODE(NV) SELP0830
C MULT(NV-2)=NVCODE(NV-1)*NVCODE(NV) SELP0840
C . SELP0850
C . SELP0860
C . SELP0870
C MULT(1)=NVCODE(2)*NVCODE(3)*...*NVCODE(NV). SELP0880
C MULT(NV)=1 SELP0890
C IF(NV.EQ.1) GO TO 164 SELP0900
C II=NV SELP0910
C DO 162 II=1,NVM SELP0920
C MULT(II-1)=MULT(II)*NVCODE(II) SELP0930
C 162 II=II-1 READ CODE RANGE FOR SELECTION STATES. SELP0940
C READ IFROM ARRAY - FAMILY FROM VALUES FOR EACH SELP0950
C VARIABLE. SELP0960
C 164 READ 30,(IFROM(I),I=1,NV) SELP0970
C READ IT0 ARRAY - FAMILY TO VALUES FOR EACH VAR- SELP0980
C ABLE. SELP0990
C READ 30,(IT0(I),I=1,NV) SELP1000
C SET ICURR(1) = ICURR(NV-1) EQUAL IFROM VALUFS. SELP1010
C IF(NV.EQ.1) GO TO 169 SELP1020
C DO 168 II=1,NVM SELP1030
C 168 ICURR(II)=IFROM(II) SELP1040
C SET ICURR(NV)=IFROM(NV)-1. SELP1050
C 169 ICURR(NV)=IFROM(NV)-1 SELP1060
C INUMBR=NV.'DO LUOP' CURRENTLY BEING INCREMENTED.SELP1070

```

C           (SEQUENCE IS INNER TO OUTER DO).          SELP1120
C   INUMBR=NV                                     SELP1130
C           THIS IS THE COUNTER FOR THE NUMBER OF ENTRIES INSEL P1140
C   KSEL.                                         SELP1150
C   LISTN=0                                       SELP1160
C                                               ***SELP1170
C                                               *SELP1180
C           THIS PROGRAM SEGMENT WILL CODE STATE NUMBERS SELP1190
C           FROM THE RANGE INFORMATION FOR A FAMILY OF SELP1200
C           NUMBERS.                                SELP1210
C                                               SELP1220
C           THE CONTROL PORTION OF THIS ROUTINE IS A NEST OFSEL P1230
C           DO LOOPS WHOSE DEPTH IS DETERMINED AT EXECUTION SELP1240
C           TIME. DO STATEMENTS ARE NOT USED.        SELP1250
C                                               SELP1260
C   172 NUMDO=NV                                 SELP1270
C           OVERALL 'DO' LOOP.                      SELP1280
C           COMPUTE VALUE FOR LATER USE IN DO STATEMENT. SELP1290
C   1100 NM1=NUMDO-1                            SELP1300
C           IS THE CURRENT INDEX OF THE VARIABLE WHOSE DO SELP1310
C           LOOP IS BEING INCREMENTED EQUAL THE TO INDEX FORSEL P1320
C           THIS VARIABLE?                         SELP1330
C   1120 IF(ICURR(INUMBR).EQ.ITO(INUMBR)) GO TO1200      SELP1340
C           NO.                                  SELP1350
C           ADD 1 TO CURRENT INDEX OF THIS VARIABLE. SELP1360
C   ICURR(INUMBR)=ICURR(INUMBR)+1                SELP1370
C                                               SELP1380
C           WAS THE INDEX JUST INCREMENTED FOR THE INNERMOSTSEL P1390
C           DO...                               SELP1400
C   IF(INUMBR.EQ.NUMDO) GO TO1170                 SELP1410
C           NO.                                  SELP1420
C           FOR ALL DO'S WITHIN THE DO JUST UPDATED, RESET SELP1430
C           THE CURRENT INDEX VALUES TO THE FROM INDEX SELP1440
C           VALUES.                            SELP1450
C   NFR=INUMBR+1                                SELP1460
C   DO1150 N=NFR,NUMDO                           SELP1470
C   1150 ICURR(N)=IFROM(N)                      SELP1480
C           INNERMOST DO WILL BE INCREMENTED NEXT. . SELP1490
C   INUMBR=NUMDO                                 SELP1500
C           COMPUTE THE STATE NUMBER FOR THIS SET OF CURRENTSEL P1510
C           VALUES.                            SELP1520
C           ISN = (ICURR(1)-1)*MULT(1)            SELP1530
C           +(ICURR(2)-1)*MULT(2)            SELP1540
C           + ...                            SELP1550
C           +(ICURR(NUMDO-1)-1)*MULT(NUMDO-1) SELP1560
C           + ICURR(NUMDO)                  SELP1570
C   1170 ISN=0                                    SELP1580
C   IF(NV.EQ.1) GO TO 1192                      SELP1585
C   DO1190 N=1,NM1                                SELP1590
C   1190 ISN=ISN+(ICURR(N)-1)*MULT(N)          SELP1600
C   1192 ISN=ISN+ICURR(NUMDO)                  SELP1610
C           GO TO 'DO LOOP' CONTINUE STATEMENT. SELP1620
C   GO TO 1299                                    SELP1630
C                                               SELP1640
C           YES                                SELP1650
C           INUMBR'TH DO LOOP CURRENT INDEX HAS REACHED THE SELP1660
C           TO INDEX VALUE.                  SELP1670

```

-123-

```
C           IS THIS THE OUTERMOST DO?          SELP1660
1200 IF(INUMBR.EQ.1) GO TO1220          SELP1690
C           NO.                                SELP1700
C           MOVE OUT ONE MORE DO LOOP.        SELP1710
C           INUMBR=INUMBR-1                  SELP1720
C           GO TO1120                         SELP1730
C           YES.                             SELP1740
C           EXECUTION OF DO LOOP NEST COMPLETE.  SELP1750
C           RETURN A -1 TO INDICATE NO FURTHER STATE NUMBERS  SELP1760
C           1220 ISN=-1                      SELP1770
C           1299 CONTINUE                     SELP1780
C           HAVE ALL STATE NUMBERS IN THIS SPECIFICATION  SELP1790
C           BEEN GENERATED?                SELP1800
C           IF(ISN.EQ.(-1)) GO TO 190         SELP1810
C           NO                               SELP1820
C           LISTN=LISTN+1                   SELP1830
C           ADD 1 TO NUMBER OF ENTRIES IN LIST.  SELP1840
C           KSEL(Listn)=ISN               SELP1850
C           STORE NUMBER JUST GENERATED IN LIST.  SELP1860
C           GO TO 1120                      SELP1870
C                                         SELP1880
C                                         *SELP1890
C                                         ***SELP1900
C                                         SELP1910
C                                         SELP1920
C                                         READ A LIST OF MULTI-TIME STATE NUMBERS.  SELP1930
C                                         READ LISTN - LENGTH OF LIST.  SELP1940
C           178 READ 10,LISTN                 SELP1950
C                                         FOR LENGTH-OF-LIST TIMES, READ A SELECTION
C                                         PATTERN INTO THE TIME PERIODS SPECIFIED.  SELP1960
C                                         SELP1970
C           DO 180 I=1,LISTN                 SELP1980
C           180 READ 30,(KSELX(I,J),J=NTFR,NTTO)  SELP1990
C                                         SET KRDSW2 TO INDICATE A SET OF DATA SELECTION  SELP2000
C                                         INFO IS IN CORE.          SELP2010
C                                         SELP2020
C           190 KRDSW2=2                   SELP2030
C                                         END OF READ SELECTION DATA.  SELP2040
C                                         *SELP2050
C                                         ****SELP2060
C                                         SELP2070
C                                         PROCESS STATE PATTERN FREQUENCY TAPE.  SELP2080
C                                         INITIALIZE COUNTERS          SELP2090
C                                         NUMBER OF PATTERNS READ.    SELP2100
C           200 NINP=0                      SELP2110
C                                         NUMBER PATTERNS SELECTED.  SELP2120
C                                         NUMBER PATTERNS NOT SELECTED.  SELP2130
C                                         NOUT1=0                      SELP2140
C                                         NOUT2=0                      SELP2150
C                                         READ A STATE PATTERN RECORD.  SELP2160
C           250 READ(KINP,END=550)MUDRD,(KS(I),I=1,NS),IFREQ  SELP2170
C                                         NO EOF                      SELP2180
C                                         WAS THERE A MODEL CHANGE?  SELP2190
C                                         YES. GO TO END OF MODEL PROCESSING.  SELP2200
C                                         IF(MODL1.NE.MODRD) GO TO 500  SELP2210
C                                         NO                          SELP2220
C                                         ADD 1 TO INPUT COUNT.      SELP2230
C           270 NINP=NINP+1                SELP2240
```

C BRANCH ON OPTION. SELP2250
C IF(KOPT.EQ.3) GO TO 320 SELP2260
C OPTIONS 1 AND 2. SELP2270
C DOES A STATE NUMBER IN ANY OF THE SPECIFIED TIMESEL P2280
C PERIODS IN THE RECORD JUST READ MATCH AN OPTION SELP2290
C 1 OR 2 SELECTION STATE NUMBER? SELP2300
C GO TO 450 FOR MATCH. SELP2310
C DO 300 J=NTFR,NTTO SELP2320
C DO 290 I=1,LISTN SELP2330
C IF(KS(I))-KSEL(I)) 300,450,290 SELP2340
290 CONTINUE SELP2350
300 CONTINUE SELP2360
C IF FALLS THRU COMPARE, HAVE NON-MATCH. SELP2370
C GO TO 400 SELP2380
C
C OPTION 3. SELP2390
C DO THE STATE NUMBERS IN THE SPECIFIED TIME SELP2400
C PERIODS OF THE RECORD JUST READ MATCH ALL THE SELP2410
C CORRESPONDING STATE NUMBERS IN AN OPTION 3 SELP2420
C SELECTION PATTERN? SELP2430
C SELP2440
320 DO 360 I=1,LISTN SELP2450
DO 340 J=NTFR,NTTO SELP2460
IF(KS(J))-KSELX(I,J)) 400,340,360 SELP2470
340 CONTINUE SELP2480
C MATCH CONDITION IF FALL THRU THIS DO. SELP2490
C GO TO 450 SELP2500
C
360 CONTINUE SELP2510
C UNMATCH IF FALL THRU THIS DO. SELP2520
C
C PROCESS NON-MATCH RECORD. SELP2530
C ADD 1 TO UNMATCHING COUNT. SELP2540
C
400 NOUT2=NOUT2+1 SELP2550
C IF UNMATCHING RECORDS ARE TO BE WRITTEN, WRITE SELP2560
C PATTERN ON KOUT 2. SELP2570
C IF(KOUT2.NE.0) WRITE(KOUT2)MOUT2,(KS(I),I=1,NS),IFREQ SELP2580
C GO TO READ NEXT RECORD. SELP2590
C GO TO 250 SELP2600
C
C PROCESS MATCHING RECORD. SELP2610
C ADD 1 TO MATCHING COUNT. SELP2620
C
450 NOUT1=NOUT1+1 SELP2630
C WRITE MATCHING RECORD ON KOUT 1. SELP2640
C WRITE(KOUT1)MOUT1,(KS(I),I=1,NS),IFREQ SELP2650
C GO TO READ NEXT RECORD. SELP2660
C GO TO 250 SELP2670
C
C CHANGE IN MODEL NUMBER. SELP2680
C DECREASE NUMBER OF MODELS PROCESSED BY 1. SELP2690
C
500 NMOD=NMOD-1 SELP2700
C PRINT INPUT MODEL NUMBER AND OUTPUT COUNTS FOR SELP2710
C THIS MODEL. SELP2720
C 510 PRINT 80,MODL1,NINP,NOUT1,NOUT2 SELP2730
C ARE ADDITIONAL MODELS TO BE PROCESSED FROM THIS SELP2740
C TAPE? SELP2750
C NO. GO TO REWIND INPUT UNIT. SELP2760
C IF(NMOD.LE.0) GO TO 570 SELP2770
C SELP2780
C SELP2790
C SELP2800
C SELP2810

C YES SELP2820
C PROCESS NEXT MODEL SELP2830
C RESET INPUT MODEL NUMBER; NUMBER OF PATTERNS SELP2840
C READ AND SELECTED, OUTPUT MODEL NUMBERS. SELP2850
C
MODL1=MODRD SELP2860
NINP=0 SELP2870
NOUT1=0 SELP2880
NOUT2=0 SELP2890
MOUT1=MODL1+INC1 SELP2900
MOUT2=MODL1+INC2 SELP2910
C GO TO 270 SELP2920
C 550 SELP2930
C EOF ON READ. SELP2940
C SET NUMBER OF MODELS PROCESSED TO -1. SELP2950
C 550 NMOD=-1 SELP2970
GO TO 510 SELP2980
C 570 SELP2990
C ALL MODELS COMPLETE ON THIS INPUT TAPE. SELP3000
C REWIND INPUT UNIT. SELP3010
C 570 REWIND KINP SELP3020
C GO TO 100 SELP3030
C YES SELP3050
C SELPAT RUN COMPLETE. SELP3060
C REWIND OUTPUT UNIT KOUT1. SELP3070
C 600 REWIND KOUT1 SELP3080
C IF .AN OUTPUT UNIT FOR NON-SELECTED PATTERNS WAS SELP3090
C DESIGNATED, REWIND KOUT2. SELP3100
C IF(KOUT2.NE.0) REWIND KOUT2 SELP3110
C PRINT END OF RUN MESSAGE. SELP3120
C PRINT 70 SELP3130
C RETURN SELP3140
C RETURN SELP3150
C
10 FORMAT(7I6) SELP3160
20 FORMAT(I6/(6I12)) SELP3170
30 FORMAT(6I12) SELP3180
70 FORMAT(22H SELPAT RUN COMPLETED.) SELP3190
80 FORMAT(14H END OF MODEL ,I6,35H INPUT N..SELECTED..NOT SELECTED.. SELP3200
1,3I12) SELP3210
90 FORMAT(174H PREVIOUS SELECTION INFO REQUESTED BUT NONE PRESENT. KINSEL SELP3220
1P AND MODEL NO. = ,2I6) SELP3230
C
REFERENCE LIST. SELP3240
C
SUBROUTINE ARGUMENTS. SELP3250
C
IFROM - ARRAY FOR FROM INDEX VALUES OF VARIABLE DEPTH NESTED DO'S SELP3300
C ITO - ARRAY FOR TO INDEX VALUES OF VARIABLE DEPTH NESTED DO'S. SELP3310
C ICURR - ARRAY FOR CURRENT INDEX VALUES OF VARIABLE DEPTH NESTED SELP3320
C DO'S. SELP3330
C MULT - ARRAY FOR THE VARIOUS PRODUCTS USED IN GENERATING A STATE SELP3340
C NUMBER. SELP3350
C NVCODE - ARRAY FOR NUMBER OF CODES DEFINED FOR EACH VARIABLE. SELP3360
C KSEL - ARRAY FOR SPECIFIC STATE NUMBER LIST. SELP3370
C KSELX - TWO DIMENSIONAL ARRAY FOR PATTERN LISTS. THE ARRAY SIZE SELP3380

C	IS VARIABLE.	SELP3390
C NI	- ROW SIZE OF KSELX.	SELP3400
C NJ	- COL SIZE OF KSELX.	SELP3410
C KS	- ARRAY FOR STATE NUMBER PATTERN.	SELP3420
C	OTHER VARIABLES.	SELP3430
C	IFREQ - FREQUENCY OF LAST PATTERN READ.	SELP3440
C INUMBR	- NUMBER OF THE DO LOOP WHOSE INDEX IS CURRENTLY BEING INCREMENTED.	SELP3450
C ISN	- STATE NUMBER GENERATED DURING EXECUTION OF CODE ROUTINE. A VALUE OF -1 IS RETURNED WHEN ALL NUMBERS HAVE BEEN GENERATED.	SELP3460
C INC1	- INCREMENT FOR MODEL NUMBER FOR SELECTED OUTPUT.	SELP3470
C INC2	- INCREMENT FOR MODEL NUMBER FOR UNSELECTED OUTPUT.	SELP3480
C	KINP - INPUT UNIT.	SELP3490
C KOUT1	- OUTPUT UNIT FOR SELECTED CASES.	SELP3500
C KOUT2	- OUTPUT UNIT FOR CASES NOT SELECTED IF THEY ARE TO BE WRITTEN ALSO.	SELP3510
C KRDSW1	- 1..READ STATE NUMBER SELECTION INFO. 2..USE STATE NUMBER SELECTION INFO FROM PREVIOUS READ,	SELP3520
C KRDSW2	- 1..NO STATE SELECTION INFO IN CORE AT PRESENT TIME. 2..THERE IS STATE SELECTION INFO IN CORE.	SELP3530
C KOPT	- OPTION NUMBER. 1 - SELECT SPECIFIC STATE NUMBERS LISTED IN DATA CARDS. 2 - SELECT SPECIFIC STATE NUMBERS GENERATED FROM A FAMILY OF STATE NUMBERS SPECIFICATION. 3 - SELECT SPECIFIC STATE NUMBER PATTERNS LISTED IN DATA CARDS.	SELP3540
C	LISTN - NUMBER OF ENTRIES IN SELECTION LIST - KSEL OR KSELX.	SELP3550
C MODL1	- MODEL NUMBER OF FIRST MODEL NUMBER ON THIS INPUT TAPE.	SELP3560
C MODRD	- MODEL NUMBER OF LAST PATTERN READ.	SELP3570
C MOUT1	- MODEL NUMBER FOR OUTPUT OF SELECTED PATTERNS.	SELP3580
C MOUT2	- MODEL NUMBER FOR OUTPUT OF PATTERNS NOT SELECTED.	SELP3590
C NTFR	- FROM-TIME OF STATE NUMBERS TO BE CHECKED AGAINST LIST.	SELP3600
C NTTO	- TO-TIME OF STATE NUMBERS TO BE CHECKED AGAINST LIST.	SELP3610
C NINP	- NUMBER OF PATTERNS READ.	SELP3620
C NDUT1	- NUMBER OF PATTERNS SELECTED.	SELP3630
C NDUT2	- NUMBER OF PATTERNS NOT SELECTED.	SELP3640
C NS	- NUMBER OF STATE NUMBERS IN PATTERN.	SELP3650
C NHOD	- NUMBER OF MODELS ON THIS TAPE TO BE PROCESSED. THE SAME SELECTION PATTERNS WILL APPLY TO ALL MODELS ON A GIVEN INPUT TAPE.	SELP3660
C NV	- NUMBER OF VARIABLES IN STATE NUMBER DEFINITION.	SELP3670
C NUMDO	- NUMBER OF DO LOOPS. THIS VARIABLE IS EQUAL NV.	SELP3680
C	END	SELP3690
C		SELP3700
C		SELP3710
C		SELP3720
C		SELP3730
C		SELP3740
C		SELP3750
C		SELP3760
C		SELP3770
C		SELP3780
C		SELP3790
C		SELP3800
C		SELP3810
C		SELP3820
C		SELP3830
C		SELP3840
C		SELP3850

```

C SUBROUTINE SMATXP(NDIM,ISN,ISVEC,KSN,KSVEC,SVEC,JCOL,P,LABELS,
C 1          LABELP)
C
C           MULTIPLY DIAGONAL S MATRIX TIMES P MATRIX
C           TO OBTAIN D MATRIX.
C           THE ELEMENTS OF THE D MATRIX ARE SUMMED BY ROW
C           TO OBTAIN AN S VECTOR.
C           SINCE S IS A DIAGONAL MATRIX, THERE WILL BE A
C           ROW IN THE D MATRIX ONLY WHEN THERE IS A CORRE-
C           SPONDING ROW IN BOTH THE INPUT S MATRIX AND THE
C           P MATRIX.
C
C IMPLICIT REAL*8(A-H,O-Z,$)
C DIMENSION ISN(1),ISVEC(1),KSN(1),KSVEC(1),SVEC(1),JCOL(1),P(1),
C 1          ,LABELS(1),LABELP(1)
C           KSVEC(1),SVEC(1) MUST BE EQUIVALENT IN MAIN PGM.
C DIMENSION NAMES(6),NAMEP(6),NFILL6(6),L1(30),L2(30)
C
C           INITIALIZATION FOR THIS CALL.
C           S RECORD TYPE VARIABLES.
C
C KSBEG=2
C KSDAT=22
C KSEND=32
C
C           D RECORD TYPE VARIABLES.
C
C KDBEG=1
C KDDAT=21
C KLEND=31
C
C           FLOMOD END OF FILE RECORD.
C
C KNEXT=40
C
C           OTHER CONSTANTS.
C
C NFILL=1
C DATA KBLANK/4H
C DO 1 I=1,6
C 1 NFILL6(I)=KBLANK
C
C           SKIP TO A NEW PAGE ON PRINTER.
C
C PRINT 2
C
C           READ OUTPUT TAPE ID AND POSITION.
C
C READ 5,IOUT
C REWIND IOUT
C
C           SET INITIAL COUNT OF FILES ON OUTPUT UNIT TO
C           ZERO.
C
C NFILES=0
C
C           READ A CONTROL CARD.
C 10 READ 20,NAMES,INPS,NAMEP,INPP,NITER,NPAIRS,NUMP,IODISK
C           HAVE ALL ARRAYS BEEN PROCESSED?
C           NO. GO TO LOCATE S MATRIX.
C
C IF(NITER.NE.0) GO TO 30
C           YES. MULTIPLICATIONS COMPLETE FOR THIS CALL.
C           ADD 1 TO COUNT OF OUTPUT FILES.
C
C NFILES=NFILES+1
C
C           WRITE FLOMOD END OF FILE RECORD.
C WRITE(IOUT) KNEXT,NFILL6,NFILL,NFILES
C
C           REWIND OUTPUT UNIT.
C
C REWIND IOUT

```

C RETURN. SMAT0570
C RETURN SMAT0580
C THERE ARE STILL ARRAYS TO BE PROCESSED. "", SMAT0590
C PROCESS THE CONTROL CARD JUST READ. SMAT0600
C INITIAL S AND P POSITIONING FOR THIS CONTROL SMAT0610
C CARD. SMAT0620
C LOCATE S MATRIX. SMAT0630
C 30 CALL POSINP(INPS,KTYPE,NAMES,NLS,LABELS) SMAT0640
C READ DATA RECORD AND FIND LABEL. SMAT0650
C 32 READ(INPS)KTYPE, SMAT0660
1 NFILL,ISCNT,(ISN(I),I=1,ISCNT),(ISVFC(I),I=1,ISCNT) SMAT0670
READ(INPS)KTYPE,NFILL,NFILL,INSUM,NFILL SMAT0680
C PRINT INPUT S NAME AND SUM. SMAT0690
PRINT 35,NAMES,INSUM SMAT0700
C TEST FOR TYPE POSITIONING REQUIRED FOR P. SMAT0710
IF(NPAIRS.GT.0) GO TO 50 SMAT0720
C POSITION TO NAMED P. SMAT0730
CALL POSINP(INPP,KTYPE,NAMFP,NLP,LABFLP) SMAT0740
GO TO 52 SMAT0750
C THE TAPE WILL BE IN POSITION FOR THE NEXT P. SMAT0760
READ(LABFLP) SMAT0770
C 50 READ(INPP)KTYPE,NAMFP,NLP,(LABFLP(I),I=1,NLP) SMAT0780
C PASS P MATRIX ROW LIST RECORD. SMAT0790
C 52 READ(INPP) SMAT0800
C PASS P MATRIX COLUMN LIST RECORD. SMAT0810
READ(INPP) SMAT0820
C
C READ ARRAY NAMES FOR OUTPUT D AND S. SMAT0830
C 60 READ 70,NAMFP,NAMES SMAT0840
C SET UP SMATXP IDENT LINE FOR OUTPUT LABELS. SMAT0850
C DATA L1/120HD MATRIX RESULTING FROM DIAGONAL S MATRIX TIMES P MATRIX SMAT0860
1 IX OPERATION SMAT0870
2//,L2/120HVECTOR OF ROW SUMS OF D MATRIX RESULTING FROM DIAGONAL S SMAT0880
3MATRIX TIMES P MATRIX OPERATION / SMAT0890
C COMPUTE OUTPUT LABEL LENGTH. SMAT0900
C NLS2=30+NLS+NLP SMAT0910
C
C WRITE(DOUT)KDRFG,NAMFP,NLS2,L1,(LABFLS(I),I=1,NLS),(LABFLP(I),I=1,NLP) SMAT0920
1 NLP SMAT0930
C
C NPROWS=0 INITIAL VALUE OF NUMBER OF ROWS IN D IS ZERO. SMAT0940
C NDLMTS=0 INITIAL VALUE OF NUMBER OF ELEMENTS IN D = ZERO. SMAT0950
C NSUM=0 INITIAL VALUE OF S SUM IS ZERO. SMAT0960
C
C S MATRIX - P MATRIX MULTIPLICATION. ***SMAT0970
C
C I = SUBSCRIPT FOR ISN, LIST OF INPUT S MATRIX *SMAT0980
C ROWS. SMAT0990
C K = SUBSCRIPT FOR JCOL, P AND KSVFC, INPUT P SMAT1000
C
C SMAT1010
C SMAT1020
C SMAT1030
C SMAT1040
C SMAT1050
C SMAT1060
C
C SMAT1070
C SMAT1080
C SMAT1090
C SMAT1100
C SMAT1110
C SMAT1120
C SMAT1130

C MATRIX AND OUTPUT D MATRIX ELEMENT LIST AND SMAT1140
C VALUES IN A ROW. SMAT1150
C I2 = SUBSCRIPT FOR KSVEC, OUTPUT S ELEMENT SMAT1160
C VALUES. INITIAL I2 VALUE WILL BE NDIM+1. SMAT1170
C I3 = SUBSCRIPT FOR OUTPUT S ELEMENT LIST IN KSN. SMAT1180
C
C I=1 SMAT1190
C I2=NDIM SMAT1200
C I3=0 SMAT1210
C READ A P RECORD SMAT1220
C 90 READ(INPP)KTYPE,KROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) SMAT1230
C WAS RECORD JUST READ THE P END LABEL? SMAT1240
C YES. GO TO WRITE D END LABEL. SMAT1250
C IF(KTYPE.EQ.33) GO TO 150 SMAT1260
C RECORD JUST READ WAS A P DATA RECORD. SMAT1270
C DOES CURRENT S ROW NUMBER EQUAL CURRENT P ROW SMAT1280
C NUMBER? SMAT1290
C YES. GO TO MULTIPLY. SMAT1300
C 95 IF(ISN(I).EQ.KROW) GO TO 100 SMAT1310
C NO. SMAT1320
C IF S ROW NUMBER IS LESS THAN P ROW NUMBER, GO TO SMAT1330
C INCREMENT S ROW NUMBER SUBSCRIPT. SMAT1340
C IF(ISN(I).LT.KROW) GO TO 125 SMAT1350
C P ROW NUMBER IS LESS THAN S ROW NUMBER. SMAT1360
C GO TO READ NEXT P RECORD. SMAT1370
C GO TO 90 SMAT1380
C
C S ROW AND P ROW MATCH. SMAT1390
C IS THE S VALUE ZERO? SMAT1400
C YES. GO TO INCREMENT S SUBSCRIPT. SMAT1420
C 100 IF(ISVEC(I).LE.0) GO TO 130 SMAT1430
C FLOAT INPUT S VALUE. SMAT1440
C S=ISVEC(I) SMAT1450
C ISUM=0 SMAT1460
C MULTIPLY AN ELEMENT OF S TIMES EACH ELEMENT OF SMAT1480
C THE CORRESPONDING ROW OF P TO GENERATE A ROW SMAT1490
C OF D. SMAT1500
C DO 110 K=1,JCNT SMAT1510
C COMPUTE K'TH ENTRY IN D MATRIX ROW. SMAT1520
C KSVEC(K)=P(K)*S+.5D0 SMAT1530
C ACCUMULATE ROW SUM. SMAT1540
C 110 ISUM=ISUM+KSVEC(K) SMAT1550
C SET K EQUAL NUMBER ENTRIES IN D ROW. SMAT1560
C K=JCNT SMAT1570
C ALL ELEMENTS IN THIS ROW OF P HAVE BEEN SMAT1580
C PROCESSED. GO TO WRITE THIS D MATRIX ROW. SMAT1590
C GO TO 128 SMAT1600
C
C S ROW NUMBER IS LESS THAN P ROW NUMBER. SMAT1610
C HAVE ALL S ELEMENTS BEEN PROCESSED? SMAT1620
C YES. GO TO PASS P RECORDS. SMAT1630
C 125 IF(I.EQ.ISCNT) GO TO 140 SMAT1640
C NO SMAT1650
C INCREMENT S ROW NUMBER SUBSCRIPT. SMAT1660
C I=I+1 SMAT1670
C GO TO COMPARE S AND P ROW NUMBERS. SMAT1680
C GO TO 95 SMAT1690
C SMAT1700

C C ALL ELEMENTS IN P MATRIX ROW HAVE BEEN MULTI- SMAT1710
C C PLIED TIMES S MATRIX ELEMENT. SMAT1720
C C 120 CONTINUE SMAT1730
C C WRITE(I,IUT)KDDAT,KROW,K,(JCOL(KK),KK=1,K),(KSVEC(KK),KK=1,K) SMAT1740
C C INCREMENT COUNT OF ROWS IN D MATRIX. SMAT1750
C C NDROWS=NROWS+1 SMAT1760
C C INCREMENT COUNT OF ELEMENTS IN D MATRIX. SMAT1770
C C NDL, TS:NDLMTS+K SMAT1780
C C INCREMENT OUTPUT S VECTOR SUM. SMAT1790
C C NSUM=NSUM+ISUM SMAT1800
C C INCREMENT OUTPUT S SUBSCRIPTS. SMAT1810
C C I2=I2+1 SMAT1820
C C I3=I3+1 SMAT1830
C C STORE CURRENT ROW NUMBER AND SUM IN OUTPUT S. SMAT1840
C C KSVEC(I2)=ISUM SMAT1850
C C KSN(I3)=KROW SMAT1860
C C MATCHING ROWS JUST PROCESSED. SMAT1870
C C HAVE ALL S MATRIX ENTRIES BEEN PROCESSED? SMAT1880
C C YES. GO TO POSITION TO END OF P ARRAY. SMAT1890
C C 130 IF(I.EQ.ISCNT) GO TO 140 SMAT1900
C C NO. INCREMENT S MATRIX INDEX. SMAT1910
C C I=I+1 SMAT1920
C C GO TO READ NEXT P RECORD. SMAT1930
C C GO TO 90 SMAT1940
C C READ REMAINING P RECORDS IF ANY. SMAT1950
C C THIS IS JUST SO TAPE WILL ALWAYS BE POSITIONED SMAT1960
C C AFTER A P END RECORD AT THE END OF A MULTIPLICA- SMAT1970
C C TION. SMAT1980
C C 140 READ(INPP)KTYPF SMAT1990
C C IF(KTYPF.EQ.33) GO TO 150 SMAT2000
C C GO TO 140 SMAT2010
C C INPUT TAPE IS POSITIONED FOR NEXT BEGINNING OF SMAT2020
C C ARRAY LABEL. SMAT2030
C C 150 CONTINUE SMAT2040
C C PRINT 141,NAMFP,NSUM SMAT2050
C C PRINT OUTPUT D SUM. SMAT2060
C C WRITE(I,IUT)NDFND,NFILL,NFILL,NROWS,NDLMTS SMAT2070
C C WRITE D MATRIX END LABEL. SMAT2080
C C WRITE(I,IUT)KSREG,NAMFS,NLS2,L2,(LABFLS(I),I=1,NLS),(LARFLP(I),I=1,SMAT2090
C C 1 NLP) SMAT2100
C C ADD 1 TO COUNT OF FILES ON OUTPUT UNIT. SMAT2110
C C NFILFS=NFILEFS+1 SMAT2120
C C *SMAT2130
C C ***SMAT2140
C C WRITE S VECTOR ON OUTPUT UNIT. SMAT2150
C C SMAT2160
C C WRITE S BEGINNING LABEL. SMAT2170
C C SMAT2180
C C WRITE(I,IUT)KSREG,NAMFS,NLS2,L2,(LABFLS(I),I=1,NLS),(LARFLP(I),I=1,SMAT2190
C C 1 NLP) SMAT2200
C C WRITE S DATA RECORD. SMAT2210
C C SMAT2220
C C IFR=NDIM+1 SMAT2230
C C WRITE(I,IUT)KSREG,NFILL,I3,(KSN(I),I=1,I3),(KSVEC(I),I=IFR,I2) SMAT2240
C C WRITE S END LABEL. SMAT2250
C C WRITE(I,IUT)KSREG,NFILL,NFILL,NSUM,NFILL SMAT2260
C C SMAT2270

C ADD 1 TO COUNT OF FILES ON OUTPUT UNIT. SMAT2
C NFILES=NFILES+1 SMAT2
C IS THIS A PAIR SPECIFICATION? SMAT2
C NO. GO TO CHECK NUMP SPECIFICATION. SMAT2
240 IF(NPAIRS.EQ.0) GO TO 260 SMAT2
C YES. SMAT2
C NPAIRS=NPAIRS-1 SMAT2
C HAVE ALL PAIRS BEEN PROCESSED? SMAT2
C YES. GO TO READ NEXT CONTROL CARD. SMAT2
C IF(NPAIRS.EQ.0) GO TO 10 SMAT2
C NO. READ LABEL OF NEXT S MATRIX. SMAT2
C READ(INPS)KTYPE,NAMES,NLS,(LABELS(I),I=1,NLS) SMAT2
C GO TO READ S DATA RECORD. SMAT2
C GO TO 32 SMAT2
C THIS IS NOT A PAIR SPECIFICATION. IS THIS A NUMPSMAT2
C SPECIFICATION? SMAT2
C NO. GO TO READ NEXT CONTROL CARD. SMAT2
260 IF(NUMP.EQ.0) GO TO 10 SMAT2
C YES SMAT2
C NUMP=NUMP-1 SMAT2
C HAVE ALL NUMP P'S BEEN PROCESSED? SMAT2
C YES. GO TO READ NEXT CONTROL CARD. SMAT2
C IF(NUMP.EQ.0) GO TO 10 SMAT2
C NO. SMAT2
C GO TO READ NEXT P LABEL. SMAT2
C GO TO 50 SMAT2
C
2 FORMAT(1H1) SMAT2
5 FORMAT(I6) SMAT2
20 FORMAT(6A4,I6,6A4,I6,4I3) SMAT2
35 FORMAT(24H INPUT S NAME AND SUM...,6A4,I12) SMAT2
70 FORMAT(6A4,6A4) SMAT2
141 FORMAT(24H D NAME AND SUM,6A4,I12) SMAT2
C
C REFERENCE LIST. SMAT2
C
C SUBROUTINE ARGUMENTS. SMAT2
C
NDIM - DIMENSION OF KSN AND KSVEC. USED TO LOCATE POSITION IN SMAT2
SVEC FOR STORING OUTPUT S. SMAT2
ISN - ELEMENT LIST FOR INPUT S. SMAT2
ISVEC - ELEMENT VALUE FOR INPUT S. SMAT2
KSN - ELEMENT LIST FOR OUTPUT S. SMAT2
KSVEC, SMAT2
SVEC - ELEMENT VALUE FOR D AND OUTPUT S. SMAT2
JCOL - ELEMENT LIST FOR P ROW AND D ROW. SMAT2
P - ELEMENT VALUE FOR P ROW. SMAT2
LABELS - ARRAY FOR INPUT S LABEL AND OUTPUT D AND S LABELS. SMAT2
LABELP - ARRAY FOR P MATRIX LABEL. SMAT2
C
C OTHER VARIABLES. SMAT2
C
INPS - INPUT UNIT FOR S. SMAT2
INPP - INPUT UNIT FOR P. MAY BE THE SAME AS INPS. SMAT2
INSUM - SUM OF INPUT S. SMAT2
ISUM - SUM OF VALUES FOR A D ROW. SMAT2

C IODISK - THIS CONTROL CARD FIELD IS NOT USED BUT IS RETAINED TO SMAT2850
C MAINTAIN COMPATIBILITY WITH SUBROUTINE SXP CONTROL CARDS. SMAT2860
C NFILES - NUMBER OF FILES ON OUTPUT UNIT. SMAT2870
C NITER - THIS CONTROL CARD FIELD IS RETAINED TO MAINTAIN COMPATI- SMAT2880
C BILITY WITH SUBROUTINE SXP CONTROL CARDS. SMAT2890
C ENTER 1 IN ALL CONTROL CARDS WITH MULTIPLY SPECIFICATIONSMAT2900
C ENTER 0 TO INDICATE MULTIPLICATION OPERATION IS COMPLETE. SMAT2910
C NLS - LENGTH OF INPUT S LABEL. SMAT2920
C NLS2 - LENGTH OF D LABEL AND OUTPUT S LABEL. SMAT2930
C NLP - LENGTH OF P LABEL. SMAT2940
C NSUM - SUM OF OUTPUT S. SMAT2950
C NPAIRS- NUMBER OF 'PAIRED (S,P)' ARRAYS. THESE ARRAYS MUST BE ON SMAT2960
C THE SAME INPUT TAPE AND IN A SPECIFIED ORDER. SMAT2970
C NUMP - NUMBER OF P MATRICES TO BE PAIRED WITH A SINGLE INPUT S SMAT2980
C SMAT2990
C END SMAT3000

```

C          SUBROUTINE SMINUS(ISNI,ISVFCI,LABELI,ISNJ,ISVECJ,LABELJ,
C                           ISNK,ISVECK)
C
C          S VECTOR I MINUS S VECTOR J = S VECTOR K.
C
C          DIMENSION ISNI(1),ISVCI(1),LABELI(1),ISNJ(1),ISVECJ(1),LABELJ(1),SMIN0010
C                           ISNK(1),ISVECK(1)SMIN0020
C          1           DIMENSION NAMEI(6),NAMEJ(6),NAMEK(6),NOLDI(6),NOLDJ(6),NULABL(30)SMIN0030
C          DATA KBLANK/4H      /,M1/4HMINU/,M2/4HS   /SMIN0040
C
C          INITIALIZATIONSMIN0050
C          PREVIOUS SI AND SJ NAMES.SMIN0060
C
C          DO 5 N=1,6SMIN0070
C          NOLDI(N)=XBLANKSMIN0080
C          5 NOLDJ(N)=KBLANKSMIN0090
C
C          SMINUS LABEL ADDITION.SMIN0100
C
C          DO 6 N=1,30SMIN0110
C          6 NULABL(N)=KBLANKSMIN0120
C          NULABL(3)=M1SMIN0130
C          NULABL(4)=M2SMIN0140
C
C          S VECTOR RECORD TYPE CONSTANTS - BEGINNING LABELSMIN0150
C          DATA RECORD AND END LABEL.SMIN0160
C
C          KSBEG=2SMIN0170
C          KSDAT=22SMIN0180
C          KSEND=32SMIN0190
C
C          SET NUMBER OF OUTPUT FILES EQUAL ZERO.SMIN0200
C
C          NFILES=0SMIN0210
C
C          READ 10,KOUTSSMIN0220
C
C          REWIND KOUTSSMIN0230
C
C          REWIND KOUTSSMIN0240
C
C          30SMIN0250
C
C          SET NUMBER OF OUTPUT FILES EQUAL ZERO.SMIN0260
C
C          RREAD INPUT UNIT NUMBER AND ARRAY NAME FORSMIN0270
C          CURRENT SI AND SJ.SMIN0280
C
C          30 READ 10,INPI,NAMEI,INPJ,NAMEJSMIN0290
C
C          HAVE ALL INPUT FILES BEEN PROCESSED?SMIN0300
C
C          YES. GO TO WRITE OUTPUT END LABEL.SMIN0310
C
C          IF(INPI.F0.0) GO TO 500SMIN0320
C
C          NO
C
C          IS PREVIOUS S(I) TO BE USED AGAIN...SMIN0330
C
C          IS PREVIOUS SI NAME = CURRENT SI NAME?SMIN0340
C
C          DO 50 N=1,6SMIN0350
C
C          IF(NAMEI(N).NE.NOLDI(N)) GO TO 60SMIN0360
C
C          50 CONTINUESMIN0370
C
C          YES
C
C          GO TO LOCATE SJ.SMIN0380
C
C          GO TO 140SMIN0390
C
C          60
C
C          NO.
C
C          IS PREVIOUS S(J) TO BE USED AS S(I)...SMIN0400
C
C          IS PREVIOUS SJ NAME = CURRENT SI NAME?SMIN0410
C
C          60 DO 70 N=1,6SMIN0420
C
C          IF(NAMEI(N).NE.NOLDJ(N)) GO TO 100SMIN0430
C
C          70 CONTINUESMIN0440
C
C          YES

```

C USE PREVIOUS SJ AS SI. SMIN0570
C MOVE PREVIOUS SJ INFO TO CORRESPONDING LOCATIONSSMIN0580
C FOR CURRENT SI INFO. SMIN0590
C
DO 80 N=1,ISCNTJ SMIN0600
ISNI(N)=ISNJ(N) SMIN0610
80 ISVECI(N)=ISVECJ(N) SMIN0620
ISCNTI=ISCNTJ SMIN0630
DO 85 N=1,NLJ SMIN0640
85 LABELI(N)=LABELJ(N) SMIN0650
NLJ=NLI SMIN0660
ISUMI=ISUMJ SMIN0670
C GO TO LOCATE SJ. SMIN0680
GO TO 140 SMIN0690
C 100 SMIN0700
C CURRENT SI MUST BE READ FROM AN INPUT UNIT. SMIN0710
C LOCATE ARRAY NAMED. SMIN0720
100 CALL POSINP(INPI,KTYPE,NAMEI,NLI,LABELI) SMIN0730
C READ DATA RECORD AND END RECORD. SMIN0740
READ(INPI)KTYPE,NFILL,ISCNTI,(ISNI(I),I=1,ISCNTI), SMIN0750
1 (ISVFC(I),I=1,ISCNTI) SMIN0760
READ(INPI)KTYPE,NFILL,NFILL,ISUMI SMIN0770
C 120 SMIN0780
C IS PREVIOUS SJ TO BE USED AGAIN... SMIN0790
C IS PREVIOUS SJ NAME = CURRENT SJ NAME? SMIN0800
120 DO 130 N=1,6 SMIN0810
IF(NAMEJ(N).NE.NOLDJ(N)) GO TO 140 SMIN0820
130 CONTINUE SMIN0830
C YES SMIN0840
C GO TO 200 SMIN0850
C 140 SMIN0860
C NO. SMIN0870
C PREVIOUS SJ IS NOT BEING USED AGAIN. SMIN0880
C / CURRENT SJ MUST BE READ FROM AN INPUT UNIT. SMIN0890
C LOCATE ARRAY NAMED. SMIN0900
140 CALL POSINP(INPJ,KTYPE,NAMEJ,NLJ,LABELJ) SMIN0910
C READ DATA RECORD AND END RECORD. SMIN0920
READ(INPJ)KTYPE,NFILL,ISCNTJ,(ISNJ(J),J=1,ISCNTJ), SMIN0930
1 (ISVFCJ(J),J=1,ISCNTJ) SMIN0940
READ(INPJ)KTYPE,NFILL,NFILL,ISUMJ SMIN0950
C ***SMIN0960
C
C 200 SMIN0970
C COMPUTE SI MINUS SJ. SMIN0980
C
C THE SI MINUS SJ SEGMENT OPERATES AS IF THREE DO SMIN0990
C LOOPS SMIN1000
C DO I = 1, ISCNTI FOR SI. SMIN1010
C DO J = 1, ISCNTJ FOR SJ. SMIN1020
C DO K = 1, ISCNTK FOR SI-SJ. SMIN1030
C WERE BEING INCREMENTED SIMULTANEOUSLY. SMIN1040
C
C INITIALIZE 'DO LOOP' INDICES. SMIN1050
200 J=1 SMIN1060
J=1 SMIN1070
K=0 SMIN1080
SMIN1090
SMIN1100
SMIN1110
SMIN1120
SMIN1130

C 210 SMIN1140
C IS SI ROW = SJ ROW? SMIN1150
C 210 IF(ISNI(I).NE.ISNJ(J)) GO TO 300 SMIN1160
C YES. SMIN1170
C COMPUTE ROW DIFFERENCE SMIN1180
C KDIF=ISVEC(I)-ISVEC(J) SMIN1190
C IS DIFFERENCE NON-ZERO? SMIN1200
C A DIFFERENCE VALUE OF ZERO WILL NOT BE STORED IN SMIN1210
C THE OUTPUT S VECTOR. SMIN1220
C IF(KDIF.EQ.0) GO TO 230 SMIN1230
C YES SMIN1240
C DIFFERENCE IS NON-ZERO. STORE IN OUTPUT S. SMIN1250
C UPDATE K SMIN1260
C K=K+1 SMIN1270
C ISNK(K)=ISNI(I) SMIN1280
C STORE DIF VALUE IN ISVECK(K) SMIN1290
C ISVECK(K)=KDIF SMIN1300
C 230 SMIN1310
C UPDATE I AND J. SMIN1320
C IS I UPDATE POSSIBLE? SMIN1330
C 230 IF(I.EQ.ISCNTI) GO TO 240 SMIN1340
C YES SMIN1350
C UPDATE I SMIN1360
C I=I+1 SMIN1370
C IS J UPDATE POSSIBLE? SMIN1380
C IF(J.EQ.ISCNTJ) GO TO 270 SMIN1390
C YES SMIN1400
C UPDATE J SMIN1410
C J=J+1 SMIN1420
C GO TO ROW NUMBER COMPARE. SMIN1430
C GO TO 210 SMIN1440
C
C 240 SMIN1450
C NO SMIN1460
C IS I UPDATE IS NOT POSSIBLE. SMIN1470
C IS J UPDATE POSSIBLE? SMIN1480
C 240 IF(J.EQ.ISCNTJ) GO TO 400 SMIN1490
C YES SMIN1500
C UPDATE J. SMIN1510
C J=J+1 SMIN1520
C 250 SMIN1530
C ELEMENTS REMAIN IN J ONLY. SMIN1540
C PLACE REMAINING J ROWS AND NEG VALUE OF ELEMENTS SMIN1550
C IN OUTPUT S. SMIN1560
C 250 DO 260 N=J,ISCNTJ SMIN1570
C IF(ISVECJ(N).EQ.0) GO TO 260 SMIN1580
C K=K+1 SMIN1590
C ISNK(K)=ISNJ(N)
C ISVECK(K)=-ISVECJ(N)
C 260 CONTINUE SMIN1600
C GO TO WRITE OUTPUT. SMIN1610
C GO TO 400 SMIN1620
C 270 SMIN1630
C ELEMENTS REMAIN IN I ONLY. SMIN1640
C PLACE REMAINING I ROWS AND VALUES IN OUTPUT S. SMIN1650
C SMIN1660
C SMIN1670
C SMIN1680
C SMIN1690
C SMIN1700

```
270 DO 280 N=I,ISCNTI          SMIN1710
    IF(ISVECI(N).EQ.0) GO TO 280  SMIN1720
    K=K+1                         SMIN1730
    ISNK(K)=ISNI(N)               SMIN1740
    ISVECK(K)=ISVECI(N)           SMIN1750
280 CONTINUE                     SMIN1760
C                                GO TO WRITE OUTPUT.  SMIN1770
    GO TO 400                      SMIN1780
C                                300                         SMIN1790
C                                UNMATCHING ROWS.        SMIN1800
C                                IS SI ROW GT SJ ROW?  SMIN1810
300 IF(ISNI(I).GT.ISNJ(J)) GO TO 340  SMIN1820
C                                NO                          SMIN1830
C                                SI ROW NUMBER IS LESS THAN SJ ROW NUMBER.  SMIN1840
C                                IS SI ROW VALUE EQUAL ZERO?  SMIN1850
    IF(ISVECI(I).EQ.0) GO TO 320  SMIN1860
C                                NO                          SMIN1870
C                                PLACE SI ROW AND VALUE IN OUTPUT S.  SMIN1880
    K=K+1                         SMIN1890
    ISNK(K)=ISNI(I)               SMIN1900
    ISVECK(K)=ISVFC(I)            SMIN1910
C                                320                         SMIN1920
C                                IS I UPDATE POSSIBLE?  SMIN1930
C                                NO. GO TO PROCESS REMAINING SJ ELEMENTS.  SMIN1940
320 IF(I.EQ.ISCNTI) GO TO 250  SMIN1950
C                                YES                         SMIN1960
C                                UPDATE I.          SMIN1970
    I=I+1                         SMIN1980
C                                GO TO ROW NUMBER COMPARE.  SMIN1990
    GO TO 210                      SMIN2000
C
C                                340                         SMIN2010
C                                SJ ROW NUMBER IS LESS THAN SI ROW NUMBER.  SMIN2020
C                                ADD J ELEMENT TO OUTPUT.  SMIN2030
C                                IS SJ ROW VALUE EQUAL ZERO?  SMIN2040
340 IF(ISVECJ(J).EQ.0) GO TO 350  SMIN2050
C                                NO                          SMIN2060
C                                PLACE SJ ROW AND NEG. VALUE IN OUTPUT S.  SMIN2070
    K=K+1                         SMIN2080
    ISNK(K)=ISNJ(J)               SMIN2090
    ISVECK(K)=-ISVECJ(J)          SMIN2100
C                                350                         SMIN2110
C                                IS J UPDATE POSSIBLE?  SMIN2120
C                                NO. GO TO PROCESS REMAINING SI ELEMENTS.  SMIN2130
350 IF(J.EQ.ISCNTJ) GO TO 270  SMIN2140
C                                YES                         SMIN2150
C                                UPDATE J.          SMIN2160
    J=J+1                         SMIN2170
C                                GO TO ROW NUMBER COMPARE.  SMIN2180
    GO TO 210                      SMIN2190
C
C                                400                         SMIN2200
C                                WRITE OUTPUT.        SMIN2210
C                                READ NAME FOR OUTPUT S.  SMIN2220
400 READ 401,NAMEK             SMIN2230
                                SMIN2240
                                SMIN2250
                                SMIN2260
                                SMIN2270
```

C DOES THE OUTPUT S CONTAIN ANY ENTRIES? SMIN2280
C IF(K.EQ.0) GO TO 440 SMIN2290
C YES SMIN2300
C CREATE NEW LABEL. SMIN2310
C NL=NLI+NLJ+30 SMIN2320
C WRITE(KOUTS)KSBE,NAMEK,NL,(LABELI(N),N=1,NLI),NULABL,
1 (LABELJ(N),N=1,NLJ) SMIN2330
C WRITE(KOUTS)KSDAT,NFILL,K,(ISNK(N),N=1,K),(ISVECK(N),N=1,K)
C ISUMK=ISUMI-ISUMJ SMIN2340
C RESET FILLER VARIABLE. IT MUST EQUAL ONE IN END
C OF ARRAY LABEL. SMIN2350
C NFILL=1 SMIN2360
C WRITE(KOUTS)KSEND, NFILL, NFILL, ISUMK,NFILL SMIN2370
C UPDATE NUMBER OF OUTPUT FILES. SMIN2380
C NFILES=NFILES+1 SMIN2390
C GO TO 450 SMIN2400
C 440 SMIN2410
C PRINT MESSAGE THAT SI AND SJ ARE IDENTICAL AND
C NO OUTPUT S BEING WRITTEN. SMIN2420
C 440 PRINT 445,NAMEI,NAMEJ,NAMEK SMIN2430
C 445 FORMAT(IX,6A4,26H IS AN EXACT DUPLICATE OF ,6A4/35H NO OUTPUT S IS
C 1S BEING WRITTEN FOR ,6A4) SMIN2440
C 450 SMIN2450
C MOVE CURRENT SI AND SJ IDENTITY TO PREVIOUS SI
C AND SJ IDENTITY. SMIN2460
C 450 DO 455 N=1,6 SMIN2470
C NOLDI(N)=NAMEI(N) SMIN2480
C 455 NOLDJ(N)=NAMEJ(N) SMIN2490
C GO TO READ A CONTROL CARD. SMIN2500
C GO TO 30 SMIN2510
C 500 SMIN2520
C END OF S-S RUN. SMIN2530
C UPDATE NUMBER OF OUTPUT FILES AND WRITE END
C LABEL. SMIN2540
C 500 KNEXT=40 SMIN2550
C NFILES=NFILES+1 SMIN2560
C SET NAME FIELD BLANK FOR END OF FILE LABEL. SMIN2570
C DO 505 I=1,6 SMIN2580
C 505 NAMEI(I)=KBLANK SMIN2590
C WRITE(KOUTS)KNEXT,NAMEI,NFILL,NFILES SMIN2600
C REWIND OUTPUT TAPE. SMIN2610
C REWIND KOUTS SMIN2620
C RETURN SMIN2630
C RETURN SMIN2640
C 10 FORMAT(I6,6A4,I6,6A4) SMIN2650
C 401 FORMAT(6X,6A4) SMIN2660
C REFERENCE LIST. SMIN2670
C SUBROUTINE ARGUMENTS. SMIN2680
C ISNI - ARRAY FOR THE LIST OF STATE NUMBERS IN S VECTOR I.
C ISVECI - ARRAY FOR THE ELEMENTS IN S VECTOR I. SMIN2690
C SMIN2700
C SMIN2710
C SMIN2720
C SMIN2730
C SMIN2740
C SMIN2750
C SMIN2760
C SMIN2770
C SMIN2780
C SMIN2790
C SMIN2800
C SMIN2810
C SMIN2820
C SMIN2830
C SMIN2840

C	LABELI - ARRAY FOR LABEL OF S VECTOR I.	SMIN2850
C	ISNJ - ARRAY FOR THE LIST OF STATE NUMBERS IN S VECTOR J.	SMIN2860
C	ISVECJ - ARRAY FOR THE ELEMENTS IN S VECTOR J.	SMIN2870
C	LABELJ - ARRAY FOR LABEL OF S VECTOR J.	SMIN2880
C	ISNK - ARRAY FOR THE LIST OF NON-ZERO STATE NUMBERS IN S VECTOR K.	SMIN2890
C	ISVECK - ARRAY FOR THE NON-ZERO ELEMENTS IN S VECTOR K.	SMIN2900
C	OTHER VARIABLES.	
C	NAMEI - ARRAY FOR THE NAME OF CURRENT S VECTOR I.	SMIN2950
C	NAMEJ - ARRAY FOR THE NAME OF CURRENT S VECTOR J.	SMIN2960
C	NAMEK - ARRAY FOR THE NAME OF CURRENT S VECTOR K.	SMIN2970
C	NOLDI - ARRAY FOR THE NAME OF PREVIOUS S VECTOR I.	SMIN2980
C	NOLDJ - ARRAY FOR THE NAME OF PREVIOUS S VECTOR J.	SMIN2990
C	NULABL - ARRAY FOR S MINUS ADDITION TO LABEL FOR S VECTOR K.	SMIN3000
C	END	SMIN3010

```

C SUBROUTINE SPAIRS(KS) SPAIR010
C
C           SPAIRS SPAIR020
C           THIS PROGRAM WILL WRITE A STATE-PAIR RECORD FOR SPAIR030
C           EACH PAIR OF CONSECUTIVE TIME PERIODS IN EACH SPAIR040
C           STATE PATTERN RECORD. THE OUTPUT-MODEL-NUMBER SPAIR050
C           WILL BE THE INPUT-MODEL-NUMBER PLUS THE TIME SPAIR060
C           PERIOD PAIR NUMBER. SPAIR070
C           SPAIR080
C           SPAIR090
C           SPAIR100
C DIMENSION KS(1) SPAIR110
C
C           READ INPUT UNIT ID, OUTPUT UNIT ID, AND NUMBER SPAIR120
C           OF STATES PER RECORD. SPAIR130
C           READ 10,KINP,KOUT,NS SPAIR140
C 10 FORMAT(3I6) SPAIR150
C           REWIND INPUT AND OUTPUT UNITS. SPAIR160
C           REWIND KINP SPAIR170
C           REWIND KOUT SPAIR180
C           SET NUMBER OF PAIRS EQUAL NUMBER OF STATES PER SPAIR190
C           RECORD MINUS 1. SPAIR200
C           NPR=NS-1 ***SPAIR210
C
C           READ A RECORD *SPAIR220
C           READ MODEL NUMBER, STATE PATTERN AND FREQUENCY. SPAIR230
C 30 READ(KINP,END=100) MOD,(KS(I),I=1,NS),KFREQ SPAIR240
C
C           WRITE OUTPUT RECORDS SPAIR250
C           DO K=1 THRU NUMBER OF PAIRS. **SPAIR260
C           SET NEW MODEL NUMBER EQUAL INPUT MODEL NUMBER SPAIR270
C           PLUS PAIR NUMBER. SPAIR280
C           NUMOD=MOD+K SPAIR290
C           WRITE OUTPUT: NEW MODEL NUMBER, STATE NUMBER(K), SPAIR310
C           STATE NUMBER(K+1), AND FREQUENCY. SPAIR320
C           WRITE(KOUT)NUMOD,KS(K),KS(K+1),KFREQ SPAIR330
C           CONTINUE SPAIR340
C 40 CONTINUE SPAIR350
C
C           GO TO READ NEXT RECORD. SPAIR360
C           GO TO 30 SPAIR370
C
C           END OF FILE ON READ. SPAIR380
C           REWIND INPUT AND OUTPUT UNITS. *SPAIR390
C
C 100 REWIND KINP **SPAIR400
C           REWIND KOUT SPAIR410
C           PRINT MESSAGE SPAIRS OPERATION COMPLETE. SPAIR420
C           PRINT 110,KINP,KOUT SPAIR430
C 110 FORMAT(/42H SPAIRS OPERATION COMPLETE FOR INPUT UNIT ,I6,5X, *SPAIR440
C           1     13H OUTPUT UNIT ,I6) ***SPAIR450
C           RETURN SPAIR460
C           RETURN SPAIR470
C           PRINT MESSAGE SPAIRS OPERATION COMPLETE. SPAIR480
C           PRINT 110,KINP,KOUT SPAIR490
C 110 FORMAT(/42H SPAIRS OPERATION COMPLETE FOR INPUT UNIT ,I6,5X, SPAIR500
C           1     13H OUTPUT UNIT ,I6) SPAIR510
C           RETURN SPAIR520
C           RETURN SPAIR530
C           RETURN SPAIR540
C           RETURN SPAIR550
C           RETURN SPAIR560

```

-140-

C	REFERENCE LIST.	SPAIR570
C	SUBROUTINE ARGUME .;S.	SPAIR580
C	KS - ARRAY FOR STATE NUMBER PATTERN.	SPAIR590
C	OTHFR VARIABLES.	SPAIR600
C	KINP - INPUT UNIT ID.	SPAIR610
C	KOUT - OUTPUT UNIT ID.	SPAIR620
C	NS - NUMBER OF STATE NUMBERS PER INPUT RECORD.	SPAIR630
C	END	SPAIR640
		SPAIR650
		SPAIR660
		SPAIR670

```

SUBROUTINE STDES(NAMEV,NAMEC,NCODE,LOC,ICODE,LIST) STDE0010
      STDES STDE0020
      GENERAL PURPOSE PROGRAM TO LIST FOR EACH STATE STDE0030
      NUMBER THE CODE MEANING FOR EACH VARIABLE. STDE0040
STDE0050
DIMENSION NAMEV(3*NV),NAMEC(SUM OF NCODE(I)*3),NCODE(NV),LOC(NV+1) STDE0070
      ICODE(NV),LIST(3*NV) STDE0080
DIMENSION NAMEV(1),NAMEC(1),NCODE(1),LOC(1),ICODE(1),LIST(1) STDE0090
DIMENSION IDMODL(30) STDE0100
      READ PRINT HEADING. STDE0110
READ 10, IDMODL STDE0120
      READ NUMBER OF VARIABLES AND NUMBER OF DESCRIPT- STDE0130
      TION LISTS TO BE PRINTED. STDE0140
READ 20,NV,NCOPYS STDE0150
      COMPUTE NV3 FOR LATER DO LOOP INDEX USE. STDE0160
NV3=NV*3 STDE0170
      COMPUTE NUMBER OF LINES REQUIRED PER STATE NUM- STDE0180
      BER DESCRIPTION. STDE0190
NLINES=(NV-1)/7+1 STDE0200
      IF THE NUMBER OF VARIABLES IS EXACTLY 7, THERE STDE0202
      WILL BE AN EXTRA SPACE AFTER EACH LINE. STDE0204
IF(NV.EQ.7) NLINES=NLINES+1 STDE0206
      COMPUTE NUMBER OF STATE NUMBER DESCRIPTIONS PER STDE0210
      PAGE. STDE0220
NDPAGE=(57/NLINES)-1 STDE0230
      ***STDE0240
      *STDE0250
FOR EACH VARIABLE.. STDE0260
      READ ALPHA ID OF VARIABLE AND NUMBER OF CODES. STDE0270
      STORE IN ARRAY 'LOC' THE BEGINNING LOCATION IN STDE0280
      NAME OF CODES ARRAY OF THE CODE NAMES FOR THE STDE0290
      FIRST VARIABLE. STDE0300
STDE0310
LOC(1)=1 STDE0320
      DO FOR EACH VARIABLE. STDE0330
DO 90 I=1,NV STDE0340
      COMPUTE SUBSCRIPTS FOR ITH VARIABLE IN NAME OF STDE0350
      VARIABLE VECTOR. STDE0360
IFR=(I-1)*3+1 STDE0370
IT0=IFR+2 STDE0380
      READ VARIABLE NUMBER, VARIABLE NAME AND NUMBER STDE0390
      OF CODES DEFINED FOR THIS VARIABLE. STDE0400
READ 30,INV,(NAMEV(II),II=IFR,IT0),NCODE(I) STDE0410
      IS THE VARIABLE NUMBER READ EQUAL THE DO LOOP STDE0420
      VARIABLE NUMBER? STDE0430
      NO, GO TO PRINT ERROR MESSAGE. STDE0440
IF(INV.NE.I) GO TO 300 STDE0450
      YES STDE0460
NCI=NCODE(I) STDE0470
      STORE IN ARRAY 'LOC' THE BEGINNING LOCATION IN STDE0480
      NAME OF CODES ARRAY OF THE CODE NAMES FOR THE STDE0490
      NEXT VARIABLE. STDE0500
LOC(I+1)=LOC(I)+NCI*3 STDE0510
      INITIALIZE SUBSCRIPT FOR READING I'TH VARIABLE STDE0520
      CODE NAMES. STDE0530

```

```
JFR=LOC(I)-3 STDE0540
C DO 80 J=1,NCI DO FOR EACH CODE FOR THIS VARIABLE. STDE0550
C JFR=JFR+3 COMPUTE SUBSCRIPTS FOR NAME OF CODE VECTOR. STDE0560
C JTO=JFR+2
C READ CODE NUMBER AND NAME. STDE0570
C READ 30,INC.(NAMEC(JJ),JJ=JFR,JTO) IS THE CODE NUMBER READ EQUAL TO DO LOOP CODE STDE0580
C NUMBER? STDE0590
C NO. GO TO PRINT ERROR MESSAGE. STDE0600
C IF(INC.NE.J) GO TO 310 STDE0610
C YES STDE0620
C 80 CONTINUE STDE0630
C CONTINUE STDE0640
C 80 CONTINUE STDE0650
C INITIALIZE THE PRINT ARRAY FOR THIS VARIABLE BY STDE0660
C STORING THE NAME FOR ITS FIRST CODE. STDE0670
C L=LOC(I) STDE0680
C LIST(IFR)=NAMEC(L) STDE0690
C LIST(IFR+1)=NAMEC(L+1) STDE0700
C LIST(IFR+2)=NAMEC(L+2) STDE0710
C 90 CONTINUE STDE0720
C *STDE0730
C ***STDE0740
C INITIALIZATION OF THE PRINT ARRAY - NUMBER OF CODE VALUE STDE0750
C BEING PRINTED-TO 1 FOR EACH VARIABLE, STDE0760
C 93 DO 95 I=1,NV STDE0770
C 95 ICODE(I)=1 STDE0780
C NS=0 *STDE0790
C INITIALIZE CURRENT STATE NUMBER. STDE0800
C STDE0810
C THE NUMBER OF DESCRIPTIONS CURRENTLY ON THE PAGE STDE0820
C IS INITIALLY SET TO THE MAXIMUM VALUE SO THAT STDE0830
C THE INITIAL BRANCH WILL BE TO THE HEADING PRINT. STDE0840
C NDCUR=NOPAGE STDE0850
C IS THERE SPACE ON THE CURRENT PAGE FOR A STATE STDE0860
C NUMBER DESCRIPTION? STDE0870
C 100 IF(NDCUR.LT.NOPAGE) GO TO 120 STDE0880
C NO STDE0890
C RESET NUMBER OF DESCRIPTIONS ON CURRENT PAGE. STDE0900
C NDCUR=0 STDE0910
C SKIP TO NEW PAGE. PRINT ONE LINE HEADING. PRINT STDE0920
C VARIABLE NAMES. STDE0930
C PRINT 97,IMODDL STDE0940
C PRINT 110,(NAMEV(I)),II=1,NV3) STDE0950
C PRINT 112 STDE0960
C 120 NDCUR=NDCUR+1 STDE0970
C INCREMENT CURRENT STATE NUMBER BY 1. STDE0980
C ADD ONE TO NUMBER OF DESCRIPTIONS ON THE CURRENT STDE0990
C PAGE. STDE1000
C NDCUR=NDCUR+1 STDE1010
C PRINT STATE NUMBER AND ITS DESCRIPTION. STDE1020
C PRINT 130,NS,(LIST(I)),II=1,NV3) STDE1030
C STDE1040
C STDE1050
C STDE1060
C STDE1070
C STDE1080
C STDE1090
C STDE1100
```

C UPDATE CODE LIST SUBSCRIPTS AND PRINT ARRAY. STDE
C THIS PROGRAM SEGMENT IS CONCEPTUALLY A SET OF STDE
C NESTED DO'S WHERE THE NUMBER OF DO'S IS VARI- STDE
C ABLE. STDE
C N WILL GO FROM NV TO 1. AT ANY GIVEN TIME N IS STDE
C THE NUMBER OF THE DO LOOP WHOSE INDEX IS BEING STDE
C TESTED AND STEPPED. STDE
C DO FOR EACH VARIABLE. STDE
C DO 160 I=1,NV COMPUTE MISC SUBSCRIPTS (N WILL GO FROM NV TO 1) STDE
C N=NV-I+1 L2 IS THE LOCATION IN THE PRINT LINE ARRAY FOR STDE
C L2=(N-1)*3+1 THE NAME OF THE CODE OF THE NTH VARIABLE. STDE
C CAN THE INDEX VALUE FOR THE NTH DO BE INCRE- STDE
C MENTED FURTHER? STDE
C IF(ICODE(N).EQ.NCODE(N)) GO TO 150 STDE
C YES STDE
C INCREMENT NTH DO INDEX VALUE. STDE
C ICODE(N)=ICODE(N)+1 L IS THE LOCATION IN THE CODE NAME ARRAY OF THE STDE
C FIRST WORD OF THE CURRENT CODE OF THE NTH STDE
C VARIABLE. STDE
C L=LOC(N)+(ICODE(N)-1)*3 PLACE NAME FOR CODE NOW INDEXED IN PRINT ARRAY. STDE
C LIST(L2) =NAMEC(L) STDE
C LIST(L2+1)=NAMEC(L+1) STDE
C LIST(L2+2)=NAMEC(L+2) STDE
C GO TO 100 GO TO PRINT DESCRIPTION CURRENTLY IN 'LIST'. STDE
C NO STDE
C INDEX VALUE FOR NTH DO CANNOT BE INCREMENTED STDE
C FURTHER. STDE
C RESET THE NTH DO INDEX TO 1. STDE
C 150 ICODE(N)=1 L IS THE LOCATION IN THE CODE NAME ARRAY OF THE STDE
C FIRST WORD OF THE FIRST CODE OF THE NTH STDE
C VARIABLE. STDE
C L=LOC(N) PLACE NAME FOR FIRST CODE FOR NTH VARIABLE IN STDE
C PRINT ARRAY. STDE
C LIST(L2) =NAMEC(L) STDE
C LIST(L2+1)=NAMEC(L+1) STDE
C LIST(L2+2)=NAMEC(L+2) STDE
C 160 CONTINUE 160 STDE
C ALL DO LOOPS ARE COMPLETE. STDE
C ALL STATES LISTED. STDE
C HAVE ALL COPIES BEEN PRINTED? STDE
C IF(NCOPY.S.LE.1) GO TO 169 STDE
C NO DECREASE NUMBER OF COPIES TO BE PRINTED BY 1. STDE
C NCOPYS=NCOPYS-1 STDE
C GO TO 93 STDE

C	169	STDE1680
C	YES	STDE1690
C	ALL COPY'S LISTED	STDE1700
C	SKIP TO NEW PAGE.	STDE1710
169 PRINT 170		STDE1720
C	RETURN	STDE1730
C		STDE1740
C		STDE1750
C	300	STDE1760
C	ERROR IN CARD ENTRY FOR VARIABLE NUMBER.	STDE1770
C	PRINT ERROR MESSAGE.	STDE1780
300 PRINT 305,I,INV		STDE1790
C	STOP	STDE1800
C		STDE1810
C	310	STDE1820
C	ERROR IN CARD ENTRY FOR CODE NUMBER.	STDE1830
C	PRINT ERROR MESSAGE.	STDE1840
310 PRINT 305,I,INV,J,INC		STDE1850
C	STOP	STDE1860
C		STDE1870
C	10 FORMAT(20A4/10A4)	STDE1880
20 FORMAT(2I6)		STDE1890
30 FORMAT(I6,3A4,I6)		STDE1900
97 FORMAT(1H1,30A4/)		STDE1910
110 FORMAT(13H STATE NUMBER,7(4X,3A4)/ (13X,7(4X,3A4)))		STDE1920
112 FORMAT(1H)		STDE1930
130 FORMAT(1X,I12,7(4X,3A4)/ (13X,7(4X,3A4)))		STDE1940
170 FORMAT(1H1)		STDE1950
305 FORMAT(38H ERROR IN STATE DESCRIPTION DATA CARDS,4I6)		STDE1960
C	REFERENCE LIST.	STDE1970
C		STDE1980
C	SUBROUTINE ARGUMENTS.	STDE1990
C		STDE2000
C	NAMEV(3*NV) - ARRAY OF VARIABLE NAMES. EACH NAME WILL BE READ AND	STDE2010
C	PRINTED WITH A 3A4 FORMAT.	STDE2020
C	NAMEC(3*SUM OF NCODE(I)) - ARRAY OF CODE NAMES. EACH NAME WILL BE	STDE2030
C	READ AND PRINTED WITH A 3A4 FORMAT.	STDE2040
C	NCODE(NV) - ARRAY CONTAINING NUMBER OF CODES DEFINED FOR EACH	STDE2050
C	VARIABLE.	STDE2060
C	LOC(NV+1) - BEGINNING LOCATION IN NAMEC VECTOR OF CODE NAMES FOR	STDE2070
C	EACH VARIABLE.	STDE2080
C	ICODE(NV) - CURRENT CODE VALUE BEING PRINTED FOR EACH VARIABLE.	STDE2090
C	LIST(3*NV) - THE ARRAY IN WHICH EACH STATE NUMBER DESCRIPTION IS	STDE2100
C	PLACED FOR PRINTING.	STDE2110
C	OTHER VARIABLES.	STDE2120
C		STDE2130
C	NV - NUMBER OF VARIABLES IN STATE NUMBER DEFINITION.	STDE2140
C	NS - NUMBER OF STATE WHOSE DESCRIPTION IS CURRENTLY BEING	STDE2150
C	PRINTED.	STDE2160
C	NLINES - NUMBER PRINT LINES REQUIRED PER DESCRIPTION.	STDE2170
C	NDPAGE - NUMBER OF DESCRIPTIONS THAT CAN BE PRINTED PER PAGE.	STDE2180
C	NDCUR - NUMBER OF DESCRIPTIONS CURRENTLY PRINTED ON THE PAGE.	STDE2190
C	END	STDE2200
C		STDE2210
C		STDE2220
C		STDE2230

SUBROUTINE STSORT(KSORT,KI,KJ,KS) STS00010
C STS00020
C THIS IS A CORE SORT TO BE USED FOR STS00030
C (1) ORIGINAL STATE PATTERN SORT STS00040
C (2) CLLAPS OUTPUT SORT STS00050
C WHEN THE NUMBER OF UNIQUE OUTPUT PATTERNS PLUS STS00060
C THEIR FREQUENCIES WILL FIT IN CORE. STS00070
C THIS OPERATION MAY BE USED WHEN THE SORT OUTPUT STS00080
C WILL FIT IN CORE REGARDLESS OF THE NUMBER OF STS00090
C INPUT RECORDS. BUT THE NUMBER OF INPUT RECORDS STS00100
C IS A CRITICAL FACTOR IN DETERMINING CPU TIME STS00110
C SINCE THIS SORT IS NOT SOPHISTICATED. STS00120
C EACH UNIQUE PATTERN IS STORED AS A COLUMN SINCE STS00130
C FORTRAN STORES ARRAYS BY COLUMN. THEREFORE THE STS00140
C 'PUSHDOWN' OPERATION WILL OPERATE ON CONSECUTIVE STS00150
C LOCATIONS. STS00160
C
C DIMENSION KSORT(KI,KJ),KS(1) STS00170
C READ 10,KOUT READ OUTPUT UNIT ID STS00180
C 10 FORMAT(4I6) STS00190
C C REWIND KI'UT REWIND OUTPUT UNIT. STS00200
C C READ INPUT UNIT ID, MODEL NUMBER, NUMBER OF STS00210
C WORDS IN INPUT RECORD, TYPE OF INPUT SWITCH. STS00220
C C 20 READ 10,KINP,MODL,NS,NSW READ INPUT UNIT ID, MODEL NUMBER, NUMBER OF STS00230
C HAVE ALL INPUT FILES BEEN PROCESSED? STS00240
C C IF(KINP.NE.0) GO TO 30 STS00250
C YES STS00260
C C REWIND KOUT REWIND OUTPUT UNIT. STS00270
C RETURN STS00280
C C 30 REWIND KINP RETURN STS00290
C READ(KINP,END=300)(KS(I),I=1,NS) STS00300
C NO EOF STS00310
C STORE KS AS FIRST COLUMN RECORD IN KSORT. STS00320
C C DD 40 I=1,NS STS00330
C 40 KSORT(I,1)=KS(I) STS00340
C C INITIALIZE COUNTERS AND CONTROL VARIABLES. STS00350
C C INITIALIZE NUMBER OF ENTRIES IN SORT ARRAY, AND STS00360
C NUMBER OF RECORDS READ. STS00370
C LAST=1 STS00380
C NCASES=1 STS00390
C IF THE FILE BEING SORTED DOES NOT HAVE A FREQ- STS00400
C UENCY WORD, STORE A 1 IN THE NSWTH WORD. STS00410
C C IF(NSW.NE.0) KSORT(NSW,1)=1 SET NSTO EQUAL THE NUMBER OF WORDS IN THE SORT STS00420
C C FIELD. THIS WILL BE THE TOTAL INPUT RECORD IF STS00430
C THE INPUT RECORD CONTAINS STATE NUMBERS ONLY. STS00440
C STS00450
C STS00460
C STS00470
C STS00480
C STS00490
C STS00500
C STS00510
C STS00520
C STS00530
C STS00540
C STS00550
C STS00560

```
NSTO=NS STS00570
C THE SORT FIELD WILL BE THE MODEL NUMBER AND THE STS00580
C STATE PATTERN BUT NOT THE FREQUENCY IF COLLAPSEDSTS00590
C OUTPUT IS BEING SORTED. STS00600
C IF(NSW.EQ.0) NSTO=NSTO-1 STS00610
C READ FOR DATA RECORD 2 PLUS ALL OTHER RECORDS. STS00620
C READ A DATA RECORD FROM KINP INTO KS. STS00640
50 READ(KINP,END=250) (KS(I),I=1,NS) STS00650
C NO EOF STS00660
C ADD 1 TO NUMBER OF RECORDS READ. STS00670
NCASES=NCASES+1 STS00680
C ***STS00690
C FILE KS INTO KSORT. *STS00700
C DO FOR EACH PATTERN IN THE SORT ARRAY. STS00710
C DO 150 I=1, LAST STS00720
C DO FOR EACH WORD IN THE SORT FIELD. STS00730
C DO 100 J=1, NSTO STS00740
C IS PATTERN ALREADY STORED IN CORE. STS00750
C IF(KS(J).LT.KSORT(J,I)) GO TO 190 STS00760
C IF(KS(J).GT.KSORT(J,I)) GO TO 150 STS00770
C 100 STS00780
C CONTINUE STS00790
100 CONTINUE STS00800
C YES STS00810
C MATCH IF FALLS THRU THIS CONTINUE. STS00820
C UPDATE FREQUENCY WORD. STS00830
C IF(NSW.EQ.0) KSORT(NS,I)=KSORT(NS,I)+KS(NS) STS00840
C IF(NSW.NE.0) KSORT(NSW,I)=KSORT(NSW,I)+1 STS00850
C GO TO READ NEXT RECORD. STS00860
C GO TO 50 STS00870
C 150 STS00880
C CONTINUE FOR DO EACH PATTERN LOOP. STS00890
150 CONTINUE STS00900
C NO MATCH AND PATTERN HAS GREATER VALUE THAN ANY STS00910
C IN ARRAY. ADD TO ARRAY. STS00920
C ADD 1 TO COUNT OF UNIQUE PATTERNS. STS00930
LAST=LAST+1 STS00940
C DOES NUMBER OF PATTERNS EXCEED SORT ARRAY DIM- STS00950
C ENSION. STS00960
C YES. GO TO PRINT ERROR MESSAGE. STS00970
C IF(LAST.GT.KJ) GO TO 350 STS00980
C NO STS00990
C MOVE KS TO COLUMN LAST OF KSORT. STS01000
C DO 170 J=1,NS STS01010
170 KSORT(J,LAST)=KS(J) STS01020
C IF THIS IS AN ORIG PATTERN TAPE ADD A FREQ WORD STS01030
C WITH THE VALUE OF 1. STS01040
C IF(NSW.NE.0) KSORT(NSW,LAST)=1 STS01050
C GO TO READ NEXT RECORD. STS01060
C GO TO 50 STS01070
C 190 STS01080
C NO MATCH. ADD PATTERN AT ITH POSITION IN SORT STS01090
C ARRAY. STS01100
C STS01110
C STS01120
C STS01130
```

C WITH ADDITION OF THIS ELEMENT, WILL NUMBER OF STS01140
C PATTERNS EXCEED SORT ARRAY DIMENSION? STS01150
C YES, GO TO PRINT ERROR MESSAGE. STS01160
C 190 IF(LAST+1.GT.KJ) GO TO 350 STS01170
C NO STS01180
C PUSH DOWN ENTRIES IN SORT ARRAY. STS01190
C CALL TMT2(KSORT(1,I),KSORT(1,I+1),(LAST-I+1)*KI) STS01200
C MOVE KS TO COLUMN I OF KSORT. STS01210
C DO 200 J=1,NS STS01220
200 KSCRT(J,I)=KS(J) STS01230
C IF THIS IS AN ORIG PATTERN TAPE ADD A FREQ WORD STS01240
C WITH THE VALUE OF 1. STS01250
C IF(NSW.NE.0) KSORT(NSW,I)=1 STS01260
C ADD 1 TO COUNT OF UNIQUE PATTERNS. STS01270
C LAST=LAST+1 STS01280
C GO TO READ NEXT RECORD. STS01290
C GO TO 50 STS01300
C *STS01310
C ***STS01320
C 250 STS01330
C END OF FILE ON READ. STS01340
C REWIND INPUT UNIT. STS01350
C 250 REWIND KINP STS01360
C PRINT NUMBER OF INPUT RECORDS AND NUMBER OF STS01370
C PATTERNS FOR THIS MODEL. STS01380
C PRINT 260,MODL,NCASES,LAST STS01390
260 FORMAT(23H STS01400
1I12/9X,
2 53H NUMBER OF OUTPUT RECORDS (UNIQUE PATTERNS OR PAIRS) ,I12) STS01410
C BRANCH ON INPUT DATA TYPE. STS01420
C IF(NSW.NE.0) GO TO 400 STS01430
C COLLAPSE INPUT: FOR EACH OF LAST UNIQUE PAT- STS01440
C TERN, WRITE NS WORDS. STS01450
C DO 280 I=1,LAST STS01460
280 WRITE(KOUT)(KSORT(J,I),J=1,NS) STS01470
C GO TO READ NEXT CONTROL CARD. STS01480
C GO TO 20 STS01490
C 400 STS01500
C GENERATE STATE NUMBER INPUT: FOR EACH OF 'LAST' STS01510
C UNIQUE PATTERNS, WRITE MODEL NUMBER AND NSW STS01520
C WORDS. STS01530
400 DO 410 I=1,LAST STS01540
410 WRITE(KOUT)MODL,(KSORT(J,I),J=1,NSW) STS01550
C GO TO READ NEXT CONTROL CARD. STS01560
C GO TO 20 STS01570
C 300 STS01580
C EOF ON FIRST READ. STS01590
C PRINT ERROR MESSAGE - EOF ON FIRST READ STS01600
300 PRINT 310,KINP,MODL STS01610
310 FORMAT(40H STS01620
1.,I6) STS01630
C EXIT STS01640
C STOP STS01650
C 350 STS01660
C DIMENSION PROBLEM. STS01670
C PRINT MESSAGE IN RE NUMBER OF PATTERNS EXCEEDINGSTS01680
C STS01690

C	DIMENSION.	STS01710
350	PRINT 360,KINP,MODL,NCASES	STS01720
360	FORMAT(68H STSORT - NUMBER OF PATTERNS EXCEEDS KJ (COL) DIMENSION.	STS01730
1	INPUT UNIT ,I6,11H MODEL NO. ,I6	STS01740
2/30H	NUMBER OF INPUT RECORDS READ ,I6)	STS01750
C	REWIND INPUT UNIT.	STS01760
C	REWIND KINP	STS01770
C	EXIT	STS01780
C	STOP	STS01790
C	REFERENCE LIST.	STS01800
C	SUBROUTINE ARGUMENTS.	STS01810
C	KSORT - ARRAY CONTAINING PATTERNS AND FREQUENCIES.	STS01820
C	KI - KSORT ROW DIMENSION. ALLOW FOR MAX STATES+MOD NO+FREQ.	STS01830
C	KJ - KSORT COL DIMENSION. ALLOW FOR MAX NUMBER PATTERNS.	STS01840
C	KS - ARRAY FOR READING INPUT.	STS01850
C	OTHER VARIABLES.	STS01860
C	LAST - NUMBER OF ENTRIES IN KSORT ARRAY. NUMBER OF OUTPUT RECS	STS01870
C	MODL - MODEL NUMBER FOR OUTPUT IF ORIGINAL STATE NUMBERS ARE	STS01880
C	BEING SORTED. THIS IS ALSO THE MODEL NUMBER THAT WILL BE	STS01890
C	PRINTED WITH THE I/O COUNTS.	STS01900
C	NCASES - NUMBER OF INPUT RECORDS READ.	STS01910
C	NS - NUMBER WORDS IN INPUT RECORD. THIS WILL BE NUMBER OF	STS01920
C	STATE NUMBERS IF NSW IS NON-ZERO, AND NUMBER OF STATE	STS01930
C	NUMBERS -PER PATTERN- PLUS TWO IF NSW IS ZERO.	STS01940
C	NSTO - THE NUMBER OF WORDS IN THE SORT FIELD.	STS01950
C	NSW - SWITCH INDICATING TYPE OF INPUT.	STS01960
C	NS+1 - UNSORTED ORIGINAL STATE NUMBER RECORDS.	STS01970
C	0 - MOD NUMB, STATE PATTERN, FREQ FROM COLLAPSE RUN.	STS01980
C	END	STS01990

```

C SUBROUTINE SXP(NDIM,ISN,ISVEC,KSN,KSVEC,SVEC,JCOL,P,LABELS,LABELP)SXP 0010
C
C          MULTIPLY S VECTOR TIMES P MATRIX TO OBTAIN           SXP 0020
C          PROJECTED S VECTOR.                                SXP 0030
C
C          IMPLICIT REAL*8(A-H,O-Z,$)                         SXP 0040
C          DIMENSION ISN(1),ISVEC(1),KSN(1),KSVEC(1),SVEC(1),JCOL(1),P(1)    SXP 0050
C          1      ,LABELS(1),LABELP(1)                           SXP 0060
C
C          KSVEC(1) AND SVEC(1) MAY HAVE BEEN EQUIVALENCED SXP 0070
C          IN THE MAIN PROGRAM. NO OTHER EQUIVALENCE RELA- SXP 0080
C          TION OF THE ARRAYS IN THE ARGUMENT LIST IS PER- SXP 0090
C          MITTED.                                         SXP 0100
C
C          DIMENSION NAMES(6),NAMEP(6),NFILL6(6)             SXP 0110
C
C          INITIALIZATION FOR THIS CALL.                   SXP 0120
C          SET RECORD TYPE CONSTANTS.                  SXP 0130
C          S VECTOR BEGINNING LABEL.                 SXP 0140
C
C          KSBEG=2                                     SXP 0150
C          XSDAT=22                                    SXP 0160
C
C          KSEND=32                                    SXP 0170
C
C          KHEXT=40                                    SXP 0180
C          NFILL=1                                     SXP 0190
C
C          DATA KBLANK/4H                            SXP 0200
C          DO 1 I=1,6                               SXP 0210
C
C          1 NFILL6(I)=KBLANK                      SXP 0220
C
C          ARRAY NFILL6 = BLANK.                   SXP 0230
C          /
C
C          SKIP TO NEW PAGE ON PRINTER.        SXP 0240
C
C          PRINT 2                                     SXP 0250
C
C          READ 5,IOUT                                SXP 0260
C          REWIND IOUT                                SXP 0270
C
C          NFILES=0                                    SXP 0280
C
C
C          ***SXP 0290
C
C          10
C          READ AN INPUT SPECIFICATION CONTROL CARD.   SXP 0300
C          READ:
C          NAMES - NAME OF S VECTOR.                SXP 0310
C          INPS - UNIT WHERE S IS LOCATED.       SXP 0320
C          NAMEP - NAME OF P MATRIX.            SXP 0330
C          INPP - UNIT WHERE P IS LOCATED.       SXP 0340
C          NITER - NUMBER ITERATIONS PER S, P PAIR. SXP 0350
C          NPairs - NUMBER 'PAIRED' (S,P) ARRAYS.  SXP 0360
C          NUMP - NUMBER P'S PER S.            SXP 0370
C
C          IODISK - INTERMEDIATE STORAGE DISK.     SXP 0380
C
C          10 READ 20,NAMES,INPS,NAMEP,INPP,NITER,NPAIRS,NUMP,IODISK
C
C          HAS ALL INPUT BEEN PROCESSED?         SXP 0390
C
C          YES. GO TO CLOSE OUTPUT FILE.        SXP 0400
C
C          IF(NITER.EQ.0) GO TO 300
C
C          30
C          NO

```

C PROCESS THE CONTROL CARD JUST READ. SXP 0570
C INITIALIZE ITERATIONS COMPLETED TO ZERO. SXP 0580
C 30 ITER=0 SXP 0590
C LOCATE NAMED S VECTOR. S LABEL IS RETURNED. SXP 0600
C CALL POSINP(INPS,KTYPE,NAMES,NLS,LABELS) SXP 0610
C READ S VECTOR DATA RECORD INTO ISN AND ISVEC. SXP 0620
C 32 READ(INPS)KTYPE,
C 1 NFILL,ISCNT,(ISN(I),I=1,ISCNT),(ISVEC(I),I=1,ISCNT) SXP 0630
C READ INPUT S SUM FROM S END RECORD. SXP 0640
C READ(INPS)KTYPE,NFILL,NFILL,INSUM,NFILL SXP 0650
C PRINT INPUT S NAME AND SUM. SXP 0660
C PRINT 35,NAMES,INSUM SXP 0670
C TEST FOR TYPE POSITIONING REQUIRED FOR P. SXP 0680
C IS THIS AN (S,P) PAIRS SPECIFICATION? SXP 0690
C IF(INPAIRS.GT.0) GO TO 50 SXP 0700
C NO SXP 0710
C LOCATE NAMED P AND RETURN P LABEL. SXP 0720
C CALL POSINP(INPP,KTYPE,NAMEP,NLP,LABELP) SXP 0730
C GO TO 52 SXP 0740
C 50 SXP 0750
C YES SXP 0760
C THIS IS AN (S,P) PAIR SPECIFICATION. SXP 0770
C THE NEXT RECORD WILL BE THE P TO BE PAIRED WITH SXP 0780
C THE S JUST READ. READ THIS P LABEL RECORD. SXP 0790
C 50 READ(INPP)KTYPE,NAMEP,NLP,(LABELP(I),I=1,NLP) SXP 0800
C SXP 0810
C SXP 0820
C 52 SXP 0830
C SKIP P MATRIX ROW LIST RECORD. SXP 0840
C 52 READ(INPP) SXP 0850
C READ P MATRIX LIST OF COLUMNS PRESENT AND INCRE- SXP 0860
C MENT DATA. SXP 0870
C READ(INPP)KTYPE,KSCNT,(KSN(K),K=1,KSCNT),NUMMD,NUMYR SXP 0880
C SXP 0890
C IS NUMBER OF ITERATIONS FOR THIS P EQUAL ONE? SXP 0900
C IF(NITER.EQ.1) GO TO 58 SXP 0910
C NO SXP 0920
C SET WORKING P UNIT EQUAL SEQUENTIAL DISK UNIT. SXP 0930
C INPX=10DISK SXP 0940
C REWIND INPX SXP 0950
C REWIND INPX SXP 0960
C COPY P MATRIX ONTO DISK. SXP 0970
C READ A P DATA RECORD FROM TAPE. SXP 0980
C 56 READ(INPP) KTYPE,KROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) SXP 0990
C WRITE RECORD JUST READ ON DISK. SXP 1000
C WRITE(INPX)KTYPE,KROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) SXP 1010
C WAS THIS A P END RECORD? SXP 1020
C NO. GO TO READ NEXT RECORD. SXP 1030
C IF(KTYPE.NE.33) GO TO 56 SXP 1040
C YES SXP 1050
C REWIND INPX SXP 1060
C GO TO 60 SXP 1070
C 58 SXP 1080
C YES SXP 1090
C THE NUMBER OF ITERATIONS IS ONE. SXP 1100
C THE P MATRIX IS NOT TRANSFERRED TO THE WORK UNITSXP 1120
C SET WORKING P UNIT EQUAL ORIGINAL INPUT UNIT FORSXP 1130

C P. SXP 1140
C 58 INPX=INPP SXP 1150
C C 60 SXP 1160
C SET UP OUTPUT S LABEL AND NAME. SXP 1170
C FIRST. COPY INFO FROM INPUT S AND P MATRIX. SXP 1180
C C 60 NLS2=90 SXP 1190
C IF(NLP.GT.30) NLS2=120 SXP 1200
C CALL TMT(NLS2-60,LABELS(61),LABELP(1)) SXP 1210
C CALL TMT(13,LABELS(31),52H PROJECTED TO MON YEAR BY TRANSITION MSXP 1230
C 1ATRIX) SXP 1240
C CALL TMT(17,LABELS(44),LABELS(43)) SXP 1250
C SECOND. INCREMENT MONTH AND YEAR. PLACE IN SXP 1260
C OUTPUT S NAME AND OUTPUT S LABEL. SXP 1270
C MONTH WILL BE IN LABELS(35). SXP 1280
C YEAR WILL BE IN LABELS(36). SXP 1290
C 65 CALL NUDATE(NAMES(5),NAMES(6),NUMMO,NUMYR) SXP 1300
C LABELS(35)=NAMES(5) SXP 1310
C LABELS(36)=NAMES(6) SXP 1320
C C OUTPUT S LABEL COMPLETE. SXP 1330
C ***SXP 1340
C *SXP 1350
C C S VECTOR - P MATRIX MULTIPLICATION. SXP 1360
C PLACE ZEROS IN OUTPUT S AREA. SXP 1370
C C DO 80 I=1,NDIM SXP 1380
C 80 SVEC(I)=0.0 SXP 1390
C C I = SUBSCRIPT FOR INPUT S, ISN. SXP 1400
C J = SUBSCRIPT FOR P MATRIX ROW, JCOL. SXP 1410
C K = SUBSCRIPT FOR OUTPUT S, KSN. SXP 1420
C C SET I TO 1(SUBSCRIPT FOR INPUT S). SXP 1430
C I=1 SXP 1440
C C 90 SXP 1450
C READ A P RECORD: TYPE, ROW NUMBER, NUMBER OF SXP 1460
C ELEMENTS, COLUMN NUMBERS, COLUMN VALUES. SXP 1470
C C 90 READ(1..PX)KTYPE,KROW,JCNT,(JCOL(J),J=1,JCNT),(P(J),J=1,JCNT) SXP 1480
C HAS THIS A P END LABEL? SXP 1490
C YES, GO TO END OF MULTIPLY SEGMENT. SXP 1500
C C IF(KTYPE.EQ.33) GO TO 150 SXP 1510
C NO SXP 1520
C DOES I'TH STATE NUMBER OF INPUT S EQUAL ROW SXP 1530
C NUMBER OF P RECORD JUST READ? SXP 1540
C C 95 IF(ISN(I).EQ.KROW) GO TO 100 SXP 1550
C NO SXP 1560
C IS I'TH STATE NUMBER OF INPUT S LESS THAN SXP 1570
C CURRENT ROW NUMBER OF P? SXP 1580
C YES, GO TO INCREMENT INDEX FOR INPUT S ELEMENT. SXP 1590
C C IF(ISN(I).LT.KROW) GO TO 125 SXP 1600
C NO SXP 1610
C S STATE NUMBER NOT PRESENT FOR CURRENT P ROW. SXP 1620
C GO TO READ NEXT P RECORD. SXP 1630
C C 100 SXP 1640
C S STATE NUMBER AND ? ROW NUMBER MATCH. SXP 1650
C MULTIPLY SXP 1660
C C SXP 1670
C SXP 1680
C SXP 1690
C SXP 1700

C IS S(I) STATE VALUE .LE.ZERO? SXP 1710
C YES. GO TO INCREMENT INPUT S SUBSCRIPT. SXP 1720
C 100 IF(ISVEC(I).LE.0) GO TO 130 SXP 1730
C NO SXP 1740
C MULTIPLY S(I) VALUE TIMES ELEMENTS OF CURRENT P SXP 1750
C ROW. SXP 1760
C FLOAT S(I) STATE VALUE. SXP 1770
C S=ISVEC(I) SXP 1780
C J=1 SXP 1790
C K=1 SET J=1 (SUBSCRIPT FOR P ROW). SXP 1800
C 110 SET K=1 (SUBSCRIPT FOR OUTPUT S). SXP 1810
C IS J'TH COLUMN NUMBER IN CURRENT P ROW EQUAL SXP 1820
C K'TH ELEMENT NUMBER IN OUTPUT S? SXP 1830
C 110 IF(JCOL(J).NE.KSH(K)) GO TO 120 SXP 1840
C YES SXP 1850
C OUTPUT S VALUE(K) = OUTPUT S VALUE(K) + P VALUE SXP 1860
C (J) * INPUT S VALUE(I). SXP 1870
C SVEC(K)=SVEC(K)+P(J)*S SXP 1880
C HAVE ALL COLUMN ELEMENTS IN THIS ROW OF P MATRIX SXP 1890
C BEEN PROCESSED? SXP 1900
C IF(J.EQ.JCNT) GO TO 130 SXP 1910
C NO SXP 1920
C INCREMENT P AND OUTPUT S SUBSCRIPTS. SXP 1930
C J=J+1 SXP 1940
C K=K+1 SXP 1950
C KSCNT WILL ALWAYS BE GE JCNT. SXP 1960
C GO TO COMPARE P COL AND OUTPUT S ELEMENT NUMBER SXP 1970
C GO TO 110 SXP 1980
C 120 K=K+1 SXP 1990
C GO TO 110 SXP 2000
C 125 SXP 2010
C P ROW NOT PRESENT FOR CURRENT S STATE NUMBER. SXP 2020
C HAVE ALL S(I) ELEMENTS BEEN PROCESSED? SXP 2030
C YES. GO TO END OF ITERATION POSITIONING OF P. SXP 2040
C 125 IF(I.EQ.ISCNT) GO TO 140 SXP 2050
C NO SXP 2060
C ADD 1 TO SUBSCRIPT I. SXP 2070
C I=I+1 SXP 2080
C GO TO COMPARE CURRENT INPUT S STATE NUMBER AND SXP 2090
C P ROW NUMBER. SXP 2100
C GO TO 95 SXP 2110
C 130 SXP 2120

-153-

```

C          PROCESSING COMPLETED FOR A MATCHING S(I) STATE      SXP 2280
C          NUMBER AND P ROW.                                     SXP 2290
C          HAVE ALL S(I) ELEMENTS BEEN PROCESSED?              SXP 2300
C          130 IF(I1.EQ.ISCNT) GO TO 140                      SXP 2310
C          NO                                                 SXP 2320
C          ADD 1 TO INPUT S SUBSCRIPT.                         SXP 2330
C          I=I+1                                              SXP 2340
C          GO TO 90                                           SXP 2350
C          GO TO READ NEXT P ROW RECORD.                     SXP 2360
C          140                                                 SXP 2370
C          YES                                              SXP 2380
C          ALL INPUT S ELEMENTS HAVE BEEN PROCESSED.        SXP 2390
C          IS WORKING P MATRIX ON DISK?                   SXP 2400
C          140 IF(NITER.GT.1) GO TO 150                      SXP 2410
C          NO                                                 SXP 2420
C          READ REMAINING RECORDS FOR THIS P MATRIX.       SXP 2430
C          THIS IS JUST SO TAPE WILL ALWAYS BE POSITIONED   SXP 2440
C          AFTER A P END RECORD AT THE END OF AN ITERATION. SXP 2450
C          DISK WILL BE POSITIONED PROPERLY BY A REWIND.    SXP 2460
C          READ NEXT P RECORD.                            SXP 2470
C          142 READ(INPP)KTYPE                           SXP 2480
C          IS THIS THE END RECORD?                      SXP 2490
C          IF(KTYPE.EQ.33) GO TO 150                      SXP 2500
C          NO                                              SXP 2510
C          GO TO 142                                       SXP 2520
C          GO TO 142                                       SXP 2530
C          150                                                 SXP 2540
C          MULTIPLICATION OF THIS S AND P COMPLETE.       SXP 2550
C          ADD 1 TO ITERATIONS COMPLETED COUNT.         SXP 2560
C          150 ITER=ITER+1                                SXP 2570
C          END OF MULTIPLY SEGMENT OF PROGRAM.           SXP 2580
C          ISUM=0                                         SXP 2590
C          DO 200 M=1,KSCNT                           SXP 2600
C          KSVEC(M)=SVEC(M)+.5D0                      *SXP 2610
C          CONVERT NEW S VALUES FROM REAL TO INTEGER.   ***SXP 2620
C          KSVEC(M)=SVEC(M)+.5D0                      SXP 2630
C          ACCUMULATE OUTPUT S SUM.                  SXP 2640
C          200 ISUM=ISUM+KSVEC(M)                      SXP 2650
C          IF THE NEW SUM IS NOT EQUAL THE OLD SUM, ADJUST SXP 2660
C          THE STATE ZERO VALUE SO THAT IT WILL BE.     SXP 2670
C          KSVEC(1)=KSVEC(1)+INSUM-ISUM                SXP 2680
C          PRINT OUTPUT S NAME AND SUM BEFORE STATE ZERO SXP 2690
C          ADJUSTMENT.                               SXP 2700
C          PRINT 220,NAMES,ISUM                        SXP 2710
C          WRITE NEW S ON OUTPUT UNIT: BEGINNING RECORD, SXP 2720
C          DATA RECORD, END RECORD.                  SXP 2730
C          WRITE(IOUT)KSBEGL,NAMES,NLS2,(LABELS(I),I=1,NLS2) SXP 2740
C          WRITE(IOUT)KSDAT,NFILL,KSCNT,(KSN(K),K=1,KSCNT),(KSVEC(K),K=1, SXP 2750
C          1 KSCNT)                                     SXP 2760
C          WRITE(IOUT)KSEND,NFILL,NFILL,INSUM,NFILL      SXP 2770
C          UPDATE NUMBER OF OUTPUT FILES.            SXP 2780

```

NFILES=NFILES+1 SXP 2850
C IS WORKING P ON DISK? SXP 2860
C NO. ITERATIONS FOR THIS S AND P COMPLETE. SXP 2870
C IF(NITER .LE.1) GO TO 240 SXP 2880
C YES SXP 2890
C REWIND INPX SXP 2900
C ARE MORE ITERATIONS TO BE PERFORMED FOR THIS SXP 2910
C AND P? SXP 2920
C IF(ITER.GE.NITER) GO TO 240 SXP 2930
C YES SXP 2940
C THE NEW S FROM THE ITERATION JUST COMPLETED WILL SXP 2950
C BE THE INPUT S FOR THE NEXT ITERATION. SXP 2960
C MOVE KSCNT TO ISCNT. SXP 2970
C ISCNT=KSCNT SXP 2980
C KSN TO ISN SXP 2990
C CALL TMT(KSCNT,ISN(1),KSN(1)) SXP 3000
C KSVEC TO ISVEC. SXP 3010
C CALL TMT(KSCNT,ISVEC(1),KSVEC(1)) SXP 3020
C GO TO INCREMENT MON AND YEAR AND CONTINUE. SXP 3030
C GO TO 65 SXP 3040
C SXP 3050
C 240 SXP 3060
C ALL ITERATIONS FOR THIS S AND P ARE COMPLETED. SXP 3070
C IS THIS A PAIR OPERATION? SXP 3080
C 240 IF(NPAIRS.EQ.0) GO TO 260 SXP 3090
C YES SXP 3100
C DECREASE NPAIRS BY 1. SXP 3110
C NPAIRS=NPAIRS-1 SXP 3120
C HAVE ALL PAIRS BEEN PROCESSED? SXP 3130
C YES. GO TO READ A CONTROL CARD. SXP 3140
C IF(NPAIRS.EQ.0) GO TO 10 SXP 3150
C NO SXP 3160
C RESET ITERATION TO 0, KTYPE TO 2. SXP 3170
C SXP 3180
C ITER=0 SXP 3190
C KTYPE=2 SXP 3200
C CALL POSFWD FOR S OF NEXT PAIR. SXP 3210
C CALL POSFWD(INPS,KTYPE,NAMES,NLS,LABELS) SXP 3220
C GO TO READ S DATA RECORD. SXP 3230
C GO TO 32 SXP 3240
C SXP 3250
C IS THIS A NUMP SET? SXP 3260
C NO, GO TO READ A CONTROL CARD. SXP 3270
C 260 IF(NUMP.EQ.0) GO TO 10 SXP 3280
C YES SXP 3290
C DECREASE NUMP BY 1. SXP 3300
C NUMP=NUMP-1 SXP 3310
C HAVE ALL P'S BEEN PROCESSED? SXP 3320
C YES. GO TO READ A CONTROL CARD. SXP 3330
C IF(NUMP.EQ.0) GO TO 10 SXP 3340
C NO SXP 3350
C RESET ITER TO 0, KTYPE TO 3. SXP 3360
C SXP 3370
C ITER=0 SXP 3380
C KTYPE=3 CALL POSFWD FOR NEXT P. SXP 3390
C CALL POSFWD(INPP,KTYPE,NAMEP,NLP,LABELP) SXP 3400
C FINAL NEW S FROM LAST ITERATION OF PREVIOUS P SXP 3410

C WILL BE THE INPUT S FOR THE FIRST ITERATION OF SXP
C THIS P. SXP
C MOVE KSCNT TO ISCNT, KSN TO ISN, KSVEC TO ISVEC. SXP
C ISCNT=KSCNT SXP
C CALL TMT(KSCNT,ISN(1),KSN(1)) SXP
C CALL TMT(KSCNT,ISVEC(1),KSVEC(1)) SXP
C GO TO READ P DATA RECORDS. SXP
C GO TO 52 SXP
C YES SXP
C MULTIPLICATIONS COMPLETE FOR THIS CALL. SXP
C ADD 1 TO NUMBER OF OUTPUT FILES. SXP
C 300 NFILES=NFILES+1 SXP
C WRITE END LABEL ON OUTPUT. SXP
C WRITE(IOUT) KNEXT,NFILL6,NFILL,NFILES SXP
C REWIND OUTPUT UNIT. SXP
C REWIND IOUT SXP
C RETURN SXP
C RETURN SXP
C 2 FORMAT (1H1) SXP
C 5 FORMAT(I6) SXP
C 20 FORMAT(6A4,I6,6A4,I6,4I3) SXP
C 35 FORMAT(/24H INPUT S NAME AND SUM...,6A4,I12) SXP
C 220 FORMAT(24H OUTPUT S NAME AND SUM...,6A4,I12) SXP
C
C REFERENCE LIST. SXP
C
C SUBROUTINE ARGUMENTS. SXP
C
C NDIM - DIMENSION OF KSN AND KSVEC. SXP
C ISN - ELEMENT LIST FOR INPUT S. SXP
C ISVEC - ELEMENT VALUE FOR INPUT S. SXP
C KSN - ELEMENT LIST FOR OUTPUT S. SXP
C KSVEC, SXP
C SVEC - ELEMENT VALUE FOR OUTPUT S. SXP
C JCOL - ELEMENT LIST FOR P ROW. SXP
C P - ELEMENT VALUE FOR P ROW. SXP
C LABELS - ARRAY FOR INPUT AND OUTPUT S VECTOR LABELS. SXP
C LABELP - ARRAY FOR P MATRIX LABELS. SXP
C
C OTHER VARIABLES. SXP
C
C INPS - INPUT UNIT FOR S. SXP
C INPP - INPUT UNIT FOR P. MAY BE THE SAME AS INPS. SXP
C INSUM - SUM OF INPUT S. SXP
C ISUM - SUM OF PROJ S BEFORE SUM FORCED TO INSUM IF NECESSARY. SXP
C IODISK - A SEQUENTIAL ACCESS DISK OR TAPE USED TO STORE P DATA SXP
C RECORDS WHEN 'NITER' IS GT 1. USING THIS TEMPORARY STOR- SXP
C AGE UNIT AVOIDS EXCESSIVE TAPE PASSING TO RELOCATE THE SXP
C ORIGINAL COPY OF P 'NITER' TIMES. SXP
C ISCNT - NUMBER OF ENTRIES IN INPUT S VECTOR. SXP
C JCNT - NUMBER OF ENTRIES IN P MATRIX ROW. SXP
C KSCNT - NUMBER OF ENTRIES IN P MATRIX COLUMN LIST AND OUTPUT S. SXP
C NLS - LENGTH OF INPUT S LABEL. SXP
C NLS2 - LENGTH OF OUTPUT S LABEL. SXP

C	NLP - LENGTH OF P LABEL.	SXP 3990
CC	NITER - NUMBER OF ITERATIONS FOR EACH S,P PAIR IN THE CONTROL CARDSXP 4000	
C	ALSO USED TO DETERMINE IF P MATRIX IS TO BE PLACED ON AND SXP 4010	
CCC	USED FROM DISK.	SXP 4020
CC	NPAIRS- NUMBER OF 'PAIRED (S,P)' ARRAYS. THESE ARRAYS MUST BE ON SXP 4030	
CC	THE SAME INPUT TAPE AND IN A SPECIFIED ORDER.	SXP 4040
CC	NUMP - NUMBER OF P MATRICES TO BE PAIRED WITH A SINGLE INPUT S SXP 4050	
CC	AND ITS PROJECTIONS.	SXP 4060
CC	NFILES - NUMBER OF FILES ON OUTPUT UNIT.	SXP 4070
C	END	SXP 4080
		SXP 4090

```
SUBROUTINE TMT(NWORDS,LTO,LFROM)          TMT 010
C                                         TMT 020
C                                         TMT 030
C                                         TMT 040
C                                         TMT 050
C                                         TMT 060
C                                         TMT 070
C                                         TMT 080
C                                         TMT 090
C                                         TMT 100
C                                         TMT 110
C                                         TMT 120
C                                         TMT 130
C                                         TMT 140
C                                         TMT 150
C                                         TMT 160
C                                         TMT 170
C                                         TMT 180
C                                         TMT 190
C                                         TMT 200
C                                         TMT 210
C                                         TMT 220
C                                         TMT 230
C                                         TMT 240
C
C     TRANSMIT DATA IN CORE IN INCREASING LOCATION
C     ORDER.                                              TMT
C     DIMENSION LTO(1),LFROM(1)                         TMT
C
C     MOVE 'NWORDS' INTEGER*4 WORDS FROM 'LFROM' ARRAY TMT
C     TO 'LTO' ARRAY.                                     TMT
C
C     DO 5 I=1,NWORDS
5 LTO(I)=LFROM(I)
RETURN
C
C     REFERENCE LIST.
C     SUBROUTINE ARGUMENTS.
C
C     NWORDS - IF THE TO AND FROM ARRAYS IN THE CALL STATEMENT ARE TMT
C               INTEGER*4 ARRAYS, THIS IS THE NUMBER OF WORDS TO BE MOVED TMT
C               IF THE TO AND FROM ARRAYS IN THE CALL STATEMENT ARE REAL*TMT
C               8 ARRAYS, THIS IS THE NUMBER OF WORDS TO BE MOVED TIMES 2TMT
C
C     LTO    - ARRAY TO WHICH ELEMENTS ARE TO BE MOVED. THIS MUST BE THE TMT
C               SAME TYPE AS THE LFROM ARRAY.                           TMT
C
C     LFROM - ARRAY FROM WHICH ELEMENTS ARE BEING COPIED. THIS ARRAY TMT
C               MUST BE THE SAME TYPE AS THE LTO ARRAY.              TMT
END
```

```
SUBROUTINE TMT2(LFROM,LTO,NWORDS)          TMT2 010
C
C           TRANSMIT DATA IN CORE IN DECREASING LOCATION      TMT2 020
C           ORDER. THIS IS A PUSH DOWN OPERATION.            TMT2 030
C           LTO(1) AND LFROM(1) ARE THE PAIR OF WORDS TO BE    TMT2 040
C           USED IN THE NWORD'TH MOVE.                      TMT2 050
C
C           DIMENSION LTO(1),LFROM(1)                         TMT2 060
C           MOVE 'NWORDS' INTEGER*4 WORDS FROM 'LFROM' ARRAY   TMT2 070
C           TO 'LTO' ARRAY.                                TMT2 080
C
C           II=NWORDS+1                                     TMT2 090
C           DO 10 I=1,NWORDS                            TMT2 100
C           II=II-1                                         TMT2 110
10 LTO(II)=LFROM(II)                         TMT2 120
      RETURN                                       TMT2 130
C
C           REFERENCE LIST.                               TMT2 140
C           SUBROUTINE ARGUMENTS.                         TMT2 150
C
C           LFROM - ARRAY FROM WHICH ELEMENTS ARE BEING COPIED. THIS ARRAY TMT2 160
C           MUST BE THE SAME TYPE AS THE LTO ARRAY.          TMT2 170
C
C           LTO - ARRAY TO WHICH ELEMENTS ARE TO BE MOVED. THIS MUST BE THE TMT2 180
C           SAME TYPE AS THE LFROM ARRAY.                  TMT2 190
C
C           NWORDS - IF THE TO AND FROM ARRAYS IN THE CALL STATEMENT ARE TMT2 200
C           INTEGER*4 ARRAYS, THIS IS THE NUMBER OF WORDS TO BE MOVED TMT2 210
C           IF THE TO AND FROM ARRAYS IN THE CALL STATEMENT ARE REAL*TMT2 220
C           8 ARRAYS, THIS IS THE NUMBER OF WORDS TO BE MOVED TIMES 2TMT2 230
C
C           END                                              TMT2 240
TMT2 250
TMT2 260
TMT2 270
TMT2 280
TMT2 290
```

VI. SAMPLE PROGRAM

Table 1, the program listed on p. 160[†], can be used to test a FLOMOD library implemented on a Non-Rand system. This deck contains all the required input data; the program output, Table 2^{††} (pp. 161-162), is a printed report. No tape input or output is required. The system being used may require changes in the JCL cards.

[†]This is the same as Fig. 1 in Ref. 2.

^{††}This is the same as Table 2 in Ref. 1.

Table 1
PRINT STATE-NUMBER DESCRIPTIONS

```
//HC795#34 JDA (317A,50,110),'STATE DFS',CLASS=A
// EXFC FORTCLG,LINH='SYS1.FL0M0D'
//FORT,SYSPIN DD *
    IMPLICIT REAL*8(A-H,O-Z,$)
    DIMENSION NAMEV(9),NAMEC(120),NCODE(3),LNC(4),ICODE(3),LIST(9)
    CALL STDFS(NAMEV,NAMEC,NCODE,LNC,ICODE,LIST)
    CALL EXIT
    END
/*
//DD,FT06F001 DD SYSPNT=A,DCB=(RECFM=FBA,LRFL=133,HLKSIZE=1330)
//GO,SYSPIN DD *
STATE DESCRIPTION: AIR FORCE LINE OFFICER MODEL AFRO RATING X CAREER FIELD
X YRS OF SERVICE
      3      1
      1 AFRO RATING      2
      1      RATED
      2      NONRATED
      2 CAREER FIELD      2
      1 OPERATIONS
      2 ALL OTHERS
      3 YRS SERVICE      24
      1      LT 1
      2      1
      3      2
      4      3
      5      4
      6      5
      7      6
      8      7
      9      8
     10      9
     11     10
     12     11
     13     12
     14     13
     15     14
     16     15
     17     16
     18     17
     19     16
     20     19
     21     20
     22     21
     23     22
     24     23
     25     24
     26     25+
/*
//
```

Table 2

STATE-NUMBER DESCRIPTIONS AS PRINTED BY THE STDES
(STATE DESCRIPTION) PROGRAM

STATE DESCRIPTION:	AIR FORCE LINE OFFICER MODEL	AERO RATING X CAREER FIELD X YEARS OF SERVICE	
STATE NUMBER	AERO RATING	CAREER FIELD	YRS SERVICE
1	RATED	OPERATIONS	LT 1
2	RATED	OPERATIONS	1
3	RATED	OPERATIONS	2
4	RATED	OPERATIONS	3
5	RATED	OPERATIONS	4
6	RATED	OPERATIONS	5
7	RATED	OPERATIONS	6
8	RATED	OPERATIONS	7
9	RATED	OPERATIONS	8
10	RATED	OPERATIONS	9
11	RATED	OPERATIONS	10
12	RATED	OPERATIONS	11
13	RATED	OPERATIONS	12
14	RATED	OPERATIONS	13
15	RATED	OPERATIONS	14
16	RATED	OPERATIONS	15
17	RATED	OPERATIONS	16
18	RATED	OPERATIONS	17
19	RATED	OPERATIONS	18
20	RATED	OPERATIONS	19
21	RATED	OPERATIONS	20
22	RATED	OPERATIONS	21
23	RATED	OPERATIONS	22
24	RATED	OPERATIONS	23
25	RATED	OPERATIONS	24
26	RATED	OPERATIONS	25+
27	RATED	ALL OTHERS	LT 1
28	RATED	ALL OTHERS	1
29	RATED	ALL OTHERS	2
30	RATED	ALL OTHERS	3
31	RATED	ALL OTHERS	4
32	RATED	ALL OTHERS	5
33	RATED	ALL OTHERS	6
34	RATED	ALL OTHERS	7
35	RATED	ALL OTHERS	8
36	RATED	ALL OTHERS	9
37	RATED	ALL OTHERS	10
38	RATED	ALL OTHERS	11
39	RATED	ALL OTHERS	12
40	RATED	ALL OTHERS	13
41	RATED	ALL OTHERS	14
42	RATED	ALL OTHERS	15
43	RATED	ALL OTHERS	16
44	RATED	ALL OTHERS	17
45	RATED	ALL OTHERS	18
46	RATED	ALL OTHERS	19
47	RATED	ALL OTHERS	20
48	RATED	ALL OTHERS	21
49	RATED	ALL OTHERS	22
50	RATED	ALL OTHERS	23
51	RATED	ALL OTHERS	24
52	RATED	ALL OTHERS	25+
53	NUNRATED	OPERATIONS	LT 1
54	NUNRATED	OPERATIONS	1
55	NUNRATED	OPERATIONS	2
56	NUNRATED	OPERATIONS	3

Table 2 (con't)

STATE-NUMBER DESCRIPTIONS AS PRINTED BY THE STDES
(STATE DESCRIPTION) PROGRAM

STATE DESCRIPTION:	AIR FORCE LINE OFFICER MODEL	AERO RATING X CAREER FIELD X YEARS OF SERVICE	
STATE NUMBER	AERO RATING	CAREER FIELD	YRS SERVICE
57	NONRATED	OPERATIONS	4
58	NONRATED	OPERATIONS	5
59	NONRATED	OPERATIONS	6
60	NONRATED	OPERATIONS	7
61	NONRATED	OPERATIONS	8
62	NONRATED	OPERATIONS	9
63	NONRATED	OPERATIONS	10
64	NONRATED	OPERATIONS	11
65	NONRATED	OPERATIONS	12
66	NONRATED	OPERATIONS	13
67	NONRATED	OPERATIONS	14
68	NONRATED	OPERATIONS	15
69	NONRATED	OPERATIONS	16
70	NONRATED	OPERATIONS	17
71	NONRATED	OPERATIONS	18
72	NONRATED	OPERATIONS	19
73	NONRATED	OPERATIONS	20
74	NONRATED	OPERATIONS	21
75	NONRATED	OPERATIONS	22
76	NONRATED	OPERATIONS	23
77	NONRATED	OPERATIONS	24
78	NONRATED	OPERATIONS	25+
79	NONRATED	ALL OTHERS	LT 1
80	NONRATED	ALL OTHERS	1
81	NONRATED	ALL OTHERS	2
82	NONRATED	ALL OTHERS	3
83	NONRATED	ALL OTHERS	4
84	NONRATED	ALL OTHERS	5
85	NONRATED	ALL OTHERS	6
86	NONRATED	ALL OTHERS	7
87	NONRATED	ALL OTHERS	8
88	NONRATED	ALL OTHERS	9
89	NONRATED	ALL OTHERS	10
90	NONRATED	ALL OTHERS	11
91	NONRATED	ALL OTHERS	12
92	NONRATED	ALL OTHERS	13
93	NONRATED	ALL OTHERS	14
94	NONRATED	ALL OTHERS	15
95	NONRATED	ALL OTHERS	16
96	NONRATED	ALL OTHERS	17
97	NONRATED	ALL OTHERS	18
98	NONRATED	ALL OTHERS	19
99	NONRATED	ALL OTHERS	20
100	NONRATED	ALL OTHERS	21
101	NONRATED	ALL OTHERS	22
102	NONRATED	ALL OTHERS	23
103	NONRATED	ALL OTHERS	24
104	NONRATED	ALL OTHERS	25+

REFERENCES

1. Merck, J. W., and Kathleen Hall, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems*, The Rand Corporation, R-514-PR, February 1971.
2. Hall, Kathleen, *A Markovian Flow Model: The Analysis of Movement in Large-Scale (Military) Personnel Systems--Program Reference Manual*, The Rand Corporation, R-534-PR, February 1971.

DOCUMENT CONTROL DATA

1. ORIGINATING ACTIVITY The Rand Corporation		2a. REPORT SECURITY CLASSIFICATION UNCLASSIFIED
		2b. GROUP
3. REPORT TITLE A MARKOVIAN FLOW MODEL: THE ANALYSIS OF MOVEMENT IN LARGE-SCALE (MILITARY) PERSONNEL SYSTEMS--PROGRAM LISTINGS		
4. AUTHOR(S) (last name, first name, initial) Hall, Kathleen		
5. REPORT DATE March 1971	6a. TOTAL NO. OF PAGES 168	6b. NO. OF REFS.
7. CONTRACT OR GRANT NO. F44620-67-C-0045	8. ORIGINATOR'S REPORT NO. R-535-PR	
9a. AVAILABILITY/LIMITATION NOTICES DDC-I		9b. SPONSORING AGENCY United States Air Force Project Rand
10. ABSTRACT The third in a series of reports describing a model of social mobility, the study of which will provide researchers with information concerning patterns of movement, projections of existing population trends, and the impact produced by changes in rates of movement. Intended to be used by the programmer/analyst in creating a program library, this report lists the 29 FORTRAN subroutines that perform the operations described in the program package. The storage required on an IBM 360/65 is given for each subroutine. Comment cards contain a step-by-step, natural-language description of source-language statements. These listings will be useful when the programs are to be executed on another computer system, or when a subroutine implementing a new operation is to be written. A sample program is included.		11. KEY WORDS Computer Programming Military Personnel Mobility Markov Processes