

AD-A246 275



2

TECHNICAL REPORT  
NATICK/TR-92/016

AD \_\_\_\_\_

# USER MANUAL FOR NATICK'S FOOTWEAR DATABASE

By  
Paula M. Poole  
Carolyn K. Bensel\*  
Richard M. Rosenstein

January 1992


Final Report  
November 1990 - December 1991

APPROVED FOR PUBLIC RELEASE;  
DISTRIBUTION UNLIMITED

UNITED STATES ARMY NATICK  
RESEARCH, DEVELOPMENT AND ENGINEERING CENTER  
NATICK, MASSACHUSETTS 01760-5000

GEO-CENTERS, INC., NEWTON CENTRE, MA 02159

\*SOLDIER SCIENCE DIRECTORATE



92 2 18 174

92-04164  
|||||

### DISCLAIMERS

The findings contained in this report are not to be construed as an official Department of the Army position unless so designated by other authorized documents.

Citation of trade names in this report does not constitute an official endorsement or approval of the use of such items.

### DESTRUCTION NOTICE

#### For Classified Documents:


Follow the procedures in DoD 5200.22-M, Industrial Security Manual, Section II-19 or DoD 5200.1-R, Information Security Program Regulation, Chapter IX.

#### For Unclassified/Limited Distribution Documents:

Destroy by any method that prevents disclosure of contents or reconstruction of the document.

REPORT DOCUMENTATION PAGE			Form Approved OMB No. 0704-0188	
Public reporting burden for this collection of information is estimated to average 1 hour per response, including the time for reviewing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and reviewing the collection of information. Send comments regarding this burden estimate or any other aspect of this collection of information, including suggestions for reducing this burden, to Washington Headquarters Services, Directorate for Information Operations and Reports, 1215 Jefferson Davis Highway, Suite 1204, Arlington, VA 22202-4302, and to the Office of Management and Budget, Paperwork Reduction Project (0704-0188), Washington, DC 20503.				
1. AGENCY USE ONLY (Leave blank)	2. REPORT DATE January 1992	3. REPORT TYPE AND DATES COVERED Final Nov 90 - Dec 91		
4. TITLE AND SUBTITLE User Manual for Natick's Footwear Database		5. FUNDING NUMBERS  PE 1L162723 PR AH98 TA AA		
6. AUTHOR(S) Paula M. Poole*, Carolyn K. Benschel, and Richard M. Rosenstein*				
7. PERFORMING ORGANIZATION NAME(S) AND ADDRESS(ES) Behavioral Sciences Division, Soldier Science Directorate U.S. Army Natick Research, Development and Engineering Center (ATTN: STRNC-YBH) Natick, MA 01760-5020		8. PERFORMING ORGANIZATION REPORT NUMBER  NATICK/TR-92/016		
9. SPONSORING/MONITORING AGENCY NAME(S) AND ADDRESS(ES) U.S. Marine Corps Research, Development, and Acquisition Command (Code CPR) Washington, DC 20380-0001		10. SPONSORING/MONITORING AGENCY REPORT NUMBER		
11. SUPPLEMENTARY NOTES  *Affiliation with GEO-CENTERS, INC., Newton Centre, MA 02159				
12a. DISTRIBUTION/AVAILABILITY STATEMENT  Approved for public release; distribution unlimited.			12b. DISTRIBUTION CODE	
13. ABSTRACT (Maximum 200 words) Natick's Footwear Database is a computerized system for the management of literature regarding lower extremity health and comfort as they relate to footwear. Six major topics define the focus and the contents of the database. These are: (1) anatomy; (2) biomechanics; (3) environment; (4) footwear; (5) injury; and (6) physiology. System capabilities include: text and keyword searches of the literature in the database; presentation on the computer screen of the results of searches; and generation of printed reports of the results of searches. An entry in the database contains the complete reference, the keywords assigned, and an overall summary of the contents. In the case of a paper dealing with an experiment, summaries of the methods employed and the results of the work are also presented. This report contains detailed information regarding the operation of the user version of the footwear database. Included are instructions for installing the database, conducting text and keyword searches, and obtaining outputs from the searches.				
14. SUBJECT TERMS FOOTWEAR DATABASE SYSTEMS ANATOMY INJURY  WOUNDS AND INJURIES BIOMECHANICS ENVIRONMENT PHYSIOLOGY  COMPUTER SEARCHES USER MANUALS HEALTH COMFORT			15. NUMBER OF PAGES 79  16. PRICE CODE	
17. SECURITY CLASSIFICATION OF REPORT UNCLASSIFIED	18. SECURITY CLASSIFICATION OF THIS PAGE UNCLASSIFIED	19. SECURITY CLASSIFICATION OF ABSTRACT UNCLASSIFIED	20. LIMITATION OF ABSTRACT  SAR	

# User Manual for





## TABLE OF CONTENTS

FIGURES . . . . .	vii
TABLES . . . . .	viii
PREFACE . . . . .	ix
SECTION 1. INTRODUCTION . . . . .	1
1.1 Background . . . . .	1
1.2 Focus of the Database and Major Topics . . . . .	3
1.3 General Information on Operation and Administration . . . . .	5
1.3.1 Purpose of the System . . . . .	5
1.3.2 Additional Documentation . . . . .	5
1.3.3 Maintenance of Data . . . . .	5
1.3.4 The User Manual . . . . .	5
1.3.5 Security . . . . .	5
1.3.6 Availability of the Literature in the Database . . . . .	6
SECTION 2. SYSTEM SUMMARY . . . . .	7
2.1 Overview . . . . .	7
2.1.1 Application Summary . . . . .	7
2.1.1.1 Conducting a Text Search . . . . .	7
2.1.1.2 Conducting a Keyword Search . . . . .	7
2.1.1.3 On-screen Viewing . . . . .	8
2.1.1.4 Printed Output . . . . .	8
2.1.1.5 General System Flowchart . . . . .	9
2.1.2 Performance . . . . .	9
2.1.3 Controls . . . . .	10
2.2 System Environment . . . . .	10
2.2.1 Hardware Required . . . . .	10
2.2.2 Software Required . . . . .	11
2.3 Contingencies and Alternate Modes of Operation . . . . .	11
2.4 Assistance and Problem Reporting . . . . .	12
SECTION 3. ACCESS TO THE SYSTEM . . . . .	13
3.1 Use of the System . . . . .	13
3.1.1 Access Control . . . . .	13
3.1.2 Installation . . . . .	13
3.2 Initiating a Session . . . . .	13
3.3 Stopping and Suspending Work . . . . .	15
SECTION 4. PROCESSING REFERENCE GUIDE . . . . .	16
4.1 Capabilities . . . . .	16
4.2 Conventions . . . . .	16
4.3 Processing Procedures . . . . .	17
4.3.1 Text Search . . . . .	17
4.3.1.1 Entering Additional Search Text . . . . .	19
4.3.1.2 Displaying User's Text . . . . .	20

## TABLE OF CONTENTS (cont'd)

4.3.1.3	Erasing User's Text . . . . .	21
4.3.1.4	Conducting a Text Search . . . . .	22
4.3.2	Keyword Search . . . . .	25
4.3.2.1	Selecting Additional Keywords . . . . .	29
4.3.2.2	Displaying User's Keywords . . . . .	30
4.3.2.3	Erasing User's Keywords . . . . .	31
4.3.2.4	Conducting a Keyword Search . . . . .	33
4.3.3	Viewing and Printing Options . . . . .	37
4.3.3.1	Contents of a Database Entry . . . . .	38
4.3.3.2	Viewing Highlighted . . . . .	42
4.3.3.3	Returning to List of Matches . . . . .	44
4.3.3.4	Printing a Report . . . . .	44
4.3.3.5	Quitting a Search . . . . .	50
4.3.4	Exiting the System . . . . .	51
SECTION 5. REFERENCES . . . . .		52
Appendix A. Suggestion and Comment Form . . . . .		53
Appendix B. Installation Instructions . . . . .		55
Appendix C. Alphabetical Listing of Error Messages . . . . .		61
Appendix D. Keywords by Major Topic as of December 16, 1991 . . . . .		69



Accession For	
NTIS GRA&I	<input checked="" type="checkbox"/>
DTIC TAB	<input type="checkbox"/>
Unannounced	<input type="checkbox"/>
Justification	
By	
Distribution/	
Availability Codes	
Dist	Avail and/or Special
A-1	

## FIGURES

Figure	Page
1. General system flowchart. . . . .	9
2. Welcoming screen for Natick's Footwear Database. . . .	14
3. Choosing between "Read Only" or "Development" versions. . . . .	15
4. Main menu with "Text Search" highlighted. . . . .	17
5. Searchable database fields during a Text Search. . . .	18
6. Entering title text. . . . .	19
7. Displaying user's text. . . . .	20
8. Confirming a request for erasure. . . . .	21
9. Erasing user's text input. . . . .	22
10. Confirming the start of a Text Search. . . . .	23
11. Confirming/negating the request for a search involving no user-specified text. . . . .	24
12. Results of a successful Text Search. . . . .	25
13. Main menu with "Keyword Search" highlighted. . . . .	26
14. Major topics to choose from during a Keyword Search. .	27
15. Keywords available under the major topic of Footwear. .	28
16. User's Keyword List. . . . .	28
17. Keywords available under the major topic of Injury. . .	29
18. User's Keyword List. . . . .	30
19. Displaying a User's Keyword List. . . . .	31
20. Confirming a request for erasure. . . . .	32
21. Erasing user's keywords. . . . .	32
22. Selecting a type of Keyword Search. . . . .	33
23. Confirming the start of a Keyword Search. . . . .	34
24. Confirming/negating the request for a search involving no user-specified keywords. . . . .	35
25. Results of a successful logical "and" Keyword Search. .	36
26. Results of a successful logical "or" Keyword Search. .	36
27. A list of matches with on-screen instructions. . . . .	37
28. View/Print menu. . . . .	38
29. First screen of record information. . . . .	39
30. Second screen of record information. . . . .	40
31. Third screen of record information. . . . .	40
32. Textual summary presented in an opened memo field. . .	43
33. Choosing currently highlighted record. . . . .	44
34. Continuing with a print request. . . . .	45
35. Choosing a detailed type of report. . . . .	46
36. Printer options. . . . .	47
37a. First page of a sample report. . . . .	48
37b. Second page of a sample report. . . . .	49
37c. Third page of a sample report. . . . .	50



## TABLES

Table	Page
1. Performance Capabilities of Natick's Footwear Database. .	10
2. Initiating a Session. . . . .	13
3. Searchable Database Fields with Acceptable Entry Forms. .	18
4. On-Screen Instructions While Viewing. . . . .	42

## **PREFACE**

This report on the operation of Natick's Footwear Database was prepared by Ms. Paula M. Poole and Mr. Richard M. Rosenstein of GEO-CENTERS, INC., Newton Centre, Massachusetts, under Army contract DAAK60-90-D-0002, and by Dr. Carolyn K. BenseL of the Human Factors Branch, Behavioral Sciences Division, Soldier Science Directorate, U.S. Army Natick Research, Development and Engineering Center (Natick).

Establishment of Natick's Footwear Database has been funded by the U.S. Marine Corps Research, Development, and Acquisition Command. The authors wish to thank Captain Kenneth J. Thompson, USMC, and Major R. Stewart Navarre, USMC, who, while serving as U.S. Marine Corps Liaison Officers at Natick, provided invaluable support and encouragement of this effort. The authors are also most grateful to Dr. James A. Vogel and Dr. Everett A. Harman of the U.S. Army Research Institute of Environmental Medicine, Natick, Massachusetts, for their cooperation during the planning and the establishment of the database.

## USER MANUAL FOR NATICK'S FOOTWEAR DATABASE

### SECTION 1. INTRODUCTION

1.1 Background. The many types of footwear in the supply systems of the U.S. Armed Forces reflect the wide range of environments in which military personnel operate, the myriad hazards that the personnel face, and the variety of occupational specialties that the personnel practice. In the U.S. Army supply system, as an example, there are over 30 items of footwear (Department of the Army, 1986). They include: boots for tropical, desert, and extreme low temperature environments; steel-toed shoes for wear when working around heavy objects; overshoes for use in the presence of toxicological agents; dress shoes for the office; and rubber boots for fire-fighting.

Regardless of its particular application, each type of military footwear should function to maintain or enhance the lower extremity health and the comfort of the wearer. A number of scientific and technical specialties are employed in arriving at a finished footwear item that will achieve this goal. Expertise in chemistry, materials technology, and engineering is needed, as is expertise in physiology, ergonomics, and physical anthropology. As a Department of Defense establishment responsible for development of military footwear, the U.S. Army Natick Research, Development, and Engineering Center (Natick) has on its staff scientists and technologists representing a number of the relevant specialties. The capabilities of the Natick staff are complemented by those of scientists at the U.S. Army Research Institute of Environmental Medicine (USARIEM), a facility that is co-located with Natick.

As a result of their efforts over the years in footwear research and development, the staffs of Natick and of USARIEM have generated a body of literature representing a broad range of footwear-related issues. Much of this literature is in the form of Natick and USARIEM technical reports that reside in the permanent collection of the Natick Technical Library. Also part of that

collection are reports prepared by universities, commercial research establishments, and industrial concerns under contract to Natick or to USARIEM. The library holdings include, in addition, reports of work carried out under Natick auspices by other government agencies. Although the literature is at hand, the sheer volume of it presents a daunting challenge to the individual trying to assemble information on a given topic. The situation is, of course, exacerbated when one is naive to the topic, as a new staff member may be.

Other sources of footwear-related information at Natick and at USARIEM are the literature collections, principally comprised of books, journal papers, and government technical reports, that individual staff members have assembled as reference material for their footwear projects. These literature collections, which can become quite sizeable, are unique to each individual, representing background information related to their particular areas of study. It is highly probable that a given piece of literature in one individual's collection would be of use to a number of staff members, yet they might not know of its existence. Indeed, as the volume of reference material increases, the individual whose collection already includes a particular paper may overlook it as a source of information.

In order to address the inefficiencies involved in locating relevant references and to exploit the literature available at Natick and at USARIEM, particularly the collection of the Natick Technical Library, the determination was made to establish a computerized database of footwear literature. The database was planned to serve as a resource for Natick and USARIEM staff members, both those experienced in and those new to footwear-related research and development, and for members of the U.S. Marine Corps and the U.S. Army responsible for formulating the footwear needs of their respective services. However, the database may also be of use to individuals in other Department of Defense agencies and to government contractors involved with footwear.

As of this writing, the software for running the database is in place and there are approximately 100 entries consisting of reference and textual information. The project has, therefore, reached a stage at which staff members may benefit from the database. In order for interested individuals to exercise the database, two reports, a maintenance manual (Poole, Bensel, and Rosenstein, 1992) and this user manual, have been prepared. In the sections that follow, the focus of the database is described, and detailed instructions for operation of the database are presented.

The literature now in the database is from the collections of Natick and USARIEM staff members. The literature consists of books, journal papers, and government technical reports. The next effort will be to add holdings from the Natick Technical Library. The foundation of the database will have been established when this is accomplished, and it is expected that future work will consist of keeping the database current by adding newly-published literature.

1.2 Focus of the Database and Major Topics. The development of footwear involves the application of many technical specialties and, thus, there is a broad array of literature related to the topic. Early in the planning process, it was decided that the footwear database would be comprised of literature that is relevant across technical disciplines. A goal that drives all military footwear development efforts, regardless of discipline, is maintaining or enhancing the lower extremity health and the comfort of the wearer. Therefore, literature dealing with lower extremity health and with comfort as related to footwear was chosen as the focus of the database.

In an undertaking of this kind, decisions made regarding appropriate subject matter are admittedly arbitrary. They reflect the judgments of those who establish and, subsequently, of those who maintain the database. In addition, changes in the state of the art and pursuit of new lines of research or development may

affect the composition of the database. However, at this stage, six major topics define the focus and the contents of the database. These are:

- a. Anatomy -- Information regarding the physical structure of the human body, with emphasis on the lower extremities.
- b. Biomechanics -- Information regarding human movement and the effects of internal and external forces acting on the human body. Descriptions of research techniques are included.
- c. Environment -- Information regarding the effects that thermal conditions and the characteristics of terrain surface composition have on the body, particularly the lower extremities. Information on designing of footwear to protect against environmental effects is also included.
- d. Footwear -- Information regarding material properties, fabrication techniques, and finished footwear items.
- e. Injury -- Information regarding etiology, diagnosis, and treatment of physical problems, with emphasis on lower extremity disorders. Also included here is information on morbidity to injury in military and civilian populations.
- f. Physiology -- Information regarding physical functioning of the body during activities involving the lower extremity.

There is a seventh topical area, labelled "Other," containing assorted materials judged to be appropriate for inclusion in the database that cannot be properly accommodated in the six major areas.

### 1.3 General Information on Operation and Administration.

1.3.1 Purpose of the System. The purpose of Natick's Footwear Database is to manage information related to footwear and lower extremity health. Capabilities include text and keyword searches, on-screen viewing, and generation of printed reports. Depending on the user's requirements, the database is capable of displaying information on the screen or generating output in the form of a reference list or a detailed report including summaries of the literature.

1.3.2 Additional Documentation. The following documents may be necessary for the operation of Natick's Footwear Database. Under normal conditions, however, consulting these documents should not be required.

- a. Manual(s) for host PC and printer.
- b. Manual(s) for host operating system (DOS).

1.3.3 Maintenance of Data. It is projected that the contents of Natick's Footwear Database will be maintained by personnel in the Behavioral Sciences Division of the Soldier Science Directorate. Individual users will not be able to modify or augment the database. However, suggestions are welcome; a form is available for such comments in Appendix A.

1.3.4 The User Manual. The purpose of this manual is to provide users with the information necessary to operate the "Read Only" version of the database system effectively.

1.3.5 Security. The literature contained in Natick's Footwear Database is unclassified. The inclusion of classified documents is not permitted. A password is required to operate the development version of the database.

1.3.6 Availability of the Literature in the Database. Users outside of Natick and USARIEM may want to acquire documents summarized in the database. They should follow their usual procedures for acquiring such materials. THE STAFFS OF NATICK AND USARIEM AND THE NATICK TECHNICAL LIBRARY CANNOT PROVIDE THE LITERATURE SUMMARIZED IN THE DATABASE.

If an organization is registered with the Defense Technical Information Center (DTIC), members of the organization may obtain technical reports published by the Department of Defense (DoD) and DoD contractors by contacting:

Defense Technical Information Center  
Cameron Station  
Alexandria, Virginia 22304-6145

Phone

Commercial: (202) 274-7633

DSN: 284-7633

Others interested in obtaining DoD technical reports should contact:

U.S. Department of Commerce  
National Technical Information Service (NTIS)  
5285 Port Royal Road  
Springfield, Virginia 22161

Phone

Commercial: (703) 487-4650

To assist users in obtaining technical reports, the database contains, as part of the reference to such reports, the accession code, or "DTIC" number, used as an identifier by both DTIC and NTIS.



## **SECTION 2. SYSTEM SUMMARY**

### **2.1 Overview.**

**2.1.1 Application Summary.** Each literature entry, or record, in Natick's Footwear Database contains reference and textual information. The textual information includes an overall summary, or synopsis, of the literature entry. It may also include summaries of the methods and the results and some comments on the entry. The user interface allows individuals who are interested in footwear and foot health to gain access to the contents of the database. Users are offered two major types of search functions: a text search and a keyword search. After successfully conducting either type of search, the user is given a list of literature that meets the demands of the search specifications. The user can view the contents of each entry on the screen or generate printed output. The development version of Natick's Footwear Database allows database maintenance personnel to edit existing records and add new literature to the database.

**2.1.1.1 Conducting a Text Search.** The "Text Search" allows the user to enter text in the form of a partial word, word, phrase, sentence, or several sentences. The text may be located in one or more of the following fields: title, author(s), editor(s), year, organization, journal, overall summary, methods summary, and results summary.

**2.1.1.2 Conducting a Keyword Search.** The "Keyword Search" allows the user to choose one or more major topics of interest. Under each major topical area, the system offers the user a predefined list of applicable keywords. The user can choose up to six keywords from one or more major topics. Before conducting a search, the user connects the keywords with a logical "and" or a logical "or."

2.1.1.3 On-screen Viewing. Once a text or keyword search has been conducted, the user is presented a list of the titles of the matched references. The user may view the title that is currently highlighted in the list of matches. Viewing a title displays three screens of information, including all applicable reference information and keywords assigned to that title. One of the screens has a description of the user's options to open windows containing summaries.

2.1.1.4 Printed Output. The user may generate one or more printed reports. Each report consists of either a single title that is currently highlighted in the list of matches or all titles in the list of matches. Also, the user may generate either a reference report or a detailed report. The reference report contains reference information for the chosen literature, whereas the detailed report contains reference information as well as keywords and any applicable textual summaries for the chosen literature.

### 2.1.1.5 General System Flowchart.




Figure 1. General system flowchart.

**2.1.2 Performance.** The following section describes system performance capabilities based on the number of records entered in the database at the time this report was published. Sample text and keyword search performance times are presented in Table 1.

**Table 1. Performance Capabilities of Natick's Footwear Database.**

Text Searched for in Title	38 records (time in seconds)	73 records (time in seconds)
no text specified	50	75
"a"	50	67
"y"	30	44
"Load"	18	18
"Load, sport shoes and playing surfaces"	15	15
Keywords	38 records (time in seconds)	73 records (time in seconds)
	Logical "and" "or"	Logical "and" "or"
no keywords specified	30 13	45 17
1 keyword	11 5	11 5
6 keywords	15 35	15 44

**2.1.3 Controls.** Personnel in the Behavioral Sciences Division of the Soldier Science Directorate are responsible for managing the system and providing supervisory controls.

## **2.2 System Environment.**

**2.2.1 Hardware Required.** A 286 or 386 IBM compatible computer with a color monitor, a minimum of 640K of memory and 3MB of hard

disk space is necessary to run the system. (Hard disk requirements may increase as the database is further developed.) It should be noted that memory resident programs such as shells may consume memory required to properly run the system. Neither expanded memory (EMS) nor a math coprocessor is required. However, FoxPro will make full use of any available EMS or a math coprocessor. Disk caches, however, should not be active while using the system due to their incompatibility with FoxPro software. Although some types of caches, such as small sized ones loaded on 386 machines, may not present any problems, testing in this area has not lead to a conclusive list of "safe" caches. **THE USE OF SOME TYPES OF DISK CACHES WHILE OPERATING THE READ ONLY VERSION OF THE SYSTEM MAY RESULT IN PROGRAM EXECUTION ERRORS.** A printer is not required to use the system for conducting searches and viewing literature. A printer, however, is required if printed reports are desired.

2.2.2 Software Required. DOS version 3.31 or higher is necessary to support the operation of Natick's Footwear Database. Specific requirements for DOS settings, such as files and buffers statements, are described in Appendix B. Consulting this appendix should only be necessary if installation is required. The files needed to run Natick's Footwear Database are on System, Keywords, Database, and Text Diskettes. Included on the System Diskettes is a copy of the Royalty-Free Run-Time version of FoxPro (v 1.02), licensed by Fox Software, Inc. of Perrysburg, OH, as well as installation files, compiled programs, report formats, and screen formats. The Keywords Diskette holds the files that make up the keywords lists for the major topics. Included on the Database Diskette(s) is the file containing all reference information and keywords assigned to each record. The Text Diskettes hold the file containing all textual summaries for each record. A complete listing of diskette contents is located in Appendix B.

2.3 Contingencies and Alternate Modes of Operation. N/A

2.4 Assistance and Problem Reporting. While using the system, assistance may be required or a problem may need to be reported. If the present report does not address the user's needs, the following guidelines should be of assistance.

A Suggestion and Comment Form is available in Appendix A of this manual. Users are encouraged to use these forms to voice suggestions and/or comment on any problems encountered while using the system. If the system is being used on a PC targeted as Natick's Footwear Database Workstation, completed forms may be left at the workstation. If the system has been loaded on any other PC, completed forms may be returned to personnel responsible for distributing the system software.

## SECTION 3. ACCESS TO THE SYSTEM

### 3.1 Use of the System.

3.1.1 Access Control. In order to protect the integrity of the database, the capability for the typical user to modify or supplement existing data is not available. Initial entry screens to the system require users to choose between a "Read Only" version or a "Development" version. The typical user would choose the read only version, whereas database maintenance personnel would choose the development version. Access to the development version requires the use of a password, the details of which are explained in the Maintenance Manual for Natick's Footwear Database (Poole, Bense, Rosenstein, 1992).

3.1.2 Installation. Under normal conditions, the database will be used on a PC where it has already been installed. Should software installation be necessary, instructions are located in Appendix B.

3.2 Initiating a Session. To begin a working session with Natick's Footwear Database, the user must change to the directory in which the system has been installed, type *foot*, and press  (see Table 2 for instructions).

**Table 2. Initiating a Session.**

<u>What To Type:</u>	<u>What Will Happen:</u>
C:\>cd \footwear <input type="text"/>	Changes to the directory where the system resides.
C:\footwear>foot <input type="text"/>	Executes start-up file for the system.

---

The first screen welcomes the user to Natick's Footwear Database (see Figure 2). Pressing any key continues the initial entry procedure with a screen that requests the user to choose between a read only version and a development version as previously described in Section 3.1.1, Access Control (see Figure 3).




Figure 2. Welcoming screen for Natick's Footwear Database.



Access to Natick's Footwear Database can be gained through two separate versions of the system, which are described below.	
Read Only Version:	This version is designed for the typical user who wishes to conduct literature searches and generate printed reports.
Development Version:	This version is designed for personnel responsible for maintaining the database. ACCESS TO THIS VERSION REQUIRES A PASSWORD.
Enter R for Read Only Version or D for Development Version	
<div style="border: 1px solid black; padding: 2px; display: inline-block;">R</div>	



**Figure 3. Choosing between "Read Only" or "Development" versions.**

Once the read only version has been selected by entering R, a working session begins with the main menu displayed and ready for use. Consult Section 4, Processing Reference Guide, for complete read only version operating instructions.

**3.3 Stopping and Suspending Work.** The proper way to interrupt use of the system is to exit from the main menu by using the "Exit" option. **REBOOTING OR POWERING DOWN THE COMPUTER SHOULD NOT BE USED AS METHODS OF EXITING THE SYSTEM.** These methods do not shut down the system properly; they leave temporary files that should be deleted in the system directory. If this happens, subsequent use of the system will generate error messages. A list of error messages and suggested corrective actions is presented in Appendix C.


## SECTION 4. PROCESSING REFERENCE GUIDE

4.1 Capabilities. The main menu offers a text search, a keyword search, and an exit option. After conducting either type of search, a list of matching literature titles is displayed, with options to view references and/or summaries on the screen, print reference and/or textual information, or quit the search.

4.2 Conventions. Natick's Footwear Database was designed to run on a PC with a color monitor. Operation with a monochrome monitor is possible, but not desirable due to lack of contrast while using the system's menus and windows. The main color of the system is blue with contrasting red, yellow, cyan, and white graphics and text. On-screen instructions generally appear at the bottom of the screen. Keystrokes required to operate the system are limited to text characters, , <Esc>, Delete, Backspace, ↑ ↓ ← →, <PgUp>, <PgDn>, Home, End, <F2>, <F3>, <F4>, and <F10>. A cursor, appearing as a white or yellow blinking underbar, usually is waiting for text input or another keystroke. The insert mode is automatically turned on at the beginning of each session, but it can be manually turned off by pressing insert (this will leave the computer in a "typeover" mode). When menus are accessed, the active option is denoted by a light bar which is a red rectangle with yellow text. Non-active menu options are presented in cyan text with no contrasting rectangle. Some of the system's menus employ the use of "hot keys." Hot keys appear in a different color and are used as a shortcut to both selecting and activating a menu item. Normally, without hot keys, the user would scroll to the desired menu option using ↑ ↓, <PgUp> or <PgDn> and then press  to activate it. With hot keys, the user can press a key letter in the title of the menu option (usually the first letter) to perform the functions of multiple keystrokes. Although hot keys are more efficient, the examples in this report utilize the arrow and return keys for choosing options.

4.3 Processing Procedures. Instructions for each main menu option is described below. Section 4.3.1 describes text searches; Section 4.3.2 describes keyword searches; Section 4.3.3 describes viewing and printing options available after conducting a text or keyword search; and Section 4.3.4 describes exiting the system.

4.3.1 Text Search. To conduct a text search, highlight "Text Search" on the main menu by using ← → and press  (see Figure 4).




**Figure 4. Main menu with "Text Search" highlighted.**

The text search offers the user a chance to search for all literature containing specified text anywhere in one or more of the following fields: title, author(s), editor(s), year, organization, journal, overall summary, methods summary, and results summary (see Figure 5). Table 3 describes each searchable database field and the acceptable entry forms. The case of the characters (upper or lower) entered for a search text does not have to match the case of the characters stored in the database.

**Table 3. Searchable Database Fields with Acceptable Entry Forms.**

<u>Database Field:</u>	<u>Entry Form:</u>
Title	up to 252 characters
Author	last name only; up to 35 characters
Editor	last name only; up to 35 characters
Year	four digit years only; entering both a starting and ending year defines a specific range; entering only a starting year defines a range that is greater than or equal to the starting year; entering only an ending year defines a range that is less than or equal to the ending year
Organization	up to 252 characters
Journal	up to 126 characters
Overall Summary	up to 252 characters
Methods Summary	up to 252 characters
Results Summary	up to 252 characters



**Figure 5. Searchable database fields during a Text Search.**

For example, if the user is interested in searching for literature with the text "plantar" in the title, he/she simply highlights title from the list of text search options using ↑ ↓ and presses . The search text can be entered in the title field, followed by a . In the example displayed in Figure 6, the search text within the title field is "plantar." Search text can be located anywhere within the search field of a qualifying title.

Text Search	
Title	***** Enter text to be searched for in Title *****
Author	Title plantar
Editor	
Year	
Organization	
Journal	
-----	
Overall Summary	
Methods Summary	
Results Summary	
-----	
Display User's Text	
Erase User's Text	
Conduct Search	

Figure 6. Entering title text.

From this point, it is possible to: 1) enter more text in another searchable database field; 2) display user's text; 3) erase user's text; or 4) conduct a search. Each of these options is described below.

**4.3.1.1 Entering Additional Search Text.** It is possible to build a search sequence that includes user specified text in one, a few, or all of the nine searchable database fields. For example, the user may wish to specify a particular time period. If multiple fields are included in the search sequence, each of the user-

specified text strings must be found if a literature entry is to qualify as a match. To add another item to the search sequence, the user highlights the desired field, enters additional search text and presses . Again, it is possible to enter as much or as little text as desired. Generally, the more text specified, the fewer pieces of literature will be found. Conversely, specifying shorter strings will result in more literature being found. The time it takes the system to complete a search increases with the amount of specified search text.

**4.3.1.2 Displaying User's Text.** The user may wish to check text specifications before conducting a search. An option under the "Text Search" menu entitled "Display User's Text" is available for such an action. This option allows the user to check for typographical errors or study a complicated search sequence. To display user's text, highlight the "Display User's Text" option using ↑ ↓ and press . A screen similar to the one presented in Figure 7 will be displayed.

Text Search	
Title	plantar
Author	
Editor	
Year	
Organization	
Journal	
Overall Summary	
Methods Summary	
Results Summary	
Display User's Text	
Erase User's Text	
Conduct Search	

Title	plantar
Author's Last Name	
Editor's Last Name	
Starting Year	1987
Ending Year	
Organization	
Journal	
Overall Summary	
Methods Summary	
Results Summary	

Press any key to continue...

**Figure 7. Displaying user's text.**


4.3.1.3 Erasing User's Text. The user may wish to erase all text that has been specified in order to start another search with a "clean slate." To erase all user input, highlight the "Erase User's Text" option using ↑ ↓ and press . The user is asked to confirm or negate the request (see Figure 8). Confirming the request for erasure displays the screen shown in Figure 9. Negating the request for erasure returns the user to the list of text search options, leaving all previously specified text intact.

Text Search	Keyword Search	EXIT
Title		
Author		
Editor		
Year		
Organization		
Journal		
-----		
Overall Summary		
Methods Summary		
Results Summary		
-----		
Display User's Text		
Erase User's Text		
Conduct Search		


  

Erase All User's Input? Y/N Y
----------------------------------

Figure 8. Confirming a request for erasure.



**Figure 9. Erasing user's text input.**

**4.3.1.4 Conducting a Text Search.** The user may conduct a text search after specifying search text. This is accomplished by choosing the "Conduct Search" option using ↑ ↓ and pressing . The user is then asked to confirm or negate the request (see Figure 10).



Text Search	Keyword Search	EXIT
Title Author Editor Year Organization Journal ----- Overall Summary Methods Summary Results Summary ----- Display User's Text Erase User's Text Conduct Search		
<div>           Conduct Search?            Y/N   Y         </div>		

**Figure 10. Confirming the start of a Text Search.**

Negating the request for a search returns the user to the list of text search options, leaving all input intact. Upon confirming the request for a search, the system begins its search for literature that meets each of the text specifications. All literature in the database is evaluated to determine if it meets the specifications of the user's search text. Qualifying literature is written to a list of matches. The user may generate a list of all the titles contained in Natick's Footwear Database by leaving all search text entries blank. The user, however, is required to confirm or negate the request for this type of search (see Figure 11).



```
No search specifications have been defined. The resulting list
of matches will consist of the entire Footwear Database.
```


```
Would you like to continue? (Y/N)
```

**Figure 11. Confirming/negating the request for a search involving no user-specified text.**


During a text search, the message, "Please wait while search is being conducted," is displayed. An unsuccessful search displays a message stating "No matches found" and then returns the user to the main menu, keeping previous input intact. A successful search displays a list of literature titles that meets the demands of the search specifications (see Figure 12). Titles of technical reports, journal articles, and chapters in edited books appear in the left-hand column; titles of books appear in the right-hand column. If a title is longer than 40 characters, only a portion of it is displayed because of screen limitations. It is possible to view the entire contents of each title by first highlighting the title and then using ← → , <Home>, or <End> to scroll the contents horizontally.


At this point, the user may want to view and/or print the results of the text search. The instructions for viewing and printing results from a text search are the same as those for viewing and printing results from a keyword search. Therefore, the

keyword search is described next and information on viewing and printing follows (see Section 4.3.3, Viewing and Printing Options).




**Figure 12. Results of a successful Text Search.**

**4.3.2 Keyword Search.** The user is advised to become familiar with available keywords prior to conducting a keyword search. New keywords may be added by database maintenance personnel. Valid keywords at the time of publication of this report are presented in Appendix D. To conduct a keyword search, highlight "Keyword Search" on the main menu by using ← → and press  (see Figure 13).



**Figure 13. Main menu with "Keyword Search" highlighted.**

The keyword search allows the user to identify literature to which one or more keywords has been assigned. Search keywords may be selected from one or more of the following major topics: Anatomy, Biomechanics, Environment, Footwear, Injury, Physiology, and Other (see Figure 14). It is possible to include up to six keywords per search. When more than one search keyword is chosen, the user must decide if the keywords are to be connected with a logical "and" or a logical "or." A logical "and" specifies that **each** qualifying piece of literature must have **all** the search keywords assigned to it. A logical "or" specifies that **each** qualifying piece of literature must have **at least one** of the search keywords assigned to it.



**Figure 14. Major topics to choose from during a Keyword Search.**

For example, to search for literature that has the keyword "hot weather combat boot" assigned to it, the user highlights "Footwear" from the list of major topics using ↑ ↓ and presses  (see Figure 15). Next, the user locates "hot weather combat boot" in the list of keywords using ↑ ↓ and presses . The keyword "hot weather combat boot" is displayed in a window titled: "User's Keyword List" (see Figure 16). After pressing any key to remove the list from the screen, the user may select another keyword from the Footwear list or press <F10> to exit the keyword list.




Figure 15. Keywords available under the major topic of Footwear.






Figure 16. User's Keyword List.

From this point, it is possible to: 1) select more keywords; 2) display user's keywords; 3) erase user's keywords; or 4) conduct a search. Each of these options is described below.

**4.3.2.1 Selecting Additional Keywords.** The user may build a search sequence that includes up to six keywords. All search keywords do not have to be chosen from the same major topic. To add another keyword to the search sequence, simply highlight the desired major topic, select the additional search keyword(s), and press . In the example presented in Figures 17 and 18, the keyword "lower extremity disorders" is chosen from the major topic of Injury. Each keyword added to a search sequence increases the system search time.




**Figure 17. Keywords available under the major topic of Injury.**



**Figure 18. User's Keyword List.**

4.3.2.2 Displaying User's Keywords. The user may wish to check specified keywords before conducting a search. An option under the "Keyword Search" menu entitled "Display User's Keywords" is available for such an action. This option allows the user to examine the list before choosing a logical "and" or a logical "or" type of keyword search. To display user's keywords, highlight the "Display User's Keywords" option using ↑ ↓ and press . A screen similar to the one presented in Figure 19 is displayed.





**Figure 19. Displaying a User's Keyword List.**

4.3.2.3 Erasing User's Keywords. The user may wish to erase all keywords that have been specified in order to start another search with a "clean slate." To erase all user input, highlight the "Erase User's Keywords" option using ↑ ↓ and press ☐. The user is asked to confirm or negate the request (see Figure 20). Confirming the request for erasure displays the screen shown in Figure 21. Negating the request for erasure returns the user to the list of keyword search options, leaving all previously specified keywords intact.




Figure 20. Confirming a request for erasure.




Figure 21. Erasing user's keywords.

4.3.2.4 Conducting a Keyword Search. The user may conduct a keyword search after specifying search keywords. This is accomplished by choosing the "Conduct Search" option using ↑ ↓ and pressing . The user is asked the type of keyword search to be performed. The user enters A to connect keywords with a logical "and" or O to connect keywords with a logical "or", and presses . When only one search keyword is specified, either connection will yield the same results. The following example involves a logical "and" keyword search (see Figure 22). The user is then asked to confirm or negate the request (see Figure 23).

Text Search	Keyword Search	EXIT
<div>MAJOR TOPICS</div> <div>Anatomy</div> <div>Biomechanics</div> <div>Environment</div> <div>Footwear</div> <div>Injury</div> <div>Physiology</div> <div>Other</div> <div>Display User's Keywords</div> <div>Erase User's Keywords</div> <div>Conduct Search</div>		
<div>You may connect your keywords with a logical &lt;AND&gt; or a logical &lt;OR&gt;</div> <div>Enter A for &lt;AND&gt; or O for &lt;OR&gt; A</div>		

Figure 22. Selecting a type of Keyword Search.

Text Search	Keyword Search	EXIT
-------------	----------------	------

**MAJOR TOPICS**

Anatomy  
 Biomechanics  
 Environment  
 Footwear  
 Injury  
 Physiology  
 Other

---

Display User's Keywords  
 Erase User's Keywords  
 Conduct Search


You may connect your keywords with  
 a logical <AND> or a logical <OR>

Enter A for <AND> or O for <OR> A

Conduct Search?  
 Y/N Y

**Figure 23. Confirming the start of a Keyword Search.**

Negating the request for a search returns the user to the list of keyword search options, leaving all input intact. Upon confirming the request for a search, the system begins its search for literature that meets the keyword search specifications. All literature in the database is evaluated to determine if it meets the specifications of the user's search keywords. Qualifying literature is written to a list of matches. The user may generate a list of all the titles contained in Natick's Footwear Database by leaving all search keyword entries blank. The user, however, is required to confirm or negate the request for this type of search (see Figure 24).



**Figure 24. Confirming/negating the request for a search involving no user-specified keywords.**

During a keyword search, the message, "Please wait while search is being conducted," is displayed. An unsuccessful search displays a message stating "No matches found" and then returns the user to the main menu, keeping previous input intact. This allows the user to make note of unsuccessful combinations of keywords and, if desired, try another search. A successful search displays a list of literature titles that meets the demands of the logical "and" keyword search specifications (see Figure 25). For comparison, Figure 26 displays the results of a logical "or" keyword search involving the same two keywords: "hot weather combat boot" and "lower extremity disorders." Report, paper, and chapter titles appear in the left-hand column and book titles appear in the right-hand column. If a title is longer than 40 characters, only a portion of it is displayed because of screen limitations. It is possible to view the entire contents of each title by first highlighting it and then using ← → , <Home>, or <End> to scroll the contents horizontally. For viewing and

printing instructions, please consult Section 4.3.3 of this report.




Figure 25. Results of a successful logical "and" Keyword Search.





Figure 26. Results of a successful logical "or" Keyword Search.


4.3.3 Viewing and Printing Options. As discussed earlier, the instructions in this section can be used for viewing and printing literature found as the result of either a text search or a keyword search. For purpose of demonstration, the search conducted in Section 4.3.1, Text Search, is continued in this section. At the bottom of the screen displaying the list of matches, there are on-screen instructions. Pressing ↑ ↓, <PgUp>, and <PgDn> allows the user to scroll the list of matches and highlight a title of interest. Pressing <F2> presents the user with a View/Print menu (see Figure 27).



**Figure 27.** A list of matches with on-screen instructions.

Before pressing <F2>, attention should be paid as to which literature title is currently highlighted. After pressing <F2>, the View/Print menu is displayed. This menu allows viewing of information stored for the currently highlighted title, returning to the list of matches, generating printed output, or quitting the search (see Figure 28). Before describing these menu options, the

information stored in the database for a piece of literature will be explained and illustrated.



**Figure 28. View/Print menu.**

4.3.3.1 Contents of a Database Entry. Whether a record is viewed on-screen or as printed output, the contents are the same. For purposes of explanation, the presentation that would be viewed on the screen is described and illustrated here. For each literature title, there are three screens of reference information. Additional screens of textual information may be accessed at the user's option. Fields of information that do not apply to a record are left blank. The contents of each of the three screens of reference information are as follows:

- a. First Screen (see Figure 29) -- This contains the title and author(s) of the piece of literature and, when applicable, the editor(s).



b. Second Screen (see Figure 30) -- This contains additional reference information. For journal articles, the name of the journal, year of publication, volume number, and relevant page numbers are presented. In the case of technical reports, the name and location of the organization releasing the report and the date of publication are presented along with any internal control number assigned by the organization and the DTIC accession code. For books, the year of publication and name and location of the publisher are presented.

c. Third Screen (see Figure 31) -- This lists the keywords assigned to the entry and allows the user to access the memo fields containing the textual information.

Title of Report/ Paper/ Chapter:	How we manage plantar fasciitis.
Title of Book:	
<hr/>	
	Author(s)
FI MI LAST	
1.S. M. Tanner	
2.J. S. Harvey	
3.	
4.	
5.	
6.	
	Editor(s)
1.J. G. Garrick	
2.	
3.	
<hr/>	
<PgUp>--Return to List of Matches      <PgDn>--View Next Screen	

Figure 29. First screen of record information.

Periodical/Organization Information			
Journal Title: The Physician and Sportsmedicine			
Volume: 16	Pages: 39-47		
Day:	Month(s): Aug-	Year: 1988	
Organization:			
Location:			
Report #:	DTIC #:		
Publisher:			
Location:			
<input type="button" value=" &lt;PgUp&gt;--View Previous Screen"/> <input type="button" value=" &lt;PgDn&gt;--View Next Screen"/>			

Figure 30. Second screen of record information.

Major Summaries			
Overall:memo	Methods:memo	Results:memo	Comments:memo
<input type="button" value=""/> Press <b>↑</b> or <b>← →</b> to Select Memo Field <input type="button" value=""/> Press <b>&lt;F3&gt;</b> to View Memo Field <input type="button" value=""/> Press <b>&lt;F4&gt;</b> to Close Memo Field			
Keywords			
1. plantar fasciitis	5.		
2. plantar fascia	6.		
3.	7.		
4.	8.		
<input type="button" value=" &lt;PgUp&gt; View Previous Screen"/> <input type="button" value=" &lt;PgDn&gt; Return to List of Matches"/>			

Figure 31. Third screen of record information.

The textual information, which is contained in four memo fields, represents summaries of various portions of the literature being treated. One of the fields, the Overall Summary, always has information; the other memo fields may or may not contain information, depending upon the nature of the particular literature. A description of each of the memo fields is as follows:

Overall -- The Overall Summary presents the most important points of the literature. The extent to which details are included in the summary depends on the nature of the literature. For example, the overall summary of an authored book is very general, whereas the overall summary of a review article is likely to contain specific information.


Methods -- The Methods Summary provides a synopsis of the methodology of a report on a single experiment. This summary contains information about the subjects, equipment, procedures, and dependent and independent variables used in the experiment.

Results -- The Results Summary presents the key findings of a research work. This summary is not as detailed as the results section of the actual report, but it is usually more extensive than the published abstract.

Comments -- The Comments field contains observations of the reviewer for Natick's Footwear Database. These comments may provide the user with additional information (e.g., the paper is a roundtable discussion or an abstract presented at a specific conference) or may alert the user to shortcomings in experimental design.


Usually, in the summaries included in Natick's Footwear Database, wording such as: "the authors cite others on..." alerts the user to thoughts that are not the author's own. However, the


author of a paper may cite numerous references to the work of others, and it would be cumbersome to include the above wording in every instance. The user is advised to consult the actual publication in order to determine the origin of specific ideas and information.


**4.3.3.2 Viewing Highlighted.** In order to view the title that is currently highlighted in the list of matches, select the "View Highlighted" option from the View/Print menu using ← → and press . This allows the user to view all information stored in the database for the highlighted title. It is not possible, however, to modify or add information while viewing.

In addition to fields of information for the highlighted title, there are also on-screen instructions denoting functions of pertinent keystrokes. Table 4 presents an outline of valid keystrokes for each of the three screens.

**Table 4. On-Screen Instructions While Viewing.**


<b>Screen #1</b> <PgUp> <PgDn>	returns user to list of matches takes user to second screen of information
<b>Screen #2</b> <PgUp> <PgDn>	returns user to first screen of information takes user to third screen of information
<b>Screen #3</b> <PgUp> <PgDn>  , ← → <F3> <F4>	returns user to second screen of information returns user to list of matches positions cursor in desired memo field opens current memo field for viewing closes current memo field



To view textual information stored for any of the four memo fields, place the cursor in the desired memo field using  or  $\leftarrow$  and press  $\langle F3 \rangle$  (see Figure 32). If a memo field contains textual information, the letter "M" in the word "Memo" will be capitalized. If a major summary memo field does not contain textual information, the letter "m" in the word "memo" will not be capitalized. Notice in the example in Figure 32 that there is textual information only in the Overall Summary.




**Figure 32. Textual summary presented in an opened memo field.**

Once a memo field, or text window, has been opened with  $\langle F3 \rangle$ , it can be scrolled using  $\uparrow \downarrow$ ,  $\langle PgUp \rangle$ , and  $\langle PgDn \rangle$ . To close a memo field, press  $\langle F4 \rangle$ . After viewing a record, the system returns to the list of matches with the next title highlighted. The user may press  $\langle F2 \rangle$  for options, or may highlight a different title and then press  $\langle F2 \rangle$  for options. Again, options allow viewing information on the screen, returning to list of matches, generating printed output, or quitting the search (see Figure 28).

4.3.3.3 Returning to List of Matches. The user may return to the list of matches by highlighting the "Return to Matches" option from the View/Print menu using ← → and pressing . If desired, the user may change the position of the highlight bar to a different title of interest.


4.3.3.4 Printing a Report. To print a report, select "Print Report" from the View/Print menu using ← → and press . Then, the user may choose either the "Currently Highlighted" or the "Entire List of Matches" option using ↑ ↓ and press . The "Currently Highlighted" option outputs information stored for any one selected title. The "Entire List of Matches" option outputs information stored for all titles in the list of matches. The demonstration report involves a single record using the "Currently Highlighted" option (see Figure 33).



**Figure 33.** Choosing currently highlighted record.

After selection of the report option, a message appears asking the user to confirm or negate the print request. Pressing Y

continues with the print request, or N cancels the print request and returns the user to the View/Print menu (see Figure 34).



**Figure 34. Continuing with a print request.**

Upon continuing with the print request, the user chooses to print either a reference report or a detailed report. A reference report includes information stored in the database that is required for referencing an article or a book. A detailed report includes the contents of a reference report, as well as assigned keywords and textual summaries. The demonstration report involves a detailed report (see Figure 35).



You may generate a reference or a detailed type  
of report for the specified scope of records.

Enter R for Reference or D for Detailed D


**Figure 35. Choosing a detailed type of report.**

Upon selection of the type of report, a list of printer choices appears. There are two types of printers from which to choose, in addition to an option to cancel the print request. The printer choices are either a dot matrix printer or a Hewlett Packard laser printer (see Figure 36). The output of the two types of printers differs only in graphical presentation and not in content. The cancel option returns the user to the View/Print menu. Selecting a type of printer automatically begins the print job. The message, "Please wait while the report is being printed..." is displayed on the screen until printing has been completed.

A print job that is in process may be canceled as follows. First, take the printer off line; usually this is accomplished by pressing the printer's on line button (check printer manual if this does not work). Second, wait for the system to generate a "Printer not ready. Retry?" message. Respond to this message by highlighting "No" and press [↵]. After a short pause, the above message appears again; respond by highlighting "No" and press [↵].



Next, the system returns to the View/Print menu. After canceling a print job, several pages may still print, depending on the size of the printer's memory. Once the printer has stopped, the printer's buffer must be cleared and the printer must be set on line. In most cases, clearing the buffer can be done by pressing the form feed button on the printer. After the printer stops printing, set it back on line by pressing the on line button. If the printer does not have a form feed button, consult the printer's manual for buffer clearing instructions.



**Figure 36. Printer options.**

The detailed report for the currently highlighted title displayed in Figures 37a-c was generated using a Hewlett Packard LaserJet III laser printer.

Detailed Report  
May 10, 1991

The following literature was located in Natick's Footwear Database as a result of the following text search specifications:

Title: plantar

Author's Last Name:

Editor's Last Name:

Starting Year: 1987

Ending Year:

Organization:

Journal:

Overall Summary: running

Methods Summary:

Results Summary:

Title of Report/Paper/Chapter: How we manage plantar fasciitis.

Title of Book: N/A

Author(s): S.M. Tanner  
J.S. Harvey

Editor(s): J.G. Garrick

Journal: The Physician and Sportsmedicine

Volume: 16 Pages: 39-47

Day: N/A Month(s): Aug Year: 1988

Organization: N/A  
Location: N/A

Report #: N/A DTIC #: N/A

Figure 37a. First page of a sample report.

KEYWORDS

1. plantar fasciitis
2. plantar fascia

MAJOR SUMMARIES

OVERALL:

Plantar fasciitis is an overuse injury caused by microtears and inflammation near the fascial insertion on the calcaneus. The authors cite others on running-specific causes of plantar fasciitis: hill running, especially for runners with tight Achilles tendon, increases traction on fascia; load of running on the heel and plantar fascia is 3-5 times that of the load of walking; congenital pes planus, tight Achilles tendon and poor shoe support allow subtalar pronation to occur, which lets the arch sag and stretches the plantar fascia; shoes with loose, poorly fitted heel counters may allow subtalar pronation to occur and allow the calcaneal fat pad to spread upon heel strike, thus permitting increased transmission of impact to the plantar fascia.

Symptoms of plantar fasciitis include heel or arch pain which increases with jumping and running. Tenderness may exist along the entire medial plantar aspect of the foot. Passive dorsiflexion of the great toe stretches the fascia, increasing pain and making the medial fascial edge easily palpable. Flexion and extension of the great toe are often decreased in runners suffering from plantar fasciitis. Passive dorsiflexion of the ankle may increase pain and indicates a tight Achilles tendon. Swelling is usually absent, but occasionally nodules from a fascial granuloma can be felt on the medial border of the fascia. A radiograph of the heel may appear normal or may show a spur projecting anteriorly from the calcaneus. Plantar fascia pain is not caused by the spur; the spur is thought to result from chronic fascial inflammation. Complete rupture of plantar fascia is uncommon, but an athlete may feel a pop on the plantar aspect of the foot while running. Swelling causes the medial longitudinal arch to take on a convex rather than a concave appearance.

The following conditions are also characterized by similar pain but are easily differentiated from plantar fasciitis: inflammation of the bursa between the calcaneus and the heel fat pad; Sever's disease; a first sacral radiculopathy; metatarsal stress fracture (calcaneal stress fractures are rare); tarsal tunnel syndrome; gout; Reiter's disease; ankylosing spondylitis; psoriatic arthropathy; and rheumatoid arthritis.

Rest is important for effective treatment; casting is seldom necessary. Runners should avoid sprinting and uphill running, and should decrease mileage by 25-75%. Alternative forms of exercise will aid in healing and will maintain conditioning. Stretching the Achilles tendon eases the plantar fascia and helps prevent recurrence of the injury. Cryotherapy may relieve pain in mild cases, but ultrasound and electrogalvanic stimulation are not consistently effective forms of therapy. Aspirin or non-steroidal anti-inflammatory drug may decrease inflammation in the acute phase. Cortisone injections should be discouraged--pain relief is temporary and cortisone may degenerate the fascia, promoting rupture. The athlete's shoe should have a firm heel counter, good heel cushioning and adequate longitudinal arch support. Running on softer surfaces is advisable. Heel lifts, low-dye taping, and orthotics may be useful for management of the condition. Surgery should be considered for patients with heel pain persisting more than one year.

---

METHODS:  
N/A

---

RESULTS:  
N/A

---

COMMENTS:  
N/A


---

---


Page 3

**Figure 37c. Third page of a sample report.**

After generating a printed report using the "Currently Highlighted" option, the system returns the user to the list of matches, with the next title highlighted. The user may select another title and/or return to the View/Print menu by pressing <F2>. After generating a printed report using the "Entire List of Matches" option, the system returns the user to the View/Print menu.

4.3.3.5 Quitting a Search. To quit a search, highlight the "Quit Search" option on the View/Print menu using ← → and press .

Quitting a search clears the text or keywords specified for the search. The system returns to the main menu, from which the user may generate another search or exit to DOS.

**4.3.4 Exiting the System.** In order to exit to DOS, highlight the "EXIT" option on the main menu using ← → and press . **THIS METHOD IS THE ONLY PROPER WAY TO EXIT THE SYSTEM.** Exiting the system by any other method such as soft booting or powering down the system will result in error messages during subsequent operation of the system. Assistance for dealing with such messages is located in Appendix C.

## SECTION 5. REFERENCES

Poole, P. M., Bensel, C. K. and Rosenstein, R. M. (1992). Maintenance manual for Natick's Footwear Database (Tech. Rep. NATICK/TR-92/015). Natick, MA: U.S. Army Natick Research, Development and Engineering Center.

Department of the Army. (1986). Size tariff for clothing, equipage and footwear (Supply Bulletin SB 10-523). Washington, DC: Department of the Army, Headquarters.

**APPENDIX A**  
**Suggestion and Comment Form**

## Appendix A. Suggestion and Comment Form

The space provided below may be used to inform database maintenance personnel of literature not presently included in the database that you feel should be. Please be sure to provide the actual article reprint or book being suggested. The space may also be used to report trouble you experienced while operating the system and/or suggestions for improving the system.

Completed forms can either be left at the PC designated as Natick's Footwear Database System, or if the system is being used on another PC, forms can be returned to personnel responsible for distributing the system software. Thank you for your time and cooperation.

[illegible]

Name \_\_\_\_\_

Organization and Phone #



**APPENDIX B**  
**Installation Instructions**

## **Appendix B. Installation Instructions**

Hardware and software requirements, which are outlined in Section 2.2.1 and Section 2.2.2 of this manual, should be carefully adhered to.

Before installing the system, it is necessary to check the contents of a DOS file called config.sys. The file may contain files=xx and buffers=xx statements, where xx is a variable number. In order for Natick's Footwear Database to run properly, the files statement should equal at least 40 and the buffers statement should equal at least 40. If the statements are already set for at least 40 each, leave the file as is and continue with the following installation instructions. If the statements are less than 40, use a text editor to set them to 40. If there are no files or buffers statements, add each statement on a new line of the config.sys file by using a text editor. Be sure not to delete or modify any other lines of the config.sys file (if any are present) -- they are there for a reason. It should be noted that setting either or both of these statements to a number higher than 40 will not improve the efficiency of the system and may even decrease efficiency. Existing config.sys files with statements higher than 40 should be left as is, however, because the higher settings may be necessary for the proper operation of other applications.

After all hardware and software requirements and configurations have been met, installation of the system may be initiated with the install.bat batch file. Due to different hard and floppy drive configurations of various computer systems, it is necessary to enter the source and target drive designators after the "install" command. The table below helps determine what the user should type to install Natick's Footwear Database on their particular computer system (other drives may be substituted if necessary).

What To Type:                      What Will Happen:

---

a:install a: c:                      Installs system from floppy drive A: to hard drive C:

b:install b: c:                      Installs system from floppy drive B: to hard drive C:

a:install a: d:                      Installs system from floppy drive A: to hard drive D:

b:install b: d:                      Installs system from floppy drive B: to hard drive D:

---

After entering the appropriate batch file command, the user will be prompted for each diskette that makes up Natick's Footwear Database System. Note that, as the size of Natick's Footwear Database increases, so may the number of diskettes required to store the system. At the time of publication, there were 4 diskettes containing system files, 1 diskette containing keywords files, 1 diskette containing the footwear database file, and 2 diskettes containing the footwear text file. The installation batch file is designed to accommodate additional diskettes as the size of the system increases. The contents of each diskette are listed below.

<u>Diskette:</u>	<u>Contents:</u>	
System Diskette #1*	back.bat foxpror2.pak foxswap.com foxunpak.exe install.bat install2.bat	
System Diskette #2	foxprort.exe	
System Diskette #3	keydet1.frx keydet2.frx keyref1.frx keyref2.frx foxuser.dbf foot3a.prx foot4a.prx foot.bat	textdet1.frx textdet2.frx textref1.frx textref2.frx foxuser.fpt foot3b.prx foot3.fky
System Diskette #4	foot3.fxp foot4.fxp run.fxp	
Keywords Diskette	anatomy.dbf biomech.dbf environ.dbf foot.dbf injury.dbf other.dbf phys.dbf	anatomy.idx biomech.idx environ.idx foot.idx injury.idx other.idx phys.idx
Database Diskette #1**	backup.001	control.001
Text Diskette #1***	backup.001	control.001
Text Diskette #2***	backup.002	control.002

\* When installed, install.bat is not copied onto the hard drive. In addition, foxpror2.pak is uncompressed onto the hard drive as two files (foxprort.rsc and foxprort.ovl) using foxunpak.exe.

\*\* When installed, these files are restored to a file called footwear.dbf on the hard drive.

\*\*\* When installed, these files are restored to a file called footwear.fpt on the hard drive.

Automatic installation of the four Systems Diskettes and the Keywords Diskette employs the use of the simple DOS copy command, whereas automatic installation of the Database Diskette(s) and Text Diskettes employs the use of the more involved DOS restore command.

Diskettes containing files installed with the copy command are prompted for with a message similar to: "Please insert System Diskette #1 in drive A: Strike a key when ready...." Upon entering the correct diskette and pressing any key, the files are copied automatically, and the system prompts the user for the next diskette in the series. If the user inserts an incorrect diskette, the prompt for the correct diskette is repeated. When the correct diskette is inserted, installation proceeds with the next diskette in the series.

Files installed with the DOS restore command are those that may eventually, if not already, occupy more than one 5 1/4 inch double sided, double density diskette. Diskettes containing these types of files (i.e., Database and Text Diskettes) are prompted for with a message similar to: "Follow the DOS prompts for the appropriate numbered backup diskette in the series of Database Diskettes. \*\*\*\*\* Insert Database Diskette #1 in A: \*\*\*\*\* Strike a key when ready...." After pressing any key, DOS will prompt the user for the first backup diskette in the series with a message similar to: "Insert backup diskette 01 in drive A: Strike any key when ready." Upon inserting the correct diskette from the appropriate series, the file is automatically restored, and the user is prompted for the next diskette in the series or a new series is started. If the user inserts an incorrect diskette, the prompt for the correct diskette is repeated. When the correct diskette is inserted, installation proceeds with the next diskette in the series. When the entire system has been loaded, DOS returns the message: "Installation of Natick's Footwear Database is complete. Type 'foot' to begin."




**APPENDIX C**  
**Alphabetical Listing of Error Messages**

## **Appendix C. Alphabetical Listing of Error Messages**

The following messages are not covered in the body of the manual. Most will only occur if proper operating procedures are not followed, or if there is trouble with the hard disk or operating system of the host PC.

### **Bad command or filename**

This is a DOS error that may occur when attempting to start up the system. Check database directory for the batch file called foot.bat. If not there, check for \*.bat. If there is another .bat file, try typing it followed by a . If there are not other .bat files, follow instructions in Appendix B and reload the system. This error may also occur while trying to install the system on a computer that is supported by DOS version 3.3 or earlier.

### **C:\path\filename.ext already exists, overwrite?**

This type of error is due to an improper shut down of the system. Note that the drive, path, file name and file extension will vary depending on the file in question. The user should respond "Yes" to the overwrite request. The files being overwritten are of a temporary nature and would have been deleted if the system had been shut down properly.

### **Cannot create file**

The operating system has returned an error to FoxPro indicating that the new file cannot be created. The inability to create a new file is usually the result of a full disk or directory. You may receive this error while conducting either a text or a keyword search. Temporary files created by the system during searches are not obvious to the user because their creation is hidden. If this error occurs, cancel the operation and check the hard disk for available space.



**File does not exist**

The file you have specified does not exist. Try entering file again, being careful to include a path if the text file for import resides in a directory other than Natick's Footwear Database directory. Also, be sure to include the file extension.

**File read error**

An error was returned by the operating system while FoxPro was attempting to read a file. System files that are unable to be read may reside on a bad sector of the hard disk. Consult DOS manual(s) for host PC.

**File write error**

An error was returned by the operating system while FoxPro was attempting to write a file. Most often, this error is the result of an attempt to write to a write-protected diskette, but may also be the result of a bad sector on the hard disk. Consult DOS manual(s) for host PC.

**Index does not match database file**

The index expression for the current index uses variables which are not contained within the current database. This error should not occur unless the system has been corrupted; try reloading system if error persists after canceling the operation and rebooting.

**Insufficient memory**

There was not enough memory for FoxPro to complete an operation. Cancel the operation and try rebooting and/or removing any memory-resident programs that may currently be installed on host PC.

**Internal consistency error**

An internal FoxPro table has been corrupted. If this error occurs, inform personnel responsible for maintaining the database; contacting the FoxPro Technical Support Line may be necessary.

**Invalid character in command**

A source line of code contains an invalid character. This is probably caused by corruption of the system files. Reloading of the system from uncorrupted disks is recommended.

**Invalid drive specification**

The floppy and/or hard drive specified during installation or backup of the system is not valid. Abort the operation and try again with correct drive designators.

**Invalid or missing resource file**

Either the FoxPro resource file (FOXPRORT.RSC) could not be found (in the system directory or along the DOS path), or the resource file found has been corrupted. Try reloading uncorrupted copies of the system disks.

**Invalid directory**

Check to be sure the system was in fact installed in the directory the user is trying to change to. The system may have been installed in a directory other than footwear or it may have been removed from the host PC all together.

**Memo file is missing/invalid**

An attempt was made to use a database file whose associated memo file (.DBT or .FPT) has been deleted, corrupted or cannot be found. Try loading an uncorrupted copy of the system disks.

**Menu is already in use**

An attempt has been made to activate a menu that is already active. This error occurs if the keys are quickly and erratically pressed. Choosing "ignore" when this error occurs will solve the problem.

**No memory for buffer, file map, or filename**

It is impossible to allocate memory for a buffer or a FoxPro internal resource. This message is very unusual and will occur

only in situations where available memory is extremely limited. Consider adding memory to the host PC or removing some memory resident programs to give FoxPro more working memory.

#### **Not enough memory to use database**

There was not enough memory to open an additional database. Try removing some memory resident programs to give FoxPro more working memory.

#### **Not ready error reading drive A**

##### **Abort, Retry, Fail?**

DOS returns this error when a diskette is not inserted in the floppy drive specified during installation or backup of the system. To continue the operation, insert appropriate diskette in designated drive and press "R" for Retry. To cancel the operation, press "A" for Abort.

#### **OS memory error**

There is a problem with your DOS free memory chain. Consult DOS manual(s) for host PC.

#### **Popup is already in use**

An attempt has been made to activate a popup that is already active. This error occurs if the keys are quickly and erratically pressed. Choosing "ignore" when this error occurs will solve the problem.

#### **Position is off the screen**

A row or column number specified in the system is larger than the number of rows or columns on the screen, window or printer. Operation of the system on a PC that has a monitor smaller than standard size or a printer with width smaller than 8 1/2" may cause this error.

**Printer not ready. Retry?**

The printer device specified is currently not accessible or the printer may be off line. Be sure printer is on line and ready for data, and then choose to continue with the request. Please note that this error also occurs during the cancellation of a print job and should be treated as specified in the appropriate section of this report.

**Record is not in index**

A database for a keyword list in use has been modified without the index having been active or reindexed. Choosing "ignore" in response to this error should solve the problem.

**Run/! command failed**

Most often this error message is a result of insufficient free memory to support the execution of a DOS command from within FoxPro. This will likely occur while the system is resetting itself after a search or while the backup option of the development version is being run. It is suggested that the user cancel the operation and follow the guidelines below.

Firstly, the command.com file must be accessible via the DOS environment variable COMSPEC. Secondly, memory resident programs, such as shells loaded prior to start up of the database, should be cleared from memory before trying the operation again. Due to canceling operation of the database during a search, a subsequent search may generate an error message that states: "C:\path\filename.ext already exists, overwrite?" Simply follow suggestions listed for this error message.

**Too many files open**

FoxPro has attempted to open more than its internal limit of files. This may be caused by the config.sys files statement not being set high enough. Choose to "cancel" the request and check DOS config.sys file (see Appendix B, Installation Instructions).

**Unable to create temporary work file(s)**

The database system has attempted to create temporary work files and was not permitted by the operating system. This is caused by a full directory or a permissions problem concerning access to the system directory.



**APPENDIX D**

**Keywords by Major Topic as of December 16, 1991**

**Appendix D. Keywords by Major Topic as of December 16, 1991**

**ANATOMY**

anatomy  
ankle anatomy  
anthropometry  
foot anatomy  
knee anatomy  
lower extremity morphology  
plantar fascia

**BIOMECHANICS**

barefoot adaptation  
biomechanics  
electromyography  
energy transfer  
load  
modelling  
sensory attenuation

**ENVIRONMENT**

altitude  
cold  
heat  
surface  
terrain

**FOOTWEAR**

hot weather combat boot  
last  
leather combat boot  
orthotics  
running shoe  
shoe construction  
shoe materials  
shoe properties  
shoe testing  
socks

**INJURY**

Achilles tendon disorders  
ankle injury  
bursitis  
cavus foot  
chondromalacia  
compartment syndrome  
crush injury  
foot injury  
foot powder/antiperspirants  
fracture  
friction blister  
frost bite  
iliotibial band syndrome  
injury  
injury rates  
knee injury  
lower extremity disorders  
muscle soreness  
neural injury  
orthotics  
plantar fasciitis  
planus foot  
rheumatic conditions  
shin splints  
stress fracture  
stretching exercises  
trench foot

**PHYSIOLOGY**

cardiorespiratory fitness  
energy economy  
fiber composition  
oxygen consumption

**OTHER**

military training  
physical training  
running