

FILE COPY

2

JULY 1987

ACN 85358

CAORA/TR-3/1

AD-A199 942

**DIVISION
MAP EXERCISE
(DIME 4.0)
VOLUME II**

**DTIC
ELECTE**
S
OCT 06 1988
D

DIME DOCUMENTATION/MODEL

Technical Report CAORA/TR-3/84

**UNITED STATES ARMY
COMBINED ARMS
CENTER**

**COMBINED ARMS
OPERATIONS RESEARCH ACTIVITY
FORT LEAVENWORTH, KS 66027**

DISTRIBUTION UNLIMITED: APPROVED FOR PUBLIC RELEASE

87-3324

30 20 5 06 6



Technical Report CAORA/TR-3/84
May, 1987

ACN 85358

DIVISION
MAP EXERCISE
(DIME 4.0)

VOLUME II

DIME DOCUMENTATION/MODEL

TECHNICAL REPORT CAORA/TR-3/84

Studies and Analysis Directorate
Combined Arms Operations Research Activity
US Army Combined Arms Center
Fort Leavenworth, KS 66027-5230

Approved by:

RONALD G. MAGEE
Director, Scientific and
Technical Support Directorate

REED E. DAVIS, JR.
Deputy, CAORA

DAVID M. MADDOX
Brigadier General, USA
Commander, CAORA

NOTICES

DESTRUCTION NOTICE

When this report is no longer needed, Department of the Army organizations will destroy it in accordance with the procedures given in AR 380-5. Department of Defense contractors will destroy the report according to the requirements of Section 14 of the Industrial Security Manual for Safeguarding Classified Information. All others will return the report to Headquarters, United States Army Training and Doctrine Command.

DISTRIBUTION STATEMENT

In addition to security regulations applicable to this document, each transmittal outside the Department of Defense must have prior approval of the United States Army Training and Doctrine Command. The DIME combat model documentation consists of three volumes. This volume is Volume II, DIME Documentation/Model. The other volumes are Volume I, Game Protocol, and Volume III, Classified Data Base and Data Description. A copy of the DIME model may be obtained by forwarding requests to:

Commander
US Army Combined Arms Operations Research Activity
ATTN: ATOR-CAT-AP (Strong)
Fort Leavenworth, Kansas 66027-5230

DISCLAIMERS

The findings and recommendations of this report are not to be construed as an official Department of the Army position unless so designated by other authorized documents.

ACKNOWLEDGEMENTS

THE Division Map Exercise (DIME) is the fourth enhancement of a battle simulation originally designed to meet the requirements for a quick-running analytical war game. DIME's continued success has resulted from the efforts of many people. In particular, the authors wish to thank MAJ Timothy J. Reischl and Stephan Arrington for their tireless efforts. While at CAORA, Tim conceived the original version of DIME, carrying it through two upgrades and finally laying out most of the model structure for the present version. Stephan Arrington developed the air defense code. The authors would also like to thank Mr. William Ralph of CAORA who edited all three volumes.

Volume I

MAJ (P) Al Resnick
Mr. Jim Schneider
Mrs. Melinda Saunders

Volume II

Mr. Kent Pickett
MAJ Jim Lunn
Mrs. Cindy Dean
Ms. Lori Carr

Volume III

Mrs. Wilma Strong
Mr. Terry Brashley

CONTENTS

TITLE PAGE	i
NOTICES	ii
ACKNOWLEDGEMENTS	iii
CONTENTS	iv
LIST OF FIGURES	viii
LIST OF TABLES	x
ABSTRACT	xii
CHAPTER 1. MODEL OVERVIEW	
1. Background and Purpose	1- 1
2. DIME Overview	1- 2
3. DIME "UNITFILE"	1- 6
4. The DIME Controller	1-15
5. The DIME Hardware	1-15
CHAPTER 2. GAME INITIALIZATION	
1. Purpose	2- 1
2. General	2- 1
3. Data Flow	2- 1
4. File Structure	2- 6
5. Algorithms	2- 7
6. "UNITFILE" Impact	2- 9
7. Code	2- 9
CHAPTER 3. DETECTION	
1. Purpose	3- 1
2. General	3- 1
3. Data Flow	3- 1
4. File Structure	3- 2
5. Algorithms	3-13
6. "UNITFILE" Impact	3-19
7. Code	3-19
CHAPTER 4. LOGISTICS	
1. Purpose	4- 1
2. General	4- 1
3. Data Flow	4- 1
4. File Structure	4- 5
5. Algorithms	4- 6
6. "UNITFILE" Impact	4-12
7. Code	4-13

CONTENTS (CONTINUED)

CHAPTER 5. AIR ATTACK/AIR DEFENSE

1. Purpose	5- 1
2. General	5- 1
3. Data Flow	5- 2
4. File Structure	5- 5
5. Algorithms	5-11
6. "UNITFILE" Impact	5-23
7. Code	5-23

CHAPTER 6. GROUND COMBAT

1. Purpose	6- 1
2. General	6- 1
3. Data Flow	6- 7
4. File Structure	6-11
5. Algorithms	6-18
6. "UNITFILE" Impact	6-46
7. Code	6-46

SECTION I. MINEFIELD ATTRITION

1. Purpose	6-I- 1
2. General	6-I- 1
3. Data Flow	6-I- 2
4. File Structure	6-I- 2
5. Algorithms	6-I- 2
6. "UNITFILE" Impact	6-I- 5
7. Code	6-I- 5

SECTION II. ARTILLERY ATTRITION

1. Purpose	6-II- 1
2. General	6-II- 1
3. Data Flow	6-II- 4
4. File Structure	6-II- 6
5. Algorithms	6-II- 7
6. "UNITFILE" Impact	6-II-11
7. Code	6-II-11

SECTION III. SMOKE

1. Purpose6-III- 1
2. General6-III- 1
3. Data Flow6-III- 1
4. File Structure6-III- 3
5. Algorithms6-III- 4
6. "UNITFILE" Impact6-III- 5
7. Code6-III- 5

CONTENTS (CONTINUED)

SECTION IV. DIRECT FILE ATTRITION

1. Purpose	6-IV- 1
2. General	6-IV- 1
3. Data Flow	6-IV- 1
4. File Structure	6-IV- 2
5. Algorithms	6-IV- 4
6. "UNITFILE" Impact	6-IV- 8
7. Code	6-IV- 8

SECTION V. HELICOPTER OPERATIONS

1. Purpose	6-V- 1
2. General	6-V- 1
3. Data Flow	6-V- 2
4. File Structure	6-V- 6
5. Algorithms	6-V-14
6. "UNITFILE" Impact	6-V-35
7. Code	6-V-35

SECTION VI. PRECISION GUIDED MUNITIONS ATTRITION

1. Purpose	6-VI- 1
2. General	6-VI- 1
3. Data Flow	6-VI- 1
4. File Structure	6-VI- 1
5. Algorithms	6-VI- 4
6. "UNITFILE" Impact	6-VI- 7
7. Code	6-VI- 7

SECTION VII. INFANTRY

1. Purpose	6-VII- 1
2. General	6-VII- 1
3. Data Flow	6-VII- 1
4. File Structure	6-VII- 5
5. Algorithms	6-VII- 5
6. "UNITFILE" Impact	6-VII-11
7. Code	6-VII-11

CHAPTER 7. CHEMICAL ATTRITION

1. Purpose	7- 1
2. General	7- 1
3. Data Flow	7- 1
4. File Structure	7- 3
5. Algorithms	7- 5
6. "UNITFILE" Impact	7- 6
7. Code	7- 7

CONTENTS (CONCLUDED)

CHAPTER 8. COMMAND AND CONTROL

1. Purpose	8- 1
2. General	8- 1
3. Data Flow	8- 1
4. File Structure	8- 2
5. Algorithms	8- 4
6. "UNITFILE" Impact	8- 5
7. Code	8- 5

CHAPTER 9. MOVEMENT GENERATOR

1. Purpose	9- 1
2. General	9- 1
3. Data Flow	9- 2
4. File Structure	9- 5
5. Algorithms	9-11
6. "UNITFILE" Impact	9-14
7. Code	9-15

CHAPTER 10. UNIT STATUS REPORT

1. Purpose10- 1
2. General10- 1
3. Data Flow10- 1
4. File Structure10- 5
5. Algorithms10- 6
6. "UNITFILE" Impact10- 9
7. Code10- 9

CHAPTER 11. UTILITY ROUTINES

1. Purpose11- 1
2. Create Routines11- 1
3. "UNITFILE" Utilities11- 1
4. Create/Zeroing Routines11- 1
5. "OMNI" Data File Utilities11- 2
6. Off-line Loss Assessment (P6)11- 5
7. Code11- 5

LIST OF FIGURES

<u>Figure</u>	<u>Page</u>
1- 1 DIME program structure	1- 3
1- 2 The DIME controller logic flow	1-18
1- 3 DIME input menu	1-19
1- 4 Executive controller code	1-20
2- 1 Game initialization program menu	2- 2
2- 2 Game initialization information flow	2- 3
2- 3 Unit input sheet	2- 4
2- 4 Game initialization logic flow	2- 8
3- 1 Detection data flow	3- 7
3- 2 Example use of intelligence threshold data	3-16
3- 3 Detection menu selection diagram	3-20
4- 1 Logistics data flow	4- 2
4- 2 Logistics logic flow	4- 7
5- 1 Air defense information flow	5- 3
5- 2 Air defense data bases	5- 6
5- 3 Air defense logic flow	5-12
5- 4 Air defense functional flow diagram	5-25
6- 1 Phase I, Blue force movement to contact	6- 3
6- 2 Phase II, direct fire battle	6- 4
6- 3 Phase III, Red force withdrawal to new reserve position	6- 5
6- 4 Information flow for ground combat program	6- 8
6- 5 An example of system losses following a 2 1/2 hour battle	6-12
6- 6 An example of the 30-minute battle updates	6-13
6- 7 DIME ground combat generalized logic flow	6-19
6- 8 Generalized logic flow for initialization of force structure in subroutine Set_battle	6-21
6- 9 Generalized logic flow for initialization of battle parameters and 6-hour artillery ammunition allocation found in subroutine Set_battle	6-25
6-10 DIME logic flow for helicopter allocation found in subprogram Helo_arrive	6-30
6-11 Logic flow for 30-minute allocation of artillery, MLRS/MRL and mortar volleys in subroutine Set_battle	6-33
6-12 Graphic depiction of procedure for close support (CS) indirect fires	6-38
6-13 Logic flow for 30-minute calculation found in subroutines Calc_movement and Mine_encounter	6-41
6-14 Minefield attrition information flow	6-I- 3
6-15 Minefield attrition logic flow	6-I- 4
6-16 Minefield attrition functional flow	6-I- 6
6-17 Logic flow of indirect fire subroutine Arty_sub	6-II- 2
6-18 Schematic of notionalized artillery target	6-II- 3
6-19 Data flow of indirect fire attrition module Arty_attrit	6-II- 5
6-20 Generalized functional flow of Arty_attrit	6-II-12
6-21 Data flow for smoke routines	6-III- 2

LIST OF FIGURES
(CONCLUDED)

<u>Figure</u>	<u>Page</u>
6-22 Generalized flow of smoke module	6-III- 7
6-23 Generalized flow of Allocate_smoke routine	6-III- 8
6-24 Generalized flow of W_smoke routine	6-III- 9
6-25 Generalized flow of Smoke_emp routine.	6-III-10
6-26 Generalized flow of routine Smoke.	6-III-11
6-27 Direct file data flow	6-IV- 3
6-28 Direct file logic flow	6-IV- 5
6-29 Direct file functional flow	6-IV- 9
6-30 Direct file functional flow of Calc_losses	6-IV-11
6-31 Data flow for helicopter attrition module.	6-V- 3
6-32 Helicopter file hierarchy	6-V- 7
6-33 Generalized logic flow of helicopter attrition module.	6-V-15
6-Va Helicopter to helicopter ranges	6-V-16
6-Vb Blue ground to Red helicopter ranges	6-V-17
6-Vc Red ground to Blue helicopter ranges	6-V-18
6-34 Functional flow of helicopter attrition module	6-V-36
6-35 PGM data flow	6-VI- 2
6-36 PGM logic flow	6-VI- 5
6-37 PGM functional flow	6-VI- 8
6-38 Infantry data flow	6-VII- 4
6-39 Generalized infantry logic flow	6-VII- 6
6-40 Ground combat personnel casualty losses for defending forces	6-VII- 8
6-41 Ground combat personnel casualty losses for attacking forces	6-VII-10
7- 1 Chemical attrition input sheet	7- 2
7- 2 Chemical data flow	7- 4
7- 3 Chemical logic flow	7- 6
7- 4 Chemical functional flow	7- 8
8- 1 Command and control data flow	8- 3
8- 2 Command and control data flow.	8- 6
9- 1 Troop movement data flow	9- 3
9- 2 Conceptual map of routes to fly	9- 6
9- 3 Cargo transport data flow	9- 7
9- 4 General flow of troop movement phase	9-16
9- 5 General flow of helicopter cargo movement phase	9-17
10- 1 Unit history output	10- 2
10- 2 Killer/victim scoreboard	10- 3
10- 3 Gamer/staff worksheet.	10- 4
10- 4 Unit status report data flow	10- 6
10- 5 Unit status report logic flow	10- 7

LIST OF TABLES

<u>Table</u>	<u>Page</u>
1- 1 The DIME "UNITFILE" Structure	1- 7
1- 2 The DIME element list structure	1-13
1- 3 Example of weapons lists in the DIME "UNITFILE"	1-14
1- 4 Impact of DIME programs on "UNITFILE" entries	1-16
1- 5 Hardware configuration of the DIME model	1-21
2- 1 Game initialization subroutine table	2-11
2- 2 Game initialization code	2-15
3- 1 Detection data support programs	3- 3
3- 2 Fractional target exposure criteria	3- 4
3- 3 Red intelligence thresholds	3- 4
3- 4 Blue intelligence thresholds	3- 5
3- 5 Time intervals between unit movements to avoid detection	3- 6
3- 6 Detection subroutine table	3-23
3- 7 Detection code	3-27
4- 1 Logistics "UNITFILE" inputs	4- 3
4- 2 Logistics "UNITFILE" updates	4-14
4- 3 Logistics subroutine table	4-17
4- 4 Logistics code	4-22
5- 1 "UNITFILE" variables affected by air defense	5-24
5- 2 Air defense subroutine table	5-29
5- 3 Air attack/air defense code	5-39
6- 1 Blue target indirect fire templates (Iifim) and indirect fire delta templates (Difim)	6-24
6- 2 Possible allocations for Blue and Red indirect fire (IF) volleys	6-26
6- 3 Firing range conditions for various tasks in DIME indirect fire allocation module	6-27
6- 4 On-site scheduling table for various numbers of helicopter cells	6-31
6- 5 Subroutine table for ground combat driver routine.	6-50
6- 6 Minefield attrition subroutine table	6-I- 8
6- 7 Artillery subroutine table	6-II-16
6- 8 Smoke subroutine table	6-III-12
6- 9 Direct fire subroutine table	6-IV-13
6-10 Helicopter subroutine table	6-V-57
6-11 PGM subroutine table	6-VI-10
6-12 Infantry force multipliers	6-VII- 3
6-13 Infantry subroutine table	6-VII-13
6-14 Ground combat code	6-VII-16

LIST OF TABLES

<u>Table</u>		<u>Page</u>
7- 1	Chemical subroutine table	7- 9
7- 2	Chemical code	7-13
8- 1	Command and control subroutine table	8- 7
8- 2	Command and control code	8-11
9- 1	Troop movement subroutine table	9-25
9- 2	Cargo transport subroutine table	9-31
9- 3	Movement code	9-39
9-3a	ADEA movement code	9-75
10- 1	Unit status report subroutine table	10-11
10- 2	Unit status report code	10-16
11- 1	"CR_NAME" program	11- 6
11- 2	"CR_TOE" program	11- 7
11- 3	"CR_UNIT" program	11- 8
11- 4	"NAMEDUMP" program	11- 9
11- 5	"STRENGTH" program	11-10
11- 6	"EFFECTIVE" program	11-12
11- 7	"CR_KV" program	11-14
11- 8	"CR_HELO" program	11-15
11- 9	"AIRPLANE" program	11-16
11-10	"CR_CHEM" program	11-19
11-11	Off-line assessment code	11-20

ABSTRACT

The Division Map Exercise (DIME) is a comprehensive, computer-assisted war game designed to portray the significant aspects of Air-Land Battle operational doctrine for the Army's primary division strike force structures. It was developed in response to a need for a quick-running low resolution battle simulation with which to address critical analytical combat development questions. Using a map board, a set of computer algorithms and manual rules, DIME portrays the important aspects of the modern battlefield which must be considered in the context of the Air-Land Battle. These include ground combat, air operations and air defense, maneuver, command and control, chemical effects and logistics.

The DIME combat model documentation consists of three volumes. This volume is Volume II, DIME Documentation/Model. The other volumes are Volume I, Game Protocol, and Volume III, Classified Data Base and Data Description.

CHAPTER 1

MODEL OVERVIEW

1. BACKGROUND AND PURPOSE.

A. One of the roles of the Combined Arms Operations Research Activity (CAORA) in Army analysis is to determine the effectiveness of tactical and doctrinal innovations for corps and division-level forces. In performing this role, CAORA is often required to develop division-level combat simulations or war games to be used as study tools. In December 1982, the Deputy Undersecretary of the Army for Operations Research (DUSA/OR) office requested that CAORA build a division-level war game to be used in the effectiveness evaluation of the High Technology Light Division (HTLD). The game was to be used in a study comparing HTLD and a conventional light infantry division.

The design criteria for the war game were:

(1) The model must fairly represent the ability of HTLD to execute the innovative tactics and maneuverability associated with the division's advanced equipment and organizational structure.

(2) The game should be "transportable" so it can be moved to Ft. Lewis for play by HTLD personnel.

(3) The game should play six hours of division combat to include resupply within one 8-hour working day.

The Division Map Exercise (DIME) was the result of an eight-month software development effort by CAORA. It was completed in October 1983 and used as CAORA's principal wargaming tool to evaluate the High Technology Light Division.

B. This document is a programmer's manual for DIME. It contains a general description of the play of the war game (a complete description can be found in the DIME Volume I, Game Protocol) and a list of the hardware necessary to run the game. This manual also contains the methodology used in the combat simulation and software documentation to include logic/data flows, variable descriptions and program listings.

C. This volume is organized into 11 chapters. This chapter contains a description of the overall model structure, the unit status file ("UNITFILE"), and the computer hardware necessary to operate the model. Chapters 2 through 11 contain documentation for the programs forming the DIME software system.

2. DIME OVERVIEW.

A. The Division Map Exercise (DIME) is a computer-assisted map exercise representing forces of up to a Blue Division engaging a Red Army. The location, movement, and deployment of the forces is represented by unit symbols placed on a 1:50,000 map. The model is ideally structured for units of Blue Battalions and Red Regiments. However, units to the resolution of brigade command posts and brigade fuel/ammunition (POL/AMMO) dumps can also be accommodated in the model. Red and Blue gamers are required to plan the distribution of ammunition and POL to all units for a six-hour period. They also maneuver their forces and structure the battles initiated during the six-hour period. The DIME model uses a set of computerized attrition and detection algorithms to determine elements surviving unit engagements. Likewise, resupply algorithms are used to maintain the current levels of ammunition and POL available to the units.

B. The structure of the model is shown in Figure 1-1. The DIME model consists of a set of BASIC software programs representing each functional aspect of the division battle. These programs operate independently, interacting only through a common unit status file containing one record for each unit. The programs are also supported by random access files containing weapon effects data (e.g., probability of kill, movement rates, etc.). The DIME programs are accessed from a menu-driven executive controller program shown in Figure 1-4 of this chapter. The normal play of six hours of division combat requires use of the programs in the following order:

(1) The game initialization program (P1). At the beginning of each six-hour gaming period, the user may update any of the records on the unit status file ("UNITFILE"). It is often necessary to change a unit's mission, resupply its ammunition and POL, and cross-attach or add combat elements to the unit. This is done with the menu-driven game initialization program (P1). If it is necessary to resupply a unit, this program must be run before the logistic support program (P2).

(2) The logistic support program (P2). This program also interacts with the "UNITFILE" to disperse the ammunition and POL available for use by each unit during the six-hour gaming period. The quantities resupplied to each unit (specified during the running of P1) are moved into an "available for consumption" status (see entries 131 through 133 on the "UNITFILE"). The logistics support program (P2) must be run after P1 and prior to any other DIME programs. If P2 is not run, available ammunition and POL will not be placed in the proper "UNITFILE" entries and the artillery, air defense, and direct fire systems will not fire in the DIME combat programs (P3 and P4).




Figure 1-1. DIME program structure.

(3) The air attack/air defense program (P3). This program calculates the losses to both air and ground elements for fixed-wing air attacks on the DIME units. The program also provides losses to both helicopters and fixed-wing aircraft when air defense (AD) units are inadvertently overflowed during ingress/egress to a target. The program must be run once for each air/ground attack that occurs during the six-hour period. These runs should occur before ground combat sectors are played. The model outputs element losses in both hard copy for game use and updates the DIME "UNITFILE". The model also updates air defense ammunition consumption on the unit status file.

(4) The ground combat program (P4). This program calculates losses to helicopters and ground elements resulting from ground combat engagements during the six-hour gaming period. The program requires as input those units engaged in combat plus a set of parameters describing Red and Blue command decisions influencing the battle; e.g., opening range for artillery and direct fire systems and break ranges for potential overrun situations. The ground combat module must be executed for each sector battle that occurs during the six-hour gaming period. The model outputs a hard copy of each battle history containing half-hour updates on force movements, helicopter attack status, and indirect fire tonnage consumptions. A killer/victim scoreboard is output at the end of the battle, summarizing losses to each force. The module also updates the "UNITFILE" with element losses and ammunition consumption for the engaging units.

(5) The chemical combat program (P5). The chemical program calculates losses to exposed forces attacked with artillery-delivered chemical munitions. The losses represent those incurred during the first 15 seconds of chemical attack while the unit is moving into a mission-oriented protective posture (MOPP) status. The program posts losses to the "UNITFILE" and updates the MOPP status of the unit. The chemical program is included in this manual for the sake of completeness. At the writing of this documentation, it has not been debugged nor used in a CAORA study. Anyone desiring to use this program is encouraged to contact one of the authors prior to its use.

(6) The detection program (P7). The detection program provides a list of detected units to both Red and Blue commanders. The list actually represents the commander's intelligence map and shows units on the opposing force as either:

- (a) not detected,
- (b) detected but not identified as to mission and composition,
- (c) identified mission and composition, or
- (d) lost, previously detected, but friendly sensors unable to track.

Although DIME is played as an open game, it is structured for closed play with the detection lists representing the current status of the friendly

commander's knowledge of enemy positions. These lists are used by the gamers to plan attacks on enemy units in the next six hours and to justify placing units in defensive missions when detected enemy units are approaching. The detection lists are also used by DIME controllers in selecting "not detected" enemy units which are overflown by friendly forces during an air strike. The units are input to the air attack module (P3) for overflight and possible air interdiction by overflown air defense elements.

(7) The unit status report (P8). Following the running of all ground combat and air strike battles for current six hours of combat, preparations begin for running the next six hours of combat. This process involves DIME programs P8, P7, and P9. The unit status report (P8) provides a status listing of all units currently in play. The listing includes the number of elements currently in the unit, ammunition and POL currently available to the unit, and the current mission of the unit. The report is used by the gamers to determine which units should be resupplied with both equipment and ammunition/POL. P8 also generates game forms for the resupply of each unit. These forms are used as input documents to P1. The unit status report also generates a "Game Run Summary" showing total losses of equipment across the division for the preceding six-hour period.

(8) The movement program (P9). The movement program calculates the time required to move units across several types of terrain or by helicopter to deployed positions specified by the gamers. Note that the movement represented by this program is of a strategic nature rather than the maneuver that occurs during combat (P4 calculates movement times during combat). Inputs to the model consist of the unit being moved and the distance it must travel to reach final deployment. Output from the model consists of the arrival time of the first element in the unit and the arrival time of the last element. In cases where the helicopters have been used to aid in movement of equipment and personnel, output also contains the number of helicopter sorties flown.

(9) The command and control program (P10). This program produces the time required for the command element to send a message changing the mission of a subordinate unit and for the subordinate unit to execute the mission change. Inputs to the program consist of the level of the command unit, the level of the subordinate unit, and the desired and current mission of the subordinate unit. Output is the time to affect the mission change. The command and communication nets are not explicitly modeled, but rather, the program uses a simple "table look-up" structure.

3. THE DIME "UNITFILE".

A. The DIME "UNITFILE" is central to the operation of all programs. The model currently will support 191 Blue units (the first 191 records on the file) and 209 Red units. Each unit record contains 150 entries describing the number of weapon systems in the unit, its ammunition/POL status, and its current mission. Table 1-1 provides a brief description of each entry in the "UNITFILE".

B. Elements 1 - 70 in the "UNITFILE" contain the weapons list for the unit. The structure of this list requires that systems performing certain battlefield functions be placed in specific positions on this list. Table 1-2 shows these system functions for each position for both the Blue and Red units. Typical systems are shown in Table 1-3.

(1) Direct fire platforms. Entries 1 - 20 (Table 1-2) for both Red and Blue contain the number of elements which are direct fire platforms. These locations are interrogated by the combat program (P4) for play in the direct fire portion of the battle. Note that locations 16 - 20 also serve as infantry carriers. P4 "mounts" and "dismounts" infantry personnel into these locations depending on unit mission and proximity to the enemy force.

(2) Artillery. The number of artillery elements are held in locations 21 - 27. DIME plays only one caliber of artillery for Blue and one for Red.

(3) Mortars. Entries 28 - 31 contain the number of mortars available to both Blue and Red units.

(4) MLRS/MRL. The number of multiple launch rocket systems (MLRS) for a Blue unit and the number of multiple rocket launchers (MRL) for a Red unit are contained in entries 32 - 35.

(5) Infantry personnel. Positions 36 - 40 contains the infantry personnel which serve as the pool for mounting/dismounting vehicles in locations 16 - 20. Other small arms are located in positions 41 - 47. Infantry personnel are allowed to participate in the battle only during the last 500 meters to closure.

(6) Air defense systems. Air defense systems must be placed in entries 48 - 54. Only hand-held type systems can be placed in entries 53 - 54, while entries 48 - 52 contain only vehicular type systems.

(7) Tank trucks. The number of fuel trucks located in entry 55 and tank trucks in entry 56 are used by the logistics program (P2) to calculate fuel hauling capacity. Water trucks are in position 57.

(8) Cargo trucks. The number of cargo trucks located in entry 58 and 59 are used by the logistics program to calculate the cargo hauling capacity of the unit.

Table 1-1. The DIME "UNITFILE" structure.

The "UNITFILE" for the Division Map Exercise (DIME) consists of 400 records, each containing 150 elements. The assignment of records consist of:
 records 1 - 191 Blue units
 records 192 - 400 Red units.

Elements are assigned to each unit record as follows:

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
1 - 70	Weapons list	The 70 weapon quantities contained in the units (see Table 1-2).
71 - 74	Vacant	
75	Major mission	1 = Attack 2 = Defend 3 = Reserve/idle 4 = Move
76	Unit size/echelon	1 = Blue battalion/Red regiment 2 = Blue company/Red battalion
77	Unit MOPP level	1 = Unit not in MOPP 2 = Unit in MOPP
78	Unit type (X.Y)	X = Player 1 = Blue 2 = Red Y = Unit type 0 = Combat unit 1 = Artillery unit 2 = Air defense (ADA) unit 3 = Attack helicopter ground/forward rearming and refueling point (FARP) 4 = Commandpost/headquarters (CP/HQ) 5 = Engineer unit 6 = POL/AMMO supply point 7 = Maintenance point 8 = Surface-to-air missile (SAM) site 9 = Communications/radar/electronic warfare (EW) site

Table 1-1. The DIME "UNITFILE" structure (continued).

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
79	Unit effectiveness	Percent unit effectiveness as a function of surviving weapons and personnel
80	Percent ADA suppressed (XX.YY)	XX = Vehicle ADA systems suppressed YY = Handheld systems suppressed
81	Supporting corps ADA unit	
82	Activity code	Status of unit 0 = Not active in game 1 = Active
83	Mission status	Represents Blue/Red mission during current 6-hour period MISSIONS: 0 = Meeting Engagement 1 = Indirect Fire 2 = Movement 3 = Frontal Attack 4 = Envelopmental Attack 5 = Delay 6 = Hasty Defense 7 = Prepared Defense 8 = Reserve/Rear Area 9 = Ambush
84	Cargo trucks alive at start of turn	
85	Fuel trucks alive at start of turn	
86	JP4 trucks alive at start of turn	
87	Vacant	

Table 1-1. The DIME "UNITFILE" structure (continued).

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
88	Vacant	
89	Sensor status	<p>X = POTA zone values (1-5) for sensor (X,Y) group Y. Y = Sensor group (0-4) detecting this particular unit. 0 = Not covered 1-3 = Applicable Blue/Red sensor group 4 = Linear FEBA-oriented sensor array</p> <p>NOTE: Default for sensor status = 1.4 POTA = probability of operational target acquisition. FEBA = forward edge of battle area.</p>
90	Unit fraction covered by sensor group	Value from 0-1.0
91	Detection status (X,Y)	<p>X = Hours left until redetected Y = Unit status with respect to detection by the opposite commander 0 = Not detected 1 = Detected but not verified 2 = Acquired/verified 3 = Lost</p>
92	Intelligence status	Total hours this target has been tracked this detection period
93 - 94	Vacant	
95 - 100	Enemy sensors detecting this unit	
101	Fuel status of unit vehicles	Value from 0-1.0
102	Fuel status of helicopters	Value from 0-1.0

Table 1-1. The DIME "UNITFILE" structure (continued).

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
103	Fuel on tankers (gallons)	
104	JP4 on tankers (gallons)	
105	Fuel on ground (gallons)	
106	JP4 on ground (gallons)	
107	Fuel use profile	
108	Fuel consumed (gallons)	
109	JP4 consumed (gallons)	
110	Fuel resupplied (gallons)	
111	JP4 resupplied (gallons)	
112	Fuel dispensed to other units	
113	JP4 dispensed to other units	
114	Vacant	
115	Helo ammo at beginning of CI	
116	DF at beginning of CI	
117	IF at beginning of CI	
118	AD at beginning of CI	
119	Direct fire ammo status (vehicles)	Value 0-1.0
120	Indirect fire ammo status (vehicles)	Value 0-1.0
121	Air defense ammo status (vehicles)	Value 0-1.0

Table 1-1. The DIME "UNITFILE" structure (continued).

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
122	Helicopter ammo status	Value 0-1.0
123	Ammo on cargo vehicle, short tons (STONS)	
124	Distribution of cargo by type (XXX.YYY)	XXX = DF ammo percent (XXX = XX.X%) YYY = IF ammo fraction (YYY = YY.Y%)
125	Ammo on ground (STONS)	
126	Distribution of ground ammo by type (XXX.YYY)	XXX = DF ammo percent (XXX = XX.X%) YYY = IF ammo fraction (YYY.Y%)
127	DF ammo use profile	
128	IF ammo use profile	
129	AD ammo use profile	
130	Helicopter ammo use profile	
131	DF ammo available to be consumed	
132	IF ammo available to be consumed	
133	AD ammo available to be consumed	
134	Helo ammo available to be consumed	
135	Ammo resupplied (STONS)	
136	Ammo resupply profile (XXX.YYY)	XXX = DF ammo percent (XXX = XX.X%) YYY = IF ammo fraction (YYY = YY.Y%)
137	Ammo dispensed to other units	

Table 1-1. The DIME "UNITFILE" structure (concluded).

<u>Element number</u>	<u>Description</u>	<u>Default value</u>
138	Dispensed ammo profile (XXX.YYY)	XXX = DF ammo percent (XXX = XX.X%) YYY = IF ammo fraction (YYY = YY.Y%)
139	Cumulative DF ammo consumed to date	
140	Cumulative IF ammo consumed to date	
141	Cumulative AD ammo consumed to date	
142	Cumulative helo ammo consumed to date	
143	Fuel consumed to date	
144	JP4 consumed to date	
145	Vacant	
146	KM traveled this turn	
147	Fuel left	
148	JP4 fuel left	
149 - 150	Vacant	

Table 1-2. The DIME element list structure.

<u>Number</u>	<u>Element Type</u>
1 - 15	Direct Fire Platform
16 - 20	Direct Fire Platform (Infantry Carrier)
21 - 27	Artillery
28 - 31	Mortar
32 - 35	MLR/MRL
36 - 40	Small Arms (Infantry for DF Carrier)
41 - 47	Small Arms
48 - 52	ADA
53 - 54	ADA (Hand-held)
55	Fuel Truck
56	JP4 Fuel Truck
57	Water Truck
58	Ammo Truck
59	Non-ammo Truck
60 - 61	E/W Truck
62	Mine Clearing Equipment
63	Obstacle Clearing Equipment
64	AVLB
65	Pontoon Bridge
66 - 67	Engineer Equipment
68 - 70	Material Handling Equipment

Table 1-3. Example of weapon lists in the DIME "UNITFILE".

<u>Element Number</u>	<u>HTLD</u>	<u>C-SERIES</u>	<u>THREAT</u>
1	LAV/25-TOW	M1	T72
2	FAV/TOW	M2	Vacant
3	HMMWV/TOW	M3	BMP 81
4	FAV/40	ITV	Vacant
5	HMMWV/40	HMMWV/TOW	BFDM-2
6	Vacant	HMMWV/40	BRDM-AT
7	DRAGON	DRAGON	AT4
8	Vacant	Vacant	ASU-85
9	Vacant	Vacant	BMD
10	Command Vehicle	Command Vehicle	Command Vehicle
11 - 15	Vacant	Vacant	Vacant
16	Vacant	Vacant	BMP
17	Vacant	Vacant	BTR
18 - 20	Vacant	Vacant	Vacant
21	155MM	155MM	152MM
22 - 27	Vacant	Vacant	Vacant
28	107MM	181MM	120MM
29 - 31	Vacant	Vacant	Vacant
32	MLRS(T)	MLRS(Sp)	MRL
33 - 35	Vacant	Vacant	Vacant
36	Viper	Viper	RPG-16
37 - 47	Vacant	Vacant	Vacant
48	VULCAN	DIVAD	XSU-X
49	ICHAP(T)	ICHAP(Sp)	SA-13
50	IHAWK	IHAWK	SA-8
51 - 52	Vacant	Vacant	Vacant
53	Stinger Post	Stinger Post	SA-14
54	Vacant	Vacant	Vacant
55	Fuel Truck	Fuel Truck	Fuel Truck
56 - 57	Vacant	Vacant	Vacant
58	Cargo Truck	Cargo Truck	Cargo Truck
59 - 61	Vacant	Vacant	Vacant
62	Sp. Vehicle	Sp. Vehicle	Sp. Vehicle
63 - 70	Vacant	Vacant	Vacant

(9) Special vehicles. The number of special vehicles must be placed in positions 60 - 70 of the "UNITFILE". These locations are reserved for vehicles that support combat (i.e. bridging equipment, communication vans, mine clearing equipment) but are not usually involved in direct combat. These vehicles are subject to attrition from artillery, helicopters, and direct fire systems. The importance of maintaining the functional positions of each system on the "UNITFILE" cannot be overemphasized. The DIME programs have been constructed to access "expected" systems in these functional positions to perform these roles in battle.

C. All DIME programs except command and control (P10) and movement (P9) interface with the "UNITFILE" records at the time of this writing. Movement (P9) as shown in Table 1-4 is capable of accessing the "UNITFILE" but is not currently operational. Table 1-4 lists the programs showing the elements on the unit record serving as program input and the elements which are updated by the program and returned as output to the "UNITFILE".

4. THE DIME CONTROLLER.

A. The DIME controller (P0) serves as the menu-driven executive routine calling each of the DIME programs. The general logic flow of the controller is quite simple and is shown in Figure 1-2. The user is required to input the desired program from the DIME menu shown in Figure 1-3. The chosen program is loaded and execution begins. Following execution of the program, control is returned to the menu for other program selections. If the QUIT option is invoked from the menu, the executive controller closes all files and terminates operations.

B. A listing of the BASIC code for the DIME executive controller is found in Figure 1-4.

5. THE DIME HARDWARE.

The DIME system was built for operation on a Hewlett Packard HP 9816. The original configuration consisted of the 9816, a printer, one floppy disk and a Winchester disk. The HP extended BASIC is also required. Table 1-5 contains a detailed listing of the hardware necessary to execute the program. Subsequent versions of the DIME combat program (P4), currently available at CAORA, have required expanded memory hardware. This has also been listed in the table under expanded hardware requirements.


Table 1-4. Impact of DIME programs on "UNITFILE" entries.

DIME program	"UNITFILE" record elements		Description of program principal activity on "UNITFILE" record
	Input	Output	
Game initialization (P1)	1-150	1-70, 75, 78-83, 89, 90, 101, 103, 105, 107, 110, 119-121, 123-129, 135-138	Program constructs and updates basic unit attributes of number of elements, mission and amount of AMMO/POL on hand.
Logistic support program (P2)	1-70, 75, 78, 101, 103, 105, 110, 112, 119-121, 123-126, 135-138	62-63, 84-85, 101, 103, 105, 108, 116-121, 123-126, 131-133, 139-141, 143, 147	Program calculates AMMO/POL consumed for non-combat functions, updates current levels of AMMO/POL and places available ammunition in locations 131 to 133 for use by P3 and P4.
Air attack/air defense program (P3)	1-70, 75, 78, 123, 126, 133	1-70, 91-92, 125-126, 133	Program calculates losses to weapons on "UNITFILE" (1-70), and air defense AMMO consumed (133). These values are then updated along with previously undetected overflown units (91, 92).
Ground combat program (P4)	1-70, 75-78, 83, 131-133	1-70, 131-133	Program calculates losses to weapons as "UNITFILE" (1-70) and the amount of direct fire, air defense and indirect fire ammunition consumed (131-133) and updates these values on the "UNITFILE".
Chemical combat program (P5)	1-70, 75, 77, 78	1-70, 77	Program calculates losses to weapons on "UNITFILE" (1-70) from chemical attack based on mission (75), unit type (78) and MOPP level (77). Updated weapons lists (1-70) and MOPP level (77) are output to "UNITFILE".

Table 1-4. Impact of DIME programs on "UNITFILE" entries (concluded):

DIME program	"UNITFILE" record elements		Description of program's principal activity on "UNITFILE" record
	Input	Output	
Detection program (P7)	1-70, 75, 78, 83, 91, 92	91, 92	Program determines number of elements exposed to sensors based on unit mission and location from sensor. Program then calculates and updates unit detection status (91) and hours unit has been tracked by friendly sensors (92).
Movement program (P9)*	1-70, 75, 77	146	Program calculates the time to move elements described in weapon lists (1-70) the distance specified by gamer. Total distance moved by unit (146) is updated to "UNITFILE".
Unit status report (P8)	1-150	101, 107-113, 119 - 141	Program uses the entire "UNITFILE" to provide a hard copy summary of the unit. The program calculates and updates parameters describing current ammunition levels following 6 hours of divisional activities.

*Not currently operational with the "UNITFILE".



*Game post-processor not currently used.

Figure 1-2. The DIME Executive Controller Logic Flow is menu driven allowing the user to select any module for use.

```

DDDDDDD      III      M      M      EEEEEEEEE
D      D      I      MM      MM      E
D      D      I      M M      M M      E
D      D      I      M MMM      M      EEEEEEE
D      D      I      M      M      E
D      D      I      M      M      E
D      D      I      M      M      E
DDDDDDD      III      M      M      EEEEEEEEE

```

PROGRAM MENU (GAME VERSION)

- | | |
|---------------------------|--------------------------------|
| 1. DATA OPERATIONS | 7. DETECTION/TARGET LIST |
| 2. LOGISTICS | 8. CONSOLIDATE/TURN SUMMARY |
| 3. AIR ATTACK/AIR DEFENSE | 9. MOVEMENT CALCULATOR |
| 4. GROUND COMBAT | 10. COMMAND/CONTROL CALCULATOR |
| 5. CHEMICAL COMBAT | 11. GAME POST PROCESSOR * |
| 6. UNIT LOSS ASSESSMENT | 12. QUIT!!!!!!!!!!!!!! |

* GAME POST PROCESSOR not currently used.

Figure 1-3. DIME input menu.

```

10 !!! "DIME" IS THE MENU CONTROL PROGRAM FOR THE DIVISION MAP EXERCISE
20 ! (DIME). DIME WAS DEVELOPED BY THE OPNS ANALYSIS BRANCH OF THE
30 ! COMBINED ARMS OPERATIONS RESEARCH ACTIVITY. THE CHIEF OF THE
40 ! PROJECT IS MR. H. KENT PICKETT, A/V 552-4613. THE PROGRAM LAST
50 ! CHANGED ON 15 SEPT 83
60 !
70 Disk$=":9134,704,0"
80 PRINTER IS 1
90 PRINT USING "@,#"
100 PRINT TABXY(1,1),TAB(17),"DDDDDDD III M M EEEEEEEEE"
110 PRINT TAB(17),"D D I MM MM E"
120 PRINT TAB(17),"D D I M M M M E"
130 PRINT TAB(17),"D D I M MMM M EEEEE"
140 PRINT TAB(17),"D D I M M E"
150 PRINT TAB(17),"D D I M M E"
160 PRINT TAB(17),"D D I M M E"
170 PRINT TAB(17),"DDDDDDD III M M EEEEEEEEE"
180 PRINT
190 PRINT TAB(24),"PROGRAM MENU ( CONTRACT BENCH )"
200 PRINT
210 PRINT "1. DATA OPERATIONS ",TAB(40),"7. DETECTION/TARGET LIST"
220 PRINT "2. LOGISTICS ",TAB(40),"8. CONSOLIDATE/TURN SUMMARY"
230 PRINT "3. AIR ATTACK/AIR DEFENSE",TAB(40),"9. MOVEMENT CALCULATOR"
240 PRINT "4. GROUND COMBAT",TAB(40),"10. COMMAND/CONTROL CALCULATOR"
250 PRINT "5. CHEMICAL COMBAT",TAB(40),"11. GAME POST PROCESSOR"
260 PRINT "6. UNIT LOSS ASSESSMENT",TAB(40),"12. QUIT!!!!!!!!!!!!!!!!"
270 INPUT "TYPE DESIRED PROGRAM NUMBER, PRESS ENTER: ",S$
280 IF S$="12" THEN GOTO Halt
300 LOAD "NEW_P"&S&&Disk$
310 Halt: !
320 PRINT USING "@,#"
330 END

```

Figure 1-4. Executive controller code.

Table 1-5. Hardware configuration for the DIME model.

Hardware Description	
HP9816 Computer	The HP9816 computer is a member of the HP series 200 family of personal technical computers. It supports a number of programming languages and operating systems, and has the capacity to link up to diverse peripheral devices.
HP9121 D/S Disc Memory	The HP9121 D/S Disc memories are random access data storage devices. The HP 9121S contains a single 3 1/2-inch disc drive providing 286.72 Kbytes of storage capacity. The HP9121D contains two 3 1/2-inch disc drives providing a total storage capacity of 573.44 Kbytes.
HP9134A Disc Memory	The HP9134A disc memory is a random access data storage device containing a 5 1/4-inch Winchester disc drive providing 4.6 Mbytes of storage capacity.
HP82905B Printer	The HP82905B Printer is a general purpose printer featuring 80 character per second bi-directional printing. The printer utilizes a 9x9 dot matrix character format. It prints in 40, 66, 80, or 132 columns. You can choose among normal, expanded, compressed, or compressed expanded characters. Normal size character may also be emphasized. The printer has a graphics mode which has the ability to print illustrations, charts, graphs, block letters, etc. using patterns of dots under software control. Functions such as line spacing, form length, and skip over perforation are also under software control.
HP9888A Bus Expander	The HP 9888A Bus expander allows for connecting up to eight interface cards and eight memory cards or up to 16 memory cards to HP Series 200 Personal Technical Computers, using an I/O slot in the computer.

CHAPTER 2

GAME INITIALIZATION

1. PURPOSE.

The purpose of the DIME game initialization program (P1) is to create and edit the unit status file ("UNITFILE"). Listings of the "UNITFILE" may also be obtained through this program, along with many other options.

2. GENERAL.

This program deals with a 400-record "UNITFILE". Records 1-191 are reserved for Blue units and records 192-400 are reserved for Red units. The program consists of 10 subroutines that run from the menu which appears at the beginning of the program (see Figure 2-1).

3. DATA FLOW.

A. Input data. Data for this program comes through two means, data files and input data (see Figure 2-2).

(1) Data files. All data files are external to the program and stored on the hard disk. These consist of the "UNITFILE", the table of organization/equipment ("TOEFILE"), the "NAMEFILE", the ammunition capacities file, the fuel capacities file, system effectiveness files and weapon type files.

(2) Input data. Data is input to this program by means of the unit input sheets and the gamer/staff worksheets.

(a) The unit input sheets are used to create an original "UNITFILE." Figure 2-3 displays the unit input sheet. Option 12 ("Enter initial unit status") should be chosen in order to input these sheets.

1. Unit #. Represents the record number for the "NAMEFILE" being created.

2. Side. A number representing the side (Blue = 1, Red = 2). This number is stored in the "TOEFILE" (position 72) as a whole number.




Figure 2-1. Game initialization program menu.




Figure 2-2. Game initialization information flow.

UNIT INPUT SHEET

** UNIT TYPE **

UNIT NO.	SIDE	UNIT TYPE
<input type="text"/>	<input type="text"/>	<input type="text"/>

- 0: COMBAT
- 1: ARTILLERY
- 2: AIR DEFENSE
- 3: FARRP
- 4: COMMAND POST
- 5: ENGINEER
- 6: SUPPLY
- 7: MAINTENANCE PT
- 8: BRIDGE
- 9: COM/EW SITE

UNIT NAME

STARTEX SYSTEM QTY

<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
1	2	3	4	5	6	7	8	9	10
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
11	12	13	14	15	16	17	18	19	20
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
21	22	23	24	25	26	27	28	29	30
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
31	32	33	34	35	36	37	38	39	40
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
41	42	43	44	45	46	47	48	49	50
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
51	52	53	54	55	56	57	58	59	60
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
61	62	63	64	65	66	67	68	69	70

MUST EQUAL 100%

** ACTIVITY CODE **

- 0: INACTIVE
- 1: ACTIVE

<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
A	B	C	D	E	F	G	H

** TACT MISSION **

- A: % FUEL ON TANKERS
- B: % AMMO ON CARGO VEHICLE
- C: % DIRECT FIRE AMMO
- D: % INDIRECT FIRE AMMO
- E: % AIR DEFENSE AMMO
- F: ACTIVITY CODE
- G: TACT MISSION
- H: ECHELON

- 0: MVMTN TO CONT
- 1: INDIRECT FIRE
- 2: MOVEMENT
- 3: FRONTAL ATTACK
- 4: ENV. ATTACK
- 5: DELAY
- 6: HASTY DEFENSE
- 7: PREP. DEFENSE
- 8: RESERVE/REAR
- 9: AMBUSH

** ECHELON **

- 0: BLUE BATTALION/RED REGIMENT
- 1: BLUE COMPANY/RED BATTALION

Figure 2-3 Unit input sheet.

3. Type. A number representing the unit type, where:

- 0 = Combat unit
- 1 = Artillery unit
- 2 = Air defense unit
- 3 = Attack helicopter site/FARP
- 4 = Command post/headquarters (CP/HQ)
- 5 = Engineer unit
- 6 = POL/AMMO supply unit
- 7 = Maintenance point
- 8 = Surface-to-air missile (SAM) site
- 9 = Communications/radar/electronic warfare (EW) site.

The unit number stored in the "TOEFILE" (position 72) is input as a "decimal" number. The number in front of the decimal is the unit's side, the number following the decimal represents the unit's type. Some examples of position in the "TOEFILE" follow:

- 1.3 represents a Blue air defense unit
- 1.8 represents a Blue SAM site
- 2.5 represents a Red engineer unit

4. Name. A 16 character alphanumeric string which represents the unit and is meaningful to the gamers. This string is held in the "NAMEFILE".

5. Input Lines 1 - 7 are used to input the actual quantity of 70 weapon elements assigned to a unit. These are the first 70 elements of each record of the "UNITFILE". These represent on-hand quantities as opposed to the authorized quantities listed in the "TOEFILE", above.

6. Line 8.

a. Fuel on tankers. The fraction of the unit's fuel, in gallons, loaded on tankers that are organic to the unit. Stored in the 103rd element of the "UNITFILE."

b. Ammo on cargo vehicle. Fraction of ammunition (loads) carried by the unit's ammunition trucks. Stored in the 123rd element of the "UNITFILE".

c. DF ammo status. Fraction of the unit's direct fire (DF) load capacity that is full (Note: DF status + IF status + AD status = 100). Stored in the 119th element of the "UNITFILE".

d. IF ammo status. Fraction of the unit's indirect fire (IF) basic load capacity that is full (Note: DF status + IF status + AD status = 100). Stored in the 120th element of the "UNITFILE".

e. AD ammo status. Fraction of the unit's air defense (AD) basic load capacity that is full (Note: DF status + IF status + AD status = 100). Stored in the 121st element of the "UNITFILE".

f. Activity code. If a unit is active in the critical incident (CI), set this to 1, otherwise it is 0. This is element 82 of the "UNITFILE".

g. Mission. Represents element 83 of the "UNITFILE", where:

- 0 = Meeting engagement
- 1 = Indirect fire
- 2 = Movement
- 3 = Frontal attack
- 4 = Envelopmental attack
- 5 = Delay
- 6 = Hasty defense
- 7 = Prepared defense
- 8 = Reserve/rear area
- 9 = Ambush.

h. Echelon. The unit's echelon. Enter 0 for Blue battalions/Red regiments (or larger) and 1 for Blue company/Red battalions. This is element 76 of the "UNITFILE".

(b) The gamer/staff worksheets (see Chapter 10, Figure 10-3) are completed by the gamers and input in P1 using Option 10 (enter game turn inputs). These worksheets are used to change "UNITFILE" information at the end of each critical incident (CI).

B. Output data. The only data output from this program is that data contained in the external files. The "UNITFILE" contains one array for each unit. Units not used should contain zeroes. The "TOEFILE" and "NAMEFILE" are normally output only during initial creation of the units.

4. FILE STRUCTURE.

Data files used in P1 are all external to the code. There are no internal files constructed as data statements within the code.

A. A(*). Contains the packaged weight of ammunition, in tons, for Red and Blue's 70 weapon elements.

B. F(*). Contains the capacity, in gallons, for Red and Blue's 70 weapon elements.

C. S(*). Contains the system effectiveness values for Red and Blue's 70 elements.

D. W(*). Contains a number (1-3) representing the ammunition type for Red and Blue's 70 elements, where:

- 1 = Direct fire
- 2 = Indirect fire (artillery)
- 3 = Air defense.

E. The "UNITFILE" is the major file within P1. A complete description of the elements within the "UNITFILE" may be found in Chapter 1.

F. The "TOEFILE" or table of organization and equipment (TOE) file consists of 400 records (one for each unit) and holds the number of starting force elements in positions 1 to 70. Position 71 of each record holds the total beginning effectiveness value for the unit. Position 72 contains a value representing the side (Red/Blue) and the type of unit.

G. The "NAMEFILE", developed into 400 records, holds the name for each of the units.

H. For further information on any data, please refer to volume III of the DIME documentation.

5. ALGORITHMS.

A. Figure 2-4 depicts the logic flow of the P1 program.

B. The major algorithm in this program calculates the combat effectiveness percentage for units. It begins by calculating the current total effectiveness:

$$C = \sum_{i=1}^{70} N_i * S_i \quad (\text{Eq. 2-1})$$

where:

- C = current total effectiveness.
- N_i = the current number of weapon systems of type i.
- S_i = the system effectiveness value for weapon type i.




Figure 2-4. Game initialization logic flow.

The percentage is then calculated for each unit by:

$$\text{Eff} = C / U \quad (\text{Eq. 2-2})$$

where:

U = the total authorized effectiveness value for unit j.
This value (U) is stored in the "TOEFILE" in record j.
Eff = the effectiveness percentage for unit j.

6. "UNITFILE" IMPACT.

All inputs to this program will affect the "UNITFILE" directly as they are entered. In addition, when item number 83 (mission status) of the "UNITFILE" is changed, it in turn causes item 75 (major mission) and items 107 and 127 - 129 (ammunition and fuel use profiles) to be changed. The game initialization program does not interact with any other program other than to return to the main DIME menu.

7. CODE.

A. The game initialization code is divided into 12 major subroutines. These subroutines correspond to the 12 items on the P1 menu (Figure 2-1). A short description of each menu option follows.

(1) Option 1 — Return to DIME menu. This merely returns control to the DIME menu (PO) discussed in Chapter 1.

(2) Option 2 — Enter name only. This option allows you to change the "NAMEFILE" for any given unit. It will not affect the "UNITFILE" or "TOEFILE".

(3) Option 3 — Enter entire file. With this option, one may enter all 150 elements of the "UNITFILE".

(4) Option 4 — Display unit status. This option prints the unit number, name, and the 150 elements of its "UNITFILE". It is possible to list specific units or all units with this option.

(5) Option 5 — Backup or Restore "UNITFILE". This copies the current "UNITFILE" from hard disk onto a floppy disc (or vice versa). The entire "UNITFILE" will not fit a single floppy disc, so one is used for Blue units and another for Red units.

(6) Option 6 — Change single value. This option permits correction of individual elements within the "UNITFILE". It does not allow, however, the changing of elements 75, 79, 107, 127, 128, or 129. Element 75 (major mission) is dependent on element 83 (mission 0-9). Elements 107 and 127 -

129 are set automatically to the same number indicated by element 83. Element 79 is the current effectiveness which changes from CI to CI, due to single value change or transfer of unit elements. Please note: the setting of elements 75, 79, 107 and 127 - 129 are always reset before each output of the "UNITFILE" in P1.

(7) Option 7 -- Build "TOEFILE". Within this option, a specific record of the "TOEFILE" may be built or displayed. Initial building is usually done in the next option (8), however, if changes need to be made to the "TOEFILE", it will have to be input in this option. Please note: If changes are made using this option, the total combat effectiveness is changed. Use the program EFF found in Chapter 11 to ensure that the effectiveness value in the "UNITFILE" is corrected.

(8) Option 8 -- Enter initial unit status (old version). The old version of this procedure is no longer in use. See Option 12, below.

(9) Option 9 -- Transfer equipment between units. This option allows transfer between units of the same side (Red/Blue). A specific weapon element (1-70) may be transferred. This routine is not restricted to transferring entire units. As described in Table 2-1, the gaining unit is the one which is receiving the equipment being transferred, and the losing unit is the one which is shipping out the equipment to the gaining unit. Not only are the weapon elements transferred, but their accompanying ammunition and fuel are transferred. This routine affects the "UNITFILE" and "TOEFILE" including the combat effectiveness which is recalculated after the transfer.

(10) Option 10 -- Enter game turn inputs. This option works off the gamer/staff worksheet which was output at the end of the previous CI through P8 (unit status report). After gamers have filled out the worksheet, it is input line by line. An echo of the inputs are also printed for record-keeping purposes.

(11) Option 11 -- Copy one unit to another. This selection permits the user to copy the data entered for one unit to another unit.

(12) Option 12 -- Enter initial unit status (new version). Data from the input sheet shown in Figure 2-3 is input using this option. Please refer to paragraph 3A(2) of this chapter for a complete discussion of the inputs.

B. Primary variables for each subroutine are listed in Table 2-1. A listing of P1 code appears in Table 2-2.

Table 2-1. Game Initialization Subroutine Table.

<u>Functional area(s):</u>	<u>A. File Operations</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>	
Main program	Allows menu selection and branches to all routines from here.	A. A(S,I)	Ammo data array for Red (S=1) and Blue (S=2) weapon elements (I=1-70).	
		B. F(S,I)	Fuel data array (in gallons).	
		C. S(S,I)	System effectiveness data.	
		D. W(S,J)	Weapon category: 1 = Direct fire 2 = Indirect fire 3 = Air defense	
Ret_master_menu	Return to DIME menu			
Input_unit_name	Allows input of individual unit names	A. M\$	Unitname; 8 character maximum	
Enter_unitfile	Enter all 150 elements of a selected unit.	A. N(I)	"UNITFILE" elements of one record (I=1-150).	
Disp_unit_stat	Prints contents of "UNITFILE" and "NAMEFILE".			
Cre_backup_file	Creates a backup of "UNITFILE" on a floppy disk.	A. File_name\$	File name under which "UNITFILE" is copied.	

Table 2-1. Game Initialization Subroutine Table. (continued)

<u>Functional area(s):</u>	<u>A. File Operations.</u>	<u>(continued)</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Cha_single_value</u>	<u>Allows changes to any of the 150 elements of the "UNITFILE".</u>	<u>Variable description</u>
Build_toefile	Build "TOEFILE"	A. U(I) "TOEFILE" elements - number of starting force elements (I=1-70), and I=71 Total beginning effectiveness value for the unit. I=72 Side and unit type.
Transfer	Transfer equipment between units	A. Ugain(I) "TOEFILE" for gaining unit when transferring equipment between units (I=1-72). B. U(I) "TOEFILE" for losing unit. C. Ngain (I) "UNITFILE" for gaining unit when transferring equipment (I=1-150). D. N(I) "UNITFILE" for losing unit. E. Eff_lose Effectiveness lost by losing unit. F. Eff_u Effectiveness of losing unit. G. Eff_ug Effectiveness of gaining unit. H. Avg_fuel Average fuel consumed. I. Tot_avg_fuel Total amount of average fuel for systems. J. Gain_df_frac Fraction of direct fire weapon systems gained.

Table 2-1. Game Initialization Subroutine Table. (continued)

Functional area(s): A. File Operations. (continued)

Subroutine called Subroutine function(s) Primary variables Variable description

Transfer (concluded)

K. Lose_df_frac	Fraction of DF systems lost.		Fraction of DF systems lost.
L. Gain_if_frac	Fraction of indirect fire systems gained.		Fraction of indirect fire systems gained.
M. Lose_df_frac	Fraction of IF systems lost.		Fraction of IF systems lost.
N. Gain_ad_frac	Fraction of AD systems gained.		Fraction of AD systems gained.
O. Lose_ad_frac	Fraction of AD systems lost.		Fraction of AD systems lost.
P. Ammo_transfer	Amount of ammo transferred.		Amount of ammo transferred.
Q. Df_ammo_trans	Amount of DF ammo transferred.		Amount of DF ammo transferred.
R. If_ammo_trans	Amount of IF ammo transferred.		Amount of IF ammo transferred.
S. Ad_ammo_trans	Amount of AF ammo transferred.		Amount of AF ammo transferred.
T. Fuel_gain	Current amount of fuel for gaining unit.		Current amount of fuel for gaining unit.
U. Fuel_lose	Current amount of fuel for losing unit.		Current amount of fuel for losing unit.
V. Ammo_gain	Current amount of ammo for gaining unit.		Current amount of ammo for gaining unit.
W. Ammo_lose	Current amount of ammo for losing unit.		Current amount of ammo for losing unit.
X. Tag	Total ammo gained.		Total ammo gained.
Y. Tal	Total ammo lost.		Total ammo lost.
Z. Tot_fuel_gain	Total fuel gained.		Total fuel gained.
AA. Tot_fuel_lose	Total fuel lost.		Total fuel lost.

Table 2-1. Logistics Subroutine Table. (concluded)

<u>Functional area(s): A. File Operations (concluded).</u>	
<u>Subroutine called</u>	<u>Subroutine function(s) Primary variables Variable description</u>
Game_turn	Accepts inputs from P8 worksheets.
Calc_combat_eff	Calculates combat effectiveness percentage for each unit.
Unitfile_disk	Before any updates are made to the "UNITFILE" this assures that positions 75, 110 and 127-129 of the "UNITFILE" correspond correctly with the unit's mission.
<u>Functional area(s): B. Check Inputs</u>	
<u>Subroutine called</u>	<u>Subroutine function(s) Primary variables Variable description</u>
Ck_var	Checks inputs for incorrect ranges.

```

10      ! P1--FILE OPERATIONS THIS VERSION PLAYS 400 UNITS AND DETAILED SENSORS
20      ! DATA CHANGED JANUARY 29, 1986 BY ROB BELFLOWER. BDM
30      ! EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
31      !      DECLASSIFIED -- AUG 7, 1986 -- BY OAO CORP.  ** DC **
40      OPTION BASE 1
50      Disk$=":9134,704,0"
56      Dcdisk$=":9134,704,0"  ! ** DC **
60      DIM Ammo_gain(3),Ammo_lose(3),Ammo_sys(3),Tal(3),Tag(3)
70      DIM A(2,70),F(2,70),S(2,70),W(2,70),U(72),Ugain(72)
80      DIM T(70),Toe(70),Sys(70),N(150),Ngain(150),M$(16),Type$(13)
90      ASSIGN @Pname TO "NAMEFILE"&Disk$
100     ASSIGN @Punit TO "UNITFILE"&Disk$
110     ASSIGN @Ptoe TO "TOEFILE"&Disk$
120     REM - INITIALIZE
121     !
122     ! ** DC ** 7 AUG 1986
123     !
130     ASSIGN @Pammocap TO "AMMO_CAP"&Dcdisk$
140     ENTER @Pammocap,1;A(*)
150     ASSIGN @Pammocap TO *
160     !
290     ASSIGN @Pfuelcap TO "FUEL_CAP"&Dcdisk$
300     ENTER @Pfuelcap,1;F(*)
310     ASSIGN @Pfuelcap TO *
450     !
460     ASSIGN @Psyseff TO "SYS_EFF"&Dcdisk$
470     ENTER @Psyseff,1;S(*)
480     ASSIGN @Psyseff TO *
490     !
500     ASSIGN @Pwpntyp TO "WPN_TYP"&Dcdisk$
510     ENTER @Pwpntyp,1;W(*)
520     ASSIGN @Pwpntyp TO *
521     !
530     ! ** END DC **
540     !
690     PRINT USING "@,#"
700     PRINT "          DATA OPERATIONS MENU"
710     PRINT "          "
720     PRINT "          1 -- RETURN TO MASTER MENU"
730     PRINT "          2 -- ENTER OR CHANGE NAME ONLY"
740     PRINT "          3 -- ENTER ENTIRE FILE (1-150) FOR A UNIT"
750     PRINT "          4 -- DISPLAY UNIT STATUS"
760     PRINT "          5 -- BACKUP OR RESTORE UNITFILE"
770     PRINT "          6 -- CHANGE SINGLE VALUE"
780     PRINT "          7 -- TOEFILE UTILITIES"
790     PRINT "          8 -- ENTER INITIAL UNIT STATUS - OLD VERSION"
800     PRINT "          9 -- TRANSFER EQUIPMENT BETWEEN UNITS"
810     PRINT "         10 -- ENTER PLAYER PB POST-GAMETURN RESUPPLY AND STATUS INFO"
820     PRINT "         11 -- COPY ONE UNIT TO ANOTHER UNIT"
830     PRINT "         12 -- ENTER INITIAL UNIT STATUS - NEW VERSION"
840     PRINT "          "
850     INPUT "ENTER NUMBER OF DESIRED ACTION--",I

```

Table 2-2. Game initialization code.

```

860  IF I=12 THEN GOSUB Init_stat
870  IF I=11 THEN GOSUB Record_number
880  IF I>10 OR I<1 THEN 690
890  ON I GOSUB Ret_master_menu,Input_unit_name,Entire_unitfile,Disp_unit_stat
Cre_backup_file,Cha_single_valu,Build_toefile,Init_unit_stat,Transfer,Game_curr
900  GOTO 690
910  !-----
920  Record_number: !
930  PRINT USING "@"
940  ASSIGN @Nname TO "NAMEFILE:9134,704,0"
950  ASSIGN @Nunit TO "UNITFILE:9134,704,0"
960  ASSIGN @Ntoe TO "TOEFILE:9134,704,0"
970  PRINT "THIS ROUTINE WILL COPY ONE UNIT RECORD INTO ANOTHER UNIT RECORD."
980  PRINT "IT WILL ERASE ANY DATA ALREADY STORED IN THE NEW RECORD"
990  PRINT "NUMBER AND REPLACE IT WITH THE CHANGED DATA. IT WILL"
1000 PRINT "NOT ERASE THE DATA STORED IN THE OLD RECORD."
1010 PRINT
1020 PRINT "USE RECORD NUMBER 999 TO END THIS ROUTINE"
1030 X=0
1040 Y=0
1050 PRINT
1060 INPUT "WHAT IS THE OLD RECORD NUMBER",X
1070 IF X=999 THEN RETURN
1080 INPUT "WHAT IS THE NEW RECORD NUMBER",Y
1090 IF Y=999 THEN RETURN
1100 ENTER @Funit,X;N(*)
1110 ENTER @Ptoe,X;U(*)
1120 ENTER @Pname,X;M$
1130 OUTPUT @Nunit,Y;N(*)
1140 OUTPUT @Ntoe,Y;U(*)
1150 OUTPUT @Nname,Y;M$
1160 GOTO 920
1170 RETURN
1180 !-----
1190 Ret_master_menu: !
1200 ASSIGN @Pname TO *
1210 ASSIGN @Punit TO *
1220 ASSIGN @Ptoe TO *
1230 GOTO Subprogram_end
1240 RETURN
1250 !-----
1260 Input_unit_name: !
1270 PRINT USING "@"
1280 INPUT "UNIT NAME ENTRY (16 CHARACTER MAXIMUM, 999=STOP). ENTER UNIT NUMBE
",I
1290 IF I=999 THEN 1360
1300 IF I<1 OR I>400 THEN 1270
1310 INPUT "ENTER UNIT NAME",M$
1320 OUTPUT @Pname,I;M$
1330 ENTER @Pname,I;M$
1340 PRINT USING "@,16A";M$
1350 GOTO 1280

```

Table 2-2. Game initialization code.

```

1360 RETURN
1370 !-----
1380 Entire_unitfile:
1390 PRINT USING "@"
1400 PRINT "UNIT FILE ENTRY (NAME,PARAMETERS)"
1410 PRINT USING "@"
1420 INPUT "ENTER UNIT NUMBER (1-400, 999=STOP)".I
1430 IF I=999 THEN 1590
1440 IF I>400 OR I<1 THEN 1410
1450 PRINT USING "@"
1460 INPUT "ENTER UNIT NAME (16 CHARACTERS)".M$
1470 PRINT M$
1480 FOR K=1 TO 15
1490     PRINT "LINE";K;" ";
1500     FOR J=1 TO 10
1510         INPUT "INPUT FIELD VALUE".N((K-1)*10+J)
1520         PRINT N((K-1)*10+J);
1530     NEXT J
1540     PRINT
1550 NEXT K
1560 OUTPUT @Pname.I;M$
1570 GOSUB Calc_combat_eff
1580 GOTO 1410
1590 RETURN
1600 !-----
1610 Disp_unit_stat:
1620 PRINT USING "@"
1630 PRINT "UNIT STATUS DISPLAY"
1640 PRINT
1650 INPUT "CHECK LOADSHEET VALUES <L>, OR SCRUTINIZE ALL 150 VALUES <S>?".Ans
1660 INPUT "ENTER OUTPUT DESIRED: 1-ALL UNITS 2-SPECIFIC UNITS",Z5
1670 INPUT "DISPLAY TO 1=SCREEN ONLY OR 2=SCREEN AND PRINTER",A$
1680 Page=0
1690 IF Z5=1 THEN
1700     Loadsheet=0
1710     PRINT USING "@,#"
1720     FOR I=1 TO 400
1730         GOSUB Print_unitfile
1740     NEXT I
1750 ELSE
1760     INPUT "UNIT NUMBER (900=START OVER, 999=MAIN MENU)".I
1770     IF I=900 THEN 1620
1780     IF I=999 THEN 1830
1790     IF I<1 OR I>400 THEN 1760
1800     GOSUB Print_unitfile
1810     GOTO 1760
1820 END IF
1830 RETURN
1840 !
1850 Print_unitfile:
1860 ENTER @Punit.I;N(*)
1870 ENTER @Pname.I;M$

```

Table 2-2. Game initialization code.

```

1880 IF N(79)=0 THEN 2820
1890 Side=INT(N(78))
1900 Kind=INT((N(78)-Side+.05)*10)
1910 IF Kind=0 THEN Type$="COMBAT"
1920 IF Kind=1 THEN Type$="ARTILLERY"
1930 IF Kind=2 THEN Type$="AIR DEFENSE"
1940 IF Kind=3 THEN Type$="FARRP"
1950 IF Kind=4 THEN Type$="COMMAND POST"
1960 IF Kind=5 THEN Type$="ENGINEER"
1970 IF Kind=6 THEN Type$="SUPPLY"
1980 IF Kind=7 THEN Type$="MAINTENANCE"
1990 IF Kind=8 THEN Type$="BRIDGE"
2000 IF Kind=9 THEN Type$="COMMO/EW SITE"
2010 PRINTER IS 1
2020 X=INT(N(124))/10
2030 Y=(N(124)-INT(N(124)))*100
2040 IF Side=1 THEN
2050   Fuel=1800
2060   Tons=6.5
2070 ELSE
2080   Fuel=1288
2090   Tons=4.5
2100 END IF
2110 IF N(103)>N(101) THEN
2120   Gal=(N(103)/Fuel/N(55))*100
2130 ELSE
2140   Gal=N(101)*100
2150 END IF
2160 Ammo=N(123)
2170 IF Gal=0 THEN Gal=1
2180 IF Ammo=0 THEN Ammo=1
2190 IF A$="1" THEN
2200   PRINT " "; "UNIT NO. ", " SIDE", "TYPE", Type$
2210   PRINT I, Side, Kind
2220   PRINT " "; M$
2230   IF Ans$="L" THEN
2240     FOR J=1 TO 70
2250       PRINT USING "6D.3D,1X,#"; N(J)
2260       IF J MOD 7=0 THEN
2270         PRINT
2280       END IF
2290     NEXT J
2300     !PRINT ROUTINE BELOW WAS ADDED AFTER THE CORRECT FORMULA WAS ADDED TO T
HE INIT_STAT ROUTINE TO LOAD DF AND IDF AMMO.
2310     PRINT " "; "% FUEL ", "% AMMO", "   %DF ", " %IF", " %ADA ", "ACTIVITY", "MIS
SION", "ECHELON"
2320     PRINT USING "7D,8D,11D,8D,11D,10D,8D,1D,10D"; Gal, 100*(Tons*N(58))/Ammo
, X, Y, 100-X-Y, N(82), N(83), N(76)
2330     PRINT
2340     PRINT
2350   ELSE
2360     PRINT USING "22(7(6D.3D,1X),/)"; N(*)

```

Table 2-2. Game initialization code.


```

2370     PRINT
2380     END IF
2390 ELSE
2400     PRINTER IS 702
2410     PRINT " "; "UNIT NO.", " SIDE", "TYPE", Type$
2420     PRINT I, Side, Kind
2430     PRINT " "; M$
2440     IF Ans$="L" THEN
2450         FOR J=1 TO 70
2460             PRINT USING "6D.3D,1X,#"; INT(N(J))
2470             IF J MOD 7=0 THEN
2480                 PRINT
2490                 END IF
2500             NEXT J
2510             PRINT " "; "% FUEL ", "% AMMO", " %DF ", " %IF", " %ADA ", "ACTIVITY", "MI
SION", "ECHELON"
2520             PRINT USING "7D,8D,11D,8D,11D,10D,8D.1D,10D"; Gal, 100*(Tons*N(58))/Amm
,X,Y,100-X-Y,N(82),N(83),N(76)
2530             Loadsheet=Loadsheet+1
2540             IF Loadsheet=3 THEN
2550                 PRINT USING "@,#"
2560                 Loadsheet=0
2570             ELSE
2580                 PRINT
2590                 PRINT
2600                 PRINT
2610             END IF
2620             PRINTER IS 1
2630             GOTO 2820
2640         ELSE
2650             PRINT USING "22(7(6D.3D,1X),/);N(*)
2660             Page=Page+1
2670             IF Page=2 THEN
2680                 PRINT USING "@,#"
2690                 Page=0
2700             ELSE
2710                 PRINT
2720                 PRINT
2730             END IF
2740             PRINTER IS 1
2750         END IF
2760     END IF
2770 ! Coun=Coun+1
2780 ! IF Coun=2 THEN 1310
2790 ! PRINTER IS 702
2800 ! GOTO 1250
2810 ! PRINTER IS 1
2820 RETURN
2830 !-----
2840 Cre_backup_file: !
2850 PRINT USING "@,#"
2860 PRINT "                BACKUP/RESTORE MENU"

```

Table 2-2. Game initialization code.

```

2870 PRINT "      "
2880 PRINT "          1 -- BACKUP UNITFILE TO FLOPPY"
2890 PRINT "          2 -- RESTORE UNITFILE FROM FLOPPY"
2900 PRINT "          3 -- RETURN TO MAIN MENU"
2910 PRINT "      "
2920 INPUT "ENTER NUMBER OF DESIRED ACTION--",J
2930 IF I=1 THEN GOTO Backunit
2940 IF I=2 THEN GOTO Restunit
2950 IF I=3 THEN RETURN
2960 GOTO Cre_backup_file
2970 Backunit: !
2980 Sunit=1
2990 Eunit=191
3000 Treccs=191
3010 Oname$="BLUE"
3020 GOSUB Make_unit
3030 Sunit=192
3040 Eunit=400
3050 Treccs=209
3060 Oname$="RED"
3070 GOSUB Make_unit
3080 RETURN
3090 Make_unit: !
3100 DISP "INSERT ";Oname$;" UNITFILE DISK IN FLOPPY DRIVE 0 - PRESS CONT WHEN
READY"
3110 PAUSE
3120 Bunit$="UNITFILE"&Oname$[1,1]
3130 DISP "CREATING ";Bunit$;"...";
3140 CREATE BDAT Bunit$&":HP9121,700,0",Treccs,1200
3150 ASSIGN @Bunit TO Bunit$&":HP9121,700,0"
3160 DISP "COPYING ";Bunit$;"...";
3170 FOR Recno=Sunit TO Eunit
3180   ENTER @Punit,Recno;N(*)
3190   OUTPUT @Bunit;N(*)
3200 NEXT Recno
3210 DISP "COMPLETE"
3220 WAIT 3
3230 RETURN
3240 Restunit: !
3250 DISP "PURGE UNITFILE FROM HARDISK (Y/N) ":
3260 INPUT Purg$
3270 IF Purg$="Y" THEN PURGE "UNITFILE"&Disk$
3280 DISP "CREATING UNITFILE..."
3290 CREATE BDAT "UNITFILE"&Disk$,400,1200
3300 ASSIGN @Punit TO "UNITFILE"&Disk$
3310 Eunit=191
3320 Iname$="BLUE"
3330 GOSUB Runit
3340 Eunit=209
3350 Iname$="RED"
3360 GOSUB Runit
3370 RETURN

```

Table 2-2. Game initialization code.

```

3380 Runit:
3390 DISP "INSERT ":Iname$: " UNITFILE DISK IN FLOPPY DRIVE 0 - PRESS CONT WHEN
READY"
3400 PAUSE
3410 Runit$="UNITFILE"&Iname$[1,1]
3420 DISP "COPYING ":Runit$;" TO UNITFILE...";
3430 ASSIGN @Runit TO Runit$&":HP9121.700,0"
3440 FOR Recno=1 TO Eunit
3450     ENTER @Runit,Recno;N(*)
3460     OUTPUT @Punit;N(*)
3470 NEXT Recno
3480 DISP "COMPLETE"
3490 WAIT 3
3500 RETURN
3510 !-----
3520 Cha_single_valu:
3530 PRINT USING "e"
3540 PRINT "CHANGE SINGLE VALUES IN THE UNITFILE"
3550 INPUT "ENTER UNIT NUMBER 1-400 (999=STOP)",I
3560 IF I=999 THEN 3670
3570 IF I<1 OR I>400 THEN 3550
3580 ENTER @Punit,I;N(*)
3590 INPUT "ENTER ITEM NUMBER, NEW VALUE (999,999=STOP)",J,NO
3600 IF J=999 THEN 3640
3610 IF J<1 OR J>150 THEN 3590
3620 N(J)=NO
3630 GOTO 3590
3640 GOSUB Calc_combat_eff
3650 OUTPUT @Punit,I;N(*)
3660 GOTO 3530
3670 RETURN
3680 !-----
3690 Build_toefile:
3700 PRINT USING "e"
3710 PRINT "TOEFILE BUILDER"
3720 INPUT "DESIRED ACTION: 1-BUILD UNIT 2-DISPLAY UNIT 3-RETURN TO MENU".Z1
3730 ON Z1 GOTO 3740,3900,690
3740 INPUT "ENTER UNIT NUMBER (999=STOP)",I
3750 IF I=999 THEN 3700
3760 IF I<1 OR I>400 THEN 3740
3770 INPUT "SIDE (1-BLUE 2-RED)",K
3780 INPUT "UNIT TYPE",L
3790 IF L<0 OR L>9 THEN 3780
3800 INPUT "ENTER NUMBER OF SYSTEMS 1-70",T(*)
3810 E=0
3820 FOR J=1 TO 70
3830     U(J)=T(J)
3840     E=E+U(J)*S(K,J)
3850 NEXT J
3860 U(71)=E
3870 U(72)=K+L/10
3880 OUTPUT @Ptoe,I;U(*)

```

Table 2-2. Game initialization code.

```

3890 GOTO 3740
3900 INPUT "1-SINGLE UNIT      2-ALL UNITS      999=STOP",Ch
3910 IF Ch=999 THEN GOTO 3720
3920 ON Ch GOSUB Sing,All
3930 GOTO 3900
3940 Sing: !
3950 INPUT "ENTER UNIT NUMBER (999=STOP)",I
3960 IF I=999 THEN 4010
3970 IF I<1 OR I>400 THEN 3900
3980 ENTER @Ptoe,I;U(*)
3990 GOSUB Print_toe
4000 GOTO 3940
4010 RETURN
4020 All: !
4030 FOR I=1 TO 400
4040     ENTER @Ptoe,I;U(*)
4050     GOSUB Print_toe
4060 NEXT I
4070 RETURN
4080 Print_toe: !
4090 PRINTER IS 702
4100 PRINT
4110 PRINT
4120 PRINT "UNIT ";I
4130 PRINT USING "7(10(5D.1D,1X),/),7D.1D,7X,7D.1D";U(*)
4140 PRINTER IS 1
4150 RETURN
4160 !-----
4170 Init_unit_stat: !
4180 PRINT USING "@"
4190 PRINT "UNIT STATUS INITIALIZATION"
4200 INPUT "ENTER UNIT NUMBER 1-400 (999=STOP)",I
4210 GOSUB Clear_out
4220 IF I=999 THEN 4710
4230 IF I<1 OR I>400 THEN 4200
4240 INPUT "ENTER UNIT NAME (16 CHARACTER MAXIMUM)",M$
4250 OUTPUT @Pname,I;M$
4260 INPUT "SIDE (1-BLUE 2-RED)",K
4270 INPUT "UNIT TYPE",L
4280 K=INT(K)
4290 L=INT(L)
4300 IF L<0 OR L>9 THEN 4270
4310 INPUT "ENTER NUMBER OF SYSTEMS 1-70",T(*)
4320 E=0
4330 FOR J=1 TO 70
4340     U(J)=T(J)
4350     E=E+U(J)*S(K,J)
4360 NEXT J
4370 U(71)=E
4380 U(72)=K+L/10
4390 OUTPUT @Ptoe,I;U(*)
4400 INPUT "ENTER LINE 1 (1-10)",N(1),N(2),N(3),N(4),N(5),N(6),N(7),N(8),N(9),N
(10)

```

Table 2-2. Game initialization code.

```

4410 INPUT "ENTER LINE 2 (11-20)",N(11),N(12),N(13),N(14),N(15),N(16),N(17),N(
8),N(19),N(20)
4420 INPUT "ENTER LINE 3 (21-30)",N(21),N(22),N(23),N(24),N(25),N(26),N(27),N(
8),N(29),N(30)
4430 INPUT "ENTER LINE 4 (31-40)",N(31),N(32),N(33),N(34),N(35),N(36),N(37),N(
8),N(39),N(40)
4440 INPUT "ENTER LINE 5 (41-50)",N(41),N(42),N(43),N(44),N(45),N(46),N(47),N(
8),N(49),N(50)
4450 INPUT "ENTER LINE 6 (51-60)",N(51),N(52),N(53),N(54),N(55),N(56),N(57),N(
8),N(59),N(60)
4460 INPUT "ENTER LINE 7 (61-70)",N(61),N(62),N(63),N(64),N(65),N(66),N(67),N(
8),N(69),N(70)
4470 INPUT "ENTER LINE 8 (75,89,77,78,90,101,103,105; 90&78 IN 2 PARTS)",N(75)
A1,A2,N(77),B1,B2,N(90),N(101),N(103),N(105)
4480 IF N(75)<1 OR N(75)>4 THEN 4470
4490 IF A1<1 OR A1>5 THEN 4470
4500 IF A2<0 OR A2>9 THEN 4470
4510 N(89)=INT(A1)+A2/10
4520 IF N(77)<>1 AND N(77)<>2 THEN 4470
4530 IF B1<>1 AND B1<>2 THEN 4470
4540 IF B2<0 OR B2>9 THEN 4470
4550 N(78)=INT(B1)+B2/10
4560 IF N(90)<0 OR N(90)>1 THEN 4470
4570 IF N(101)<0 OR N(101)>1 THEN 4470
4580 INPUT "ENTER LINE 9 (119-125,81-83,76)",N(119),N(120),N(121),N(122),N(123)
,N(124),N(125),N(81),N(82),N(83),N(76)
4590 IF N(119)<0 OR N(119)>1 THEN 4580
4600 IF N(120)<0 OR N(120)>1 THEN 4580
4610 IF N(121)<0 OR N(121)>1 THEN 4580
4620 IF N(81)<1 OR N(81)>400 THEN 4580
4630 IF N(82)<>0 AND N(82)<>1 THEN 4580
4640 IF N(83)<0 OR N(83)>9 THEN 4580
4650 IF N(76)<>0 AND N(76)<>1 THEN 4580
4660 N(139)=0
4670 N(140)=0
4680 N(141)=0
4690 GOSUB Unitfile_disk
4700 GOTO 4200
4710 RETURN
4720 Clear_out:
4730 FOR Ikp=1 TO 150
4740     N(Ikp)=0
4750 NEXT Ikp
4760 RETURN
4770 !-----
4780 Init_stat:
4790 PRINT USING "@"
4800 PRINT "                                UNIT STATUS INITIALIZATION"
4810 INPUT "ENTER UNIT NUMBER 1-400 (999=STOP)",I
4820 IF I=999 THEN RETURN
4830 IF I<1 OR I>400 THEN 4810
4840 INPUT "SIDE (1=BLUE, 2=RED)",K

```

Table 2-2. Game initialization code.

```

4850 INPUT "UNIT TYPE",L
4860 K=INT(K)
4870 L=INT(L)
4880 IF L<0 OR L>9 THEN 4850
4890 INPUT "ENTER UNIT NAME (16 CHARACTER MAXIMUM)",M$
4900 OUTPUT @Pname,I;M$
4910 DISP "ENTER THE NUMBER OF SYSTEMS 1-70"
4920 FOR G=1 TO 7
4930 PRINT "LINE";G;" ";
4940 FOR J=1 TO 10
4950 INPUT "INPUT FIELD VALUE",T((G-1)*10+J)
4960 PRINT T((G-1)*10+J);
4970 NEXT J
4980 PRINT
4990 NEXT G
5000 E=0
5010 FOR J=1 TO 70
5020 U(J)=T(J)
5030 E=E+U(J)*S(K,J)
5040 N(J)=T(J)
5050 NEXT J
5060 U(71)=E
5070 U(72)=K+L/10
5080 OUTPUT @Ptoe,I;U(*)
5090 N(89)=5.9
5100 N(77)=1
5110 N(78)=K+L/10
5120 N(90)=1
5130 PRINT USING "@"
5140 !PRINT "DOES THIS UNIT HAVE ITS NORMAL FUEL SUPPLY?"
5150 !INPUT "ANSWER <Y>ES IF IT DOES, <N>O IF IT HAS EITHER MORE OR LESS".A$
5160 !IF A$="Y" THEN
5170 ! N(101)=1
5180 ! IF K=1 THEN
5190 ! N(103)=N(55)*1800
5200 ! ELSE
5210 ! N(103)=N(55)*1288
5220 ! END IF
5230 ! ELSE
5240 INPUT "WHAT PERCENT OF NORMAL FUEL DOES THIS UNIT HAVE",X
5250 Percent=X/100
5260 IF Percent>1 THEN
5270 N(101)=1
5280 ELSE
5290 N(101)=Percent
5300 END IF
5310 IF K=1 THEN
5320 IF Percent>1 THEN
5330 N(103)=N(55)*1800
5340 N(105)=(N(55)*1800*Percent)-N(103)
5350 ELSE
5360 N(103)=N(55)*1800*Percent

```

Table 2-2. Game initialization code.

```

5370      N(105)=0
5380      END IF
5390      ELSE
5400      IF Percent>1 THEN
5410      N(103)=N(55)*1288
5420      N(105)=(N(55)*1288*Percent)-N(103)
5430      ELSE
5440      N(103)=N(55)*1288*Percent
5450      N(105)=0
5460      END IF
5470      END IF
5480 ! END IF
5490 PRINT USING "@"
5500 ! PRINT "DOES THIS UNIT HAVE ITS NORMAL AMMUNITION SUPPLY?"
5510 ! INPUT "ANSWER <Y>ES IF IT DOES, <N>O IF IT HAS EITHER MORE OR LESS AMMUNI
TION", A$
5520 ! IF A$="Y" THEN
5530 !   N(119)=1
5540 !   N(120)=1
5550 !   N(121)=1
5560 !   IF K=1 THEN
5570 !     N(123)=N(58)*6.5
5580 !     ELSE
5590 !     N(123)=N(58)*4.5
5600 !   END IF
5610 !   N(125)=0
5620 !   ELSE
5630 INPUT "WHAT PERCENT OF ITS NORMAL AMMUNITION DOES THIS UNIT HAVE", X
5640 Percent=X/100
5650 IF Percent>1 THEN
5660   N(119)=1
5670   N(120)=1
5680   N(121)=1
5690   IF K=1 THEN
5700     N(123)=N(58)*6.5
5710     N(125)=(N(58)*6.5*Percent)-N(123)
5720   ELSE
5730     N(123)=N(58)*4.5
5740     N(125)=(N(58)*4.5*Percent)-N(123)
5750   END IF
5760 ELSE
5770   N(119)=Percent
5780   N(120)=Percent
5790   N(121)=Percent
5800   IF K=1 THEN
5810     N(123)=N(58)*6.5*Percent
5820     N(125)=0
5830   ELSE
5840     N(123)=N(58)*4.5*Percent
5850     N(125)=0
5860   END IF
5870 END IF

```

Table 2-2. Game initialization code.

```

5880 ! END IF
5890 PRINT USING "@"
5900 INPUT "WHAT IS THE PERCENTAGE OF DIRECT FIRE AMMUNITION".Y
5910 INPUT "WHAT IS THE PERCENTAGE OF INDIRECT FIRE AMMUNITION",Y
5920 INPUT "WHAT IS THE PERCENTAGE OF AIR DEFENSE AMMUNITION",Z
5930 IF X+Y+Z<>100 THEN
5940     PRINT USING "@,#"
5950     PRINT "PERCENTAGES OF AMMUNITION DO NOT ADD UP TO 100%. TRY IT AGAIN."
5960     WAIT 3
5970     GOTO 5890
5980 END IF
5990 N(124)=X+Y/100 !UNITS WERE CREATED WITH FORMULA. IT SHOULD BE
        N(124)=(X*10)+(Y/100). NEXT LINE ALSO
6000 N(126)=X+Y/100
6010 !INPUT "WHAT IS THE SUPPORTING ADA UNIT",N(81)
6020 INPUT "IS THIS UNIT ACTIVE <1> OR INACTIVE <0>",N(82)
6030 INPUT "WHAT IS THIS UNIT'S TACTICAL MISSION",X
6040 ! INPUT "WHAT IS THIS UNIT'S TACTICAL MISSION FOR THE 2ND 3 HOURS",Y
6050 X=INT(X)
6060 Y=INT(X)
6070 N(83)=X+Y/10
6080 IF K=1 THEN
6090     INPUT "IS THIS UNIT A BATTALION (0) OR COMPANY (1) ",Esch
6100     ELSE
6110     INPUT "IS THIS UNIT A REGIMENT (0) OR BATTALION (1) ".Esch
6120     END IF
6130 IF Esch<>0 AND Esch<>1 THEN
6140     DISP "UNIT ECHELON MUST BE ""0"" OR ""1"" "
6150     WAIT 3
6160     GOTO 6080
6170     ELSE
6180     N(76)=Esch
6190     END IF
6200 GOSUB Unitfile_disk
6210 GOTO 4780
6220 RETURN
6230 Transfer: ! THIS SUBROUTINE TRANSFERS EQUIPMENT BETWEEN UNITS
6240 Start_input:PRINT USING "@, #, 23A"; "UNIT EQUIPMENT TRANSFER"
6250 INPUT "ENTER UNIT # LOSSING ELEMENT AND UNIT # GAINING ELEMENT -- STOP (999",L,G
6260 IF L=999 AND G=999 THEN Transend
6270 IF L<1 OR L>400 OR G<1 OR G>400 THEN 6250
6280 IF L<192 THEN
6290     Side_l=1
6300     ELSE
6310     Side_l=2
6320     END IF
6330 IF G<192 THEN
6340     Side_g=1
6350     ELSE
6360     Side_g=2
6370     END IF

```

Table 2-2. Game initialization code.


```

6380 IF Side_1<>Side_g THEN
6390   DISP "UNITS NOT ON SAME SIDE, CHECK YOUR DATA, PRESS CONTINUE TO PROCEED"
"
6400   PAUSE
6410   GOTO 6250
6420 ELSE
6430   Side=Side_1
6440 END IF
6450 Element_input: !
6460 FOR I=1 TO 70
6470   Sys(I)=0
6480   Toe(I)=0
6490 NEXT I
6500 !
6510 REM - ADJUST TOEFILE FOR LOSING AND GAINING UNITS
6520 ENTER @Ptoe,G;Ugain(*)
6530 ENTER @Ptoe,L;U(*)
6540 ENTER @Punit,G;Ngain(*)
6550 ENTER @Punit,L;N(*)
6560 INPUT "ENTER ELEMENT NUMBER TO BE TRANSFERED",Elmt_no_trans
6570 INPUT "NUMBER OF ELEMENTS TO BE TRANSFERED",Sys(Elmt_no_trans)
6580 Eff_gain=0
6590 Eff_lose=0
6600 Int_sys=N(Elmt_no_trans)-Sys(Elmt_no_trans)
6610 IF Int_sys<0 THEN
6620   PRINT USING "@"
6630   PRINT "ELEMENT ";Elmt_no_trans;" IS NEGATIVE FOR LOSING UNIT, CHECK YOUR
DATA, PRESS CONTINUE TO PROCEED"
6640   PAUSE
6650   GOTO Start_input
6660 END IF
6670 Int_sys=U(Elmt_no_trans)-Sys(Elmt_no_trans)
6680 IF Int_sys<0 THEN
6690   PRINT USING "@"
6700   PRINT "TOE ITEM ";Elmt_no_trans;" IS NEGATIVE FOR LOSING UNIT, CHECK YOU
R DATA, PRESS CONTINUE TO PROCEED"
6710   PAUSE
6720   GOTO Start_input
6730 ELSE
6740   Ugain(Elmt_no_trans)=Ugain(Elmt_no_trans)+Sys(Elmt_no_trans)
6750   U(Elmt_no_trans)=Int_sys
6760   Eff_lose=Sys(Elmt_no_trans)*S(Side,Elmt_no_trans)
6770 END IF
6780 Ugain(71)=Eff_lose+Ugain(71)
6790 U(71)=U(71)-Eff_lose
6800 !
6810 IF U(71)=0 OR Ugain(71)=0 THEN Ni
6820 Eff_u=0
6830 Eff_ug=0
6840 FOR Le=1 TO 70
6850   Eff_u=Eff_u+S(Side,Le)*N(Le)
6860   Eff_ug=Eff_ug+S(Side,Le)*Ngain(Le)

```

Table 2-2. Game initialization code.

```

6870 NEXT Le
6880 N(79)=Eff_u/U(71)
6890 Ngain(79)=Eff_ug/Ugain(71)
6900 Ni: '
6910 !
6920 ! UPDATE UNITFILE STATUS
6930 REM - ADJUST CARGO/FUEL TRUCK LEVELS
6940 IF Sys(55)=0 THEN Adjust_cargo
6950 Avg_fuel=N(103)/N(55)
6960 Tot_avg_fuel=Avg_fuel*Sys(55)
6970 N(103)=N(103)-Tot_avg_fuel
6980 Ngain(103)=Ngain(103)+Tot_avg_fuel
6990 IF N(103)<0 THEN N(103)=0
7000 Adjust_cargo: ! ADJUST CARGO LEVELS
7010 IF Sys(58)=0 THEN Tally_systems
7020 Gain_df_frac=INT(Ngain(124))/1000
7030 Lose_df_frac=INT(N(124))/1000
7040 Gain_if_frac=Ngain(124)-INT(Ngain(124))
7050 Lose_if_frac=N(124)-INT(N(124))
7060 Gain_ad_frac=1-(Gain_df_frac+Gain_if_frac)
7070 Lose_ad_frac=1-(Lose_df_frac+Lose_if_frac)
7080 Avg_ammo_lose=N(123)/N(58)
7090 Ammo_transfer=Avg_ammo_lose*Sys(58)
7100 N(123)=N(123)-Ammo_transfer
7110 Df_ammo_trans=Ammo_transfer*Lose_df_frac
7120 If_ammo_trans=Ammo_transfer*Lose_if_frac
7130 Ad_ammo_trans=Ammo_transfer*Lose_ad_frac
7140 Df_ammo=0
7150 If_ammo=0
7160 Ad_ammo=0
7170 Df_ammo=Df_ammo_trans+Gain_df_frac*Ngain(123)
7180 If_ammo=If_ammo_trans+Gain_if_frac*Ngain(123)
7190 Ad_ammo=Ad_ammo_trans+Gain_ad_frac*Ngain(123)
7200 Tot_ammo=Df_ammo+If_ammo+Ad_ammo
7210 Ngain(123)=Tot_ammo
7220 N1=(Df_ammo/Tot_ammo)*1000
7230 N2=If_ammo/Tot_ammo
7240 Ngain(124)=INT(N1)+N2
7250 Tally_systems: ! ADJUST VEHICLE AMMO LEVELS AND TRANSFER SYSTEMS
7260 Tot_fuel_lose=0
7270 Tot_fuel_gain=0
7280 Fuel_gain=0
7290 Fuel_lose=0
7300 Fuel_sys=0
7310 FOR I=1 TO 3
7320     Ammo_gain(I)=0
7330     Ammo_lose(I)=0
7340     Ammo_sys(I)=0
7350     Tal(I)=0
7360     Tag(I)=0
7370 NEXT I
7380 REM - TALLY FUEL/AMMO

```

Table 2-2. Game initialization code.

```

7390 FOR I=1 TO 70
7400   Fuel_gain=Fuel_gain+Ngain(I)*F(Side,I)*Ngain(101)
7410   Fuel_lose=Fuel_lose+N(I)*F(Side,I)*N(101)
7420   Fuel_sys=Fuel_sys+Sys(I)*F(Side,I)*N(101)
7430   Ammo_gain(W(Side,I))=Ammo_gain(W(Side,I))+A(Side,I)*Ngain(118+W(Side,I))
*Ngain(I)
7440   Ammo_lose(W(Side,I))=Ammo_lose(W(Side,I))+A(Side,I)*N(118+W(Side,I))*N(I
)
7450   Ammo_sys(W(Side,I))=Ammo_sys(W(Side,I))+A(Side,I)*N(118+W(Side,I))*Sys(I
)
7460 NEXT I
7470 Fuel_gain=Fuel_gain+Fuel_sys
7480 Fuel_lose=Fuel_lose-Fuel_sys
7490 FOR I=1 TO 3
7500   Ammo_gain(I)=Ammo_gain(I)+Ammo_sys(I)
7510   Ammo_lose(I)=Ammo_lose(I)-Ammo_sys(I)
7520 NEXT I
7530 FOR I=1 TO 70
7540   Ngain(I)=Ngain(I)+Sys(I)
7550   N(I)=N(I)-Sys(I)
7560   Tag(W(Side,I))=Tag(W(Side,I))+Ngain(I)*A(Side,I)
7570   Tal(W(Side,I))=Tal(W(Side,I))+N(I)*A(Side,I)
7580   Tot_fuel_gain=Tot_fuel_gain+Ngain(I)*F(Side,I)
7590   Tot_fuel_lose=Tot_fuel_lose+N(I)*F(Side,I)
7600 NEXT I
7610 REM - UPDATE UNIT AMMO/FUEL STATUS
7620 FOR I=1 TO 3
7630   IF Tag(I)=0 THEN
7640     Ngain(118+I)=0
7650   ELSE
7660     Ngain(118+I)=Ammo_gain(I)/Tag(I)
7670   END IF
7680   IF Ngain(118+I)>1 THEN Ngain(118+I)=1
7690   IF Tal(I)=0 THEN
7700     N(118+I)=0
7710   ELSE
7720     N(118+I)=Ammo_lose(I)/Tal(I)
7730     IF N(118+I)>1 THEN N(118+I)=1
7740   END IF
7750 NEXT I
7760 IF Tot_fuel_gain=0 THEN
7770   Ngain(101)=0
7780 ELSE
7790   Ngain(101)=Fuel_gain/Tot_fuel_gain
7800 END IF
7810 IF Ngain(101)>1 THEN Ngain(101)=1
7820 IF Tot_fuel_lose=0 THEN
7830   N(101)=0
7840 ELSE
7850   N(101)=Fuel_lose/Tot_fuel_lose
7860 END IF
7870 REM - CALCULATE UNIT EFFECTIVENESS

```

Table 2-2. Game initialization code.

```

7880 Eff_gain=0
7890 Eff_lose=0
7900 FOR I=1 TO 70
7910   Eff_gain=Ngain(I)*S(Side,I)+Eff_gain
7920   Eff_lose=N(I)*S(Side,I)+Eff_lose
7930 NEXT I
7940 IF Ugain(71)=0 THEN
7950   Ngain(79)=0
7960 ELSE
7970   Ngain(79)=Eff_gain/Ugain(71)
7980 END IF
7990 IF U(71)=0 THEN
8000   N(79)=0
8010 ELSE
8020   N(79)=Eff_lose/U(71)
8030 END IF
8040 REM - WRITE TO FILE
8050 OUTPUT @Punit,G;Ngain(*)
8060 OUTPUT @Punit,L;N(*)
8070 OUTPUT @Ptoe,G;Ugain(*)
8080 OUTPUT @Ptoe,L;U(*)
8090 INPUT "ANY MORE ELEMENTS TO TRANSFER? (Y OR N)",Q$
8100 IF Q$="N" THEN B120
8110 IF Q$="Y" THEN Element_input
8120 INPUT "ANY MORE UNITS TO TRANSFER? (Y OR N)",Q$
8130 IF Q$<>"Y" AND Q$<>"N" THEN B120
8140 IF Q$="Y" THEN Start_input
8150 Transend: !
8160 RETURN
8170 !-----
8180 Game_turn: !
8190 !PRINT USING "@"
8200 !PRINTER IS 702
8210 !PRINT USING "@"
8220 PRINT "***** GAME TURN RESUPPLY *****"
8230 PRINTER IS 1
8240 PRINT "ENTER UNIT FILE CHANGES FOR GAME TURN"
8250 REPEAT
8260   PRINT USING "//"
8270   REPEAT
8280     INPUT "ENTER UNIT NUMBER (1-400, 999=STOP)",I
8290     UNTIL I<=400 AND I>=1 OR I=999
8300     IF I=999 THEN GOTO The_end
8310     PRINT "UNIT ";I
8320     PRINT
8330     PRINT
8340     ENTER @Punit,I;N(*)
8350     !
8360     REPEAT
8370       REPEAT
8380         INPUT "ENTER LINE # (1-6, 999=NEXT UNIT) ".L
8390         UNTIL L=1 OR L=2 OR L=3 OR L=4 OR L=5 OR L=6 OR L=999

```

Table 2-2. Game initialization code.

```

8400     IF L=999 THEN GOTO End_lines
8410     ON L GOSUB Line1,Line2,Line3,Line4,Line5,Line6
8420 End_lines: !
8430     UNTIL L=999
8440     OUTPUT @Punit,I;N(*)
8450     UNTIL I=999
8460 The_end:!
8470     RETURN
8480 Line1:!
8490     PRINT "      LINE 1:"
8500     INPUT "ENTER: ACTIVITY, MOPP LEVEL, MISSION, KV MOVED",N(82),N(77),N(83),I
(146)
8510     CALL Ck_var("ACTIVITY","OR",N(82),0,2)
8520     CALL Ck_var("MOPP LEVEL","OR",N(77),1,2)
8530     GOSUB Unitfile_disk
8540     PRINT "      ",N(82),N(77),N(83),N(146)
8550     PRINTER IS 1
8560     RETURN
8570 Line2:!
8580     PRINT "      LINE 2:"
8590     INPUT "ENTER: SENSOR GP, ZONE, PCT COVERED",N89y,N(89),N(90)
8600     CALL Ck_var("SENSOR GROUP","TO",N89y,0,9)
8610     CALL Ck_var("ZONE","TO",N(89),1,5)
8620     CALL Ck_var("PCT COVERED","THRU",N(90),0,100)
8630     PRINT "      ",N89y,N(89),N(90)
8640     PRINTER IS 1
8650     N(89)=(INT(N(89)))+(N89y/10)
8660     N(90)=N(90)/100
8670     RETURN
8680 Line3:!
8690     PRINT "      LINE 3:"
8700     INPUT "ENTER PCT ADA SUPPRESSION DATA: Vehicle, Hand held, Corps ada",N(80
),N80y,Xx
8710     IF Xx=0 THEN
8720         N(81)=N(81)
8730     ELSE
8740         N(81)=Xx
8750     END IF
8760     CALL Ck_var("Vehicle","TO",N(80),0,99)
8770     CALL Ck_var("Hand held","TO",N80y,0,99)
8780     PRINT "      ",N(80),N80y,N(81)
8790     PRINTER IS 1
8800     N(80)=(INT(N(80)))+(N80y/100)
8810     RETURN
8820 Line4:!
8830     PRINT "      LINE 4:"
8840     INPUT "ENTER RESUPPLY DATA: DF(Tons),IF(Tons),AD(Tons), FUEL(Gal)",N1,N2,N
3,N(110)
8850     N(135)=N1+N2+N3
8860     IF (N1+N2+N3)=0 THEN
8870         Ndf=0
8880         Nif=0

```

Table 2-2. Game initialization code.

```

8890     N(136)=0
8900 END IF
8910 PRINT "      "," DF"," IF"," ADA","TOTAL","FUEL"
8920 PRINT "      ",N1,N2,N3,N(135),N(110)
8930 IF N(135)<=0 THEN 9050
8940 !FOR J=1 TO 3
8950     !IF N(J)=0 THEN
8960         !GOTO 4467
8970     !ELSE
8980         !N(J)=100*N(J)/N(135)
8990     !END IF
9000 !NEXT J
9010 Ndf=N1/(N1+N2+N3)
9020 Nif=N2/(N1+N2+N3)
9030 IF Nif=1 THEN Nif=.999
9040 N(136)=(INT(Ndf*1000))+Nif
9050 PRINTER IS 1
9060 RETURN
9070 Line5: !
9080 PRINT "      LINE 5:"
9090 INPUT "ENTER DISPENSED DATA: DF(Tons), IF(Tons), AD(Tons), FUEL(Gal)",N1,N2,
N3,N(112)
9100 N(137)=N1+N2+N3
9110 IF N(137)=0 THEN
9120     Ndf=0
9130     Nif=0
9140     N(138)=0
9150 END IF
9160 IF N(137)<=0 THEN 9300
9170 PRINT "      "," DF"," IF"," ADA","TOTAL","FUEL"
9180 PRINT "      ",N1,N2,N3,N(137),N(112)
9190 !FOR J=1 TO 3
9200     !IF N(J)=0 THEN
9210         !GOTO 4492
9220     !ELSE
9230         !N(J)=100*N(J)/N(137)
9240     !END IF
9250 !NEXT J
9260 Ndf=N1/(N1+N2+N3)
9270 Nif=N2/(N1+N2+N3)
9280 IF Nif=1 THEN Nif=.999
9290 N(138)=(INT(Ndf*1000))+Nif
9300 PRINTER IS 1
9310 RETURN
9320 Line6: !
9330 IF I>191 THEN PRINT "      LINE 6: GR RADAR, CB RADAR, LRRP, SLAR, RPV, FO"
9340 IF I<192 THEN PRINT "      LINE 6: GR RADAR, CB RADAR, LRRP, RFV, SLAR, FO"
9350 INPUT N(95),N(96),N(97),N(98),N(99),N(100)
9360 PRINT "      LINE 6: ";N(95);N(96);N(97);N(98);N(99);N(100)
9370 PRINTER IS 1
9380 RETURN
9390 !-----

```

Table 2-2. Game initialization code.

```

9400 Calc_combat_eff: !
9410 ENTER @Ptoe, I; U(*)
9420 U0=0
9430 K=INT(N(78))
9440 IF K=0 THEN 9490
9450 FOR J=1 TO 70
9460   U0=U0+N(J)*S(K, J)
9470 NEXT J
9480 N(79)=U0/U(71)
9490 GOSUB Unitfile_disk
9500 RETURN
9510 !-----
9520 Unitfile_disk: !
9530 N1=INT(N(83))
9540 IF N(78)=0 THEN 9760
9550 !SET MAJOR MISSION
9560 SELECT N1
9570 CASE 0
9580   N(75)=4
9590 CASE 1
9600   N(75)=1
9610 CASE 2
9620   N(75)=4
9630 CASE 3 TO 4
9640   N(75)=1
9650 CASE 5 TO 7
9660   N(75)=2
9670 CASE 8
9680   N(75)=3
9690 CASE 9
9700   N(75)=4
9710 END SELECT
9720 N(127)=N(83)
9730 N(128)=N(83)
9740 N(129)=N(83)
9750 N(107)=N(83)
9760 OUTPUT @Punit, I; N(*)
9770 RETURN
9780 !*****
9790 Zero_unit: !
9800 M$=" "
9810 IF Choices$="B" THEN
9820   INPUT "ZERO OUT WHICH UNIT?", Unit
9830   IF Unit<1 OR Unit>400 THEN 9820
9840   FOR K=1 TO 150
9850     N(K)=0
9860   NEXT K
9870   OUTPUT @Punit, Unit; N(*)
9880   OUTPUT @Ptoe; N(*)
9890   OUTPUT @Pname, Unit; M$
9900   RETURN
9910 END IF

```

Table 2-2. Game initialization code.

```

9920 IF Choice$="C" THEN
9930   FOR Unit=1 TO 191
9940     FOR K=1 TO 150
9950       N(K)=0
9960     NEXT K
9970     OUTPUT @Punit,Unit;N(*)
9980     OUTPUT @Ptoe;N(*)
9990     OUTPUT @Pname,Unit;M$
10000    NEXT Unit
10010    RETURN
10020 END IF
10030 IF Choice$="D" THEN
10040   FOR Unit=192 TO 400
10050     FOR K=1 TO 150
10060       N(K)=0
10070     NEXT K
10080     OUTPUT @Punit,Unit;N(*)
10090     OUTPUT @Ptoe;N(*)
10100     OUTPUT @Pname,Unit;M$
10110    NEXT Unit
10120    RETURN
10130 END IF
10140 IF Choice$="E" THEN
10150   FOR Unit=1 TO 400
10160     FOR K=1 TO 150
10170       N(K)=0
10180     NEXT K
10190     OUTPUT @Punit,Unit;N(*)
10200     OUTPUT @Ptoe;N(*)
10210     OUTPUT @Pname,Unit;M$
10220    NEXT Unit
10230    RETURN
10240 END IF
10250 IF Choice$="F" THEN
10260   PRINT "ZERO OUT FROM WHICH UNIT TO WHICH UNIT?"
10270   INPUT "(INPUT STARTING UNIT NUMBER,ENDING UNIT NUMBER)",First,Last
10280   IF First<1 OR First>Last THEN
10290     PRINT "ERROR IN STARTING UNIT NUMBER.  TRY AGAIN."
10300     GOTO 10260
10310   END IF
10320   IF Last<First OR Last>400 THEN
10330     PRINT "ERROR IN ENDING UNIT NUMBER.  TRY AGAIN."
10340     GOTO 10260
10350   END IF
10360   FOR Unit=First TO Last
10370     FOR K=1 TO 150
10380       N(K)=0
10390     NEXT K
10400     OUTPUT @Punit,Unit;N(*)
10410     OUTPUT @Ptoe;N(*)
10420     OUTPUT @Pname,Unit;M$
10430   NEXT Unit

```

Table 2-2. Game initialization code.


```

10440 RETURN
10450 END IF
10460 RETURN
10470 !-----
10480 Subprogram_end: !
10490 LOAD "DIME"&Disk$
10500 END
10510 !*****
10520 SUB Ck_var (Var_name$,T$,Variable,Min_value,Max_value)
!0530 SELECT T$
10540 CASE "THRU"
10550 WHILE Variable<Min_value OR Variable>Max_value
10560 GOSUB Print_error
10570 END WHILE
10580 CASE "OR"
10590 GOTO Case_to
10600 CASE "TO"
10610 Case_to:FOR M=Min_value TO Max_value
10620 IF Variable=M THEN GOTO End_select
10630 NEXT M
10640 GOSUB Print_error
10650 GOTO Case_to
10660 End_select:!
10670 END SELECT
10680 GOTO Rtrn
10690 Print_error: !
10700 PRINT
10710 PRINT "** ERROR: ";Variable;" IS INVALID FOR ";Var_name$
10720 PRINT "INPUT: ";Min_value;" ";T$;" ";Max_value;" ONLY"
10730 INPUT Variable
10740 RETURN
10750 Rtrn:!
10760 SUBEND

```

Table 2-2. Game initialization code.

CHAPTER 3

DETECTION

1. PURPOSE.

The DIME detection program attempts to portray the detection of units and the intelligence fusion process necessary to recognize unit type and location.

2. GENERAL.

A. The DIME detection program (P7) is a straightforward adaptation of the DAME detection module discussed in CAORA/TR-5/83, Deep Attack Map Exercise (DAME) Game Rules and Operation Procedures.

B. The detection program consists of a main program and 15 associated data bases.

C. The program requires gamer inputs describing the location of each enemy sensor group covering the targeted unit. Output from the program consists of a list of units which have been detected (simply found but not fully identified), verified (found, identified, and being tracked), or lost (previously verified/detected but now lost). The list represents the intelligence map held by the friendly commander. In essence, it is his view of the battlefield with respect to enemy units and is intended to be used as a basis for his decision to tactically respond to these units. The program provides one list for the Blue commander and one list for the Red commander.

3. DATA FLOW.

A. The detection program uses three types of data inputs: the unit status file ("UNITFILE"), auxiliary, and online data files.

(1) The detection program accesses the "UNITFILE" for the following inputs:

- (a) Sensor status (element 89)
- (b) Unit type (element 78)
- (c) Unit fraction covered by sensor groups (element 90)
- (d) Detection status (element 91)
- (e) Intelligence status (element 92)
- (f) Activity code (element 82)

(2) The auxiliary stored data is generated by running 14 support programs. Table 3-1 indicates these 14 support programs and the resulting files created by executing these programs. A complete discussion of the file structure for these 15 files is covered under paragraph 4 of this chapter. For further information, refer to Volume III of the DIME documentation.

(3) The detection program uses four online data files:

- (a) Exposure profiles for individual elements in a unit (Table 3-2)
- (b) Red intelligence thresholds (Table 3-3)
- (c) Blue intelligence thresholds (Table 3-4)
- (d) Unit movement profile (Table 3-5).

B. The detection program combines the inputs listed in paragraph 3A with the three-step methodology discussed under paragraph 5 to provide the following outputs:

- (1) A list of units which have been detected, verified, or lost.
- (2) An updated "UNITFILE" for the next critical incident (CI).

C. Figure 3-1 indicates the generalized data flow for the detection program.

4. FILE STRUCTURE.

The detection program requires 15 auxiliary files, four online files, and the "UNITFILE". This section will address the file structure for these data files.

A. Auxiliary. The auxiliary files consist of 15 files: REDPOTA, BLUPOT1, RFLEE, BFLEE, BLBDG, RDBDE, RDCOR, RS1TO6, BS1TO6, RTHOLD, BTHOLD, REI, BEI, RSENPRO, and BSENPRO.

Table 3-1. Detection data support programs.

Program Name	Purpose	Resulting File Name
LDBPOT1	Loads the POTA* data for Red sensors detecting Blue units.	BLUPOT1
LDRPOTA	Loads the POTA* data for Blue sensors detecting Red units.	REDPOTA
LBFLEE	Loads the target movement profile for the Blue units.	BFLEE
LFLEE	Loads the target movement profile for the Red units.	RFLEE
LBLBDG	Loads the sensor data for Blue battalions in contact between 0-10 km.	BLBDG
LRDBDE	Loads the sensor data for Red regiments in contact between 0-10 km.	RDBDE
LRDCOR	Loads the sensor data for Red commanders for units between 0-3 km.	RDCOR
LS1T06	Loads the detection probabilities for six Blue sensors against 5 signature types.	BS1T06
LRS1T06	Loads the detection probabilities for six Red sensors against 5 signature types.	RS1T06
LBTHOLD	Loads the Blue intelligence threshold percentages developed by DAME.	BTHOLD
LRTHOLD	Loads the Red intelligence threshold percentages developed by DAME.	RTHOLD
LBEI	Loads the Blue sensor profile data developed by DAME.	BEI
LREI	Loads the Red sensor profile data developed by DAME.	REI
GROUPBLD	Loads the Blue and Red sensor groups.	BSENPRO RSENPRO

*Probability of operational target acquisition.

Table 3-2. Fractional target exposure criteria. (Target fractions which are exposed in various mission postures.)

<u>Mission</u>	<u>Target element categories</u>				
	<u>Personnel</u>	<u>Vehicles</u>	<u>Tanks/APC</u>	<u>Artillery</u>	<u>Rockets</u>
Attack	.40	.75	.75	.75	.75
Defend	.10	.30	.30	.60	.50
Reserve	.30	.40	.40	.60	.50
Move	.10	.65	.65	.60	.50

Table 3-3. Red intelligence thresholds. (fraction of exposed Blue elements which must be detected to correctly associate elements with Blue unit types.)

<u>Unit Type</u>	<u>Target element categories</u>				
	<u>Personnel</u>	<u>Vehicles</u>	<u>Tanks/APC</u>	<u>Artillery</u>	<u>Rockets</u>
Combat	.20	.40	.50	.50	.40
Artillery	.20	.40	.50	.50	.40
ADA	.20	.40	.60	.50	.40
AH Gnd/FARP	.20	.40	.20	.20	.40
CP/HQ	.20	.30	.40	.20	.40
Engineer	.20	.40	.60	.20	.40
POL/Ammo	.20	.45	.80	.20	.40
Maintenance	.20	.50	.40	.20	.40
SAM	.20	.30	.20	.30	.40
Radar/EW	.20	.40	.10	0	.40

Table 3-4. Blue intelligence thresholds. (Fraction of exposed Red elements which must be detected to correctly associate with Red unit types.)

<u>Unit Type</u>	<u>Target element categories</u>				
	<u>Personnel</u>	<u>Vehicles</u>	<u>Tanks/APC</u>	<u>Artillery</u>	<u>Rockets</u>
Combat	.20	.25	.35	.30	.40
Artillery	.20	.25	.35	.35	.40
ADA	.20	.30	.35	.30	.40
AH Gnd/FARP	.20	.35	.20	.20	.40
CP/HQ	.20	.30	.40	.20	.40
Engineer	.20	.25	.40	.20	.40
POL/Ammo	.20	.40	.40	.20	.40
Maintenance	.20	.40	.40	.20	.40
SAM	.20	.30	.20	.30	.40
Radar/EW	.20	.40	.10	0	.40

Table 3-5. Time intervals between unit movements to avoid detection

<u>Unit type</u>	<u>Red stationary time (hours)</u>	<u>Blue stationary time (hours)</u>
Combat	2	2
Artillery	3	4
ADA	3	3
AH Gnd/FARP	3	3
CP/HQ	2	6
Engineer	4	6
POL/Ammo	12	12
Maintenance	24	24
SAM	24	24
Radar/EW	3	6




Figure 3-1. Detection data flow.

(1) REDPOTA. A file containing 10 records representing the probability of operational target acquisition (POTA) for the Blue sensors detecting the Red targets. Each record contains the probability of detection as a function of 10 targets/units and five zones.

(a) Targets/units.

1. Combat.
2. Artillery.
3. Air defense (ADA).
4. Attack helicopter ground forward arming and refueling point (FARP).
5. Command post/headquarters (CP/HQ).
6. Engineer.
7. Fuel/ammunition (POL/AMMO) supply point.
8. Maintenance point.
9. Surface-to-air missile (SAM) site.
10. Communication/radar/electronic warfare (EW) site.

(b) Target surveillance zones.

1. Zone I. 0-3 km beyond Forward Edge of the Battle Area.
2. Zone II. 3-12 km beyond FEBA.
3. Zone III. 12-25 km beyond FEBA.
4. Zone IV. 25-100 km beyond FEBA.
5. Zone V. 100-200 km beyond FEBA.

(2) BLUPOT1. Same as REDPOTA except this file contains the probability of operational target acquisition (POTA) of the Red sensors detecting the Blue targets.

(3) RFLLEE. A file containing the stationary profile time for the 10 targets listed under REDPOTA above. This file contains one record with 10 entries. Each entry represents the time in hours a Red target remains stationary until it moves.

(4) BFLEE. Same as RFLEE except this file contains the stationary profile time for the Blue targets.

(5) BLBDG. A file containing the probability of a Blue reconnaissance party detecting any of the 10 Red targets within 10 kilometers of the Blue battalion.

(6) RDBDE. Same as BLBDG except this file contains the probability a Red reconnaissance party can detect any of the 10 Blue targets when the Red brigade is in contact.

(7) RDCOR. A file containing the probability a Red commander can detect and/or verify 10 Blue units within 0-3 km from Red commander.

(8) RS1T06. A file containing the probability of detection for six Red sensors detecting five target types. The file consists of 30 records. The records are structured in the following manner where:

Sensor 1 is Small Fred.
Sensor 2 is Big Fred.
Sensor 3 is Forward Observer (FO), day.
Sensor 4 is Long-range reconnaissance patrol (LRRP).
Sensor 5 is Remotely piloted vehicle (RPV)/Drones.
Sensor 6 is Side-looking airborne radar (SLAR).

(a) Record 1 contains the probability that sensor 1 can detect personnel located in zones 1-5 (see REDPOTA above for zones). Each record has five entries.

(b) Record 2 contains the probability that sensor 1 can detect vehicles located in zones 1-5.

(c) Record 3 contains the probability that sensor 1 can detect tanks/armored personnel carriers located in zones 1-5.

(d) Record 4 contains the probability that sensor 1 can detect artillery targets located in zones 1-5.

(e) Record 5 contains the probability that sensor 1 can detect rocket targets located in zones 1-5.

(f) Records 6-10 contains the probability that sensor 2 can detect five targets (personnel, vehicles, tank/armored personnel carriers (APCs), artillery, rockets) located in one of the five zones.

(g) Records 11-15 contains the probability for sensor 3.

(h) Records 16-20 contains the probability for sensor 4.

(i) Records 21-25 contains the probability for sensor 5.

(j) Records 26-30 contains the probability for sensor 6.

(9) BS1T06. Same as RS1T06 except this file contains the probability of detection for six Blue sensors detecting the five target types where:

Sensor 1 is AN/PPS-15.
Sensor 2 is AN/TPQ-37.
Sensor 3 is FO (day).
Sensor 4 is LRRP.
Sensor 5 is target acquisition designation aerial
reconnaissance system (TADARS).
Sensor 6 is SLAR (ASARS).

(10) RTHOLD. A file containing the threshold percentage for five Red target types in 10 unit types. The file has 10 records. Each record represents one of 10 unit types (see REDPOTA) against five targets (personnel, vehicle, tank/APC, artillery, rockets). Each record contains five entries representing the percent of target which must be detected before the unit is detected.

(11) BTHOLD. Same as RTHOLD except this file contains the threshold percentage for five Blue target types in 10 unit types.

(12) REI. A file containing four records representing the percent of Red target types available for detection in one of four missions.

(a) Target types.

1. Personnel.
2. Vehicle.
3. Tanks/APC.
4. Artillery.
5. Rockets.

(b) Missions.

1. Attack.
2. Defend.
3. Reserve.
4. Move.

(13) BEI. Same as REI except this file contains the percent of Blue target types available for detection in one of four missions.

(14) RSENPRO. A file containing three records describing three Red group profiles. The record structure is as follows.

(a) Record 1. For sensor group 1, each entry represents:

1. Number of ground radars in group.
2. Number of artillery radars in group.
3. Number of LRRP in group.
4. Number of RPV in group.
5. Number of SLAR in group.
6. Number of FO in group.

(b) Record 2. Same as record 1 for sensor group 2.

(c) Record 3. Same as record 1 for sensor group 3.

(15) BSENPRO. Same as RSENPRO except this file contains the three Blue group profiles as a function of the sensors in the group.

B. Online. The online files consist of four files: exposure profiles, Red intelligence threshold, Blue intelligence threshold, and unit movement profile.

(1) Exposure profiles. The exposure profiles shown in Table 3-2 represents an effort to relate an element exposure profile to each of the five signature types in one of four missions.

(a) The exposure profile data is contained in four records of five elements each, where each record represents one of four missions (attack, defend, reserve, move) and each element represents one of five signature types (personnel, vehicle, tank/APC, artillery, rockets).

(b) The exposure profiles were developed by the DAME project team using military judgment.

(2) Red/Blue intelligence thresholds. The intelligence threshold tables shown in Tables 3-3 and 3-4 represent the fraction of exposed Blue/Red elements which must be detected to correctly associate elements with Blue/Red unit types. The intelligence threshold data is contained in 10 records of five elements each, where each record represents one of 10 unit types (combat, artillery, ADA, FARP site, command post, engineer, POL/AMMO, maintenance, SAM, radar) and each element represents one of five signature types.

(3) Unit movement profile. The unit movement profiles shown in Table 3-5 represent the time intervals between unit movements to avoid detection. The movement profile data consists of 10 records of two elements each, where

each record represents one of 10 unit types and each element represents one of two forces (Blue, Red).

C. "UNITFILE". The "UNITFILE" is a 400-record file containing 150 elements. Records 1-191 represent the Blue units and records 192-400 represent the Red units. The detection program requires six elements on the "UNITFILE."

(1) Sensor status. Element 89 contains the sensor status (X.Y) where:

X = POTA zone values (1-5) for sensor group Y.

Y = Sensor groups (0-4) detecting this particular unit.

- 0 = Not covered
- 1-3 = Applicable Blue/Red sensor group
- 4 = Linear FEBA oriented - sensor array

Default = (1.4).

(2) Unit type. Element 78 contains the unit type (X.Y), where:

X = Player ID

- 1 = Blue
- 2 = Red

Y = Unit type

- 0 = Combat
- 1 = Artillery
- 2 = ADA
- 3 = FARP
- 4 = CP/HQ
- 5 = Engineer
- 6 = POL/AMMO supply
- 7 = Maintenance
- 8 = SAM site
- 9 = Com/radar/EW site.

(3) Unit fraction covered by sensor group. Element 90 contains a real value of 0 - 1.0 indicating the fraction of the unit covered by a sensor group.

(4) Detection status. Element 91 contains the detection status for each unit (X.Y), where:

X = Represents hours left until redetected

Y = Represents the unit status with respect to detection by the opposite commander

- 0 = Not detected
- 1 = Detected but not verified

2 = Acquired/verified
3 = Lost

(5) Intelligence status. Element 92 contains the total hours this target has been tracked this detection.

(6) Activity code. Element 82 indicates the status of the unit as not active (0) or active (1).

5. ALGORITHMS.

A. In simulating the production of the commander's intelligence map, the program considers three processes.

(1) The ability of the friendly sensors to detect individual elements of the enemy unit.

(a) Calculation of element detection by sensor groups considers elements of target units to be divided into five categories: personnel, armored combat vehicle, support vehicles, artillery, and large rockets. Target units and their associated elements can be located in one of five range bands from the sensors. In order to simplify game play, location of sensor groups is represented on the map board. Sensor groups consist of one or more individual sensors of varying types. Sensors in a group have individual detection probabilities limiting their range effectiveness. However, the program assumes that an individually exposed target element is covered by all persons in the group having an effective range to that element. The probability of the sensor group detecting an individual element is given by:

$$P_{Ge} = 1 - \prod_{\text{all } i} (1 - P'_{ie})^{n_i} \quad (\text{Eq. 3-1})$$

where:

P_{Ge} = the probability that an exposed element of type e is detected by sensor group G.
 P'_{ie} = the probability that sensor i can detect element e.
 n_i = the number of sensors of type i in group G.

(b) As mentioned in the previous paragraph, the probabilities of detection P'_{ie} are range dependent and hence the probability of group detection P_{Ge} is also range dependent. The sensor detection probabilities P_{ie} were developed from sensor performance parameters found in the Target Acquisition Study (TAS II) conducted by Concepts Analysis Activity (CAA) in 1980. The data is classified and will not be presented in this document. However, it should be noted that the probabilities include the following parameters:

$$P'_{ie} = P_{ie} * P_{los} * P_a * P_c * P_j \quad (\text{Eq. 3-2})$$

where:

P_{ie} = the probability that sensor i can detect element e , given that the element is exposed and the sensor is functioning.

P_{los} = probability the sensor has line of sight to the target; in cases where sensors do not require line of sight, this probability is set to 1.

P_a = probability that the sensor is available at the moment the target is exposed.

P_c = probability that the crew manning the sensor will recognize the sensor representation of the target element.

P_j = probability that sensor is not jammed. The jamming probabilities are currently input estimates supplied by the gamer.

(2) The intelligence fusion process whereby numbers of detected enemy elements are mapped into the detection of enemy units by friendly personnel.

(a) The ability of the friendly force to recognize a unit from sensor detections of individual elements is represented in the program by two processes. The first process describes the exposure profile of the target unit. The second process calculates the probability that the unit will be recognized by intelligence personnel and correctly categorized as one of 10 unit types.

(b) The exposure profiles for individual elements in a unit are shown in Table 3-2. All target unit elements in the DIME unit files are categorized by the detection program as one of five signature types. The exposure percentages shown in Table 3-2 are then applied to the sum of the unit elements giving the number of elements exposed to the sensors. Table 3-2 was developed by the DAME project team using military judgment. It represents an effort to relate an element exposure profile to the unit mission.

(c) Tables 3-3 and 3-4 are percentages which are applied to the numbers of exposed target elements. The resulting numbers of elements are intelligence thresholds used by the program to simulate the fusion process of identifying a unit from its parts. The example in figure 3-2 provides an overview of the use of Tables 3-3 and 3-4 by the program. A Blue battalion executing a "move" mission has the number of elements as shown in the DIME "UNITFILE". These elements are then categorized into the five types shown

INPUT. Unit information is extracted from UNITFILE. Composition of unit and unit mission ("move" in this case) are determined.

M1	M2	M3	ITV	INF	CHD	ARTY	ADA	TRK	SP
44	13	6	0	84	4	4	0	14	3

STEP 1. Unit systems are categorized by major type.

PERS	VEH	AFV	ARTY	RKTS
84	17	67	4	0

STEP 2. Exposure profile data (Table 3-3) is applied to element categories. The number of elements is determined.

.10	.65	.65	.60	.50
-----	-----	-----	-----	-----

STEP 3. Intelligence thresholds for unit detection (Table 3-4) are applied.

.20	.40	.50	.50	.40
-----	-----	-----	-----	-----

RESULT. Threshold numbers for unit detection.

1.7 Personnel 4.4 Vehicles 21.8 AFV 1.2 Artillery 0 Rockets

Figure 3-2. Example use of intelligence threshold data.

in step 1. In the second step, the program extracts the exposure profile percentages for a "move" from Table 3-2 and calculates these numbers of elements exposed to that sensor group. In step three, the intelligence profile is extracted from Table 3-3 and applied to the exposed elements to generate the numbers of unit elements representing intelligence thresholds. These represent the number of elements which must be detected before the intelligence map is posted with a unit detection. In the example, two personnel, five vehicles, 22 tanks, and two artillery pieces must be detected before the unit will be detected as a battalion.

(d) The detection program uses a normal approximation of the binomial distribution to calculate the probability of detecting the least threshold number of elements in each category in the following manner:

$$P_{ce} = 1 - \Phi[(T_e - \bar{X}_e)/\delta_e] \quad (\text{Eq. 3-3})$$

where:

P_{ce} = probability that the intel personnel receiving reports from sensor group c will detect enough category e elements to identify the unit.

$\Phi(X)$ = the cumulative normal density function evaluated to X.

T_e = the number of threshold elements of category e needed to detect the unit.

\bar{X}_e, δ_e = the mean and standard deviation of the normal approximation to the binomial distribution.

T_e is represented by:

$$T_e = S_e * E_e * I_e * Z \quad (\text{Eq. 3-4})$$

where:

S_e = the sum of elements of type e in the unit.

E_e = the fraction of elements of type e exposed under the current mission (see Table 3-2).

I_e = the minimal fraction of elements of type e which must be detected before the unit can be detected (see Tables 3-3 and 3-4).

Z = a factor adjusting the intelligence threshold for units which were previously detected but are now lost. $Z = 1.0$ for units not previously detected and 0.75 for units lost during tracking.

\bar{X}_e is represented by:

$$\bar{X}_e = S_e * E_e * P_{Ge} \quad (\text{Eq. 3-5})$$

where:

S_e and E_e are described above and P_{Ge} = probability that sensor group G will detect an element of type e.

δ_e is represented by:

$$\delta_e = S_e * E_e * P_{Ge} * (1 - P_{Ge}) \quad (\text{Eq. 3-6})$$

where S_e , E_e and P_{Ge} are as described above.

The detection program calculates P_{Ge} for each element category within the unit. These probabilities are used in a Monte Carlo evaluation to determine which categories are detected within the unit. Units are "detected" and posted on the intelligence list if one-half or more of their element categories are detected.

(e) The use of target exposure profiles (Table 3-2), intelligence detection profiles (Tables 3-3 and 3-4), and the normal binomial approximation structure has some inherent assumptions and limitations. The reader is reminded that due to a paucity of field data, Table 3-2 was developed using military judgment. The underlying assumption in the use of this table is that the unit mission (not the unit type) describes the level of concealment the unit is able to achieve. Tables 3-3 and 3-4 are totally subjective in nature. They were also developed by the DAME programming team using military judgment. They were built under the assumption that a good intelligence officer will identify units with some prior knowledge of their type and mission. He will have maps to estimate reasonable deployment areas and some knowledge of enemy force structures to guide him in use of sensor reports. Finally, the use of the normal approximation of the binomial distribution works well when units have several elements. In a battalion/regimental game where most categories have more than 10 elements, it is adequate. Care should be used in applying it to smaller units.

(3) Unit losses and unit verification.

(a) Following the detection of a target unit, the program also represents the tracking of that unit by the sensor groups. Units are allowed to change positions to avoid detection at a tactically realistic rate. Table 3-5 contains the unit movement profile showing the time intervals at the end of which a unit will purposefully move to confuse the sensors. This table was also based on data used in the TAS II study. This movement should not be confused with a "move" mission where a unit is required to travel to another point on the battlefield. The avoidance movement is merely a changing of positions while maintaining the same

mission and staying in the same tactical area. The program uses the following set of automated rules to represent tracking of detected units.

1. Units that are detected remain detected until they move.
2. Units that move to avoid detection must be redetected following their movement.
3. Units that are executing a move mission must be redetected every three hours.
4. Previously detected units that are not redetected during a move are placed in a "lost" status for three hours. If not redetected during the next three hours, they are moved to an "undetected" status and are removed from the intelligence list.
5. Detection thresholds are lowered to 75 percent of their normal values for redetecting moving units or units in a "lost" status.

(b) The program represents three states of unit detection.

1. Detected - a unit has been found and its type has been identified. Its mission, exact location, and strength are unknown.
2. Verified - The type and exact location of a unit are known. A reasonable estimate has been made of unit mission and strength.
3. Lost - A previously detected or verified unit has been lost during a move. Within three hours, the position and unit type are either known or moved to undetected status.

The program moves units from a "detected" to "verified" status if detection is maintained for four hours.

B. The previous paragraphs have described the principal methodology used in building the DIME target intelligence maps. This methodology is applied to both Blue and Red unit files during each three-hour period of the game. The program has three other features representing special intelligence situations which also impact the target hits.

(1) Begin game for Red/Blue. This feature initializes the target detection list and represents accumulated intelligence knowledge at the beginning of the game. The methodology is a simplified version of the one described above. Sensor groups and intelligence thresholds are ignored and replaced with tabular probabilities representing unit detections as a function of unit range from the forward line of own troops (FLOT). The unit detection probabilities were taken from the results of TAS II. This feature is required preceding the start of a game.

(2) Update intelligence for Blue/Red units in contact. The previous paragraphs have described a methodology for the detection of units which are

at ranges beyond the visual capabilities of localized battalion personnel. However, when battalions are within 10km of enemy units they are considered to be in contact by the DIME intelligence program. This is represented in the program by a special data base representing detection probabilities of long-range reconnaissance patrols against elements of enemy units. The methodology for calculating detection of enemy units is the same as that listed in paragraph 5a above.

(3) Red commander's verification of Blue units. One of the critical aspects of the deep strike game is Red's ability to identify Blue units operating in his rear area. It was believed that Red players would require a special representation of the sensor elements directly under the control of the Red commander. Specifically, air reconnaissance assets would probably be used by the Red commander to "verify" the presence of Blue units having a "detected" status operating in his rear area. In order to simulate this, the program uses probabilities of element detection representing airborne photo assets flying over a detected Blue unit. Any Blue unit redetected by the airborne units is immediately posted as "verified" on the Red commander's intelligence map. The methodology for unit identification is identical to that described in paragraph 5a above.

6. "UNITFILE" IMPACT.

The "UNITFILE" inputs and outputs are essential to the detection program.

A. Inputs. The detection program uses the unit information stored in elements 75, 89, 78, 90, 91, 92 and 82 to produce an intelligence map for both the Blue and Red commanders. (See the discussion under paragraphs 3, 4, and 5 of this chapter.)

B. Outputs. In addition to providing the intelligence map, the detection program updates the "UNITFILE" for the following words:

(1) Detection status (91). The detection status is represented by two numbers (X,Y), where the first number represents the hours left until the unit can be redetected and the second number represents the unit status as not detected (0), detected (1), verified (2), or lost (3).

(2) Total hours target has been tracked this detection (92). This value is an integer value identifying the total detection time, where maximum detection time is three hours.

7. CODE.

The detection code consists of a driver routine and seven subroutines: Load_pota, Decompos, Print_det_unit, Bld_sen_grp, Blue_in_contact, Prob_of_detect, and Normal_approx.

A. The driver routine controls the detection program through a menu-subroutine format. Figure 3-3 shows the menu with the accompanying subroutines.

B. Upon selection of the appropriate option, the driver routine calls one of three major subroutines: Load_pota, Blue_in_contact and Bld_sen_grp.

(1) Load_pota subroutine reads in the appropriate data files from both the auxiliary stored files and the "UNITFILE". This data, in turn, is passed to the Prob_of_detect routine.

(a) The Prob_of_detect routine applies a normal approximation methodology to determine a list of units which have been detected, verified, or lost.

(b) Once a unit has been classified as detected, verified, or lost, this information is passed to the Decompose routine and the Print_det_unit routine. The Decompose routine updates the "UNITFILE" for elements 91 and 92. The Print_det_unit routine prints out a list of the units and their intelligence status as either detected, verified, or lost.

(2) Blue_in_contact. The Blue_in_contact routine reads in the appropriate data files for battalions that are within 10 km of enemy units. This data, along with the unit information stored on the "UNITFILE" is passed to the Decompose routine and the Print_det_unit routine. Again the commander is provided a list of the unit's intelligence status and the "UNITFILE" is updated accordingly. Contrary to its name, this routine is used for both Red and Blue.

(3) Bld_sen_group. The Bld_sen_group subroutine allows the gamer to create, change, or list Red and Blue sensor groups. The gamer specifies the number of sensors, per type, he wishes to assign to each sensor group. The sensor groups consist of six types for both Blue and Red.

(a) The Blue sensor group is composed of the following six types of sensors:

1. Ground radar
2. Artillery radar
3. LRRP
4. SLAR
5. Air Force/Infrared (AF/IR)
6. FO.




Figure 3-3. Detection menu selection diagram.

(b) The Red sensor group is composed of the following six types of sensors:

1. Ground radar
2. Artillery radar
3. LRRP
4. RPV
5. SLAR
6. FO.

These sensor groups are placed into the Bsenpro and Rsenpro files which are used within the Load_pota routine to determine the commander's intelligence list.

C. The subroutines and their primary variables are contained in Table 3-6. A listing of the original P7 code appears in Table 3-7.

Table 3-6. Detection Subroutine Table.

<u>Functional area(s):</u>	<u>A. Main Routine</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>	
Driver	Sets the random number seed. Selects the appropriate option and transfers control to that section of code.			
Load_pota	Updates current list at beginning of CI.	A. H1(I,J)	Detection probabilities for sensor I where I represents the target type and J represents the sensor zone. I: 1 = Personnel 2 = Vehicles 3 = Tanks/APCs 4 = Artillery 5 = Rockets J: (1-5) sensor zones	
		B. H2(*) - H6(*)	Detection probabilities for sensors 2 - 6.	
		C. E1(I,J)	Array containing fraction of elements of unit I available for detection when unit is on mission J.	
		D. F8(I,J)	Intelligence threshold array holding the fraction of a unit that must be detected before a unit detection can be assessed where: I = Element categories 1-5 J = Sensor groups 106	
		E. G3(I,J)	Array containing the number of sensors of sensor type J (1-6) of group I (1-3).	
		F. P1(I,J)	Array containing POTA detection probability for unit I (1-10) and zone J (1-5).	

Table 3-6. Detection Subroutine Table.

<u>Functional area(s):</u>	<u>A. Main Routine</u>	<u>(continued)</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Load_pota (concluded)</u>		<u>Variable description</u>
	G. S1	Blue or Red detection flag. S1 = 1 if Blue detecting Red S1 = 2 if Red detecting Blue.
	H. O1	Variable containing value 1-8; user selected options for acquisition module flow.
	I. N1	The number of hours of intelligence needed (must be a multiple of 3).
	J. J1	Fraction of sensor messages jammed.
	K. N(*)	Copy of "UNITFILE" entries
	L. S5	Saved variable for sensor group covering current unit.
	M. Q1	Integer part of packed data returned from decomposition subroutine.
	N. Q2	Fractional part of packed data returned from decomposition subroutine.
	O. D2	Unit detection flag: D2 = 0 - unit not found D2 = 1 - unit found.

Table 3-6. Detection Subroutine Table.

<u>Functional area(s):</u>	<u>A. Main Routine</u>	<u>(continued)</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
<u>Normal_approx</u>	Uses the standardized normal distribution $N(0,1)$ to approximate a binomial distribution. Subroutine returns the value D2 as the estimated parameter for the binomial.	A. X			Normalized random variable $N(0,1)$ for approximating the binomial.
<u>Bldg_sen_gp</u>	Calls the Build_sen_group subroutine.				
<u>Print_det_unit</u>	Prints the current unit detection status for proper unit.				
<u>Blue_in_contact</u>	Updates Blue/Red unit commanders intelligence map for Blue/Red in contact	A. P7(I)			Contains the probability of detection for unit I (1-10) under one of the following searches: Blue battalion, Red regiment, Red commander.
		B. F(I)			Holds unit profile for Red or Blue unit I (1-10).
		C. N1			Number of Red or Blue units contacted.
<u>Decompose</u>	Decomposes the proper "UNITFILE" entry N(I) into integer and fractional parts.	A. D8			The absolute value of the "UNITFILE" entry being decomposed.
<u>Prob_of_detect</u>	Sums the elements in a unit (adjusted by the percent covered).	A. T2(I)			Array containing the total number of elements in unit I adjusted by the percent covered. (N(92))

Table 3-6. Detection Subroutine Table.

<u>Functional area(s):</u>	<u>A. Main Routine (concluded)</u>	<u>Primary variables</u>	<u>Variable description</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>		
Prob_of_detect (concluded)	Calculates detection of selected target type. Attempts to detect elements with calculated probabilities.	B. D C. M D. P9(I) E. M9 F. T5 G. T6 H. Z8	Proper zone unit Unit mission Probability of detection for target type I (1-5). Probability of element detection for current element. Number of element categories in this unit containing elements. Number of element categories detected. Intelligence factor: Z8 = 1 - target has been detected. Z8 - .75 = target is being tracked.
<u>Functional area(s):</u>	<u>B. Build sen_group</u>	<u>Primary variables</u>	<u>Variable description</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>		
Main Driver	Builds 3 sensor groups for Blue and 3 sensor groups for Red.	A. S(I)	Array containing number of each sensor type; I = 1-6.

Table 3-7. Detection code.

```

10  !!! - "P7" IS THE ACQUISITION PROGRAM FOR DIME. CODED BY MR. TOM BUTHERO
      SAD, CAORA, AV 552-5481.          DATED 22 OCT 83
20  ! EXPANDED VERSION -- JUNE 9, 1986 -- BY DAO CORP.
30  OPTION BASE 1
40  DIM P1(10,5),N(150),F(10),P7(10),H1(5,9),H2(5,9),H3(5,9),H4(5,9),H5(5,9)
6(5,9),F8(5,10),G3(400,6),P9(5),T2(5),E1(5,4),M$[16],Tm$[7],Temp(150)
50  Disk$=":9134,704,0"
60  Disk2$=":9134,704,0"
70  ! - SET RANDOM NUMBER SEED
80  PRINT USING "@"
90  PRINT "THIS IS THE DIME ACQUISITION PROGRAM"
100 INPUT "INPUT THE RANDOM NUMBER SEED FOR DETECTIONS ; RANGE 1-10000",R5
110 INPUT "WHAT IS THE GAME TIME?",Tm$
120 RANDOMIZE R5
130 FOR I=1 TO 10
140   RS=RND
150 NEXT I
160 PRINT USING "@"
170 PRINT "SELECT ONE OF THE FOLLOWING OPTIONS"
180 PRINT "BEGIN GAME FOR BLUE-1"
190 PRINT "BEGIN GAME FOR RED-2"
200 PRINT "UPDATE CURRENT LIST AT BEGINNING OF CI BLUE-3"
210 PRINT "UPDATE CURRENT LIST AT BEGINNING OF CI RED-4"
220 PRINT "UPDATE BLUE INTEL FOR BLUE IN CONTACT-5"
230 PRINT "UPDATE RED INTEL FOR RED IN CONTACT-6"
240 PRINT "UPDATE RED INTEL FOR RED COMMANDER VERIFICATION-7"
250 PRINT "BUILD SENSOR GROUPS-8"
260 PRINT "STOP RUN-9"
270 INPUT "INPUT OPTION",O1
280 IF O1=9 THEN 5270
290 ON O1 GOSUB Load_pota,Load_pota,Load_pota,Load_pota,Blue_in_contact,Blue
n_contact,Blue_in_contact,Bld_sen_grp
300 GOTO 160
310 Load_pota:
320 ON O1 GOTO 1280,1420,340,810
330 ! - BLUE CI UPDATE
340 ASSIGN @Path1 TO "BS1T06"%Disk2$
350 FOR I=1 TO 5
360   ENTER @Path1,I;H1(I,1);H1(I,2);H1(I,3);H1(I,4);H1(I,5)
370 NEXT I
380 J=6
390 FOR I=1 TO 5
400   ENTER @Path1,J;H2(I,1);H2(I,2);H2(I,3);H2(I,4);H2(I,5)
410   J=J+1
420 NEXT I
430 FOR I=1 TO 5
440   ENTER @Path1,J;H3(I,1);H3(I,2);H3(I,3);H3(I,4);H3(I,5)
450   J=J+1
460 NEXT I
470 FOR I=1 TO 5
480   ENTER @Path1,J;H4(I,1);H4(I,2);H4(I,3);H4(I,4);H4(I,5)
490   J=J+1

```

Table 3-7. Detection code.

```

500 NEXT I
510 FOR I=1 TO 5
520   ENTER @Path1,J;H5(I,1);H5(I,2);H5(I,3);H5(I,4);H5(I,5)
530   J=J+1
540 NEXT I
550 FOR I=1 TO 5
560   ENTER @Path1,J;H6(I,1);H6(I,2);H6(I,3);H6(I,4);H6(I,5)
570   J=J+1
580 NEXT I
590 ASSIGN @Path1 TO *
600 ASSIGN @Path2 TO "RE1"&Disk2*
610 FOR I=1 TO 4
620   ENTER @Path2;E1(I,1);E1(I,2);E1(I,3);E1(I,4);E1(I,5)
630 NEXT I
640 ASSIGN @Path2 TO *
650 ASSIGN @Path3 TO "BTHOLD"&Disk2*
660 FOR J=1 TO 10
670   ENTER @Path3;F8(1,J);F8(2,J);F8(3,J);F8(4,J);F8(5,J)
680 NEXT J
690 ASSIGN @Path3 TO *
700 ASSIGN @Path4 TO "UNITFILE"&Disk2*
710 FOR I=1 TO 191
720   ENTER @Path4,I;Temp(*)
730   FOR J=95 TO 100
740     K=J-94
750     G3(I,K)=Temp(J)
760   NEXT J
770 NEXT I
780 ASSIGN @Path4 TO *
790 GOTO 1280
800 ! - RED CI UPDATE
810 ASSIGN @Path5 TO "RS1T06"&Disk2*
820 FOR I=1 TO 5
830   ENTER @Path5,I;H1(I,1);H1(I,2);H1(I,3);H1(I,4);H1(I,5)
840 NEXT I
850 J=6
860 FOR I=1 TO 5
870   ENTER @Path5,J;H2(I,1);H2(I,2);H2(I,3);H2(I,4);H2(I,5)
880   J=J+1
890 NEXT I
900 FOR I=1 TO 5
910   ENTER @Path5,J;H3(I,1);H3(I,2);H3(I,3);H3(I,4);H3(I,5)
920   J=J+1
930 NEXT I
940 FOR I=1 TO 5
950   ENTER @Path5,J;H4(I,1);H4(I,2);H4(I,3);H4(I,4);H4(I,5)
960   J=J+1
970 NEXT I
980 FOR I=1 TO 5
990   ENTER @Path5,J;H5(I,1);H5(I,2);H5(I,3);H5(I,4);H5(I,5)
1000  J=J+1
1010 NEXT I

```

Table 3-7. Detection code.

```

1020 FOR I=1 TO 5
1030   ENTER @Path5,J;H6(I,1);H6(I,2);H6(I,3);H6(I,4);H6(I,5)
1040   J=J+1
1050 NEXT I
1060 ASSIGN @Path5 TO *
1070 ASSIGN @Path6 TO "BE1"&Disk2$
1080 FOR I=1 TO 4
1090   ENTER @Path6;E1(I,1);E1(I,2);E1(I,3);E1(I,4);E1(I,5)
1100 NEXT I
1110 ASSIGN @Path6 TO *
1120 ASSIGN @Path7 TO "RTHOLD"&Disk2$
1130 FOR J=1 TO 10
1140   ENTER @Path7;F8(1,J);F8(2,J);F8(3,J);F8(4,J);F8(5,J)
1150 NEXT J
1160 ASSIGN @Path7 TO *
1170 ASSIGN @Path8 TO "UNITFILE"&Disk2$
1180 FOR I=192 TO 400
1190   ENTER @Path8,I;Temp(*)
1200   FOR J=95 TO 100
1210     K=J-94
1220     G3(I,K)=Temp(J)
1230   NEXT J
1240 NEXT I
1250 ASSIGN @Path8 TO *
1260 GOTO 1420
1270 ! - BEGIN GAME FOR BLUE, LOAD RED POTA
1280 ASSIGN @Path9 TO "REDPOTA"&Disk2$
1290 FOR I=1 TO 10
1300   ENTER @Path9;P1(I,1);P1(I,2);P1(I,3);P1(I,4);P1(I,5)
1310 NEXT I
1320 ASSIGN @Path9 TO *
1330 ASSIGN @Path10 TO "RFLEE"&Disk2$
1340 ENTER @Path10;F(*)
1350 ASSIGN @Path10 TO *
1360 ! - SET FLAG FOR RED
1370 S1=1
1380 L6=192
1390 L7=400
1400 GOTO 1550
1410 ! - BEGIN GAME FOR RED, LOAD BLUE POTA
1420 ASSIGN @Path11 TO "BLUPOT1"&Disk2$
1430 FOR I=1 TO 10
1440   ENTER @Path11;P1(I,1);P1(I,2);P1(I,3);P1(I,4);P1(I,5)
1450 NEXT I
1460 ASSIGN @Path11 TO *
1470 ASSIGN @Path12 TO "BFLEE"&Disk2$
1480 ENTER @Path12;F(*)
1490 ASSIGN @Path12 TO *
1500 ! - SET FLAG FOR BLUE
1510 S1=2
1520 L6=1
1530 L7=191

```

Table 3-7. Detection code.

```

1540 ! - OPEN DIME UNITFILE
1550 ASSIGN @Path13 TO "UNITFILE"&Disk$
1560 INPUT "INPUT NUMBER OF HOURS OF INTEL NEEDED (MUST BE MULTIPLE OF 3)",N1
1570 N1=N1/3
1580 N1=INT(N1)
1590 J=0
1600 REPEAT
1610     INPUT "INPUT FRACTION OF SENSOR MESSAGES JAMMED",J1
1620 UNTIL J1>=0 AND J1<=1
1630 ! - SET TIME LOOP FOR DETECTIONS
1640 FOR T=1 TO N1
1650     ! - SET UNIT RECORD LOOP
1660     FOR J=L6 TO L7
1670         D1=1
1680     ! - RETRIEVE RECORD FOR UNIT TO BE DETECTED
1690     ENTER @Path13,J;N(*)
1700     IF S1=INT(N(78)) OR N(82)=0 THEN 2830
1710     ! - CHECK FOR LOST TARGET
1720     IF N(91)<.29 OR N(91)>.31 THEN 1750
1730     N(91)=0
1740     ! - CHECK FOR TARGET COVERAGE BY SOME SENSOR GROUP
1750     D=N(89)
1760     GOSUB Decompose
1770     S5=Q2
1780     Z5=Q1
1790     IF S5<>0 THEN 1890
1800     ! - TARGET NOT COVERED BY SENSOR
1810     D=N(91)
1820     GOSUB Decompose
1830     IF Q2=1 OR Q2=2 THEN 2420
1840     ! - TARGET NOT PREVIOUSLY DETECTED OR IN LOST STATUS
1850     N(91)=0
1860     N(92)=0
1870     GOTO 2820
1880     ! - TARGET UNDER SENSOR COVERAGE, DECOMPOSE TIME
1890     D=N(91)
1900     GOSUB Decompose
1910     ! - CHECK FOR DETECTION STATUS
1920     IF Q2>0 THEN 2460
1930     ! - SYSTEM NOT PREVIOUSLY DETECTED, DECOMPOSE LOCATION, PERFORM
1940     ! - DETECTION FUNCTION, AND SET UP POINTERS FOR PROPER POTA TABLE
1950     D=N(89)
1960     GOSUB Decompose
1970     ! - SAVE ZONE IN Z5 AND SAVE SENSOR GROUP IN S5
1980     Z5=Q1
1990     S5=Q2
2000     ! - SELECT UNIT TYPE
2010     D=N(78)
2020     GOSUB Decompose
2030     Q2=Q2+1
2040     Q1=Z5
2050     ! - SELECT PROPER PROBABILITY, RETRIEVE SENSOR

```

Table 3-7. Detection code.

```

2060     IF S5<0 THEN 2090
2070     PRINT "ERROR AT 1110";S5;Q1;N(89);N(78)
2080     STOP
2090     IF S5>8.5 AND S5<=9.5 THEN 2160
2100     GOSUB Prob_of_detect
2110     D=N(78)
2120     GOSUB Decompose
2130     IF D2=0 THEN 2390
2140     ! - UNIT DETECTED
2150     GOTO 2250
2160     ! - COVERED BY GENERAL GROUP
2170     P5=P1(Q2,Q1)
2180     R5=RND
2190     IF R5>P5 THEN 2390
2200     ! - CHECK FOR EW INTERFERENCE
2210     R5=RND
2220     IF R5>1-J1 THEN 2390
2230     ! - SYSTEM HAS BEEN DETECTED, UPDATE FLEE TIME DETECTION STATUS
2240     ! - AND MOVE TO NEW RECORD
2250     D=N(78)
2260     GOSUB Decompose
2270     Q1=F(Q2+1)
2280     Q2=1
2290     IF D1=1 THEN 2350
2300     ! - TARGET PREVIOUSLY DETECTED AND BEING TRACKED, TAKE OLD STATUS
2310     S=Q1
2320     D=N(91)
2330     GOSUB Decompose
2340     Q1=S
2350     N(91)=Q1+Q2/10
2360     ! - UPDATE TIME WATCHED
2370     N(92)=N(92)+3
2380     GOTO 2720
2390     N(91)=0
2400     ! - CHECK FOR LOST UNIT
2410     IF D1<2 THEN 2430
2420     N(91)=.3
2430     N(92)=0
2440     GOTO 2820
2450     ! - SYSTEM PREVIOUSLY DETECTED
2460     IF N(75)<>3 THEN 2510
2470     ! - SYSTEM IS STATIONARY, UPDATE TIME WATCHED
2480     N(92)=N(92)+3
2490     GOTO 2720
2500     ! - CHECK FOR SYSTEM MOVING
2510     IF N(75)<>4 THEN 2580
2520     ! - SYSTEM IS MOVING, SET STATIONARY TIME TO ZERO, TAKE OFF
2530     ! - DETECTED LIST, AND TRY TO DETECT
2540     D1=2
2550     GOTO 1950
2560     ! - SYSTEM IS EITHER IN ATTACK OR DEFEND AND DETECTED, UPDATE FLEE
2570     ! - TIME AND DETECT TIME

```


Table 3-7. Detection code.

```

2580     N(92)=N(92)+3
2590     D=N(91)
2600     GOSUB Decompose
2610     Q1=Q1-3
2620     IF Q1<=0 THEN 2670
2630     N(91)=Q1+Q2/10
2640     GOTO 2720
2650     ! - SYSTEM HAS MOVED, TIME TO REDETECT SYSTEM. FLEE TIME HAS
2660     ! - EXPIRED, SET DETECTION TO ZERO AND GO TO NEW RECORD
2670     N(92)=N(92)-3
2680     ! - SUBTRACT FLEE TIME
2690     D1=2
2700     GOTO 1950
2710     ! - CHECK ON VERIFICATION OF UNIT
2720     D=N(92)
2730     GOSUB Decompose
2740     S3=N(92)
2750     ! - COMPARE TIME OF DETECT WITH FLEE TIME, RETRIEVE FLEE TIME
2760     D=N(78)
2770     GOSUB Decompose
2780     Q2=Q2+1
2790     IF S3<4 THEN 2820
2800     ! - SYSTEM IS VERIFIED, UPDATE UNITFILE
2810     N(91)=INT(N(91))+.2
2820     OUTPUT @Path13,J;N(*)
2830     NEXT J
2840     NEXT T
2850     ASSIGN @Path13 TO *
2860     GOSUB Print_det_unit
2870     RETURN
2880     !
2890     Bld_sen_grp: !
2900     CALL Build_sen_group
2910     RETURN
2920     !
2930     !
2940     Print_det_unit: !
2950     ASSIGN @Path13 TO "UNITFILE"&Disk$
2960     ASSIGN @Path14 TO "NAMEFILE"&Disk$
2970     INPUT "TARGET LIST TO SCREEN OR PRINTER? (S/P)",S_p_$
2980     IF S_p_$="P" THEN PRINTER IS 702
2990     PRINT USING "@,@"
3000     IF S1=2 THEN 3030
3010     PRINT "BLUE COMMANDER TARGET LIST AS OF ";Tm$
3020     GOTO 3040
3030     PRINT "RED COMMANDER TARGET LIST AS OF ";Tm$
3040     PRINT "UNIT DETECTION STATUS"
3050     FOR I=L6 TO L7
3060         ENTER @Path13,I;N(*)
3070         ENTER @Path14,I;M$
3080         IF S1=INT(N(78)) OR N(82)=0 THEN 3160
3090         D=N(91)

```

Table 3-7. Detection code.

```

3100 GOSUB Decompose
3110 IF Q2=0 THEN 3160
3120 IF Q2=2 THEN 3150
3130 PRINT USING "10X,3D,5X,16A,5X,10A";I,"DETECTED","-----"
3140 GOTO 3160
3150 PRINT USING "10X,3D,5X,16A,5X,10A";I,M$,"-----"
3160 NEXT I
3170 PRINTER IS .
3180 PRINT USING "/////////"
3190 PRINT "PRESS CONT TO PROCEED"
3200 PAUSE
3210 ASSIGN @Path13 TO *
3220 ASSIGN @Path14 TO *
3230 RETURN
3240 !
3250 Blue_in_contact: !UPDATE BLUE UNIT COMMANDER'S INTELLIGENCE MAP FOR BLUE IN
CONTACT
3260 S1=1
3270 L6=192
3280 L7=400
3290 IF D1<6 THEN 3340
3300 S1=2
3310 L6=1
3320 L7=191
3330 IF D1=6 THEN 3340
3340 ON D1-4 GOTO 3360,3440,3520
3350 ! - BLUE INTEL UNIT, LOAD BLUE DETECTION PROBABILITIES
3360 ASSIGN @Path14 TO "BLBDG"&Disk2$
3370 ENTER @Path14;P7(*)
3380 ASSIGN @Path14 TO *
3390 ASSIGN @Path10 TO "RFLER"&Disk2$
3400 ENTER @Path10;F(*)
3410 ASSIGN @Path10 TO *
3420 GOTO 3580
3430 ! - RED INTEL UNIT, LOAD RED BDE DETECTION PROBABILITIES
3440 ASSIGN @Path15 TO "RDBDE"&Disk2$
3450 ENTER @Path15;P7(*)
3460 ASSIGN @Path15 TO *
3470 ASSIGN @Path12 TO "BFLER"&Disk2$
3480 ENTER @Path12;F(*)
3490 ASSIGN @Path12 TO *
3500 GOTO 3580
3510 ! - RED COMMANDER'S INTELLIGENCE
3520 ASSIGN @Path16 TO "RDCOR"&Disk2$
3530 ENTER @Path16;P7(*)
3540 ASSIGN @Path16 TO *
3550 ASSIGN @Path12 TO "BFLER"&Disk2$
3560 ENTER @Path12;F(*)
3570 ASSIGN @Path12 TO *
3580 ASSIGN @Path13 TO "UNITFILE"&Disk$
3590 PRINT USING "@"
3600 IF S1=2 THEN 3630

```

Table 3-7. Detection code.

```

3610 INPUT "INPUT NUMBER OF RED UNITS CONTACTED",N1
3620 GOTO 3640
3630 INPUT "INPUT NUMBER OF BLUE UNITS CONTACTED",N1
3640 FOR I=1 TO N1
3650     INPUT "INPUT UNIT NUMBER",J
3660     ENTER @Path13,J;N(*)
3670     IF S1<>INT(N(78)) AND N(82)<>0 THEN 3730
3680     ! - UNIT IS SAME SIDE AS SEARCHER
3690     IF N(82)=0 THEN PRINT "UNIT ";J;" IS INACTIVE, INPUT CORRECT UNIT"
3700     IF S1=INT(N(78)) THEN PRINT "UNIT ";J;" IS ON SAME FORCE AS INTEL MAP,"
INPUT CORRECT UNIT"
3710     GOTO 3650
3720     ! - CHECK ON UNIT DETECTION
3730     D=N(78)
3740     GOSUB Decompose
3750     R5=RND
3760     V2=Q2+1
3770     IF R5>P7(V2) THEN 3860
3780     ! - UNIT IS ACQUIRED, SET ACQUISITION AND FLEE TIME
3790     D=N(91)
3800     GOSUB Decompose
3810     ! - CHECK FLEE TIME
3820     IF Q1>F(V2) THEN 3840
3830     Q1=F(V2)
3840     N(91)=Q1+.2
3850     OUTPUT @Path13,J;N(*)
3860 NEXT I
3870 GOSUB Print_det_unit
3880 ASSIGN @Path13 TO *
3890 RETURN
3900 !
3910 Decompose: !
3920 D8=ABS(D)
3930 Q1=INT(D8)
3940 Q2=INT((D8-Q1)*10+.1)
3950 RETURN
3960 !
3970 Prob_of_detect: !SUM ELEMENTS IN UNIT ADJUSTED BY PERCENT COVERED
3980 IF JK<192 THEN
3990     Tot_sml_arms=0
4000     FOR I=36 TO 47
4010         Tot_sml_arms=Tot_sml_arms+N(I)
4020     NEXT I
4030     T2(1)=(Tot_sml_arms+N(7)+N(8)+N(53)+N(54))*N(90)
4040     Tot_veh=0
4050     FOR I=55 TO 70
4060         Tot_veh=Tot_veh+N(I)
4070     NEXT I
4080     FOR I=16 TO 20
4090         Tot_veh=Tot_veh+N(I)
4100     NEXT I
4110     T2(2)=(N(10)+N(2)+N(4)+Tot_veh)*N(90)

```

Table 3-7. Detection code.

```

4120 T2(3)=(N(1)+N(3))*N(90)
4130 Tot_if=0
4140 FOR I=21 TO 35
4150 Tot_if=Tot_if+N(I)
4160 NEXT I
4170 T2(4)=(Tot_if+N(5))*N(90)
4180 Tot_ada=0
4190 FOR I=48 TO 52
4200 Tot_ada=Tot_ada+N(I)
4210 NEXT I
4220 T2(5)=Tot_ada*N(90)
4230 ELSE
4240 Tot_sml_arms=0
4250 FOR I=36 TO 47
4260 Tot_sml_arms=Tot_sml_arms+N(I)
4270 NEXT I
4280 T2(1)=(N(7)+N(8)+Tot_sml_arms+N(53)+N(54))*N(90)
4290 Tot_trks=0
4300 FOR I=55 TO 61
4310 Tot_trks=Tot_trks+N(I)
4320 NEXT I
4330 T2(2)=(N(10)+Tot_trks)*N(90)
4340 Tot_df_car=0
4350 FOR I=16 TO 20
4360 Tot_df_car=Tot_df_car+N(I)
4370 NEXT I
4380 Tot_sp_veh=0
4390 FOR I=62 TO 70
4400 Tot_sp_veh=Tot_sp_veh+N(I)
4410 NEXT I
4420 T2(3)=(N(1)+N(3)+N(5)+N(6)+N(48)+Tot_df_car+Tot_sp_veh)*N(90)
4430 Tot_if=0
4440 FOR I=21 TO 35
4450 Tot_if=Tot_if+N(I)
4460 NEXT I
4470 T2(4)=(N(9)+Tot_if)*N(90)
4480 T2(5)=(N(49)+N(50)+N(51)+N(52))*N(90)
4490 END IF
4500 ! - OBTAIN PROPER ZONE FOR UNIT
4510 D=N(89)
4520 GOSUB Decompose
4530 ! - SELECT UNIT MISSION
4540 M=N(75)
4550 ! - CALCULATE PROBABILITY OF DETECTION OF THIS TARGET TYPE
4560 FOR K8=1 TO 5
4570 P9(K8)=1
4580 IF INT(T2(K8))<=0 THEN 4770
4590 ! - CHECK ALL ELEMENTS BY THIS GROUP
4600 T4=INT(T2(K8))
4610 FOR K9=1 TO 6
4620 IF G3(J,K9)=0 THEN 4760
4630 ON K9 GOTO 4640,4660,4680,4700,4720,4740

```

Table 3-7. Detection code.

```

4640     M9=H1(K8,Q1)
4650     GOTO 4750
4660     M9=H2(K8,Q1)
4670     GOTO 4750
4680     M9=H3(K8,Q1)
4690     GOTO 4750
4700     M9=H4(K8,Q1)
4710     GOTO 4750
4720     M9=H5(K8,Q1)
4730     GOTO 4750
4740     M9=H6(K8,Q1)
4750     P9(K8)=P9(K8)*(1-(1-J1)*M9)^G3(J,K9)
4760     NEXT K9
4770     P9(K8)=1-P9(K8)
4780     NEXT K8
4790     ! - INDIVIDUAL PROBABILITIES ARE NOW IN P9, ATTEMPT TO DETECT
4800     T5=0
4810     T6=0
4820     ! - SET UP UNIT TYPE
4830     D=N(78)
4840     GOSUB Decompose
4850     U4=Q2+1
4860     FOR I8=1 TO 5
4870         IF T2(I8)<=0 THEN 5050
4880         T5=T5+1
4890         ! - CALCULATE NUMBER OF ELEMENTS WHICH MUST BE DETECTED
4900         IF P9(I8)<.01 THEN 5050
4910         IF P9(I8)>.99 THEN 5040
4920         ! - Z8 IS INTELLIGENCE FACTOR, IF TARGET HAS BEEN DELETED THEN Z8 = FULL
HRESHOLD, IF TRACKING THEN Z8 = .75
4930         Z8=1
4940         IF D1=2 THEN Z8=.75
4950         D8=T2(I8)*F8(I8,U4)*E1(I8,M)*Z8
4960         ! - SET MEAN AND STANDARD DEVIATION FOR NORMAL
4970         X1=T2(I8)*P9(I8)*E1(I8,M)
4980         S8=T2(I8)*P9(I8)*(1-P9(I8))*E1(I8,M)
4990         X=(D8-X1)/SQR(S8)
5000         GOSUB Normal_approx
5010         R5=RND
5020         IF R5<D2 THEN 5050
5030         ! - UNIT ELEMENTS DETECTED
5040         T6=T6+1
5050     NEXT I8
5060     ! - IF ONE-HALF IS DETECTED THEN UNIT IS DETECTED
5070     D2=0
5080     IF T6=0 AND T5=0 THEN 5110
5090     IF T6<T5/2 THEN 5110
5100     D2=1
5110     RETURN
5120     !
5130     Normal_approx: '
5140     IF ABS(X)>20 THEN 5220

```

Table 3-7. Detection code.

```

5150 T8=1/(1+.2316419*ABS(X))
5160 D2=T8*(.31938153+T8*(-.356563782+1.781477937*T8))
5170 D2=D2+T8^4*(-1.821255978+1.330274429*T8)
5180 D2=SQR(1/(2*PI))*EXP(-X*X/2)*D2
5190 T8=10^(5+INT(-LGT(D2)))
5200 D2=INT(T8*D2+.5)/T8
5210 GOTO 5230
5220 D2=0
5230 IF X<0 THEN 5250
5240 D2=1-D2
5250 RETURN
5260 !
5270 PRINT USING "@"
5280 PRINT "THE RANDOM SEED FOR NEXT RUN IS"
5290 PRINT USING 5300;R5*10000
5300 IMAGE 7D.3D
5310 PRINT USING "//////"
5320 PRINT "PRESS CONT TO PROCEED"
5330 PAUSE
5340 LOAD "DIME"&Disk$
5350 END
5360 SUB Build_sen_group
5370 ! (GROUPBLD) BUILDS 9 SENSOR GROUPS FOR BLUE AND 9 FOR RED
5380 DIM S(1:6)
5390 Disk2$=":9134,704,0"
5400 PRINT "THIS IS THE DIME SENSOR GROUP BUILDER"
5410 PRINT "SELECT ONE OF THE FOLLOWING OPTIONS"
5420 PRINT "BUILD BLUE SENSOR GROUPS - 1"
5430 PRINT "BUILD RED SENSOR GROUPS - 2"
5440 PRINT "DUMPFILERS/STOP - 3"
5450 INPUT O1
5460 ON O1 GOTO 5470,5560,5650
5470 PRINT "BUILDING BLUE GROUPS"
5480 ASSIGN @Path13 TO "BSENPRO"&Disk2$
5490 FOR I=1 TO 9
5500 PRINT "INPUT NUMBER OF SENSORS OF EACH TYPE FOR GROUP ":I:"GDRADAR,AR"
RADAR,LRRP,SLAR,AF/IR,FO"
5510 INPUT S(1),S(2),S(3),S(4),S(5),S(6)
5520 OUTPUT @Path13;S(*)
5530 NEXT I
5540 ASSIGN @Path13 TO *
5550 GOTO 5410
5560 PRINT "BUILDING RED SENSOR GROUPS"
5570 ASSIGN @Path14 TO "RSENPRO"&Disk2$
5580 FOR J=1 TO 9
5590 PRINT "INPUT NUMBER OF SENSORS OF EACH TYPE FOR GROUP ":J:"GDRADAR,AR"
RADAR,LRRP,RPV,SLAR,FO"
5600 INPUT S(1),S(2),S(3),S(4),S(5),S(6)
5610 OUTPUT @Path14;S(*)
5620 NEXT J
5630 ASSIGN @Path14 TO *
5640 GOTO 5410

```

Table 3-7. Detection code.

```
5650 PRINT "DUMPING SENSOR FILES"
5660 ASSIGN @Path13 TO "RSENPRO"&Disk2$
5670 PRINT "BLUE"
5680 PRINT "GDRADAR,ARTRADAR,LRRP,SLAR,AF/IR,FO"
5690 FOR K=1 TO 9
5700     ENTER @Path13;S(*)
5710     PRINT "GROUP ";K,S(1);S(2);S(3);S(4);S(5);S(6)
5720 NEXT K
5730 ASSIGN @Path13 TO *
5740 PRINT "RED"
5750 ASSIGN @Path14 TO "RSENPRO"&Disk2$
5760 PRINT "GDRADAR,ARTRADAR,LRRP,RPV,SLAR,FO"
5770 FOR L=1 TO 9
5780     ENTER @Path14;S(*)
5790     PRINT "GROUP ";L,S(1);S(2);S(3);S(4);S(5);S(6)
5800 NEXT L
5810 ASSIGN @Path14 TO *
5820 !
5830 SUBEND
```

CHAPTER 4

LOGISTICS

1. PURPOSE.

The purpose of the DIME logistics program (P2) is to establish initial levels of ammunition and fuel available for combat operations during the ground combat (P4) and air defense (P3) programs.

2. GENERAL.

The logistics program calculates the total ammunition and fuel (POL) available for the DIME model by:

A. Calculating the total combat and noncombat ammunition/fuel available as a function of:

(1) Basic load and/or fuel capacity for each of the 70 elements on a unit's weapons list.

(2) Resupplied ammunition/fuel.

(3) Excess ammunition/fuel returned from ground combat and air defense programs.

B. Subtracting the ammunition allocated for noncombat consumption from the total allocation and placing the total remaining combat allocation into elements 131-133 of the unit status file ("UNITFILE"). This combat allocation is depleted during the execution of the ground combat and air defense programs.

C. And, finally, distributing the remaining ammunition/fuel quantities available onto the trucks alive at the start of the game turn. Any excess ammunition or fuel is stored on the ground.

3. DATA FLOW.

A. The DIME logistics program contains two types of data inputs: auxiliary storage and online data statements. See Figure 4-1 for the data flow of this program.

(1) Auxiliary storage.

(a) "UNITFILE". Table 4-1 contains a list of "UNITFILE" elements required as inputs by the logistics program. Each element's location within




Figure 4-1. Logistics data flow.

Table 4-1. Logistics "UNITFILE" inputs.

<u>"UNITFILE" Locations</u>	<u>Element Description</u>
101	Fuel status of unit vehicles; value ranges from 0 to 1.0.
102	Fuel status of unit helicopters; value ranges from 0 to 1.0.
103	Fuel on tankers (gallons).
104	JP4 on tankers (gallons).
105	Fuel on ground (gallons).
106	JP4 on ground (gallons).
110	Fuel resupplied (gallons).
111	JP4 resupplied (gallons).
112	Fuel dispensed to other units (gallons).
113	JP4 dispensed to other units (gallons).
119 - 121	DF, IF, and AD vehicle ammunition status; values range from 0 to 1.0.
122	Helicopter ammunition status.
123	Ammunition on cargo vehicles (short tons).
124	Distribution of cargo by type (XXX.YYY).*
125	Ammunition on ground (short tons).
126	Distribution of ground ammunition by type (XXX.YYY).*

* (XXX.YYY) represents: XXX = DF ammo percent (XXX = XX.X%)
 YYY = IF ammo percent (YYY = YY.Y%)
 AD ammo percent is the amount remaining (100 - XX.X - YY.Y).

Table 4-1. Logistics "UNITFILE" inputs (continued).

<u>"UNITFILE" Locations</u>	<u>Element Description</u>
131 - 133	DF, IF, and AD ammunition available for consumption (short tons).
134	Helicopter ammunition available for consumption.
135	Ammunition resupplied (short tons).
136	Ammunition resupply profile (XXX.YYY).*
137	Ammunition dispensed to other units (short tons).
138	Dispensed ammunition profile (XXX.YYY).*
139 - 141	DF, IF, and AD ammunition consumed to date (short tons).
142	Helicopter ammunition consumed to date (short tons).
143	Fuel consumed to date (gallons).
144	JP4 consumed to date (gallons).

Refer to Chapter 1 for a complete description of the entire "UNITFILE".

* (XXX.YYY) represents: XXX = DF ammo percent (XXX = XX.X%)
 YYY = IF ammo percent (YYY = YY.Y%)
 AD ammo percent is the amount remaining (100 - XX.X - YY.Y).

the "UNITFILE" and a short description are furnished. The elements are listed in ascending order according to their locations within the "UNITFILE".

(b) "NAMEFILE". The "NAMEFILE" contains the names for the units stored in the "UNITFILE".

(2) Online data. The logistics program uses six online data arrays.

(a) The fuel array contains fuel consumption values.

(b) The ammo array contains ammunition consumption values.

(c) The truck capacity array contains the carrying capacity of each truck.

(d) The ammo capacity array contains the package weight for each weapon in tons.

(e) The fuel capacity array contains the fuel required by each weapon element in gallons. If an element does not require fuel, a zero is assigned to the array.

(f) The weapon type array indicates the type of ammunition being fired (AD, IF, DF).

B. The logistics program combines the inputs listed in Table 4-1 with the methodology discussed in paragraph 5 to provide an updated "UNITFILE" for the current critical incident (CI).

4. FILE STRUCTURE.

The execution of the logistics program requires the "UNITFILE", two auxiliary files, and six online data arrays.

A. Auxiliary storage.

(1) The "UNITFILE" is created by the interactive running of the game initialization program (P1). It consists of 400 records, each containing 150 elements. The assignment of records is as follows: records 1-191 Blue units, and records 192-400 Red units. The logistics program requires the use of 32 elements on the "UNITFILE" as inputs and/or outputs. Refer to Tables 4-1 and 4-2 for these inputs and outputs.

(2) The "NAMEFILE" is the only other auxiliary file required by the logistics program except for the "UNITFILE". This file consists of a record containing the names of all units. It is created new for each game by the interactive running of the game initialization program (P1) and contains character strings that identify the units assigned to the game.

B. Online data. Online data consists of six data arrays: Fuel(*), Ammo(*), Truck_cap(*), Ammo_cap(*), Fuel_cap(*), Wpn_type(*).

(1) Fuel(I,J). Fuel(I,J) is a 10 x 70 array containing the consumption of fuel, in gallons, per six hours for 70 elements under 10 missions:

Missions:

- 0 = Meeting engagement
- 1 = Indirect fire
- 2 = Movement
- 3 = Frontal attack
- 4 = Envelopmental attack
- 5 = Delay
- 6 = Hasty defense
- 7 = Prepared defense
- 8 = Reserve/rear area
- 9 = Ambush

(2) Ammo(I,J). Ammo(I,J) is a 10 x 70 array containing the noncombat consumption of ammunition in tons per six hours for 70 elements operating under 10 missions (see above). These values represent leakage within the system.

(3) Truck_cap(J). Truck_cap(J) is a two-dimensioned array containing the fuel-carrying capacity in gallons for a single truck and the cargo-carrying capacity in tons for a single truck.

(4) Ammo_cap(J). Ammo_cap(J) is a 70-dimensioned array containing the packaged weight, in tons, for each of the 70 DIME elements. The packaged weight is constrained by the basic load for a weapon or the rate of fire of a weapon. If an element does not fire, then a zero value is assigned.

(5) Fuel_cap(J). Fuel_cap(J) is a 70-dimensioned array containing the capacity, in gallons, for those DIME elements carrying fuel. If an element does not carry fuel, then a zero value is assigned.

(6) Wpn_type(J). Wpn_type(J) is a 70-dimensioned array containing a pointer describing the type of ammunition being fired by the 70 elements on the DIME unit structure file. The entries are either: 1=direct fire (DF), 2=indirect fire (IF), or 3=air defense (AD). If a DIME element does not fire ammunition, then a value of 3 is assigned.

5. ALGORITHMS.

A. Figure 4-2 presents a generalized logic flow of the logistics program. The program first determines the total vehicle (weapon) capacity for both fuel and ammunition of an active unit. It then calculates combat




Figure 4-2. Logistics logic flow.

and noncombat fuel consumption as well as noncombat ammunition consumption. Totals of the supplies on hand are computed and then checked to see that the quantities of ammunition/fuel used do not exceed the amounts on hand. Consumption values within the "UNITFILE" are updated. Other figures calculated by the logistics program include ammunition/fuel status, quantities remaining, and truck/ground storage sums. The "UNITFILE" is updated as required. These calculations are performed for each active unit.

B. The following paragraphs provide a detailed description of the algorithms used in the calculation of fuel and ammunition values necessary for the running of the air defense and ground combat programs.

(1) Fuel calculations.

(a) Calculate the total fuel capacity of all weapons in gallons.

$$F_t = \sum_{i=1}^{70} N_{e_i} * F_{c_i} \quad (\text{Eq. 4-1})$$

where:

F_t = total fuel capacity.
 N_{e_i} = number of elements of each weapon type i where i represents the 70 DIME weapons.
 F_{c_i} = fuel capacity of each weapon type i .

(b) Calculate both combat and noncombat fuel consumption in gallons.

$$F_{con} = \sum_{i=1}^{70} N_{e_i} * E_{f_i} \quad (\text{Eq. 4-2})$$

where:

E_{con} = total fuel consumed.
 N_{e_i} = number of elements of each weapon type i .
 E_{f_i} = fuel expended for combat and noncombat missions for each weapon type i .

(c) Calculate amount of fuel, in gallons, available for use at the beginning of the game turn.

$$W_f = \sum_{i=1}^{70} N_{e_i} * F_{c_i} * F_s \quad (\text{Eq. 4-3a})$$

$$F_{ava} = W_f + T_f + G_f + R_f \quad (\text{Eq. 4-3b})$$

where:

W_f = amount of fuel on the 70 DIME weapons.
 N_{e_i} = number of elements of each weapon type i .
 F_{c_i} = fuel capacity of each weapon type i .
 F_s = fuel status of unit weapons; value ranges from 0 to 1.0.
 F_{ava} = fuel available for use.
 T_f = amount of fuel on trucks.
 G_f = amount of fuel on ground.
 R_f = amount of fuel resupplied.

(d) Calculate the quantity of fuel, in gallons, remaining after consumption and dispensation values are considered.

$$F_{rem} = F_{ava} - (F_{con} + D_f) \quad (\text{Eq. 4-4})$$

where:

F_{rem} = fuel remaining.
 F_{ava} = fuel available for use; see (Eq. 4-3b) above.
 F_{con} = fuel consumed; see (Eq. 4-2) above.
 D_f = fuel dispensed to other units.

(2) Ammunition calculations.

(a) Calculate the ammunition capacity in tons of all weapons combined.

$$A_{t_j} = \sum_{i=1}^{70} N_{e_{ij}} * A_{c_{ij}} \quad (\text{Eq. 4-5})$$

where:

A_{t_j} = total ammunition capacity for weapon type i , ammunition category j where:
 $j = 1$ direct fire
 $= 2$ indirect fire
 $= 3$ air defense.

Ne_{ij} = number of elements of each weapon type i , ammunition category j .
 Ac_{ij} = ammunition capacity of each weapon type i , ammunition category j .

(b) Calculate noncombat ammunition consumption, in tons, for each category of direct fire (DF), indirect fire (IF) and air defense (AD).

$$Nac_j = \sum_{i=1}^{70} Ne_{ij} * Ea_{ij} \quad (\text{Eq. 4-6})$$

where:

Nac_j = noncombat DF, IF, or AD ammunition consumed.
 Ne_{ij} = number of elements of each weapon type i , ammunition category j .
 Ea_{ij} = ammunition expended for noncombat missions for each weapon type i , ammunition category j .

(c) Calculate the quantity of DF, IF, and AD ammunition available for use at the beginning of each game turn.

1. Calculate the amount of DF, IF, and AD ammunition loaded onto the 70 DIME elements.

$$Wa_j = \sum_{i=1}^{70} Ne_{ij} * Ac_{ij} * As_j \quad (\text{Eq. 4-7a})$$

where:

Wa_j = the total amount of ammunition loaded onto all weapon elements in ammo category j .
 Ne_{ij} = number of elements of each weapon type i , ammunition category j .
 Ac_{ij} = ammunition capacity of each weapon type i , ammunition category j .
 As_j = ammunition status of each DF, IF or AD weapon. Value ranges from 0 to 1.0.

2. Calculate the amount of DF, IF, and AD ammunition loaded onto the cargo trucks.

$$Ta_j = Fl_j * At \quad (\text{Eq. 4-7b})$$

where:

T_{aj} = the total amount of ammunition loaded onto all cargo trucks in ammo category j.
 $F1_j$ = % of DF, IF, or AD ammunition on cargo vehicles.
 A_t = quantity of ammunition on cargo vehicles.

3. Calculate the amount of DF, IF, and AD ammunition on the ground.

$$G_{aj} = F2_j * A_g \quad (\text{Eq. 4-7c})$$

where:

G_{aj} = the total amount of ammunition on the ground in ammo category j.
 $F2_j$ = % of DF, IF, or AD ammunition on the ground.
 A_g = quantity of ammunition on the ground.

4. Calculate the amount of DF, IF, and AD ammunition resupplied (R_{aj}).

$$R_{aj} = F3_j * A_r \quad (\text{Eq. 4-7d})$$

where:

$F3_j$ = % of DF, IF or AD ammunition resupplied
 A_r = quantity of ammunition resupplied.

5. Calculate DF, IF, and AD ammunition available at game turn initialization.

$$Aava_j = Wa_j + Ta_j + Ga_j + Ra_j + Pa_j \quad (\text{Eq. 4-7e})$$

where:

Pa_j = amount of DF, IF, or AD ammunition left from previous turn.

(d) Calculate DF, IF, and AD ammunition remaining after consumption and dispensation values are considered.

$$Da_j = F4_j * Ad \quad (\text{Eq. 4-8a})$$

$$Arem_j = Aava_j - (Nac_j + Da_j) \quad (\text{Eq. 4-8b})$$

where:

Da_j = quantity of DF, IF, or AD ammunition dispensed to other units.
 $F4_j$ = % of DF, IF, or AD ammunition dispensed to other units.
 Ad = total ammunition dispensed to other units.
 $Arem_j$ = ammunition remaining.
 Aav_j = DF, IF, or AD ammunition available for use. See (Eq. 4-7e) above.
 Nac = noncombat DF, IF, or AD ammunition consumed. See (Eq. 4-6) above.

6. "UNITFILE" IMPACT.

In order to fully understand the function of the logistics program within the DIME framework, it is necessary to have an understanding of the relationships existing between it, the air defense program (P3), the ground combat program (P4), and the unit status report program (P8). The following paragraphs describe these relationships.

A. The logistics program (P2) is executed once at the beginning of each turn. It calculates the available quantities of all ammunition and fuel and the net amounts resulting from leakage, dispensation, and resupply. It should be noted that fuel consumption values include combat as well as noncombat expenditures. This means that P2 is the only program in DIME to calculate fuel consumption values. From the net ammunition amount, P2 calculates the percent of direct fire, indirect fire, and air defense ammunition 'loaded' onto the weapons and trucks. The remainder is placed on the ground. The net DF, IF, and AD amounts are placed in positions 131- 133 of the "UNITFILE" to be consumed and/or destroyed during the execution of the air defense (P3) and ground combat (P4) programs.

B. The air defense (P3) and ground combat (P4) programs may be executed zero to N times, N being constrained only by ammunition availability. When each battle is over, both P3 and P4 place the unused fuel and ammunition back in positions 131-133 of the "UNITFILE."

C. The unit status report (P8) is executed once at the end of each game turn. It compares the remaining quantities of DF, IF, and AD ammunition placed in the "UNITFILE" by P3 and P4 with the combat and noncombat ammunition quantities available at the beginning of the turn, positions 116 - 118 of the "UNITFILE", in order to determine consumption values. It then redistributes the ammunition to the weapons, trucks, and onto the ground in a similar manner to that of P2. P8 then makes this information available to the gamer in the form of a unit history. The unit history also includes the number of systems remaining, unit mission, and detection status.

D. Because P2 calculates the noncombat consumption, resupply, and dispensation values of DF, IF, and AD ammunition, it must reevaluate the quantities P8 distributes among the weapons, trucks, and ground storage in the preceding game turn. It then allocates appropriate levels of ammunition for the execution of P3 and P4 in the current game turn.

E. Table 4-2 contains a list of all "UNITFILE" elements updated by the logistics program. Each element's location within the "UNITFILE" and a short description are furnished. The elements are listed in ascending order according to their locations within the "UNITFILE".

7. CODE.

A. The logistics code is written as one program without major subroutines. The code initiates the algorithms discussed in paragraph 5 of this chapter. After the appropriate Blue/Red data is read, the following will occur with each unit processed:

(1) Position 82 of the "UNITFILE" is tested for zero. If it is zero, the unit is inactive and logistics processing is not done for the unit.

(2) Calculations occur for active units which determine fuel supplies on hand, fuel supplies consumed (non-combat), and the current vehicle fuel capacity. Similar calculations occur for ammunition.

(3) Ammunition quantities remaining after non-combat consumption and dispensation to other units are tested. If the amounts consumed and dispensed exceed that which was on hand, a message is printed to make the controllers/gamers aware of this occurrence. The amount remaining is then set to zero.

Table 4-2. Logistics "UNITFILE" updates.

<u>"UNITFILE" locations</u>	<u>Element description</u>
84	Cargo trucks alive at start of turn.
85	Fuel trucks alive at start of turn.
86	JP4 trucks alive at start of turn.
101	Fuel status of unit vehicles; value ranges from 0 to 1.0.
102	JP4 status of unit vehicles; value ranges from 0 to 1.0.
103	Fuel on tankers (gallons).
104	JP4 on tankers (gallons).
105	Fuel on ground (gallons).
106	JP4 on ground (gallons).
108	Fuel consumed during the current game turn (gallons).
109	JP4 consumed during the current game turn
115	Helicopter ammunition at start of turn (short tons).
116 - 118	DF, IF and AD ammunition at start of turn (short tons).
119 - 121	DF, IF and AD vehicle ammunition status; values range from 0 to 1.0.
122	Helicopter ammunition status; values range from 0 to 1.0.
123	Ammunition on cargo vehicles (short tons).

Table 4-2. Logistics "UNITFILE" updates (concluded).

<u>"UNITFILE" locations</u>	<u>Element description</u>
124	Distribution of cargo by type (XXX.YYY).*
125	Ammunition on ground (short tons).
126	Distribution of ground ammunition by type (XXX.YYY).*
131 - 133	DF, IF and AD ammunition available for consumption (short tons).
134	Helicopter ammunition available for consumption (short tons).
139 - 141	Cumulative DF, IF, and AD ammunition consumed to date (short tons).
142	Cumulative helicopter ammunition consumed to date (short tons).
143	Cumulative fuel consumed to date (gallons).
144	Cumulative JP4 consumed to date (gallons).
147	Fuel left after consumption and dispensation values are figured.
148	JP4 left after consumption and dispensation values are figured.

* Refer to Table 4-1 of this chapter for a detailed description.

(4) The status for ammunition and fuel are calculated. The status amounts are calculated by dividing the remaining amounts (after non-combat consumption and dispensation) by the total vehicle capacity. Excess fuel and ammunition are calculated and stored on the ground for use during combat. This excess is determined by any fuel and ammunition which was not consumed, dispensed, or placed on vehicles.

B. Table 4-3 provides a summary of the logistics program's primary variables and their description. A listing of P2 code appears in Table 4-4.

Table 4-3. Logistics Subroutine Table.

<u>Functional area(s):</u>	<u>A. Initialize supply variables and read data</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>	
Main program	Calls subroutines	A. N(*)	150 element array which holds data provided by the UNITFILE.	
		B. Ammo	Holding variable for the noncombat consumption of ammo in tons.	
		C. Fuel	Holding variable for the combat and noncombat consumption of fuel in gallons.	
Blue_data	Reads Blue logistics data	A. Fuel (I,J)	Consumption of fuel in gallons per 6 hours for 70 elements under 10 missions: Missions: 0 = combat unit 1 = artillery unit 2 = air defense unit 3 = AH Ground Sites/FAARP 4 = CP/HQ 5 = Engineer Unit 6 = POL/Ammo Supply pt 7 = Maintenance pt 8 = SAM site 9 = Commo/Radar/EW site	
		B. Ammo (I,J)	Noncombat consumption of ammo in tons per 6 hours for J=1-70 elements operating under I=1-10 missions (see above). These values represent leakage within the system.	

Table 4-3. Logistics Subroutine Table.

<u>Functional area(s):</u>	<u>A. Initialize supply variables and read data</u>	<u>(continued)</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Variable description</u>		
<u>Blue_data</u> (continued)		
	C. Truck_cap(*)	Contains the carrying capacity in gallons/tons for a single fuel/single cargo truck.
	D. Ammo_cap(*)	Contains the packaged weight, in tons, for each of the 70 DIME elements. The packaged weight is constrained by: (1) basic load for weapon or (2) rate of fire of weapon. If an element does not fire, then a zero (0) value is assigned. NOTE: The values contained in Ammo_cap(*) must correspond with the weight files contained within the Operations Module (P1), the Ground Attrition Module (P4), and the Air Defense Module (P3).
	E. Fuel_cap(*)	Contains the capacity in gallons for those DIME elements carrying fuel. If an element does not carry fuel, then a zero (0) value is assigned. NOTE: The values contained in Fuel_cap(*) must correspond with the arrays F(1,J) and F(2,J) contained within the Operations Module, P1.

Table 4-3. Logistics Subroutine Table.

<u>Functional area(s):</u>	<u>A. Initialize supply variables and read data</u>	(continued)
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Variable description</u>		
Blue_data (concluded)	F. Wpn_type(*)	Contains a pointer file describing the type of ammunition being fired by the 70 elements on the DIME unit structure file. The entries are either: (1) DF, (2) indirect fire, or (3) air defense. If a DIME element does not fire ammunition then a value of one (1) is assigned. NOTE: The values contained in Wpn_type(*) must have the same values as the arrays W(1,J) and W(2,J) contained within the Operations Module (Pl).
Red_data	Reads Red Logistics data	See Blue data above
Init_unit_var	Initializes unit supply variables	A. Tot_veh_fuel Contains the total fuel carrying capacity in gallons for the unit vehicles (weapons). B. Fuel_used Contains the total quantity of POL in gallons consumed for combat and noncombat purposes. C. Fuel_on_hand Contains the total quantity of POL available for combat and noncombat consumption at start of turn. D. Fuel_left Excess fuel remaining after combat and noncombat consumption is determined.

Table 4-3. Logistics Subroutine Table.

<u>Functional area(s):</u>	<u>A. Initialize supply variables and read data</u>	<u>(concluded)</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Init_unit_var</u>	<u>Variable description</u>	
<u>(concluded)</u>		
E. Ammo_total	Total quantity of DF, IF, and AD ammo in tons remaining after noncombat consumption is determined.	
F. Load_cap	Variable representing the quantity of fuel in gallons loaded into the fuel trucks.	
G. Ammo_on_hand(*)	Three element array containing the quantities of DF, IF, and AD ammo in tons available at start of turn.	
H. Free(*)	Three element array which holds percents of DF, IF, and AD ammo used in the calculation of ammo on hand.	
I. Tot_veh_ammo(*)	A 3 element array which contains the total DF, IF and AD ammo capacities for the 70 DIME unit vehicles (weapons).	
J. Ammo_used(*)	Contains the quantities of DF, IF and AD ammo consumed by non-combat processes.	
K. Ammo_left(*)	Contains the DF, IF and AD ammo quantities remaining after non-combat consumption and dispensation values are subtracted.	

Table 4-3. Logistics Subroutine Table.

<u>Functional area(s):</u>	<u>B. Calculation of ammunition and POL levels.</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Main program	Determines ammo/POL available for consumption A	See Functional area variable lists.	non-combat consumption values, and combat fuel expenditures.	
<u>Functional area(s):</u>	<u>C. Allocation of ammunition and POL.</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Main program	Distributes ammo/POL into the trucks and	See Functional Area A variable lists.		
<u>Functional area(s):</u>	<u>D. Establish UNITFILE Arrays.</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Main program	Updates UNITFILE elements for both Blue and Red forces.	See Functional Area A variable lists.		

Table 4-4. Logistics code.

```

10  REM      "P2" IS THE LOGISTICS PROGRAM FOR DIME
20  ! DATA CHANGED 21 FEB 85. ROB BELFLOWER  PLAYS 400 UNITS
30  ! EXPANDED VERSION -- JUNE 9, 1986 -- BY DAO CORP.
31  ! DECLASSIFIED -- AUG 7, 1986 -- BY DAO CORP.  ** DC **
40  OPTION BASE 1
50  !
60  Disk$=":9134,704,0"
64  Dcdisk$=":9134,704,0"  ! ** DC **
70  PRINTER IS 1
80  DIM N(150),Fuel(10,70),Ammo(10,70),Fuel_cap(70),Ammo_cap(70),Frac(3)
90  DIM Wpn_type(70),Ammo_used(3),Ammo_on_hand(3),Tot_veh_ammo(3),Truck_cap(7)
100 DIM Ammo_left(3)
101 DIM Dataline(70),Dummyrec(70)  ! ** DC **
102 INTEGER Element,Recnum  ! ** DC **
110 INTEGER I,J,K
120 PRINTER IS 1
130 PRINT USING "@,#"
140 PRINT TABXY(30,19);"LOGISTICS MODULE"
150 INPUT "DO YOU WANT TO DO POST-GAMETURN RESUPPLY <R> OR DO YOU WANT TO RUN
P2 <P>?",Ans$
160 IF Ans$="R" THEN
170   PRINT "LOADING DATA OPERATIONS MENU...PLEASE BE PATIENT."
180   LOAD "P1:9134,704,0"
190 END IF
200 INPUT "HOW MANY HOURS OF SUPPLY DO YOU WANT TO RUN?",Hour
210 ! IF Hour<6 THEN Hour=6
220 ASSIGN @Path TO "UNITFILE"&Disk$
230 ASSIGN @Pname TO "NAMEFILE"&Disk$
240 !
250 GOSUB Blue_data  ! READ BLUE LOG DATA
260 !
270 ! BEGIN UNIT PROCESSING LOOP
280 !
290 PRINT USING "@,#"
300 FOR I=1 TO 400
310   ENTER @Pname,I;M$
320   IF I=192 THEN GOSUB Red_data  ! READ RED LOG DATA
330   ENTER @Path,I;N(*)
340   IF M$=" " THEN GOTO Next_unit
350   IF N(82)=0 OR N(82)=2 THEN  ! UNIT IS IN
ACTIVE
360     PRINT USING "3D,2X,8A";I,"INACTIVE"
370     GOTO Next_unit
380   END IF
390   GOSUB Init_unit_var  ! ZERO UNIT VARIABLES
400   PRINT USING "3D,2X,10A";I,"PROCESSING"
410   !
420   Ipt1=N(83)
430   !
440   ! COMPUTE SUPPLIES ON HAND, CONSUMED, AND TOTAL VEHICLE CAPACITY
450   FOR J=1 TO 70
460     Tot_veh_fuel=Tot_veh_fuel+N(J)*Fuel_cap(J)

```

Table 4-4. Logistics code.

```

470      Tot_veh_ammo(Wpn_type(J))=Tot_veh_ammo(Wpn_type(J))+N(J)*Ammo_cap(J)
480      ! Fuel1=(Fuel(Ipt1,J)) !FUEL USE BY 3-HOURS ROB
490      FOR X=1 TO 2
500          X1st=INT(Ipt1)
510          X2nd=(Ipt1-X1st)*10
520          IF X=1 THEN Fuel1=(Fuel(X1st+1,J))
530          IF X=2 THEN Fuel1=Fuel1+(Fuel(X2nd+1,J))
540      NEXT X
550      Fuel1=(Fuel1/2)*INT(Hour/6) !ROB
560      Fuel_used=Fuel_used+N(J)*Fuel1
570      Fuel_on_hand=Fuel_on_hand+N(J)*Fuel_cap(J)*N(101)
580      !Ammo1=(Ammo(Ipt1,J)) ROB
590      Ammo1=0!ROB
600      Ammo_used(Wpn_type(J))=Ammo_used(Wpn_type(J))+N(J)*Ammo1
610      Ammo_on_hand(Wpn_type(J))=Ammo_on_hand(Wpn_type(J))+N(J)*Ammo_cap(J)*
(118+Wpn_type(J))
620      NEXT J
630      !
640      ! COMPUTE TOTAL OF SUPPLIES ON HAND
650      Fuel_on_hand=Fuel_on_hand+N(103)+N(105)+N(110)          ! TOTAL FUEL IN
NIT
660      ! ADD TRUCK CARRIED AMMO
670      Frac(1)=INT(N(124))/1000
680      Frac(2)=N(124)-INT(N(124))
690      Frac(3)=1-(Frac(1)+Frac(2))
700      IF Frac(3)<=0 THEN Frac(3)=0
710      FOR J=1 TO 3
720          Ammo_on_hand(J)=Ammo_on_hand(J)+Frac(J)*N(123)
730      NEXT J
740      !
750      ! ADD GROUND STORED SUPPLIES
760      Frac(1)=INT(N(126))/1000
770      Frac(2)=N(126)-INT(N(126))
780      Frac(3)=1-(Frac(1)+Frac(2))
790      IF Frac(3)<=0 THEN Frac(3)=0
800      FOR J=1 TO 3
810          Ammo_on_hand(J)=Ammo_on_hand(J)+Frac(J)*N(125)
820      NEXT J
830      !
840      ! ADD RESUPPLY
850      Frac(1)=INT(N(136))/1000
860      Frac(2)=N(136)-INT(N(136))
870      Frac(3)=1-(Frac(1)+Frac(2))
880      IF Frac(3)<=0 THEN Frac(3)=0
890      FOR J=1 TO 3
900          Ammo_on_hand(J)=Ammo_on_hand(J)+Frac(J)*N(135)
910      NEXT J
920      !
930      !ADD LEFT FROM PREVIOUS BATTLE
940      FOR J=1 TO 3
950          Ammo_on_hand(J)=Ammo_on_hand(J)+N(130+J)
960      NEXT J

```

Table 4-4. Logistics code.

```

970
980   CHECK THAT AMOUNT FIRED/USED DOES NOT EXCEED ON-HAND AMOUNT
990   Frac(1)=INT(N(138))/1000
1000  Frac(2)=N(138)-INT(N(138))
1010  Frac(3)=1-(Frac(1)+Frac(2))
1020  IF Frac(3)<=0 THEN Frac(3)=0
1030  FOR J=1 TO 3
1040     Ammo_left(J)=Ammo_on_hand(J)-(Ammo_used(J)+Frac(J)*N(137))
1050     IF Ammo_left(J)<0 THEN
1060         SELECT J
1070         CASE 1
1080             Ammotype$="DF"
1090         CASE 2
1100             Ammotype$="IF"
1110         CASE 3
1120             Ammotype$="AD"
1130         END SELECT
1140         PRINTER IS 702
1150         PRINT
1160         PRINT "*** UNIT ";M$;"(";"I;")";" HAS DISPENSED/USED ":-Ammo_left(J)
1170         PRINT "          MORE ";Ammotype$;" TONS THAN AVAILABLE!"
1180         PRINTER IS 1
1190         Ammo_used(J)=Ammo_on_hand(J)
1200         Ammo_left(J)=0
1210     END IF
1220 NEXT J
1230 Fuel_left=Fuel_on_hand-(Fuel_used+N(112))
1240 IF Fuel_left<0 THEN
1250     PRINTER IS 702
1260     PRINT
1270     PRINT "*** UNIT ";M$;"(";"I;")";" HAS DISPENSED/USED ":-Fuel_left
1280     PRINT "          MORE GALLONS OF FUEL THAN AVAILABLE!"
1290     PRINTER IS 1
1300     Fuel_used=Fuel_on_hand
1310     Fuel_left=0
1320 END IF
1330
1340 N(147)=Fuel_left
1350
1360 UPDATE CONSUMPTION RECORD
1370 FOR J=1 TO 3
1380     N(130+J)=Ammo_left(J)
1390     N(138+J)=Ammo_used(J)+N(138+J)
1400     N(115+J)=Ammo_on_hand(J)
1410 NEXT J
1420 N(108)=Fuel_used
1430 N(143)=N(143)+Fuel_used
1440
1450 CALCULATE FUEL STATUS AND REMAINING FUEL
1460 IF Tot_veh_fuel<1 THEN 1550
1470 IF Tot_veh_fuel)=Fuel_left THEN
1480     N(101)=Fuel_left/Tot_veh_fuel

```

Table 4-4. Logistics code.

```

1490     Fuel_left=0
1500     ELSE
1510         N(101)=1
1520         Fuel_left=Fuel_left-Tot_veh_fuel
1530     END IF
1540     !
1550     !   CALCULATE AMMO STATUS AND REMAINING AMMO
1560     FOR J=1 TO 3
1570         IF Tot_veh_ammo(J)<=0 THEN
1580             N(118+J)=0
1590             GOTO 1680
1600         END IF
1610         IF Tot_veh_ammo(J)>=Ammo_left(J) THEN
1620             N(118+J)=Ammo_left(J)/Tot_veh_ammo(J)
1630             Ammo_left(J)=0
1640         ELSE
1650             N(118+J)=1
1660             Ammo_left(J)=Ammo_left(J)-Tot_veh_ammo(J)
1670         END IF
1680     NEXT J
1690     !
1700     !   CALCULATE TRUCK/GROUND FUEL STORAGE
1710     IF Fuel_left>0 THEN
1720         Load_cap=N(55)*Truck_cap(1)
1730         IF Load_cap>Fuel_left THEN
1740             N(103)=Fuel_left           ! FUEL ON TANKERS
1750             N(105)=0                 ! FUEL ON GROUND
1760         ELSE
1770             N(103)=Load_cap
1780             N(105)=Fuel_left-Load_cap
1790         END IF
1800     ELSE
1810         N(103)=0
1820         N(105)=0
1830     END IF
1840     !
1850     N(85)=N(55)
1860     IF N(146)>0 THEN N(105)=0 ! DUMPS FUEL ON GROUND FOR MOVING UNIT
1870     !   CALCULATE TRUCK/GROUND AMMO STORAGE
1880     Ammo_total=Ammo_left(1)+Ammo_left(2)+Ammo_left(3)
1890     IF Ammo_total>0 THEN
1900         S1=Ammo_left(1)/Ammo_total*1000
1910         S2=Ammo_left(2)/Ammo_total
1920         N(124)=INT(S1)+S2
1930         N(126)=N(124)
1940         Load_cap=N(58)*Truck_cap(4)
1950         IF Ammo_total<=Load_cap THEN
1960             N(123)=Ammo_total
1970             N(125)=0
1980             N(126)=0
1990         ELSE
2000             N(123)=Load_cap

```


Table 4-4. Logistics code.

```

2010      N(125)=Ammo_total-Load_cap
2020      END IF
2030      ELSE
2040          N(123)=0          ! AMMO ON CGO VEHICLES
2050          N(124)=0          ! DIST OF AMMO ON CGO VEH
2060          N(125)=0          ! AMMO STORED ON GROUND
2070          N(126)=0          ! DIST OF AMMO ON GROUND
2080      END IF
2090      N(84)=N(58)
2100      IF N(146)>0 THEN N(125)=0 ! DUMPS AMMO ON GROUND FOR MOVING UNIT
2110      !
2120      Write_out: ! WRITE OUT TO UNIT FILE
2130          OUTPUT @Path,I;N(*)
2140          PRINTER IS 1
2150      Next_unit: ! END OF UNIT PROCESSING
2160      NEXT I
2170      !
2180      !
2190      !
2200      ASSIGN @Path TO *
2210      PRINT
2220      PRINT
2230      PRINT "LOGISTICS PROCESSING COMPLETED "
2240      LOAD "DIME"&Disk$
2250      GOTO Halt
2260      !
2270      !
2280      ! ***** END OF MAIN PROGRAM *****
2290      !
2300      !
2310      Blue_data: ! THIS SBR HOLDS BLUE LOGISTICS DATA
2320      !
2321      ! ** DC ** 7 AUG 1986
2322      !
2330      ASSIGN @Pammouse TO "BLAMMO_USE"&Dcdisk$
2331      FOR Recnum=1 TO 10
2332          ENTER @Pammouse,Recnum;Dataline(*)
2333          FOR Element=1 TO 70
2334              Ammo(Recnum,Element)=Dataline(Element)
2335          NEXT Element
2336      NEXT Recnum
2350      ASSIGN @Pammouse TO *
2360      !
2370      ASSIGN @Pfueluse TO "BLFUEL_USE"&Dcdisk$
2380      FOR Recnum=1 TO 10
2381          ENTER @Pfueluse,Recnum;Dataline(*)
2382          FOR Element=1 TO 70
2383              Fuel(Recnum,Element)=Dataline(Element)
2384          NEXT Element
2385      NEXT Recnum
2390      ASSIGN @Pfueluse TO *
2400      !

```

Table 4-4. Logistics code.

```

3760 ASSIGN @Ptrkcap TO "BL_TRK_CAP"&Dcdisk$
3770 ENTER @Ptrkcap,1;Truck_cap(*)
3780 ASSIGN @Ptrkcap TO *
3786 !
3790 ASSIGN @Pammocap TO "AMMO_CAP"&Dcdisk$
3800 ENTER @Pammocap,1;Ammo_cap(*)
3810 ASSIGN @Pammocap TO *
3820 !
3830 ASSIGN @Pfuelcap TO "FUEL_CAP"&Dcdisk$
3840 ENTER @Pfuelcap,1;Fuel_cap(*)
3850 ASSIGN @Pfuelcap TO *
3860 !
3870 ASSIGN @Pwpntyp TO "WPN_TYF"&Dcdisk$
3880 ENTER @Pwpntyp,1;Wpn_type(*)
3890 ASSIGN @Pwpntyp TO *
3900 ! ** END DC **
4070 !
4080 RETURN
4090 !
4100 ! *****
4110 !
4120 Red_data: ! THIS SBR HOLDS RED LOGISTICS DATA
4130 !
4140 ASSIGN @Pammouse TO "RDAMMO_USE"&Dcdisk$
4150 FOR Recnum=1 TO 10
4151     ENTER @Pammouse,Recnum;Dataline(*)
4152     FOR Element=1 TO 70
4153         Ammo(Recnum,Element)=Dataline(Element)
4154     NEXT Element
4155 NEXT Recnum
4160 ASSIGN @Pammouse TO *
4170 !
4860 ASSIGN @Pfueluse TO "RDFUEL_USE"&Dcdisk$
4870 FOR Recnum=1 TO 10
4871     ENTER @Pfueluse,Recnum;Dataline(*)
4872     FOR Element=1 TO 70
4873         Fuel(Recnum,Element)=Dataline(Element)
4874     NEXT Element
4875 NEXT Recnum
4880 ASSIGN @Pfueluse TO *
4890 !
4900 ASSIGN @Ptrkcap TO "RD_TRK_CAP"&Dcdisk$
5590 ENTER @Ptrkcap,1;Truck_cap(*)
5600 ASSIGN @Ptrkcap TO *
5610 !
5611 ASSIGN @Pammocap TO "AMMO_CAP"&Dcdisk$
5620 ENTER @Pammocap,1;Dummyrec(*).Ammo_cap(*)
5630 ASSIGN @Pammocap TO *
5640 !
5700 ASSIGN @Pfuelcap TO "FUEL_CAP"&Dcdisk$
5710 ENTER @Pfuelcap,1;Dummyrec(*).Fuel_cap(*)
5720 ASSIGN @Pfuelcap TO *

```

Table 4-4. Logistics code.

```
5730 !
5790 ASSIGN @Fwpntyp TO "WPN_TYP"&Dcdisk$
5800 ENTER @Fwpntyp,1;Dummyrec(*),Wpn_type(*)
5810 ASSIGN @Fwpntyp TO *
5811 !
5880 ! ** END DC **
5890 !
5900 RETURN
5910 !
5920 ! *****
5930 !
5940 Init_unit_var: ! THIS SBR INITIALIZES UNIT SUPPLY VARIABLES
5950 !
5960 Tot_veh_fuel=0
5970 Fuel_used=0
5980 Fuel_on_hand=0
5990 Fuel_left=0
6000 Ammo_total=0
6010 Load_cap=0
6020 FOR J=1 TO 3
6030     Ammo_on_hand(J)=0
6040     Frac(J)=0
6050     Tot_veh_ammo(J)=0
6060     Ammo_used(J)=0
6070     Ammo_left(J)=0
6080 NEXT J
6090 RETURN
6100 !
6110 ! *****
6120 Halt:END
```

CHAPTER 5

AIR ATTACK/AIR DEFENSE

1. PURPOSE.

The purpose of the DIME air defense program is to realistically game air-to-ground and ground-to-air interactions between ground forces and opposing aircraft. Four types of aircraft and 70 types of ground elements, which include four types of air defense weapon systems, are played.

2. GENERAL.

A. Both Red and Blue forces are given appropriate capabilities and limitations in order to realistically mirror current and future equipment, vehicles, weapons, aircraft, and munitions.

B. Air operations are separated into two phases: ingress/egress and air strike.

(1) The ingress/egress phase calculates the attrition suffered by aircraft which fly over previously undetected air defense units.

(2) The air strike phase calculates the attrition in both aircraft and ground elements resulting from interdiction at the target area.

C. Program characteristics include:

(1) Four aircraft types, two fixed wing and two helicopters, are played for each force (Red and Blue).

(2) The following four generic air defense types are played:

(a) Man-portable, shoulder-fired missile system.

(b) Self-propelled, low-altitude guided missile system.

(c) Self-propelled gun system.

(d) Low to medium altitude over watch missile system.

(3) Aircraft losses during ingress and egress are calculated using the methodology from the Air Defense Air-to-Ground Engagement (ADAGE) model.

(4) Aircraft and ground losses during the strike phase are calculated using methodology from the Joint Munitions Effectiveness Manual (JMEM) and ADAGE.

(5) Aircraft have multiple munition loads including cluster munitions, guided missiles, area rockets, and guns.

(6) Aircraft loads are tailored to the expected target types.

(7) Attrition to both ground targets and aircraft is driven by delivery profiles for aircraft munitions.

(8) Air strikes are terminated by one of the following:

(a) Delivery of all aircraft munitions.

(b) Aircraft losses exceed threshold.

(c) Perceived ground losses exceed threshold.

(9) Mounted infantry casualties are assessed in proportion to carrier vehicle losses.

3. DATA FLOW.

The air defense program is dependent upon inputs from the user. Blue or Red aircraft are first chosen. It is then decided whether those aircraft will fly ingress, strike, or egress. Figure 5-1 shows the data flow.

A. Ingress/egress inputs.

(1) The number of aircraft making the flight.

(2) The type of aircraft:

<u>Input</u>	<u>Blue</u>	<u>Red</u>
1	A10	M28 (Frogfoot)
2	F16	M27 (Flogger)
3	UH60	Halo
4	AH64	Hind

(3) Altitude, in feet, which the aircraft is flying.

(4) Number of ground units overflowed by aircraft.

(5) CAS/BAI. The two types of aircraft flights possible are close air support and battlefield air interdiction.

(6) High/low density. This input represents the density of the air defense systems as either high or low.

(7) Unit identification. The unit number(s), up to a maximum of five, of the enemy unit(s) overflowed.




Figure 5-1. Air defense information flow.

(8) Terrain. Corresponding terrain occupied by each unit overflown.

- 1 = Open
- 2 = Rolling
- 3 = Hilly
- 4 = Mountainous

B. Strike inputs.

(1) The number of aircraft making the strike.

(2) Aircraft type.

(3) Aircraft mission.

- 1 = Bridge
- 2 = Antiarmor
- 3 = Antipersonnel
- 4 = Strike POL point
- 5 = Strike AMMO point

(4) Aircraft break point. The maximum percentage of attrition the aircraft will incur before breaking the attack.

(5) The percent of the target unit in the open (having limited overhead protective cover).

(6) CAS/BAI.

(7) High/low density.

(8) Target length. The length dimension of the area occupied by the target unit(s) in meters.

(9) Target width. The width of the target in meters.

(10) Target posture. The strategic (major) mission of the target.

- 1 = Attack
- 2 = Defend
- 3 = Reserve
- 4 = Move

(11) Target type. The unit type of the target.

- 0 = Combat unit
- 1 = Artillery unit
- 2 = Air defense unit
- 3 = Attack helicopter ground/forward rearming and refueling point (FARP)

- 4 = Command post/headquarters (CP/HQ)
- 5 = Engineer unit
- 6 = POL/AMMO supply point
- 7 = Maintenance point
- 8 = Bridge
- 9 = Communications/radar/electronic warfare (EW) sites.

(12) Number of targeted units.

(13) Unit identification. The unit number(s), up to a maximum of five, of the enemy unit(s) targeted.

(14) Terrain.

(15) Percent targeted. The percentage of each unit targeted depending on air intelligence, target location, camouflage of target, operational mission, and terrain.

C. Additional options beside ingress, egress, and strike, include:

(1) Status report. This report may be used to print information or help debug any changes to the program. Options available are as follows:

- (a) List current results.
- (b) List Blue air cumulative results.
- (c) List Red air cumulative results.
- (d) List debug unit information.
- (e) List debug flight information.
- (f) List debug strike information.

(2) Update results. This option allows the choice of storing the information from the current ingress, egress, or strike flight or purging its information to enable rerunning.

(3) Exit module. If return to the DIME driver is desired, the exit option is chosen. A prompt then appears to ensure updates to files. "Reminder to save final results (Y/N)" is answered N if an update had been accomplished and will continue exiting from the program.

4. FILE STRUCTURE.

DIME air defense data files are used by the program to describe aircraft performance, weapons and munitions capabilities, and target characteristics. The data are stored on random access files as shown in Figure 5-2.




Figure 5-2. Air defense data bases.

A. Aircraft profile files.

(1) The aircraft profile files contain data describing air defense weapon characteristics against a specific type aircraft. Two files exist for each aircraft played, one for ingress and one for egress.

(2) The structure of the random access file is as follows. Air defense (ADA) weapons represent positions 48 - 54 of the "UNITFILE".

Array Name: Flt_profile(*). File Name: The file name is based on the aircraft type and whether the aircraft is ingressing or egressing (example: AIO_ING).

<u>File Positions</u>	<u>Description</u>
1 through 7	Minimum altitude (meters) that the 7 ADA weapons can engage the aircraft.
8 through 14	Maximum altitude (meters) that the 7 ADA weapons can engage the aircraft.
15 through 21	Radius of effects for range of the 7 ADA weapons to engage the aircraft in meters.
22 through 28	Probability of participation of 7 ADA weapons against the aircraft.
29 through 35	Number of rounds/basic load for each of the 7 ADA weapons.
36 through 42	Weight (pounds) of one round for the 7 ADA weapons.
43 through 49	Number of rounds fired/engagement for the 7 ADA weapons against the aircraft.
50 through 56	Probability of five-minute survivability for aircraft against ADA weapons.

B. Air strike files.

(1) The air strike files contain data describing aircraft performance against each of the 70 target element types. Also included is data describing air defense weapon characteristics against the aircraft with its particular flight profile driven by the type of munition it is carrying. Multiple files exist for each aircraft type, one for each type of aircraft-delivered munition used.

(2) The structure of the random access files is as follows. ADA weapons represent positions 48 - 54 on the "UNITFILE".

Array Name: Stk_profile (*)

File Name: Aircraft type-munitions load: (example: A10 MK20)

<u>File Position</u>	<u>Description</u>
1	Code 1 = Bomb 2 = Missile 3 = Gun
2	Effective lethal area of principal target for above munition type (meters squared; m ²).
3	Minimum number of passes to deliver the above munition; for a gun, the maximum number of passes.
4	Rounds delivered per engagement. This consists of one for a guided missile ordnance load and guns dropped from bombs, given a target is engaged.
5	Number of rounds/basic load for this ammunition type carried by aircraft.
6 - 9	Probability of detecting the principal target per pass given the target is exposed for attack, defend, move, and reserve.
10 - 13	Probability that aircraft has line of site (LOS) with principal target in the woods for attack, defend, move, and reserve.
14 - 83	Probability that the target element in the lethal area will be destroyed by munition type. For point fire, single-shot PK are used.
84	Probability that bridge is destroyed.
85	Probability of ammunition (AMMO) point destruction.

<u>File Position</u>	<u>Description</u>
86	Probability of POL point destruction.
87 - 156	Effective lethal area for each element in DIME which corresponds to above target element PKs for munition (m ²).
157	Effective lethal area for a bridge (m ²).
158	Effective lethal area for an AMMO point (m ²). Note: Use specific target size of structured target if applicable.
159	Effective lethal area for POL point (m ²). Note: Use specific target size of structured target if applicable.
160	Scaling factor used for targets in the woods. Note: When AMMO PK is given for a specific target density, enter AMMO density here.
161	Scaling factor used for personnel in foxholes. Note: When POL PK is given for a specific target density, enter POL density here.
162 - 168	Minimum altitude that 7 ADA weapons can engage the aircraft for this delivery profile. Over target area assume 0 for all 7 ADA weapons (meters).
169 - 175	Maximum altitude that the 7 ADA weapons can engage the aircraft for this delivery profile. Over target area, assume 100,000 for all 7 ADA weapons (meters).
176 - 182	Radius of effects for range of the 7 ADA weapons against the aircraft for this delivery profile (meters).
183 - 189	Probability of participation for ADA weapons against the aircraft for this delivery profile.
190 - 196	Number of rounds/basic load for each of the 7 ADA weapons (pounds).
197 - 203	Weight of one round for the 7 ADA weapons (pounds).
204 - 210	Number of rounds fired/engagement for the ADA weapons against the aircraft for this delivery.

<u>File Position</u>	<u>Description</u>
211 - 217	Probability of five-minute survivability for aircraft under this delivery profile against ADA weapon.
218 - 224	Probability of 30-second survivability for aircraft under this delivery profile against ADA weapon.

C. Munitions load profile files.

(1) The munitions load profile files contain data describing the ammunition carried by a particular aircraft type. Multiple files exist for each aircraft type, one for each type mission flown.

(2) These files are used to access the strike profile files.

File Name: Aircraft Type-Missions (example: A1OARM, for anti-armor mission)

<u>File Position</u>	<u>Description</u>
1	Number of munition types carried by the aircraft. This number reflects the following number of records to be read. The order of the records reflects the sequential order of munitions dropped over the target area.
2	File name of the first munition type of ADA profile for the aircraft.
.	.
:	:
.	.
N	File name of the Nth munition type and ADA profile for the aircraft.

D. Unit area files.

(1) The unit area files contain data describing the size in square meters of 10 unit types. Two files exist, one for Red units and one Blue units. Each file lists 10 unit types and contains four unit postures for each type.

(2) The array is Unit type area (I,J) where I represents the unit types and J represents unit posture.

- I: 1 = Combat unit
 2 = Artillery unit
 3 = Air defense (ADA) unit
 4 = Attack helicopter ground/forward arming and refueling point (FARP)
 5 = Command post/headquarters (CP/HQ)
 6 = Engineer unit
 7 = POL/AMMO supply point
 8 = Maintenance point
 9 = Surface-to-air missile (SAM) site
 10 = Communications/radar/electronic warfare (EW) site.
- J: 1 = Attack
 2 = Defend
 3 = Reserve
 4 = Move.

E. Weighted target fractions.

(1) The weighted target fractions files contain data describing the aircrafts' preference for the 70 elements plus POL dumps and ammunition dumps. Two files exist, one for Red elements and one for Blue elements. Each file lists an integer value between zero and 10 as a function of the five air combat missions. The higher the value, the greater the preference for firing at that target.

(2) The array is $Ac_ms_tgt_wts(I,J)$ where:

I: Target elements
 1-70 plus POL and AMMO

J: Aircraft mission
 1 = Bridge
 2 = Armor
 3 = Personnel
 4 = POL
 5 = AMMO

5. ALGORITHMS.

A. Figure 5-3 presents a generalized logic flow of the processes occurring in the DIME air defense program. The purpose of this diagram is to provide a framework for consideration of the various algorithms used in the program. The DIME air defense program is a deterministic model using expected value techniques for calculating losses on both aircraft and ground




Figure 5-3. Air defense logic flow.

elements. The model first determines the appropriate parameters for aircraft and target elements. Next, specific characteristics are determined for the targeted units. Then aircraft attrition is figured by determining the number of air defense elements available in the battle area, calculating the number of subpasses in the flight, calculating the air defense artillery suppression factor, calculating the amount of air defense munitions expended, and, finally, calculating the number of aircraft killed. Attrition to ground elements is figured by calculating equipment losses due to area munitions, equipment losses due to point munitions, and mounted infantry losses as vehicles are destroyed. The "UNITFILE" is updated to reflect elements lost and amount of ammunition expended.

B. The following paragraphs provide a detailed description of the algorithms used for the calculation of subpasses, passes, air defense suppression, air defense munition expenditures, aircraft kills, area losses, point losses, and mounted infantry losses. When MIN() appears in the following algorithms, it represents a minimum function where the minimum of the items within the parentheses are used in the calculations.

C. The following pass and subpass calculations are performed for each group of aircraft sent on an ingress, strike or egress mission.

(1) Calculate subpasses. The number of tactical groupings the flight is divided into, based on the mission (close air support or basic air interdiction) and on tactical considerations. The number of subpasses that a flight is divided into is calculated as follows:

$$N_{sp} = N_{ac} / (2 * N_{max}) \quad (\text{Eq. 5-1})$$

where:

N_{sp} = the number of subpasses.
 N_{ac} = the number of aircraft in the flight.
 N_{max} = the maximum number of aircraft that would be flown on that specific type of mission due to tactical considerations.

Note: N_{max} is multiplied by two in order to simulate air defense saturation achieved by tactical spacing between subpasses.

(2) Calculate passes. The number of times an aircraft must fly over the target area to deliver its ordnance is calculated as follows:

$$N_p = M_p / P_d \quad (\text{Eq. 5-2})$$

where:

N_p = the number of passes.
 M_p = the minimum number of passes required to deliver the load of munitions.
 P_d = the probability of detecting the principal target per pass.

D. All of the following equations are calculated for each subpass.

(1) Calculate air defense suppression. Air defense suppression is based on the unit's mission/activities at the time of the strike.

(a) Vehicular mounted air defense weapons are suppressed as follows:

$$Nwa_i = \prod_{i=1}^i [Nw_i * (1 - Sf_i)] \quad (\text{Eq. 5-3})$$

where:

Nwa_i = the number of air defense weapons available of type i after suppression.
 Nw_i = the number of air defense weapons available of type i .
 Sf_i = the suppression factor for type i air defense weapons.

(b) Hand-held air defense weapons are suppressed as follows:

$$Nwa_i = \prod_{i=1}^i [Nw_i * (1 - Sf_i)] * Df_i \quad (\text{Eq. 5-4})$$

where:

Df_i = the fraction of hand-held air defense weapons dismounted at the time of attack.

(2) Calculations of air defense ammunition expenditures are as follows:

(a) Target area:

$$Ta = Tl * Tw \quad (\text{Eq. 5-5})$$

where:

Ta = target area.
 Tl = target length.
 Tw = target width.

(b) Unit area:

$$Ua = \text{MIN}(U, Ta) \quad (\text{Eq. 5-6})$$

where:

Ua = the unit area.

U = the area required by the units given the current posture.

(c) Air defense area factor:

$$Af_i = \text{PI} * [(R_i)^2] / Ua \quad (\text{Eq. 5-7})$$

where:

Af_i = the target area factor for air defense system type i.

PI = the symbol designating the ratio of the circumference of a circle to its diameter; approximately 3.1415927.

R_i = the range of air defense system type i.

(d) Number of weapons engaging aircraft:

$$Nwe_i = Af_i * Nwa_i * Pp_i \quad (\text{Eq. 5-8})$$

where:

Nwe_i = the number of air defense weapons of type i engaging the aircraft.

Pp_i = the percentage of air defense system type i that will participate.

(e) Basic load for air defense weapons:

$$Bl_i = Nr_i * Rw_i \quad (\text{Eq. 5-9})$$

$$Tl = \sum_i Bl_i \quad (\text{Eq. 5-10})$$

where:

Bl_i = the basic load weight for air defense weapon type i.

Nr_i = the number of rounds of ammunition in the basic load for air defense weapon system type i.

Rw_i = the weight of one round of ammunition for air defense weapon system type i.

Tl = the total basic load weight for all air defense weapon types in the battle area.

(f) Number of rounds available:

$$Ra_i = Bl_i * Ta * 2000/Tl \quad (\text{Eq. 5-11})$$

where:

Ra_i = the number of rounds of air defense ammunition available of type i.
 Bl_i = the basic load weight for air defense weapon type i.
 Ta = the total tons of air defense ammunition available.
 Tl = the total basic load weight for all air defense weapon types in the battle.

(g) Number of loads fired:

$$Rf_i = \text{MIN}(Ra_i, Rf_i) * Nwe_i \quad (\text{Eq. 5-12})$$

$$Lf_i = Rf_i / Rfe_i \quad (\text{Eq. 5-13})$$

where:

Rf_i = the number of air defense rounds fired per type i.
 Rfe_i = the number of rounds fired per engagement by air defense weapon type i.
 Lf_i = the number of air defense ammunition loads fired per type i.

(3) Number of aircraft kills. The number of aircraft kills is calculated as follows:

(a) Probability of kill:

$$Psk_i = (1 - Pk_i) / Npa \quad (\text{Eq. 5-14})$$

$$Psa_i = (1 - Pa_i) / Npa \quad (\text{Eq. 5-15})$$

$$Pskp = \prod_{i=1}^i [(1 - Psk_i) \uparrow Lf_i] \quad (\text{Eq. 5-16})$$

$$Psap = \prod_{i=1}^i [(1 - Psa_i) \uparrow Lf_i] \quad (\text{Eq. 5-17})$$

where:

P_{sk_i} = the probability of one aircraft in the pass being killed in 30 seconds by air defense weapons type i.
 P_{k_i} = the probability of one aircraft surviving for 30 seconds against air defense weapons type i.
 N_{pa} = the number of aircraft in a subpass
 P_{sa_i} = the probability of one aircraft in the subpass being killed in five minutes against air defense weapon type i.
 P_{a_i} = the probability of one aircraft surviving for five minutes against air defense weapon type i.
 P_{skp} = the probability of killing an aircraft out of the subpass, in 30 seconds based on the number of loads fired.
 P_{sap} = the probability of killing an aircraft out of the subpass, in five minutes based on the number of loads fired.

(b) Number of aircraft lost:

$$N_{psk} = (1 - P_{skp}) * N_{pa} * E_e \quad (\text{Eq. 5-18})$$

$$N_{spa} = (1 - P_{sap}) * N_{pa} * E_e \quad (\text{Eq. 5-19})$$

$$N_{sac} = N_{pa} - N_{psk} \quad (\text{Eq. 5-20})$$

$$N_{acl} = \sum N_{psa} \quad (\text{Eq. 5-21})$$

where:

N_{psk} = the number of aircraft lost within 30 seconds of engagement.
 E_e = the effective engagement factor, based on the perceived density of enemy air defense.
 N_{psa} = the number of aircraft lost within five minutes of engagement.
 N_{sac} = the number of aircraft available for the strike.
 N_{acl} = the number of aircraft lost on the flight.

(4) Number of ground elements lost to area munitions during a strike. The number of elements lost is calculated in the following manner.

(a) Kill equations are dependent on whether one plane can cover the target area or if more are necessary. In order to determine this, the following calculation are performed.

$$U_a = \text{MIN}(U_{atp}, L * W) \quad (\text{Eq. 5-22})$$

$$T_a = \text{MIN}(L * W, 3 * U_a) \quad (\text{Eq. 5-22a})$$

$$P_c = A_{ta}/T_a \quad (\text{Eq. 5-22b})$$

where:

Uatp = area (in meters squared) required by elements in the units, given the current posture of the unit.
L = target length (in meters)
W = target width (in meters)
Ua = unit area (in square meters)
Ta = size of target area (in square meters)
Ata = effective lethal area for the aircraft (in square meters)
Pc = the number of planes to cover the target area

(b) The probability of kill for an element targeted by aircraft must be adjusted according to the terrain as follows:

$$PK_j = Pac_j * [Tfo + (Tfw * Sfw)] \quad (\text{Eq. 5-23})$$

where:

PK_j = the probability that target element type j is killed subject to terrain considerations.
Pac_j = the probability of kill of target element type j by the aircraft-delivered area munition.
Tfo = the fraction of the target in the open.
Tfw = the fraction of the target in the woods.
Sfw = the scaling factor used for targets in the woods.

(c) If the target area is small enough to be covered by one plane ($Pc \leq 1$), the number of ground elements lost is:

$$Ne_{ij} = [1 - (1 - PK_j)^{\uparrow} (Nsac * Ef)] * Ne_j \quad (\text{Eq. 5-24})$$

where:

Ne_{ij} = the number of type j elements lost to the flight of aircraft.
Nsac = the number of aircraft performing the strike.
Ef = the effectiveness factor for aircraft munitions based on the perceived density of air defense weapons.
Ne_j = the number of elements of type j in the target area.

(b) If the target area is larger and $Pc > 1$, the coverage attained by a group of aircraft is calculated as:

$$C_j = Cac_j * Ef * Nsac / Ta \quad (\text{Eq. 5-25})$$

where:

C_j = the coverage ratio of the target area to the munitions coverage area.
 Cac_j = the munitions area coverage of one aircraft with respect to target elements type j.
 Ta = the size of the target area

(c) If the target area is greater than the area which can be covered by all aircraft ($C_j < 1$), then the ground element losses are:

$$Nel_j = C_j * PK_j * Ne_j \quad (\text{Eq. 5-26})$$

where:

Nel_j = the number of type j elements lost to the flight of aircraft.

(d) If the aircraft can cover the entire area ($C_j \geq 1$), then ground element losses (Nel_j) are:

$$Nel_j = [1 - (1 - PK_j)^{C_j}] * Ne_j \quad (\text{Eq. 5-27})$$

(5) The amount of POL and/or ammunition lost to munitions during a strike is calculated in the following manner:

(a) Loss equations are dependent on whether one plane can cover the target area or if more are necessary. In order to determine this, the following calculations are performed.

$$Ua = \text{MIN}(Uatp, L * W) \quad (\text{Eq. 5-28})$$

$$Ta = \text{MIN}(L * W, 3 * Ua) \quad (\text{Eq. 5-28a})$$

$$Pc = Ata/Ta \quad (\text{Eq. 5-28b})$$

(b) If the target area is small enough to be covered by one plane ($Pc \leq 1$), the POL and ammunition lost is:

$$Nm_elmt_lost = [1 - (1 - PK)^{Nm_stk_ac * Eff_shots}] * Num_elmt_left \quad (\text{Eq. 5-29})$$

where:

Nm_elmt_lost = the number of elements lost to a flight of aircraft.
 PK = the probability that the element is killed
 Nm_stk_ac = the number of strike aircraft

Eff_shots = the effectiveness factor for aircraft munitions, based on the perceived density of air defense weapons
Nm_elmt_left = the number of elements in the target area

(c) If it is necessary for more than one plane to cover the target area ($P_c > 1$), the ammunition and POL dumps must be translated into equivalent targets:

$$\text{Equiv_area} = \text{Nm_elmt_tgt} / \text{Dens} \quad (\text{Eq. 5-30})$$

$$\text{Equiv_tgt} = \text{Equiv_area} / \text{PK_area} \quad (\text{Eq. 5-31})$$

where:

Equiv_area = the perceived target area due to the target elements and target density

Nm_elmt_tgt = the amount of POL or ammunition in the target area.

Dens = the density of the target area for either POL or ammunition.

Equiv_tgt = the number of equivalent Pk targets in the target area.

PK_area = the effective lethal area for either an ammo point or a POL point; this is found in the strike files, position 158 or 159.

(d) If the targeted area is larger and $P_c > 1$, the coverage capability of the entire strike group is calculated:

$$C = (\text{Eff_shots} * \text{Nm_stk_ac}) / \text{Equiv_tgt} \quad (\text{Eq. 5-32})$$

where:

C = the coverage ratio of the target area to the munitions coverage area.

If the aircraft can cover the entire area or more ($C \geq 1$), POL and ammunition losses are calculated:

$$\text{Nm_elmt_lost} = [1 - (1 - \text{PK}) \uparrow C] * \text{Nm_elmt_left} \quad (\text{Eq. 5-32a})$$

where:

Nm_elmt_lost = the amount of POL or ammunition lost to the strike aircraft.

If the target area is greater than that which can be covered by all aircraft ($C \leq 1$), then the POL and ammunition losses are calculated as:

$$Nm_elmt_lost = PK * C * Nm_elmt_left \quad (\text{Eq. 5-32b})$$

(6) The number of ground elements lost to point munitions during a strike is calculated in the following manner:

(a) The total ammunition used by the aircraft strike force is:

$$Rac = Np * Nrfe \quad (\text{Eq. 5-33})$$

$$Nb = B1 * Nsac/Rac \quad (\text{Eq. 5-34})$$

where:

Rac = the number of rounds an aircraft could deliver per strike.

Np = the number of passes required by an aircraft to deliver its ordnance.

Nrfe = the number of rounds fired per engagement by an aircraft.

Nb = the effective number of aircraft in the strike based on ammunition availability.

B1 = the number of rounds of ammunition in the basic load for an aircraft.

Nsac = the number of aircraft performing the strike.

(b) Calculate target element preference factor. The preference factor associated with target elements is calculated as follows:

$$Pf_j = Mtw_j * Ne_j * Pk_j \quad (\text{Eq. 5-35})$$

$$Spf_j = \sum_j Pf_j \quad (\text{Eq. 5-36})$$

where:

Pf_j = the preference factor for target element j.

Mtw_j = the mission related target weight for element j.

Ne_j = the number of elements of type j in the target area.

Pk_j = the aircraft's probability of killing target element type j.

Spf = the sum of all preference factors for all elements of the target, for one aircraft.

(c) Calculate target element preference ratio factor. The preference ratio factor is calculated as follows:

$$Pfr_j = Pf_j / Spf \quad (\text{Eq. 5-37})$$

$$Tpf_j = Pfr_j * Nb \quad (\text{Eq. 5-38})$$

where:

Pfr_j = the preference ratio factor for target element j.
 Tpf_j = the total preference factor for all aircraft in the flight against target element type j.
 Nb = the effective number of aircraft in the strike.

(d) Calculate number of target elements lost. The losses represent the target selection process as being dependent; all aircraft fire at different targets. The number of elements lost is calculated as follows:

$$Nel_j = Pk_j * Tpf_j * Ef \quad (\text{Eq. 5-39})$$

where:

Nel_j = the number of type j elements lost to the flight of aircraft.
 Pk_j = the aircraft's probability of killing target element type j.
 Ef = the effectiveness factor for aircraft munitions based on the perceived density of air defense weapons.

(7) The number of mounted infantry losses during a strike. The number of mounted infantry lost when vehicles are destroyed is calculated as follows:

(a) Mount ratio; the number of infantry mounted on vehicles is calculated as follows:

$$Mr = \text{MIN} (NI/Nv, 8) \quad (\text{Eq. 5-40})$$

where:

Mr = the mount ratio; the number of infantry mounted on a troop-carrying vehicle.
 NI = the number of infantry troops in the battle area.
 Nv = the number troop-carrying vehicles in the battle area.

(b) Vehicles lost. The number of infantry-carrying vehicles lost is calculated as follows:

$$Fe = Nv * Pe/Nvu \quad (\text{Eq. 5-41})$$

$$VL = Fe * Nv1 \quad (\text{Eq. 5-42})$$

where:

Fe = the fraction of troop-carrying vehicles exposed.
Pe = the percent of the targeted unit in the battle area.
Nvu = the number of vehicles in the targeted unit.
VL = the number of troop-carrying vehicles lost in the battle.
Nv1 = the number of vehicles lost in the battle.

(c) Mount losses. The number of infantry lost in vehicles is calculated as follows:

$$Per = VL * Mr \quad (\text{Eq. 5-43})$$

where:

Per = the number of personnel lost in vehicles.
VL = the number of troop carrying vehicles lost in the battle.
Mr = the number of troops mounted in vehicles.

6. "UNITFILE" IMPACT.

Table 5-1 provides a summary of the principal variables in "UNITFILE" by the air defense program.

7. CODE.

A. Introduction. This section contains information on the DIME air defense. The second paragraph describes the functional areas of the program and a system flowchart. The third paragraph contains figures and tables that briefly explain the subroutines called from each functional area and the primary variables influenced by each subroutine.

B. Functional areas. This section contains a brief overview of the functional areas in the DIME air defense program. As shown in Figure 5-4 (functional flow diagram), the air defense program actually contains two distinct sections, one modeling ingress/egress operations and one modeling strike operations. The two operations share many of the same subroutines in the program.

Table 5-1. "UNITFILE" variables affected by air defense.

<u>Element number</u>	<u>Name</u>	<u>Description</u>
1-70	Weapons list	The 70 weapon type quantities present within the unit.
75	Major mission	1 = Attack 2 = Defend 3 = Reserve/Idle 4 = Move
78	Unit Type (X.Y)	X = Player identification (X.Y) 1 = Blue 2 = Red Y = Unit type 0 = Combat unit 1 = Artillery unit 2 = Air defense (ADA) unit 3 = Attack helicopter ground/forward arming and refueling point 4 = Command post/headquarters (CP/HQ) 5 = Engineer unit 6 = Fuel/ammunition (POL/AMMO) supply unit 7 = Maintenance point 8 = Surface-to-air missile (SAM) site 9 = Communication/radar/electronic warfare (EW) site
80	Percent ADA suppressed (XX.YY)	XX = Vehicle ADA systems suppressed YY = Handheld systems suppressed
91	Detection status (X.Y)	X = Hours left until redetected Y = Unit status with respect to detection by the opposite commander 0 = Not detected 1 = Detected but not verified 2 = Acquired/verified 3 = Lost
92	Intelligence Status	Total hours this target has been status tracked this detection period
133	AD ammo	The amount of AD ammunition available to be consumed




Figure 5-4. Air defense functional flow.

(1) As shown in Figure 5-4, both operations are triggered by the input of low-resolution data. Low-resolution data include the force (Red or Blue), the operation (ingress/egress or strike), aircraft information (number, type, and altitude of aircraft), and target information (width, length, and identification of units). An air defense input sheet is used to facilitate loading of this input data.

(2) After a gamer selects the force, aircraft, and target information, the DIME air defense program selects the appropriate high-resolution data corresponding to the operation (ingress/egress or strike) selected.

(3) For ingress/egress operations, the following procedures are used:

(a) High-resolution data include air defense weapon characteristics such as maximum and minimum altitude, range, basic load, rates of fire, and air defense probabilities of kill for each defense weapon played. Target information is also included, such as the number and type of elements in the target area and the amount of ammunition available to the ground elements. This information is contained in data files which are accessed by the type of aircraft and mission. Currently, four types of aircraft for each force are played, two fixed wing and two rotary wing. Ground units are made up of elements selected from the data base developed for DIME. DIME allows for 70 different elements per side plus two special elements.

(b) The next major functional area calculates aircraft losses. This major functional area is composed of the following four subareas:

1. First, calculating the number of subpasses is required in order to partition the flight of aircraft into increments of a size corresponding to the actual number of aircraft that would pass over a unit at any one time. Aircraft losses are calculated for each subpass increment, then are added together to determine total aircraft losses.

2. Next, air defense suppression calculates the readiness/reaction time of the air defense systems. These computations are based on the unit's mission at the time of the overflight.

3. The third subarea calculates the amount of air defense ammunition available and the amount fired during the engagement.

4. The last subarea calculates the number of aircraft lost and updates the number of aircraft available for follow-on missions.

(4) For strike operations, the following procedures are used:

(a) High-resolution strike data are similar to ingress/egress data with the addition of aircraft capabilities against ground elements. This information includes munition capabilities against each target element, flight profiles for each type munition carried, and tactical considerations based on mission requirements.

(b) The next major functional area calculates results of the strike operation. Aircraft kills and kills of ground elements are calculated on an interactive basis. This major functional area is composed of the following areas:

1. First, the number of passes required by each aircraft in order to deliver the load of munitions carried must be calculated.

2. Then, four subareas are used to calculate the number of aircraft lost. These subareas are the same four used in ingress/egress operations to calculate aircraft losses.

3. Next, losses to ground elements as a result of area-type munitions are calculated.

4. Losses to ground elements as a result of point-type munitions are then calculated.

5. The last of these functional areas calculates the number of mounted infantry lost when their vehicles are destroyed.

(5) The next major functional area of the DIME air defense program deals with the results of both ingress/egress and strike operations. Actions in this area include updating files with the number of remaining operational elements, listing results of surface-to-air and air-to-surface action, and to ready files for the next iteration of the battle. This functional area is composed of three subareas.

(a) The first of these subareas is used to output the results of the operation. Results include the number and type of aircraft killed and the number of each ground element destroyed.

(b) The next subarea is used to either update or purge the files with the results of the last battle increment.

(c) The last of these subareas is used to ready the program for the next increment.

(6) Finally, the last procedure allows for entry of new low-resolution data for a new battle or for exit from the DIME air defense program.

C. Subroutine summary. Table 5-2 provides a summary of the DIME air defense program subroutines and their primary variables. Subroutines called by each functional area are shown and the function of each subroutine is described. The primary variables for each subroutine are listed and described.

D. Code listing. A listing of the P3 program code appears in Table 5-3.

Table 5-2. DIME Air Defense Subroutines

A. Functional Area: Load low resolution data.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main program	Calls subroutines	A. Fct_hnd_ada_dmt	Fraction of hand-to-hand and weapons dismounted
Choose_color	Initializes Blue and Red forces	A. Frc_clr\$	Force color (Red or Blue)
Flight_input	Inputs initial ingress/egress information	A. Nm_ac_input B. Ac_mission C. Tgt_width D. Tgt_length E. Nm_units F. Terr	Number of aircraft input Aircraft mission Target width Target length Number of units Type Terrain
Strike_input	Inputs initial strike information	A. Ac_type B. Ac_brkp_pct C. Tgt_pct_open D. Tgt_epsr_pct	Aircraft type Aircraft breakpoint percentage Percent of target in open Percent of target in area
Change_answer	Allows changes to information entered	A. Nm_units_chosen	Number of units chosen

Table 5-2. DIME Air Defense Subroutines (continued)

<u>B. Functional Area: Load high resolution ingress/egress data.</u>	
<u>Subroutine called</u>	<u>Subroutine function(s) Primary variables Variable descriptions</u>
<u>Select_parms</u>	<p>A. Aircraft\$ Type aircraft</p> <p>B. Flt\$ Aircraft mission</p> <p>C. Activity Target mission</p> <p>D. Tgt_type Target type</p>
<u>Flight_data</u>	<p>Equates low resolution entries to specific high resolution data</p> <p>Sets air defense parameters for the type of aircraft.</p> <p>A. Unit_type_area Size of area required by type of unit.</p> <p>B. Min_ada_alt Minimum altitude for air defense weapon</p> <p>C. Max_ada_alt Maximum altitude for air defense weapon</p> <p>D. Ada_range Range of air defense weapon</p> <p>E. Ada_prtcptn Probability of participation for air defense weapon</p> <p>F. Ada_rnd_bs_ld Number of rounds of basic load for air defense weapon</p> <p>G. Flt_profile Data file contents</p> <p>H. Ada_rnd_wt Weight of one round of ammunition</p> <p>I. Ada_rnd_frd_eng Number of rounds fired per engagement</p>

Table 5-2. DIME Air Defense Subroutines (continued)

<u>B. Functional Area:</u>	<u>Load high resolution ingress/egress data.</u> (continued)	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Subroutine called</u>				
<u>Flight_data</u>			J. Ada_psk_ac	Probability of surviving for 30 seconds
			K. Altitude	Altitude
<u>Select_units</u>		A. Unit_id_ptr		Unit Identification Pointer
	Stores target unit information in temporary files			
<u>Flight_attrition</u>		A. Break_point		Break Point
	Calls subroutines to calculate aircraft losses	B. Tgt_posture		Target Posture
		C. T_sub_pass		Total number of sub passes
		D. Nm_ac_left_1		Number of aircraft left after first pass
		E. Tl_ada_ton_frd		Total tons of air defense ammunition fired
		P. Tac_lost_pass		Total aircraft lost per pass
		G. Nm_psa_ac_lost		Number of aircraft lost in five minutes
		H. Nm_ac_left		Number of aircraft left

Table 5-2. DIME Air Defense Subroutines (continued)

<u>Functional Area:</u>	<u>Load high resolution ingress/egress data.</u>	(continued)	
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Select_ada_info</u>	Sets air defense counts to totals contained in target units	A. Nm_ada_wpn B. Ada_suprsn_pet C. Unit_posture D. Unit_type	Number of air defense weapons Percentage of air defense Unit posture Unit type
<u>Calc_sub_pass</u>	Calculates the number of aircraft exposed to ground units at any one time	A. Eff_shots B. Eff_engage C. Nm_sub_pass D. Pass_acft E. Cas_bai	Scaling factor for aircraft Sealing factor for air defense Number of sub passes Number of aircraft in the pass Close air support or Battlefield air interdiction
<u>Calc_ada_suprsn</u>	Calculates the suppression factor for air defense weapons	A. Suprsn_fire B. Nm_ada_wpn_avl	Suppressed fraction Number of air defense weapons available

Table 5-2. DIME Air Defense Subroutines (continued)

<u>Functional Area:</u>	<u>Load high resolution ingress/egress data.</u>	(continued)	
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calc_ada_rnds	Calculates the number of air defense rounds fired	A. Tgt_a	Target Area
		B. Unit_area	Unit Area
		C. Ada_area_fctr	Air defense area factor
		D. Nm_ada_vpn_eng	Number of air defense weapons engaging
		E. Tl_ada_bs_ld_wt	Total air defense in basic load weight
		F. Ada_bs_ld_wt	Air defense basic load weight
		G. Ada_rnd_avl	Number of air defense rounds available
		H. Ada_rnd_frd	Number of air defense rounds fired
		I. Ada_lds_fd	Number of air defense loads fired
		Calc_ac_losses	Calculates the number of aircraft lost.
B. Nm_psk_ac_lost	Number of aircraft lost in 30 seconds		
C. Nm_stk_ac	Number of strike aircraft		
D. Nm_ac_lost_fit	Number of aircraft lost this flight		
E. Ada_tons_avl	Tons of air defense ammunition available		

Table 5-2. DIME Air Defense Subroutines (continued)

C. Functional area: Load high resolution strike data

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Strike_data; Strike_init	Calls subroutines to set strike data. Initialize strike variables.	A. Ac_brkpt_fre B. Tgt_fre_open	Aircraft break point fraction Fraction of target in the open
		C. Tgt_fre_woods	Fraction of target in the woods
		D. Altitude_meters	Altitude in meters
		E. Tgt_expar_fre	Portion of target exposed
		F. Tl_ada_tons	Total tons of air defense ammunition
		G. Nm_elmt_lost_fl	Number of elements lost to the flight
		H. Nm_elmt_tgt	Number of elements in the target
Select_stk_info	Sets parameters for strike operation	A. Nm_vehicles B. Suprsn_frc_1 C. Suprsn_frc_2 D. Nm_elmt_left E. Mount_ratio F. Nm_infantry	Number of vehicles Suppression factor number 1 Suppression factor number 2 Number of elements left Ratio of mounted infantry Number of infantry

Table 5-2. DIME Air Defense Subroutines (continued)

<u>Functional area:</u>	<u>Load high resolution strike data</u>	<u>(continued)</u>	
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Strike_apportion	Sets parameters for mounted infantry losses	A. Tl_ac_passes	Total aircraft passes
		B. Frct	Fraction of troop carrying vehicles lost in the unit
		C. V_lost_unit	Vehicles lost in the unit
		D. Mount_losses	Mount infantry losses
		E. Vehicles_lost	Vehicles lost
Strike_attrition	Calculates mounted infantry losses	A. T_plos	Total probability of Loss
Strike_profile	Sets air defense parameters for the type aircraft flown	A. Wpn_load_code	Aircraft munition type
		B. Ac_area_prn_tgt	Effective lethal area for munition
		C. Min_ac_passes	Minimum number of passes required to deliver munitions
		D. Nm_ac_rnds_eng	Rounds delivered for engagement
		E. Nm_ac_rnd_bs_ld	Number of rounds in basic load
		F. Prn_tgt_wds_frc	Scaling factor for targets in the woods
		G. Prsnl_fxhl_frc	Scaling factor for personnel in foxholes

Table 5-2. DIME Air Defense Subroutines (continued)

<u>C. Functional area:</u>	<u>Load high resolution strike data</u>	<u>(continued)</u>	
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Strike_profile</u> (concluded)		H. Ac_plos_prn_tgt	Probability of aircraft loss
		I. Ac_pdtc_prn_tgt	Probability of detecting target
		J. Ac_tgt_pk	Probability of destroying target
		K. Ac_tgt_area	Lethal area for type munitions carried by aircraft
<u>Strike_info</u>	Calculates aircraft passes when more than one munition type is carried	A. Nm_ac_passes	Number of aircraft passes
<u>Calc_area_losses</u>	Calculates elements lost to area munitions	A. Tgt_area	Target area
		B. Nm_areas	Number of arms
		C. Nm_elmt_lost	Number of elements lost
<u>Calc_point_losses</u>	Calculates elements lost to area	A. Tgt_area	Target area
		B. Nm_areas	Number areas
		C. Nm_elmt_lost	Number of elements lost

Table 5-2. DIME Air Defense Subroutines (continued)

C. Functional area: Load high resolution strike data (concluded)	
<u>Subroutine called</u>	<u>Subroutine function(s)</u> <u>Primary variables</u> <u>Variable descriptions</u>
Calc_point_loss	Calculates elements lost to point munitions A. Nm_elmt Number of elements
D. Functional Area: Results	
<u>Subroutine called</u>	<u>Subroutine function(s)</u> <u>Primary variables</u> <u>Variable descriptions</u>
Flight_results	Lists results to include number of aircraft and ground elements killed A. R_target_names\$ Red target names B. B_target_names\$ Blue target names
Store_results	Routes units in temporary files A. Nm_units_played Number of units played
Add_results	Calculates number of aircraft for next phase of air operation A. Nm_ac_flighting Number of aircraft ingressing B. Nm_ac_fit_egr Number of aircraft egressing C. Nm_ac_fit_stk Number of aircraft striking D. Nm_ac_lost_ing Number of aircraft lost ingressing E. Nm_ac_lost_egr Number of aircraft lost egressing

Table 5-2. DIME Air Defense Subroutines (continued)

D. Functional area: Results

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Add results (concluded)</u>			
	F. Nm_ac_lost_atk		Number of aircraft lost striking
	G. Nm_elmt_lost_ac		Number of elements lost to aircraft
	H. Nm_ac_lost_ada		Number of aircraft lost to ADA
	I. Nm_ac_avl_egr		Number of aircraft available to ingress
	J. Nm_ac_avl_stk		Number of aircraft available to strike

E. Functional Area: Update Results

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Update_results</u>	Calls subroutines to update and purge results.	A. Tl_ac_fit_ing B. Tl_ac_fit_egr C. Tl_ac_fit_stk	Total aircraft ingressing Total aircraft egressing Total aircraft striking
<u>Cumulate_totals</u>	Totals aircraft information for future use.	A. Tl_ac_lost_ing B. Tl_ac_lost_egr C. Tl_ac_lost_stk D. Tl_ac_lost_ada E. Tl_eimt_lost_ac	Total aircraft lost ingressing Total aircraft lost egressing Total aircraft lost striking Total aircraft lost Total target elements lost

Table 5-3. Air attack/Air defense code.

```

10 ! THIS PROGRAM IS THE AIR ATTACK / AIR DEFENSE MODULE FOR DIME (P3).
20 ! THIS PROGRAM WAS CODED BY STEVE ARRINGTON AND CINDY JAHNKE
30 ! 22 OCT 1983.
40 ! DATA LAST CHANGED BY ROB BELFLOWER, 21 MARCH 1985, BDM
50 ! EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
51 ! DECLASSIFIED -- AUG 7, 1986 -- BY OAO CORP.  ** DC **
60 OPTION BASE 1
70 DIM Ac_burst_wt(72),Ac_burst_wt_frc(72)
80 DIM Ac_pdtc_prn_tgt(4),Ac_plos_prn_tgt(4)
90 DIM Ac_tgt_area(72),Ac_tgt_pk(72)
100 DIM Ac_ms_tgt_wts(72,5),Ada_area_fctr(7)
110 DIM Ada_bs_ld_wt(7),Ada_lds_frd(7)
120 DIM Ada_mobility_tp(7),Ada_prtcptn(7)
130 DIM Ada_psa_ac(7),Ada_psk_ac(7)
140 DIM Ada_range(7),Ada_rnd_bs_ld(7)
150 DIM Ada_rnd_frd(7),Ada_rnd_frd_eng(7)
160 DIM Ada_rnd_wt(7),B_target_name$(350)
170 DIM Fct_hnd_ada_dmt(4,2),Flt_profile(56)
180 DIM Max_ada_alt(7),Min_ada_alt(7)
190 DIM Nm_ac_avl_egr(4),Nm_ac_avl_stk(4)
200 DIM Nm_ac_flt_ing(4),Nm_ac_flt_egr(4)
210 DIM Nm_ac_flt_stk(4),Nm_ac_lost_ada(4)
220 DIM Nm_ac_lost_ing(4),Nm_ac_lost_egr(4)
230 DIM Nm_ac_lost_stk(4),Nm_ada_wpn(7)
240 DIM Nm_ada_wpn_avl(7),Nm_ada_wpn_eng(7)
250 DIM Nm_elmt_left(72),Nm_elmt_lost_ac(72)
260 DIM Nm_elmt_lost_fl(72),Nm_elmt_tgt(72)
270 DIM O(72),R_target_name$(350)
280 DIM Stk_profile(224),Suprsn_frc(2)
290 DIM T$(350),T_plos(4),Terr(5)
300 DIM Tgt_expsr_pct(5),Tgt_expsr_frc(5)
310 DIM Tl_ac_flt_ing(4),Tl_ac_flt_egr(4)
320 DIM Tl_ac_flt_stk(4),Tl_ac_lost_ada(4)
330 DIM Tl_ac_lost_egr(4),Tl_ac_lost_ing(4)
340 DIM Tl_ac_lost_stk(4),Tl_elmt_ac(72)
350 DIM Unit(150),Unit_id(5),Unit_id_20_150(20)
360 DIM Unit_info(150),Unit_store_5_15(5,150)
370 DIM Unitstore_20_15(20,150),Unit_type_area(10,4)
380 DIM Wpn_ld_template$(3)(14),Tm$(7),Frac_inf(5)
390!
400!
410 Nm_units_played=0
420 !
430 Disk$=":HP9134,701"
431 Dcdisk$=":HP9134,701,0" ! ** DC **
440!
450 Main_program: !
460!
470 !LOAD TERRAIN FLOS DATA
471 !
472 ! ** DC **
473 !

```

Table 5-3. Air attack/Air defense code.

```

480 ASSIGN @Ptploss TO "TOT_FLOSS"&Dcdisk$
490 ENTER @Ptploss,1;T_plos(*)
500 ASSIGN @Ptploss TO *
510 !LOAD FRACTION DISMOUNTED
520 ASSIGN @Pfrcdsm TO "FRAC_DISM"&Dcdisk$
530 ENTER @Pfrcdsm,1;Fct_hnd_ada_dmt(*)
540 ASSIGN @Pfrcdsm TO *
580 ! ** END DC **
590 New_color: !
600 PRINTER IS 1
610 GOSUB Choose_color
620 Menu$="REPEAT"
630 WHILE Menu$="REPEAT"
640     GOSUB Menu_selection
650     SELECT Option$
660     CASE "INGRESS","EGRESS"
670         GOSUB Flight_input
680         GOSUB Flight_output
690         GOSUB Change_answer
700         IF Answer$="N" THEN
710             GOSUB Flight_data
720             GOSUB Flight_atrition
730             GOSUB Flight_results
740         END IF
750     CASE "STRIKE"
760         GOSUB Strike_input
770         GOSUB Strike_output
780         GOSUB Change_answer
790         IF Answer$="N" THEN
800             GOSUB Strike_data
810             GOSUB Strike_atrition
820             GOSUB Flight_results
830         END IF
840     CASE "STATUS"
850         GOSUB Status_report
860     CASE "UPDATE"
870         GOSUB Update_results
880     CASE "EXIT"
890         GOSUB Exit_module
900     CASE ELSE
910         BEEP
920     END SELECT
930 END WHILE
940 !
950 STOP
960 !
970 !*****
*
980 !
990 Add_results: !
1000!
1010 SELECT Flight$

```

Table 5-3. Air attack/Air defense code.

```

1020 CASE "INGRESS"
1030   Nm_ac_flt_ing(Ac_type)=Nm_ac_flt_ing(Ac_type)+Nm_ac_input
1040   Nm_ac_lost_ing(Ac_type)=Nm_ac_lost_ing(Ac_type)+Nm_ac_lost_flt
1050 CASE "EGRESS"
1060   Nm_ac_flt_egr(Ac_type)=Nm_ac_flt_egr(Ac_type)+Nm_ac_input
1070   Nm_ac_lost_egr(Ac_type)=Nm_ac_lost_egr(Ac_type)+Nm_ac_lost_flt
1080 CASE "STRIKE"
1090   Nm_ac_flt_stk(Ac_type)=Nm_ac_flt_stk(Ac_type)+Nm_ac_input
1100   Nm_ac_lost_stk(Ac_type)=Nm_ac_lost_stk(Ac_type)+Nm_ac_lost_flt
1110   FOR I=1 TO 72
1120     Nm_elmt_lost_ac(I)=Nm_elmt_lost_ac(I)+Nm_elmt_lost_fl(I)
1130   NEXT I
1140 END SELECT
1150 !
1160 Nm_ac_lost_ada(Ac_type)=Nm_ac_lost_ada(Ac_type)+Nm_ac_lost_flt
1170 Nm_ac_avl_stk(Ac_type)=Nm_ac_flt_ing(Ac_type)-Nm_ac_lost_ing(Ac_type)-Nm_
c_flt_stk(Ac_type)
1180 Nm_ac_avl_egr(Ac_type)=Nm_ac_flt_egr(Ac_type)-Nm_ac_lost_egr(Ac_type)-Nm_
c_lost_stk(Ac_type)-Nm_ac_flt_egr(Ac_type)
1190 !
1200 RETURN
1210!
1220!*****
*
1230!
1240 Calc_ac_losses:
1250 Tl_ada_tons_frd=0
1260 Psk_product=1
1270 Psa_product=1
1280 FOR I=1 TO 7
1290   IF Altitude_meters<=Max_ada_alt(I) AND Altitude_meters>=Min_ada_alt(I)
ND Ada_lds_frd(I)>0 THEN
1300     Psk_term=(1-Ada_psk_ac(I))/FNMax(Pass_acft,1)
1310     Psa_term=(1-Ada_psa_ac(I))/FNMax(Pass_acft,1)
1320     !
1330     Psk_product=Psk_product*(1-Psk_term)^Ada_lds_frd(I)
1340     Psa_product=Psa_product*(1-Psa_term)^Ada_lds_frd(I)
1350     !
1360     Ada_tons_frd=Ada_rnd_frd(I)*Ada_rnd_wt(I)/2000
1370     Tl_ada_tons_frd=Tl_ada_tons_frd+Ada_tons_frd
1380   END IF
1390   !
1400 NEXT I
1410 Nm_psk_ac_lost=(1-Psk_product)*Pass_acft*Eff_engage
1420 Nm_psa_ac_lost=(1-Psa_product)*Pass_acft*Eff_engage
1430 !
1440 Nm_stk_ac=Pass_acft-Nm_psk_ac_lost
1450 Nm_ac_lost_flt=Nm_ac_lost_flt+Nm_psa_ac_lost
1460 !
1470 !
1480 Ada_tons_avl=Ada_tons_avl-Tl_ada_tons_frd
1490 Unit(133)=Ada_tons_avl

```

Table 5-3. Air attack/Air defense code.

```

1500 Unit(141)=Unit(141)+Tl_ada_tons_frd
1510 !
1520 IF Option$="INGRESS" OR Option$="EGRESS" THEN
1530 PRINT USING Fmt_call1;Nm_psa_ac_lost,Acprint$," LOST TO AD ELEMENTS OF U'
IT ",Unit_id(This_unit)." DURING ",Option$
1540 Fmt_call1:IMAGE 3D,D,1X,4A,29A,3D,8A,7A
1550 END IF
1560 !
1570 RETURN
1580!
1590!*****
*
1600!
1610 Calc_ada_rnds:!
1620!
1630 Tgt_a=Tgt_length*Tgt_width
1640 Unit_area=FNMin(Unit_type_area(Unit_type,Unit_posture),Tgt_a)
1650 FOR I=1 TO 7
1660 Ada_area_fctr(I)=PI*(Ada_range(I)^2)/FNMax(Unit_area,.0000001)
1670 Ada_area_fctr(I)=FNMin(Ada_area_fctr(I),1)
1680 NEXT I
1690 FOR I=1 TO 7
1700 Nm_ada_wpn_eng(I)=Ada_area_fctr(I)*Nm_ada_wpn_avl(I)*Ada_prtcptn(I)
1710 NEXT I
1720 Nm_ada_wpn_eng(6)=Nm_ada_wpn_eng(6)*Plos
1730 Nm_ada_wpn_eng(7)=Nm_ada_wpn_eng(7)*Plos
1740 Tl_ada_bs_ld_wt=0
1750 FOR I=1 TO 7
1760 Ada_bs_ld_wt(I)=Ada_rnd_bs_ld(I)*Ada_rnd_wt(I)*Nm_ada_wpn(I)
1770 Tl_ada_bs_ld_wt=Tl_ada_bs_ld_wt+Ada_bs_ld_wt(I)
1780 NEXT I
1790 FOR I=1 TO 7
1800 Ada_rnd_avl=Ada_rnd_bs_ld(I)*Ada_tons_avl*2000/FNMax(Tl_ada_bs_ld_wt,.0
00001)
1810 Ada_rnd_frd(I)=FNMin(Ada_rnd_avl,Ada_rnd_frd_eng(I))*Nm_ada_wpn_eng(I)
1820 Ada_lds_frd(I)=Ada_rnd_frd(I)/FNMax(Ada_rnd_frd_eng(I),.0000001)
1830 NEXT I
1840 RETURN
1850!
1860!*****
*
1870!
1880 Calc_ada_suprsn:!
1890!
1900 !SET TYPE OF MOBILITY FOR ADA WEAPONS
1910 Ada_mobility_tp(1)=1 !VEHICLE
1920 Ada_mobility_tp(2)=1 !VEHICLE
1930 Ada_mobility_tp(3)=1 !VEHICLE
1940 Ada_mobility_tp(4)=1 !VEHICLE
1950 Ada_mobility_tp(5)=1 !VEHICLE
1960 Ada_mobility_tp(6)=2 !HAND-HELD
1970 Ada_mobility_tp(7)=2 !HAND-HELD

```

Table 5-3. Air attack/Air defense code.

```

1980 !
1990 !UNPACK ADA SUPPRESSION PERCENTAGE FOR HAND-HELD/VEHICLE ADA WEAPONS
2000 Suprsn_frc(1)=INT(Ada_suprsn_pct)
2010 Suprsn_frc(2)=Ada_suprsn_pct-Suprsn_frc(1) !HAND-HELD
2020 Suprsn_frc(1)=Suprsn_frc(1)/100 !VEHICLE
2030 !
2040 FOR I=1 TO 7
2050 Nm_ada_wpn_avl(I)=Nm_ada_wpn(I)*(1-Suprsn_frc(Ada_mobility_tp(I)))
2060 NEXT I
2070 !CONSIDER HAND HELD WEAPONS OUT OF CARRIER
2080 Nm_ada_wpn_avl(6)=Nm_ada_wpn_avl(6)*Fct_hnd_ada_dmt(Tgt_posture,Ada_side)
2090 Nm_ada_wpn_avl(7)=Nm_ada_wpn_avl(7)*Fct_hnd_ada_dmt(Tgt_posture,Ada_side)
2100 !
2110 RETURN
2120 !
2130 !*****
2140 !
2150 Calc_area_loss: !
2160 !
2170 Tgt_area=Tgt_length*Tgt_width
2180 IF Tgt_area>=3*Unit_area THEN
2190 Tgt_area=3*Unit_area
2200 END IF
2210 !
2220 Tgt_area=FNMax(Tgt_area,1)
2230 !
2240 !IF Tgt_type=6 THEN GOSUB Calc_answer
2250 FOR I=1 TO 72
2260 Pk=Ac_tgt_pk(I)*(Tgt_frc_open+Tgt_frc_woods*Prn_tgt_wds_frc)
2270 Nm_areas=FNMin(Ac_tgt_area(I)/Tgt_area,1)
2280 IF Nm_areas=1 THEN
2290 ! ONE PLANE CAN COVER TARGET
2300 Nm_elt_lost=(1-(1-Pk)^(Nm_stk_ac*Eff_shots))*Nm_elt_left(I)
2310 ELSE
2320 ! CALCULATE COVERAGE BY STRIKE GROUP.
2330 ! THIS ASSUMES DEPENDENCE FROM PASS TO PASS
2340 C=((Ac_tgt_area(I)*Eff_shots*Nm_stk_ac)/Tgt_area
2350 IF C>=1 THEN
2360 !COVERAGE BY ALL AIRCRAFT IN PASS MORE THAN ONCE OVER THE
2370 !TARGET AREA.
2380 Nm_elt_lost=(1-(1-Pk)^C)*Nm_elt_left(I)
2390 ELSE
2400 !COVERAGE BY ALL AIRCRAFT IN PASS LESS THAN THE TARGET AREA.
2410 Nm_elt_lost=C*Pk*Nm_elt_left(I)
2420 END IF
2430 END IF
2440 Nm_elt_lost_fl(I)=Nm_elt_lost_fl(I)+Nm_elt_lost
2450 Nm_elt_left(I)=Nm_elt_left(I)-Nm_elt_lost
2460 NEXT I
2470 !
2480 FOR I=1 TO 7
2490 Nm_ada_wpn(I)=Nm_elt_left(I+47)

```

Table 5-3. Air attack/Air defense code.

```

2500 NEXT I
2510 '
2520 RETURN
2530!
2540!*****
2550!
2560 Calc_answer: !
2570!
2580 IF Ac_mission=4 THEN
2590   I=72
2600 ELSE
2610   I=71
2620 END IF
2630 Pk_area=Stk_profile(I+38)
2640 Dens=Stk_profile(I+40)
2650 Pk=Ac_tgt_pk(I)
2660 Equiv_area=Nm_elmt_tgt(I)/Dens
2670 Equiv_tgt=Equiv_area/Pk_area
2680 Equiv_tgt=FNMin(Equiv_tgt,1)
2690 IF Equiv_tgt<1 THEN GOTO 2730
2700   ! CASE 1   ONE AC COVERS TARGET
2710   Nm_elmt_lost=(1-(1-Pk)(Nm_stk_ac*Eff_shots))*Nm_elmt_left(I)
2720   GOTO 2800
2730   C=(Eff_shots*Nm_stk_ac)/Equiv_tgt
2740   IF C<1 THEN GOTO 2780
2750   ! CASE 2   ALL AC TOGETHER COVER TARGET
2760   Nm_elmt_lost=(1-(1-Pk)C)*Nm_elmt_left(I)
2770   GOTO 2800
2780   ! CASE 3   ALL AC COVER LESS THAN TARGET
2790   Nm_elmt_lost=Pk*C*Nm_elmt_left(I)
2800   Nm_elmt_lost_f1(I)=Nm_elmt_lost_f1(I)+Nm_elmt_lost
2810   Nm_elmt_left(I)=Nm_elmt_left(I)-Nm_elmt_lost
2820!
2830 RETURN
2840!
2850!*****
2860!
2870 Calc_point_loss: !
2880!
2890 Brgg=0
2900 IF Tgt_type=8 THEN GOTO 2930
2910 GOTO 3120
2920 IF Destroy=2 THEN 3120
2930 Pk=Stk_profile(86)
2940 R3=Unit_info(94)          !*** GET SEED *****
2950 IF R4=0 THEN R3=R5
2960 R4=1
2970 RANDOMIZE R3             !*** RANDOMIZE NUMBER ****
2980 FOR I=1 TO 10
2990   R3=RND
3000 NEXT I
3010 Psurvb=(1-Pk)Nm_stk_ac

```

Table 5-3. Air attack/Air defense code.

```

3020 Seed=R3*100
3030 Unit_store_5_15(1,94)=Seed
3040 Unit_info(94)=Seed
3050 PRINTER IS 1
3060 IF Psurv<R3 THEN GOTO 3090
3070 Brgg=1
3080 GOTO 3230
3090 Brgg=2
3100 Destroy=1
3110 GOTO 3230
3120 Divisor=FNMax(Nm_ac_passes*Nm_ac_rnds_eng,1)
3130 Nm_ac_bursts=Nm_ac_rnd_bs_ld*Nm_stk_ac/Divisor
3140 Constant=Tgt_frc_open+Tgt_frc_woods*Ac_plus_prn_tgt(Tgt_posture)
3150 Constant=Ac_pdtc_prn_tgt(Tgt_posture)*Constant
3160 Tl_ac_burst_wt=0
3170 !
3180 FOR I=1 TO 72
3190   Ac_burst_wt(I)=Ac_ms_tgt_wts(I,Ac_mission)*Nm_elmt_left(I)*Ac_tgt_pk(I)
3200   Tl_ac_burst_wt=Tl_ac_burst_wt+Ac_burst_wt(I)
3210 NEXT I
3220 !
3230 FOR I=1 TO 72
3240   Ac_burst_wt_frc(I)=Ac_burst_wt(I)/FNMax(Tl_ac_burst_wt,.0000001)
3250   Expnt=Ac_burst_wt_frc(I)*Nm_ac_bursts
3260   Nm_elmt=Nm_elmt_left(I)*Constant
3270   !
3280   ! IT IS ASSUMED THAT ALL AIRCRAFT FIRE AT DIFFERENT TARGETS
3290   ! (i.e. THE TARGET SELECTION IS DEPENDENT)
3300   ! CONSEQUENTLY, THE EXPECTED KILLS FROM A BINOMIAL SEEMS APPROPRIATE
3310   !
3320   Nm_elmt_lost=Ac_tgt_pk(I)*Expnt*Eff_shots
3330   Nm_elmt_lost=FNMin(Nm_elmt_lost,Nm_elmt)
3340   !
3350   Nm_elmt_lost_fl(I)=Nm_elmt_lost_fl(I)+Nm_elmt_lost
3360   Nm_elmt_left(I)=Nm_elmt_left(I)-Nm_elmt_lost
3370 NEXT I
3380 !
3390 FOR I=1 TO 7
3400   Nm_ada_wpn(I)=Nm_elmt_left(I+47)
3410 NEXT I
3420 !
3430 RETURN
3440 !
3450 !*****
3460 !
3470 Calc_sub_pass: !
3480 ! CALCULATES # OF SUBPASSES MADE BY A WING OF A/C AS THEY STRIKE THE TARGET
3490 ! OR INGRESS/EGRESS OVER THE TARGET.
3500 ! THE AD ATTRITION DATA IS ON A PASS BASIS HENCE, WE MUST
3510 ! SUBDIVIDE THE WING TO SEPERATE THE NUMBER OF A/C AS THEY
3520 ! ARE EXPOSED TO THE AIR DEFENSE ELEMENTS OF THE TARGET.
3530 !

```


Table 5-3. Air attack/Air defense code.

```

3540 !CALC THE EFFECTIVENESS OF THE PLANE DELIVERY BASED ON PERCEIVED DENSITY OF
3550 !   AIR DEFENSE.
3560 !
3570 SELECT High_low
3580 CASE 1 !AIR COMMANDER BELIEVES THAT AD IS HIGH DENSITY. PLANES ARE CLOSEL
3590 !SPACED ; THEIR EFFECTIVENESS IS DECREASED.
3600     Eff_shots=.8
3610     Eff_engage=.9
3620 CASE 2 !AIR COMMANDER BELIEVES THAT AD IS LOW DENSITY. PLANES ARE FURTHER
3630 !SPACED ; THEIR EFFECTIVENESS IS INCREASED.
3640     Eff_shots=.95
3650     Eff_engage=1
3660 END SELECT
3670 !
3680 !CALC THE NUMBER OF EXPOSED PLANES PER PASS AND THE NUMBER OF PASSES
3690 SELECT Cas_bai
3700 CASE 1 !AIR COMMANDER PERFORMING CLOSE AIR SUPPORT.
3710     Nm_sub_pass=INT(Nm_ac_left1/4+.5)
3720     IF Nm_sub_pass=0 THEN
3730         Nm_sub_pass=1
3740         Pass_acft=1
3750         GOTO End_sub_pass
3760     END IF
3770     Pass_acft=Nm_ac_left1/Nm_sub_pass
3780 CASE 2 !AIR COMMANDER PERFORMING BASIC AIR INTERDICTION.
3790     Nm_sub_pass=INT(Nm_ac_left1/8+.5)
3800     IF Nm_sub_pass=0 THEN
3810         Nm_sub_pass=1
3820         Pass_acft=1
3830         GOTO End_sub_pass
3840     END IF
3850     Pass_acft=Nm_ac_left1/Nm_sub_pass
3860 END SELECT
3870 End_sub_pass: !
3880 RETURN
3890 !
3900 !
3910 !*****
3920 !
3930 Change_answer: !
3940 !
3950 REPEAT
3960     PRINT
3970     PRINT "DO YOU WISH TO CHANGE ANSWERS? (Y/N)"
3980     INPUT Answer$
3990     UNTIL Answer$="Y" OR Answer$="N"
4000 !
4010 Nm_units_chosen=Nm_units+Nm_units_played
4020 IF Nm_units_chosen>20 THEN
4030     BEEP
4040     PRINT
4050     PRINT " ** ERROR: Number of units played will exceed storage"

```

Table 5-3. Air attack/Air defense code.

```

4060 PRINT " capability. You must update or purge results."
4070 Answer$="Y"
4080 END IF
4090
4100 RETURN
4110
4120 !*****
*
4130
4140 Choose_color: !
4150
4160 PRINT
4170 PRINT
4180 PRINT "AIR ATTACK / AIR DEFENSE MODULE"
4190 REPEAT
4200 PRINT
4210 PRINT "SELECT BLUE OR RED AIR (B/R)"
4220 INPUT Answer$
4230 UNTIL Answer$="B" OR Answer$="R"
4240 IF Answer$="B" THEN
4250 Frc_clr$="BLUE"
4260 Clr$="BL"
4270 Ada_side=2
4280 ELSE
4290 Frc_clr$="RED"
4300 Clr$="RD"
4310 Ada_side=1
4320 END IF
4330 !
4340 RETURN
4350
4360 !*****
4370
4380 Cumulate_totals:!
4390
4400 ASSIGN @Path TO Clr$&"_AIR_INF"&":HP9134,701"
4410 ENTER @Path,1;Tl_ac_flt_ing(*),Tl_ac_flt_egr(*),Tl_ac_flt_stk(*),Tl_ac_lost_ing(*),Tl_ac_lost_egr(*),Tl_ac_lost_stk(*),Tl_ac_lost_ada(*),Tl_elmt_ac(*)
4420
4430 FOR I=1 TO 4
4440 Tl_ac_flt_ing(I)=Tl_ac_flt_ing(I)+Nm_ac_flt_ing(I)
4450 Tl_ac_flt_egr(I)=Tl_ac_flt_egr(I)+Nm_ac_flt_egr(I)
4460 Tl_ac_flt_stk(I)=Tl_ac_flt_stk(I)+Nm_ac_flt_stk(I)
4470 Tl_ac_lost_ing(I)=Tl_ac_lost_ing(I)+Nm_ac_lost_ing(I)
4480 Tl_ac_lost_egr(I)=Tl_ac_lost_egr(I)+Nm_ac_lost_egr(I)
4490 Tl_ac_lost_stk(I)=Tl_ac_lost_stk(I)+Nm_ac_lost_stk(I)
4500 Tl_ac_lost_ada(I)=Tl_ac_lost_ada(I)+Nm_ac_lost_ada(I)
4510 NEXT I
4520
4530 FOR I=1 TO 72
4540 Tl_elmt_ac(I)=Tl_elmt_ac(I)+Nm_elmt_lost_ac(I)
4550 NEXT I

```

Table 5-3. Air attack/Air defense code.

```

4560 !
4570 OUTPUT @Path.1;Tl_ac_flt_ing(*).Tl_ac_flt_eqr(*).Tl_ac_flt_stk(*).Tl_ac_lo
st_ing(*).Tl_ac_lost_eqr(*).Tl_ac_lost_stk(*).Tl_ac_lost_ada(*).Tl_elmt_ac(*)
4580 ASSIGN @Path TO *
4590 !
4600 RETURN
4610 !
4620 !*****
4630 !
4640 Exit_module: !
4650 !
4660 REPEAT
4670 PRINT
4680 INPUT "REMINDER TO SAVE FINAL RESULTS (Y/N)".Answer$
4690 UNTIL Answer$="Y" OR Answer$="N"
4700 IF Answer$="Y" THEN
4710 PRINT
4720 PRINT "SELECT UPDATE RESULTS AND STATUS REPORT FROM MENU"
4730 WAIT 7
4740 ELSE
4750 REPEAT
4760 INPUT "CHOOSE BLUE/RED OR EXIT TO DIME MENU (COLOR/EXIT)".New_color$
4770 UNTIL New_color$="COLOR" OR New_color$="EXIT"
4780 IF New_color$="COLOR" THEN LOAD "NEW_P3:HP9134.701"
4790 PRINT
4800 PRINT "EXIT FROM AIR DEFENSE/AIR ATTACK MODULE"
4810 Menu$="FINISHED"
4820 LOAD "DIME:HP9134.701"
4830 END IF
4840 !
4850 !
4860 RETURN
4870 !
4880 !*****
4890 !
4900 File_error_1: !
4910 BEEP
4920 PRINT
4930 PRINT "**ERROR: ",File$&Disk$;" DOES NOT EXIST ON THE AA/AD DATABASE"
4940 RETURN
4950 !
4960 File_error_2: !
4970 BEEP
4980 PRINT
4990 PRINT "ERROR: ",File$&Disk$;" DOES NOT EXIST ON THE AA/AD DATABASE"
5000 PRINT " RESUBMIT A/C AND MISSION BY CHOOSING THE FOLLOWING:"
5010 PRINT
5020 PRINT "ENTER A/C TYPE (1-4)"
5030 INPUT Ac_type
5040 CALL Check_var("A/C TYPE",Ac_type,1,4)
5050 IF Flight$="STRIKE" THEN
5060 PRINT

```

Table 5-3. Air attack/Air defense code.

```

5070 PRINT "ENTER AIR COMBAT MISSION (1-5)"
5080 INPUT Ac_mission
5090 !IF Ac_mission=1 THEN INPUT "WHAT IS THE RANDOM SEED".RS
5100 CALL Check_var("AC MISSION",Ac_mission,1,5)
5110 END IF
5120 GOSUB Select_prmtrs
5130 File$=Aircraft$&"_"&Flt$
5140 RETURN
5150!
5160!*****
5170!
5180 Flight_atrition: !
5190!
5200 Break_point=.5*Nm_ac_left
5210 !
5220 FOR This_unit=1 TO Nm_units
5230 FOR J=1 TO 150
5240 Unit(J)=Unit_store_5_15(This_unit,J)
5250 NEXT J
5260 GOSUB Select_ada_info
5270 Tgt_posture=Unit(75)
5280 T_sub_pass=0
5290 Nm_ac_left1=Nm_ac_left
5300 IF Nm_ac_left<.1 THEN Store_loop
5310 Tac_lost_pass=0
5320 GOSUB Calc_sub_pass
5330 REPEAT
5340 T_sub_pass=T_sub_pass+1
5350 GOSUB Calc_ada_suprsn
5360 ! SET PLOS FOR ADA HAND HELD ROUNDS
5370 Plos=T_plos(Terr(This_unit))
5380 GOSUB Calc_ada_rnds
5390 GOSUB Calc_ac_losses
5400 Tac_lost_pass=Tac_lost_pass+Nm_psa_ac_lost
5410 UNTIL T_sub_pass>=Nm_sub_pass OR (Tac_lost_pass+Nm_ac_lost_flt)>=Break_
oint OR (Nm_ac_left1-Tac_lost_pass)<.1
5420 Nm_ac_left=FNMax(0,Nm_ac_left-Tac_lost_pass)
5430 Nm_psa_ac_lost=Tac_lost_pass
5440 Store_loop: !
5450 FOR J=1 TO 150
5460 Unit_store_5_15(This_unit,J)=Unit(J)
5470 NEXT J
5480 NEXT This_unit
5490 !
5500 RETURN
5510!
5520!*****
5530!
5540 Flight_data: !
5550!
5560 Ac_load=1
5570 Nm_ac_left=Nm_ac_input

```

Table 5-3. Air attack/Air defense code.

```

5580 Nm_ac_lost_flt=0
5590 Altitude_meters=Altitude*.3048
5600 GOSUB Select_units
5610 GOSUB Select_prmtrs
5620 !
5630 File%=Aircraft%&"_&Flt%
5640 ON ERROR GOSUB File_error_2
5650 ASSIGN @Path TO File%&Disk%
5660 OFF ERROR
5670 PRINTER IS 702
5680 GOSUB Flight_output
5690 PRINTER IS 1
5700 ENTER @Path,1;Flt_profile(*)
5710 ASSIGN @Path TO *
5720 FOR I=1 TO 7
5730   Min_ada_alt(I)=Flt_profile(I)
5740   Max_ada_alt(I)=Flt_profile(I+7)
5750   Ada_range(I)=Flt_profile(I+14)
5760   Ada_prtcptn(I)=Flt_profile(I+21)
5770   Ada_rnd_bs_ld(I)=Flt_profile(I+28)
5780   Ada_rnd_wt(I)=Flt_profile(I+35)
5790   Ada_rnd_frd_eng(I)=Flt_profile(I+42)
5800   Ada_psa_ac(I)=Flt_profile(I+49)
5810   Ada_psk_ac(I)=1
5820 NEXT I
5830 !
5840 File%=Clr%&"_UN_AREA"
5850 ASSIGN @Path TO File%&Disk%
5860 ENTER @Path,1;Unit_type_area(*)
5870 ASSIGN @Path TO *
5880 !
5890 RETURN
5900!
5910!*****>
5920!
5930 Flight_input:
5940!
5950 PRINT
5960 PRINT "      INPUT THE FOLLOWING FOR THE ":"Frc_clr%:" AIR ":"Flight%
5970 IF Flight%="EGRESS" THEN
5980   PRINT
5990   PRINT USING Fmtfi;"TOTAL A/C AVAILABLE FOR EGRESS:  ",Nm_ac_avl_egr(*)
6000 END IF
6010 IF Flight%="INGRESS" THEN
6020   PRINT
6030   INPUT "WHAT IS THE GAME TIME?",&Tm%
6040 END IF
6050 PRINT
6060 PRINT "ENTER:  # OF A/C, A/C TYPE, ALTITUDE, # UNITS OVERFLOWN"
6070 INPUT Nm_ac_input,Ac_type,Altitude,Nm_units
6080 !
6090 CALL Check_var("A/C TYPE",Ac_type,1,4)

```

Table 5-3. Air attack/Air defense code.

```

6100 !
6110 !
6120 PRINT
6130 PRINT "ENTER: TYPE OF STRIKE -- CAS OR BAI (INPUT 1 OR 2)"
6140 INPUT Cas_bai
6150 CALL Check_var("TYPE OF STRIKE (CAS OR BAI)",Cas_bai,1,2)
6160 PRINT
6170 PRINT "ENTER: EXPECTED DENSITY OF AD -- HIGH OR LOW (INPUT 1 OR 2)"
6180 INPUT High_low
6190 CALL Check_var("EXPECTED DENSITY OF AD",High_low,1,2)
6200 !
6210 !
6220 CALL Unit_read(Frc_clr$,Nm_units,Unit_id(*),Terr(*))
6230 Ac_mission=0
6240 !
6250 !SET THE TARGET AREA PARAMETERS FOR USE IN AREA FIRE
6260 Tgt_width=1.0E+8
6270 Tgt_length=1.0E+8
6280 !
6290 Fmtf1:IMAGE 31A,2X,4(3D.D,2X)
6300!
6310 RETURN
6320!
6330!*****
6340!
6350 Flight_output:!
6360!
6370 GOSUB Select_prmtrs
6380 !
6390 PRINT USING "///"
6400 PRINT "THE FOLLOWING INPUTS WERE CHOSEN FOR THE ";Frc_clr$;" AIR ";Flight$;";"
6410 PRINT
6420 IF Flight$="INGRESS" THEN
6430 PRINT
6440 PRINT "FLIGHT TIME IS ",Tm$
6450 PRINT
6460 END IF
6470 PRINT " # OF A/C, A/C TYPE, ALTITUDE, # UNITS OVERFLOWN"
6480 PRINT USING Fmt1:Nm_ac_input,Acprint$,Altitude,"ft",Nm_units
6490 !
6500 !
6510 PRINT
6520 SELECT Cas_bai
6530 CASE 1
6540 PRINT "Aircraft performing CAS."
6550 CASE 2
6560 PRINT "Aircraft performing BAI."
6570 END SELECT
6580 PRINT
6590 SELECT High_low
6600 CASE 1

```

Table 5-3. Air attack/Air defense code.

```

6610 PRINT "In a perceived high-density AD environment."
6620 CASE 2
6630 PRINT "In a perceived low-density AD environment."
6640 END SELECT
6650 !
6660 !
6670 PRINT
6680 PRINT USING Fmt2;"UNIT-ID'S OVERFLOWN: ";Unit_id(*)
6690 PRINT USING Fmt2;" TERRAIN: ";Terr(*)
6700 !
6710 Fmt1: IMAGE 9D,5X, 5A, 8D,2A,19D
6720 Fmt2: IMAGE 20A,3X,5(3D,3X)
6730 !
6740 RETURN
6750 !
6760 !*****
6770 !
6780 Flight_results: !
6790 !
6800 IF Nm_ac_lost_flt>Nm_ac_input THEN Nm_ac_lost_flt=Nm_ac_input
6810 IF Flight$="STRIKE" THEN
6820 PRINT
6830 PRINT USING Fmtfr2;"RESULTS OF THE",Acprint$,Flt$,"STRIKE: ".Nm_ac_input,
t."FLOWN",Nm_ac_lost_flt,"KILLED",Tl_ac_passes,"PASSES"
6840 PRINT
6850 R_target_name$(1,125)="T55 DF BMP73DF BRDM3BRDM5AT-75AGS17T12 CMD-
VDF DF DF DF DF BMPATBTR DF-ICDF-ICDF-ICARTY ARTY ARTY ARTY "
6860 R_target_name$(126,250)="ARTY ARTY MORTRMORTRMORTRMORTRMRL MRL MRL MF
L INF INF INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSZSU-XSA-13SA-6 "
6870 R_target_name$(251,350)="ADA ADA SA-14ADAHHF-TRKJ4TRKWATERCGO-TNATRKEW
TRKEWTRKENGR OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
6880 B_target_name$(1,125)="DF FAV-TM551 FAV40HNV-GDF DRAGNLAW DF CMD-
VDF DF DF DF DF HNV40DF-ICDF-ICDF-ICDF-ICARTY ARTY ARTY ARTY "
6890 B_target_name$(126,250)="ARTY ARTY MORTRMORTRMORTRMORTRMRLRSTMLRSTMLRSTML
RSTINF INF INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSVULCNAVNGRIHAWK"
6900 B_target_name$(251,350)="ADA ADA STINGADAHHF-TRKJ4TRKWATERCGO-TNATRKEW
TRKEWTRKENGR OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
6910 SELECT Frc_clr$
6920 CASE "BLUE"
6930 Target_victim$="RED"
6940 T$=R_target_name$
6950 CASE "RED"
6960 Target_victim$="BLUE"
6970 T$=B_target_name$
6980 END SELECT
6990 FOR Out=1 TO 72
7000 Q(Out)=Nm_elt_lost_fl(Out)
7010 NEXT Out
7020 PRINT Target_victim$:" ELEMENT LOSSES INFLICTED:"
7030 PRINT
7040 FOR X=10 TO 70 STEP 10
7050 PRINT USING Fmtfr1a:T$(X-10)*5+1:5),T$(X-9)*5+1:5),T$(X-8)*5+1:5),T
$(X-7)*5+1:5),T$(X-6)*5+1:5),T$(X-5)*5+1:5),T$(X-4)*5+1:5),T$(X-3)*5+1:5)

```

Table 5-3. Air attack/Air defense code.

```

7060 PRINT USING Fmtfr1b:T$(X-2)*5+1;5],T$(X-1)*5+1;5]
7070 PRINT USING Fmtfr1:0(X-9),0(X-8),0(X-7),0(X-6),0(X-5),0(X-4),0(X-3),0
X-2),0(X-1),0(X)
7080 NEXT X
7090 PRINT USING "12A,8D.D,5X,12A,8D.D";" FOL(gal) ";0(71);" AMMO(tons) ";0
72)
7100 PRINT
7110 IF Brgg=0 THEN GOTO 7180
7120 !IF Brgg=1 THEN GOTO 7150
7130 !IF Brgg=2 THEN GOTO 7130
7140 IF Destroy=0 THEN GOTO 7170
7150 PRINT "BRIDGE DESTROYED" ' THE SEED IS",R3
7160 GOTO 7180
7170 PRINT "BRIDGE NOT DESTROYED" ! THE SEED IS ",R3
7180 ELSE
7190 PRINT
7200 PRINT USING Fmtfr3;"RESULTS OF THE",Acprint$,Flight$," : ".Nm_ac_input,"
FLDWN",Nm_ac_lost_flt,"KILLED"
7210 END IF
7220 !
7230 IF Answer$<>"XYZ" THEN
7240 REPEAT
7250 PRINT
7260 PRINT "DO YOU WISH TO SUBTRACT THE ABOVE LOSSES? (Y/N)"
7270 INPUT Answer$
7280 UNTIL Answer$="Y" OR Answer$="N"
7290 END IF
7300 !
7310 IF Answer$="Y" THEN
7320 Answer$="XYZ"
7330 PRINTER IS 702
7340 GOSUB Flight_results
7350 GOSUB Store_results
7360 GOSUB Add_results
7370 PRINTER IS 1
7380 END IF
7390 !
7400 Fmtfr1: IMAGE 10(2X,3D.D)
7410 Fmtfr1a: IMAGE #,7(2X,5A)
7420 Fmtfr1b: IMAGE 2(2X,5A)
7430 Fmtfr2: IMAGE 15A,4A,7A,10A,3D.D,1X,6A,3D.D,1X,7A,3D,1X,7A
7440 Fmtfr3: IMAGE 15A,5A,7A,3A,3D.D,1X,6A,3D.D,1X,7A
7450!
7460 RETURN
7470!
7480:*****
7490!
7500 Init_totals: !
7510!
7520 FOR I=1 TO 4
7530 Nm_ac_flt_ing(I)=0
7540 Nm_ac_flt_egr(I)=0

```


Table 5-3. Air attack/Air defense code.

```

7550     Nm_ac_flt_stk(I)=0
7560     Nm_ac_lost_ing(I)=0
7570     Nm_ac_lost_egr(I)=0
7580     Nm_ac_lost_stk(I)=0
7590     Nm_ac_lost_ada(I)=0
7600     Nm_ac_avl_stk(I)=0
7610     Nm_ac_avl_egr(I)=0
7620     NEXT I
7630     FOR I=1 TO 20
7640         FOR J=1 TO 150
7650             Unitstore_20_15(I,J)=0
7660         NEXT J
7670         Unit_id_20_150(I)=0
7680     NEXT I
7690     FOR I=1 TO 72
7700         Nm_elmt_lost_ac(I)=0
7710     NEXT I
7720     Nm_units_played=0
7730     !
7740     RETURN
7750 !
7760 !*****
7770 !
7780 List_debug_flt: '
7790 !
7800     PRINT
7810     PRINT Aircraft$&Flt$&Disk$,Flt_profile(*)
7820     PRINT
7830     PRINT "MIN_ADA_ALT",Min_ada_alt(*)
7840     PRINT
7850     PRINT "MAX_ADA_ALT",Max_ada_alt(*)
7860     PRINT
7870     PRINT "ADA_RANGE  ",Ada_range(*)
7880     PRINT
7890     PRINT "ADA_PRTCPTN",Ada_prtcptn(*)
7900     PRINT
7910     PRINT "ADA_RND_BS_LD",Ada_rnd_bs_ld(*)
7920     PRINT
7930     PRINT "ADA_RND_WT  ",Ada_rnd_wt(*)
7940     PRINT
7950     PRINT "ADA_RND_FRD_ENG",Ada_rnd_frd_eng(*)
7960     PRINT
7970     PRINT "ADA_PSA_AC  ",Ada_psa_ac(*)
7980     PRINT
7990     PRINT "ADA_PSK_AC  ",Ada_psk_ac(*)
8000     PRINT
8010     PRINT "NM_ADA_WPN  ",Nm_ada_wpn(*)
8020     PRINT
8030     PRINT "NM_ADA_WPN_AVL",Nm_ada_wpn_avl(*)
8040     PRINT
8050     PRINT "UNIT_TYPE  ":Unit_type,"UNIT_POSTURE  ":Unit_posture,"UNIT_AREA  ":Un
t_area

```

Table 5-3. Air attack/Air defense code.

```

8060 PRINT
8070 PRINT "ADA_AREA_FCTR",Ada_area_fctr(*)
8080 PRINT
8090 PRINT "NM_ADA_WFN_ENG",Nm_ada_wpn_eng(*)
8100 PRINT
8110 PRINT "ADA_BS_LD_WT",Ada_bs_ld_wt(*)
8120 PRINT
8130 PRINT "TL_ADA_BS_LD_WT",Tl_ada_bs_ld_wt
8140 PRINT
8150 PRINT "ADA_RND_FRD",Ada_rnd_frd(*)
8160 PRINT
8170 PRINT "ADA_LDS_FRD",Ada_lds_frd(*)
8180 PRINT
8190 PRINT "TL_ADA_TONS_FRD",Tl_ada_tons_frd,"ADA_TONS_AVL",Ada_tons_avl
8200 !
8210 RETURN
8220 !
8230 !*****
8240 !
8250 List_debug_stk: !
8260 !
8270 PRINT
8280 PRINT Wpn_ld_template$(Ac_load)&Disk$,Stk_profile(*)
8290 PRINT
8300 PRINT "WPN_LOAD_CODE",Wpn_load_code
8310 PRINT
8320 PRINT "AC_AREA_PRN_TGT",Ac_area_prn_tgt
8330 PRINT
8340 PRINT "MIN_AC_PASSES ",Min_ac_passes
8350 PRINT
8360 PRINT "NM_AC_RNDS_ENG ",Nm_ac_rnds_eng
8370 PRINT
8380 PRINT "NM_AC_RND_BS_LD",Nm_ac_rnd_bs_ld
8390 PRINT
8400 PRINT "AC_PDTC_PRN_TGT",Ac_pdtc_prn_tgt(*)
8410 PRINT
8420 PRINT "AC_PLOS_PRN_TGT",Ac_plos_prn_tgt(*)
8430 PRINT
8440 PRINT "AC_TGT_PK ",Ac_tgt_pk(*)
8450 PRINT
8460 PRINT "AC_TGT_AREA ",Ac_tgt_area(*)
8470 PRINT
8480 PRINT "PRN_TGT_WDS_FRC",Prn_tgt_wds_frc
8490 PRINT
8500 PRINT "PRSNL_FXHL_FRC",Prsnl_fxhl_frc
8510 PRINT
8520 PRINT "TGT_AREA ",Tgt_area
8530 PRINT
8540 PRINT "NM_AC_PASSES",Nm_ac_passes
8550 PRINT
8560 PRINT "NM_AC_BURSTS",Nm_ac_bursts
8570 PRINT

```

Table 5-3. Air attack/Air defense code.

```

8580 PRINT "CONSTANT",Constant
8590 PRINT
8600 PRINT "AC_BURST_WT",Ac_burst_wt(*)
8610 PRINT
8620 PRINT "TL_AC_BURST_WT",Tl_ac_burst_wt
8630 PRINT
8640 PRINT "AC_BURST_WT_FRC",Ac_burst_wt_frc(*)
8650 PRINT
8660 PRINT "NM_VEHICLES ";Nm_vehicles,"VEHICLES_LOST ",Vehicles_lost
8670 PRINT
8680 PRINT "NM_INFANTRY ";Nm_infantry,"MOUNT_RATIO ";Mount_ratio
8690 PRINT
8700 PRINT "MOUNT_LOSSES ";Mount_losses,"NM_ELMT_LOST_FL(10) ";Nm_elmt_lost_fl
8710 '
8720 RETURN
8730!
8740!*****
8750!
8760 List_debug_unit: !
8770!
8780 ASSIGN @Path TO "UNITFILE:HP9134,701"
8790 FOR I=1 TO Nm_units
8800     ENTER @Path.Unit_id(I);Unit_info(*)
8810     PRINT
8820     PRINT "UNITFILE RECORD";Unit_id(I),Unit_info(*)
8830 NEXT I
8840 ASSIGN @Path TO *
8850 !
8860 FOR I=1 TO Nm_units
8870     FOR J=1 TO 150
8880         Unit_info(J)=Unit_store_5_15(I,J)
8890     NEXT J
8900     PRINT
8910     PRINT "UNIT_5_150 RECORD";Unit_id(I),Unit_info(*)
8920 NEXT I
8930 !
8940 FOR I=1 TO Nm_units_played
8950     FOR J=1 TO 150
8960         Unit_info(J)=Unitstore_20_15(I,J)
8970     NEXT J
8980     PRINT
8990     PRINT "UNIT_20_150 RECORD";Unit_id_20_150(I),Unit_info(*)
9000 NEXT I
9010 !
9020 RETURN
9030!
9040!*****
9050!
9060 List_results:!
9070!
9080 PRINT

```

Table 5-3. Air attack/Air defense code.

```

9090 PRINT
9100 PRINT USING Fmt1r1:Frc_clr$:" AIR CURRENT RESULTS"
9110 PRINT USING Fmt1r2:"TYPE (1-4)"
9120 PRINT USING Fmt1r3:"TOTAL AIRCRAFT INGRESS FLIGHTS".Nm_ac_flt_ing(*)
9130 PRINT USING Fmt1r3:"TOTAL AIRCRAFT EGRESS FLIGHTS".Nm_ac_flt_egr(*)
9140 PRINT USING Fmt1r3:"TOTAL AIRCRAFT STRIKES ".Nm_ac_flt_stk(*)
9150 PRINT USING Fmt1r3:"TOTAL AIRCRAFT INGRESS LOSSES ".Nm_ac_lost_ing(*)
9160 PRINT USING Fmt1r3:"TOTAL AIRCRAFT EGRESS LOSSES ".Nm_ac_lost_egr(*)
9170 PRINT USING Fmt1r3:"TOTAL AIRCRAFT STRIKE LOSSES ".Nm_ac_lost_stk(*)
9180 PRINT USING Fmt1r3:"TOTAL AIRCRAFT LOST TO ADA ".Nm_ac_lost_ada(*)
9190 PRINT USING Fmt1r3:"AIRCRAFT AVAILABLE FOR COMBAT ".Nm_ac_avl_stk(*)
9200 PRINT USING Fmt1r3:"AIRCRAFT AVAILABLE FOR EGRESS ".Nm_ac_avl_egr(*)
9210 PRINT USING Fmt1r4:"TYPE ( 1-70, POL, AMMO)"
9220 PRINT USING Fmt1r5:"TOTAL TARGET ELEMENT LOSSES ".Nm_eltm_lost_ac(*)
9230 PRINT USING Fmt1r2:"UNIT_ID"
9240 PRINT USING Fmt1r6:"UNITS REMAINING FOR UPDATE ".Unit_id_20_150(*)
9250 !
9260 Fmt1r1:IMAGE 20X,4A,25A
9270 Fmt1r2:IMAGE /,42X,10A,/
9280 Fmt1r3:IMAGE 30A,4(2X,4D.1D)
9290 Fmt1r4:IMAGE /,34X,24A,/
9300 Fmt1r5:IMAGE 30A,1(4(2X,6D.1D),/),17(30X,4(2X,6D.1D),/)
9310 Fmt1r6:IMAGE 30A,1(4(3X,3D),/),5(30X,4(3X,3D),/)
9320 !
9330 RETURN
9340 !
9350 !*****
9360 !
9370 List_totals:
9380 !
9390 File$=Status_clr$&"_AIR_INF"
9400 ASSIGN @Path TO File$&":HP9134,701"
9410 ENTER @Path.1:Tl_ac_flt_ing(*),Tl_ac_flt_egr(*),Tl_ac_flt_stk(*),Tl_ac_lost_ing(*),Tl_ac_lost_egr(*),Tl_ac_lost_stk(*),Tl_ac_lost_ada(*),Tl_eltm_ac(*)
9420 ASSIGN @Path TO *
9430 !
9440 PRINT
9450 PRINT
9460 PRINT USING Fmt1t1:Status_frc_clr$:" AIR ACCUMULATIVE RESULTS"
9470 PRINT USING Fmt1t2:"TYPE (1-4)"
9480 PRINT USING Fmt1t3:"TOTAL AIRCRAFT INGRESS FLIGHTS".Tl_ac_flt_ing(*)
9490 PRINT USING Fmt1t3:"TOTAL AIRCRAFT EGRESS FLIGHTS".Tl_ac_flt_egr(*)
9500 PRINT USING Fmt1t3:"TOTAL AIRCRAFT STRIKES ".Tl_ac_flt_stk(*)
9510 PRINT USING Fmt1t3:"TOTAL AIRCRAFT INGRESS LOSSES ".Tl_ac_lost_ing(*)
9520 PRINT USING Fmt1t3:"TOTAL AIRCRAFT EGRESS LOSSES ".Tl_ac_lost_egr(*)
9530 PRINT USING Fmt1t3:"TOTAL AIRCRAFT STRIKE LOSSES ".Tl_ac_lost_stk(*)
9540 PRINT USING Fmt1t3:"TOTAL AIRCRAFT LOST TO ADA ".Tl_ac_lost_ada(*)
9550 PRINT USING Fmt1t4:"TYPE ( 1-70, AMMO, POL)"
9560 PRINT USING Fmt1t5:"TOTAL TARGET ELEMENT LOSSES ".Tl_eltm_ac(*)
9570 !
9580 Fmt1t1:IMAGE 20X,4A,25A
9590 Fmt1t2:IMAGE /,42X,10A,/

```

Table 5-3. Air attack/Air defense code.

```

9600 Fmt1t3: IMAGE 30A,4(2X,3D.1D)
9610 Fmt1t4: IMAGE /,34X,24A,/
9620 Fmt1t5: IMAGE 30A,1(4(2X,3D.1D),/),17(30X,4(2X,3D.1D),/)
9630 !
9640 RETURN
9650!
9660! *****
9670!
9680 Menu_selection: !
9690!
9700 PRINT USING "///"
9710 PRINT "DIME AIR DEFENSE/AIR ATTACK MENU:  SELECT OPTION"
9720 PRINT "      (1) ";Frc_clr$;" AIR INGRESS"
9730 PRINT "      (2) ";Frc_clr$;" AIR EGRESS"
9740 PRINT "      (3) ";Frc_clr$;" AIR STRIKE"
9750 PRINT "      (4) STATUS REPORT"
9760 PRINT "      (5) UPDATE RESULTS"
9770 PRINT "      (6) EXIT AIR DEFENSE MODULE"
9780 INPUT Menu_optn
9790 !
9800 SELECT Menu_optn
9810 CASE 1
9820     PRINTER IS 702
9830     PRINT USING "@"
9840     PRINTER IS 1
9850     Option$="INGRESS"
9860     Flight$="INGRESS"
9870 CASE 2
9880     PRINTER IS 702
9890     PRINT USING "@"
9900     PRINTER IS 1
9910     Option$="EGRESS"
9920     Flight$="EGRESS"
9930 CASE 3
9940     PRINTER IS 702
9950     PRINT USING "@"
9960     PRINTER IS 1
9970     Option$="STRIKE"
9980     Flight$="STRIKE"
9990 CASE 4
10000     Option$="STATUS"
10010 CASE 5
10020     Option$="UPDATE"
10030 CASE 6
10040     Option$="EXIT"
10050 CASE ELSE
10060     Option$="ERROR"
10070 END SELECT
10080 !
10090 RETURN
10100!
10110! *****
*
```

Table 5-3. Air attack/Air defense code.

```

10120!
10130 Select_ada_info:!
10140!
10150 FOR X=1 TO 7
10160   Nm_ada_wpn(X)=Unit(X+47)
10170 NEXT X
10180 !
10190 Tl_ada_tons_frd=0
10200 Ada_tons_avl=Unit(133)
10210 CALL Check_var("UNIT(80)",Unit(80),0.,100.100)
10220 Ada_suprsn_pct=Unit(80)
10230 CALL Check_var("UNIT(75)",Unit(75),1,4)
10240 Unit_posture=Unit(75)
10250 CALL Check_var("UNIT(78)",Unit(78),1,0.2,9)
10260 Unit_clr_type=Unit(78)
10270 !
10280 !UNPACK UNIT TYPE AND COLOR
10290 Clr=INT(Unit_clr_type)
10300 Unit_type=Unit_clr_type-Clr
10310 Unit_type=Unit_type*10+1
10320 !
10330 !RESET DETECTION STATUS
10340 Unit(91)=3.2
10350 IF Unit(92)<=3 THEN
10360   Unit(92)=3
10370 END IF
10380 !
10390 RETURN
10400!
10410!*****:
*
10420!
10430 Select_prmtrs:!
10440!
10450 IF Frc_clr$="BLUE" THEN
10460   SELECT Ac_type
10470   CASE 1
10480     Acprint$="A10"
10490     Aircraft$="A10"
10500   CASE 2
10510     Acprint$="F16"
10520     Aircraft$="F16"
10530   CASE 3
10540     Acprint$="AH-1"
10550     Aircraft$="AH64"
10560   CASE 4
10570     Acprint$="OH58"
10580     Aircraft$="OH58"
10590   END SELECT
10600 ELSE
10610   SELECT Ac_type
10620   CASE 1

```

Table 5-3. Air attack/Air defense code.

```

10630     Acprint$="SU25"
10640     Aircraft$="M28"
10650     CASE 2
10660     Acprint$="MI27"
10670     Aircraft$="M27"
10680     CASE 3
10690     Acprint$="HIND"
10700     Aircraft$="HIND"
10710     CASE 4
10720     Acprint$="HIP"
10730     Aircraft$="HIP"
10740     END SELECT
10750     END IF
10760     !
10770     SELECT Flight$
10780     CASE "INGRESS"
10790     Flt$="ING"
10800     CASE "EGRESS"
10810     Flt$="EGR"
10820     CASE "STRIKE"
10830     SELECT Ac_mission
10840     CASE 1
10850     Flt$="BRG"
10860     CASE 2
10870     Flt$="ARMOR"
10880     CASE 3
10890     Flt$="PRSNL"
10900     CASE 4
10910     Flt$="POL"
10920     CASE 5
10930     Flt$="AMMO"
10940     END SELECT
10950     END SELECT
10960     !
10970     SELECT Tgt_posture
10980     CASE 1
10990     Activity$=" ATTACK"
11000     CASE 2
11010     Activity$=" DEFEND"
11020     CASE 3
11030     Activity$="RESERVE"
11040     CASE 4
11050     Activity$=" MOVE"
11060     END SELECT
11070     !
11080     SELECT Tgt_type
11090     CASE 0
11100     Tgt_type$=" COMBAT"
11110     CASE 1
11120     Tgt_type$=" ARTY"
11130     CASE 2
11140     Tgt_type$=" ADA"

```

Table 5-3. Air attack/Air defense code.

```

11150 CASE 3
11160   Tgt_type$="   FARP"
11170 CASE 4
11180   Tgt_type$="   CP/HQ"
11190 CASE 5
11200   Tgt_type$="   ENGR"
11210 CASE 6
11220   Tgt_type$="POL/AMMO"
11230 CASE 7
11240   Tgt_type$="   MAINT"
11250 CASE 8
11260   Tgt_type$="   BRIDGE"
11270 CASE 9
11280   Tgt_type$="COMMD/EW"
11290 END SELECT
11300!
11310 RETURN
11320!
11330!*****
*
11340!
11350 Select_stk_info: !
11360!
11370 Nm_vehicles=0
11380 Nm_infantry=0
11390 FOR I=1 TO Nm_units
11400   FOR J=1 TO 70
11410     Nm_elmt_tgt(J)=Nm_elmt_tgt(J)+Unit_store_5_15(I,J)*Tgt_expsr_frc(I)
11420   NEXT J
11430   Nm_elmt_tgt(71)=Nm_elmt_tgt(71)+Unit_store_5_15(I,105)*Tgt_expsr_frc(I)
11440   Nm_elmt_tgt(72)=Nm_elmt_tgt(72)+Unit_store_5_15(I,125)*Tgt_expsr_frc(I)
11450   Tl_ada_tons=Tl_ada_tons+Unit_store_5_15(I,133)*Tgt_expsr_frc(I)
11460   !
11470   Suprsn_frc_1=INT(Unit_store_5_15(I,80))
11480   Suprsn_frc_2=Unit_store_5_15(I,80)-Suprsn_frc_1
11490   Suprsn_frc_1=Suprsn_frc_1/100
11500   Tl_suprsn_1=Tl_suprsn_1+Suprsn_frc_1
11510   Tl_suprsn_2=Tl_suprsn_2+Suprsn_frc_2
11520 NEXT I
11530 !
11540 Tl_suprsn_1=Tl_suprsn_1/FNMax(Nm_units,.0000001)
11550 Tl_suprsn_2=Tl_suprsn_2/FNMax(Nm_units,.0000001)
11560 Ada_suprsn_pct=100*Tl_suprsn_1+Tl_suprsn_2
11570 !
11580 SELECT Tgt_posture
11590 CASE 1,4
11600   FOR J=36 TO 40
11610     Nm_infantry=Nm_elmt_tgt(J)+Nm_infantry
11620   NEXT J
11630   FOR J=16 TO 20
11640     Nm_vehicles=Nm_elmt_tgt(J)+Nm_vehicles
11650   NEXT J

```


Table 5-3. Air attack/Air defense code.

```

11660 FOR J=1 TO 5
11670   Inf=J+35
11680   Frac_inf(J)=Nm_elmt_tgt(Inf)/FNMax(Nm_infantry,1)
11690 NEXT J
11700 Mount_ratio=Nm_infantry/FNMax(Nm_vehicles,1)
11710 Mount_ratio=FNMin(Mount_ratio,8)
11720 FOR J=1 TO 5
11730   Inf=J+35
11740   Nm_elmt_tgt(Inf)=FNMax(Nm_infantry-Nm_vehicles*Mount_ratio,0)*Frac_inf
(J)
11750 NEXT J
11760 END SELECT
11770 !
11780 FOR X=1 TO 7
11790   Nm_ada_wpn(X)=Nm_elmt_tgt(X+47)
11800 NEXT X
11810 Ada_tons_avl=Tl_ada_tons
11820 !
11830 FOR I=1 TO 72
11840   Nm_elmt_left(I)=Nm_elmt_tgt(I)
11850 NEXT I
11860'
11870'*****
*
11880'
11890 Select_units:'
11900'
11910 FOR I=1 TO Nm_units
11920   Unit_id_ptr=0
11930   Cnt=0
11940   REPEAT
11950     Cnt=Cnt+1
11960     IF Unit_id_20_150(Cnt)=Unit_id(I) THEN
11970       Unit_id_ptr=Cnt
11980       FOR J=1 TO 150
11990         Unit_store_5_15(I,J)=Unitstore_20_15(Cnt,J)
12000       NEXT J
12010     END IF
12020   UNTIL Cnt>=Nm_units_played OR Unit_id_20_150(I)=Unit_id(I)
12030   !
12040   IF Unit_id_ptr=0 THEN
12050     ASSIGN @Path TO "UNITFILE:HP9134,701"
12060     ENTER @Path,Unit_id(I);Unit_info(*)
12070     ASSIGN @Path TO *
12080     FOR J=1 TO 150
12090       Unit_store_5_15(I,J)=Unit_info(J)
12100     NEXT J
12110   END IF
12120 NEXT I
12130 !
12140 FOR I=Nm_units+1 TO 5
12150   FOR J=1 TO 150

```

Table 5-3. Air attack/Air defense code.

```

12160     Unit_store_5_15(1,J)=0
12170     NEXT J
12180     NEXT I
12190     !
12200     RETURN
12210     !
12220     !*****
*
12230     !
12240     Status_report:!
12250     !
12260     Nm_option=0
12270     WHILE Nm_option<>7
12280         PRINT
12290         PRINT "STATUS REPORT MENU:  SELECT OPTION"
12300         PRINT "      (1) LIST CURRENT RESULTS"
12310         PRINT "      (2) LIST BLUE AIR ACCUMULATIVE RESULTS"
12320         PRINT "      (3) LIST RED AIR ACCUMULATIVE RESULTS"
12330         PRINT "      (4) LIST DEBUG UNIT INFORMATION"
12340         PRINT "      (5) LIST DEBUG FLIGHT INFORMATION"
12350         PRINT "      (6) LIST DEBUG STRIKE INFORMATION"
12360         PRINT "      (7) EXIT"
12370         INPUT Nm_option
12380         !
12390         SELECT Nm_option
12400         CASE 1,2,3,4,5,6
12410             REPEAT
12420                 PRINT
12430                 PRINT "DISPLAY RESULTS ON PRINTER OR SCREEN? (P/S)"
12440                 INPUT Answer$
12450                 UNTIL Answer$="P" OR Answer$="S"
12460                 IF Answer$="P" THEN
12470                     PRINTER IS 702
12480                     PRINT USING "@"
12490                 END IF
12500             END SELECT
12510             !
12520             SELECT Nm_option
12530             CASE 1
12540                 GOSUB List_results
12550             CASE 2
12560                 Status_clr$="BL"
12570                 Status_frc_clr$="BLUE"
12580                 GOSUB List_totals
12590             CASE 3
12600                 Status_clr$="RD"
12610                 Status_frc_clr$="RED"
12620                 GOSUB List_totals
12630             CASE 4
12640                 GOSUB List_debug_unit
12650             CASE 5
12660                 GOSUB List_debugflt

```

Table 5-3. Air attack/Air defense code.

```

12670 CASE 6
12680 GOSUB List_debug_stk
12690 CASE 7
12700 CASE ELSE
12710 BEEP
12720 END SELECT
12730 PRINTER IS 1
12740 END WHILE
12750 !
12760 RETURN
12770 !
12780 !*****
*
12790 !
12800 Store_results: !
12810 !
12820 FOR I=1 TO Nm_units
12830 Unit_id_ptr=0
12840 Cnt=0
12850 REPEAT
12860 Cnt=Cnt+1
12870 IF Unit_id_20_150(Cnt)=Unit_id(I) THEN
12880 Unit_id_ptr=Cnt
12890 FOR J=1 TO 150
12900 Unitstore_20_15(Cnt,J)=Unit_store_5_15(I,J)
12910 NEXT J
12920 END IF
12930 UNTIL Cnt>=Nm_units_played OR Unit_id_20_150(Cnt)=Unit_id(I)
12940 !
12950 IF Unit_id_ptr=0 AND Nm_units_played<20 THEN
12960 Nm_units_played=Nm_units_played+1
12970 Cnt=Nm_units_played
12980 FOR J=1 TO 150
12990 Unitstore_20_15(Cnt,J)=Unit_store_5_15(I,J)
13000 NEXT J
13010 Unit_id_20_150(Cnt)=Unit_id(I)
13020 END IF
13030 NEXT I
13040 !
13050 RETURN
13060 !
13070 !*****
*
13080 !
13090 Strike_aportion: !
13100 !
13110 Mount_loss_tot=0
13120 !LOOP TO APPORTION INFANTRY LOSSES
13130 FOR I=1 TO Nm_units
13140 Mount_losses=0
13150 !TAKE INFANTRY ON GROUND OUT FIRST
13160 FOR J=1 TO 5

```

Table 5-3. Air attack/Air defense code.

```

13170     Inf=J+35
13180     Frct=Unit_store_5_15(I,Inf)*Tgt_expsr_frc(I)/FNMax:(Nm_vehicles*Mount_
atio*Frac_inf(J)+Nm_elmt_tgt(Inf),.0000001) !RESTORE DENOMINATOR TO REPRESENT
13190     ! INFANTRY BEFORE MOUNTING
13200     Unit_store_5_15(I,Inf)=Unit_store_5_15(I,Inf)-Frct*Nm_elmt_lost_f1(Ir
)
13210     NEXT J
13220     !NOW REMOVE PERSONNEL LOSSES FROM VEHICLES
13230     SELECT Tgt_posture
13240     CASE 1,4
13250         Perrsnl=0
13260         FOR J=16 TO 20
13270             Frct=Unit_store_5_15(I,J)*Tgt_expsr_frc(I)/FNMax:(Nm_elmt_tgt(J),.00
0001)
13280             V_lost_unit=Frct*Nm_elmt_lost_f1(J)
13290             Perrsnl=V_lost_unit*Mount_ratio+Perrsnl
13300         NEXT J
13310         Tot_uni_inf=0
13320         FOR J=36 TO 40
13330             Tot_uni_inf=Tot_uni_inf+Unit_store_5_15(I,J)
13340         NEXT J
13350         Perrsnl=FNMin(Tot_uni_inf,Perrsnl)
13360         Mount_losses=Mount_losses+Perrsnl
13370         FOR J=1 TO 5
13380             Inf=J+35
13390             Unit_store_5_15(I,Inf)=Unit_store_5_15(I,Inf)-Perrsnl*Frac_inf(J)
13400         NEXT J
13410     END SELECT
13420     Mount_loss_tot=Mount_loss_tot+Mount_losses
13430     NEXT I
13440     FOR J=1 TO 5
13450         Inf=J+35
13460         Nm_elmt_lost_f1(Inf)=Nm_elmt_lost_f1(Inf)+Mount_loss_tot*Frac_inf(J)
13470     NEXT J
13480     FOR I=1 TO Nm_units
13490         FOR J=1 TO 70
13500             Frct=Unit_store_5_15(I,J)*Tgt_expsr_frc(I)/FNMax:(Nm_elmt_tgt(J),.00000
01)
13510             IF J>35 AND J<41 THEN 13530
13520             Unit_store_5_15(I,J)=Unit_store_5_15(I,J)-Frct*Nm_elmt_lost_f1(J)
13530         NEXT J
13540         Frct=Unit_store_5_15(I,105)*Tgt_expsr_frc(I)/FNMax:(Nm_elmt_tgt(71),.0000
001)
13550         Unit_store_5_15(I,105)=Unit_store_5_15(I,105)-Frct*Nm_elmt_lost_f1(71)
13560         !
13570         Frct=Unit_store_5_15(I,125)*Tgt_expsr_frc(I)/FNMax:(Nm_elmt_tgt(72),.0000
001)
13580         Unit_store_5_15(I,125)=Unit_store_5_15(I,125)-Frct*Nm_elmt_lost_f1(72)
13590         !
13600         Frct=Unit_store_5_15(I,133)*Tgt_expsr_frc(I)/FNMax:(Tl_ada_tons,.0000001)
13610         Unit_store_5_15(I,133)=Unit_store_5_15(I,133)-Frct*Tl_ada_tons_frd
13620         !

```

Table 5-3. Air attack/Air defense code.

```

13630 Unit_store_5_15(I,141)=Unit_store_5_15(I,141)+Frct*Tl_ada_tons_frd
13640 Unit_store_5_15(I,91)=3.2
13650 IF Unit_store_5_15(I,92)<=3 THEN
13660     Unit_store_5_15(I,92)=3
13670 END IF
13680 NEXT I
13690 !
13700 RETURN
13710 !
13720 !*****
*
13730 !
13740 Strike_atrition:!
13750 !
13760 Break_point=Nm_ac_input*Ac_brkpt_frc
13770 Ac_load=0
13780 Tl_ac_passes=0
13790 R4=0
13800 REPEAT
13810     Ac_load=Ac_load+1
13820     Ac_pass=0
13830     GOSUB Strike_profile
13840     GOSUB Strike_info
13850     PRINT
13860     REPEAT
13870         Ac_pass=Ac_pass+1
13880         Tl_ac_passes=Tl_ac_passes+1
13890         T_sub_pass=0
13900         Nm_ac_left1=Nm_ac_left
13910         IF Nm_ac_left<.1 THEN Strk_apport
13920         Tac_lost_pass=0
13930         GOSUB Calc_sub_pass
13940         REPEAT
13950             T_sub_pass=T_sub_pass+1
13960             GOSUB Calc_ada_suprsn
13970             ! SET PLOS FOR ADA HAND HELD ROUNDS
13980             Plos=T_plos(Terr(1))
13990             GOSUB Calc_ada_rnds
14000             GOSUB Calc_ac_losses
14010             !
14020             !
14030             SELECT Wpn_load_code
14040             CASE 1
14050                 GOSUB Calc_area_loss
14060             CASE 2,3
14070                 GOSUB Calc_point_loss
14080             CASE ELSE
14090                 BEEP
14100                 PRINT "**ERROR: IN WPN_LOAD_CODE FOR ";File$&Disk$
14110             END SELECT
14120             Tac_lost_pass=Tac_lost_pass+Nm_psa_ac_lost
14130             UNTIL T_sub_pass>=Nm_sub_pass OR Nm_ac_lostflt>=Break_point OR (Nm_ac
_left1-Tac_lost_pass)<.1

```

Table 5-3. Air attack/Air defense code.

```

14140     Nm_ac_left=FNMax(0,Nm_ac_left1-Tac_lost_pass)
14150     Nm_psa_ac_lost=FNMin(Nm_ac_left1,Tac_lost_pass)
14160     !
14170     PRINT USING Fmt_sal;"DELIVERY PROFILE:   ";File$;"  PASS ";Ac_pass:"
:Acprint$;"  LOST ";Nm_psa_ac_lost
14180     PRINTER IS 702
14190     !PRINT
14200     PRINT USING Fmt_sal;"DELIVERY PROFILE:   ";File$;"  PASS ";Ac_pass:"
:Acprint$;"  LOST ";Nm_psa_ac_lost
14210     IF Brgg=0 THEN GOTO 14300
14220     !IF Brgg=1 THEN GOTO 14270
14230     !IF Brgg=2 THEN GOTO 14250
14240     IF Destroy=1 THEN
14250         !PRINT "BRIDGE DESTROYED"!  THE SEED IS",R3
14260         Destroy=2
14270     ELSE
14280         !PRINT "BRIDGE NOT DESTROYED"!  THE SEED IS",R3
14290     END IF
14300     PRINTER IS 1
14310     UNTIL Ac_pass>=Nm_ac_passes OR Nm_ac_lost_flt>=Break_point OF Nm_ac_le+
<.1
14320 UNTIL Ac_load>=Nm_wpn_loads OR Nm_ac_lost_flt>=Break_point OR Nm_ac_left
1
14330 Strk_apport:  !
14340 GOSUB Strike_aportion
14350     !
14360 IF Nm_ac_lost_flt>Break_point AND Ac_load<Nm_wpn_loads THEN
14370     PRINTER IS 702
14380     PRINT
14390     PRINT Frc_clr$;" ATTACK DISCONTINUED DUE TO EXCESSIVE ";Acprint$;" LOSS
S "
14400     PRINTER IS 1
14410 END IF
14420     !
14430 Fmt_sal:IMAGE 20A,9A,7A,3D,10X,1A,5A,7A,5D.D
14440 RETURN
14450!
14460!*****
*
14470!
14480 Strike_data:!
14490!
14500 GOSUB Strike_init
14510 GOSUB Select_prmtrs
14520 GOSUB Select_units
14530 GOSUB Select_stk_info
14540     !
14550 File$=Aircraft$&" "&Flt$
14560 ON ERROR GOSUB File_error_2
14570 ASSIGN @Path TO File$&Disk$
14580 OFF ERROR
14590 PRINTER IS 702

```

Table 5-3. Air attack/Air defense code.

```

14600 GOSUB Strike_output
14610 PRINTER IS 1
14620 ENTER @Path,1:Nm_wpn_loads,Wpn_ld_template$(*)
14630 ASSIGN @Path TO *
14640 !
14650 File$=Clr$& "_UN_AREA"
14660 ASSIGN @Path TO File$&&Disk$
14670 ENTER @Path,1:Unit_type_area(*)
14680 ASSIGN @Path TO *
14690 !
14700 File$=Clr$& "_AC_TGWT"
14710 ASSIGN @Path TO File$&&Disk$
14720 ENTER @Path,1:Ac_ms_tgt_wts(*)
14730 ASSIGN @Path TO *
14740 !
14750 RETURN
14760!
14770! *****
*
14780!
14790 Strike_info: '
14800!
14810 IF Wpn_load_code>=2 THEN
14820   Divisor=FNMax(Ac_pdtc_prn_tgt(Tgt_posture),.0000001)
14830   Nm_ac_passes=FNMin(Min_ac_passes/Divisor,1.3*Min_ac_passes)
14840   Nm_ac_passes=INT(Nm_ac_passes+.5)
14850   !
14860   IF Tgt_posture<=2 THEN
14870     Ac_tgt_pk(7)=Ac_tgt_pk(7)*Prsnl_fxhl_frc
14880     FOR X=36 TO 47
14890       Ac_tgt_pk(X)=Ac_tgt_pk(X)*Prsnl_fxhl_frc
14900     NEXT X
14910     Ac_tgt_pk(53)=Ac_tgt_pk(53)*Prsnl_fxhl_frc
14920     Ac_tgt_pk(54)=Ac_tgt_pk(54)*Prsnl_fxhl_frc
14930     IF Frc_clr$="BLUE" THEN
14940       Ac_tgt_pk(8)=Ac_tgt_pk(8)*Prsnl_fxhl_frc
14950       FOR X=28 TO 31
14960         Ac_tgt_pk(X)=Ac_tgt_pk(X)*Prsnl_fxhl_frc
14970       NEXT X
14980     END IF
14990   END IF
15000 ELSE
15010   Nm_ac_passes=Min_ac_passes
15020 END IF
15030 '
15040 RETURN
15050!
15060! *****
15070!
15080 Strike_init: '
15090!
15100 Ac_brkpt_frc=Ac_brkpt_pct/100

```

Table 5-3. Air attack/Air defense code.

```

15110 Tgt_frc_open=Tgt_pct_open/100
15120 Tgt_frc_woods=1-Tgt_frc_open
15130 Altitude_meters=500
15140 Nm_ac_left=Nm_ac_input
15150 Unit_type=Tgt_type+1
15160 Unit_posture=Tgt_posture
15170 FOR I=1 TO Nm_units
15180   Tgt_expsr_frc(I)=Tgt_expsr_pct(I)/100
15190 NEXT I
15200   !
15210 Tl_ada_tons=0
15220 Tl_ada_tons_frd=0
15230 Nm_ac_lost_flt=0
15240 Tl_suprsn_1=0
15250 Tl_suprsn_2=0
15260 FOR I=1 TO 72
15270   Nm_elmt_lost_f1(I)=0
15280   Nm_elmt_tgt(I)=0
15290 NEXT I
15300   !
15310 RETURN
15320 !
15330 !*****!
15340 !
15350 Strike_input: !
15360 !
15370 Destroy=0
15380 PRINT
15390 PRINT
15400 PRINT "   INPUT THE FOLLOWING INFORMATION FOR A ";Frc_clr$;" AIR STRIKE"
15410 PRINT
15420 PRINT USING Fmtsi;"TOTAL A/C AVAILABLE FOR COMBAT:";Nm_ac_avl_stk(*)
15430 PRINT
15440 PRINT "ENTER: # OF A/C, A/C TYPE, A/C MISSION, A/C BREAKPOINT, TGT % IN OF
EN"
15450 INPUT Nm_ac_input,Ac_type,Ac_mission,Ac_brkpt_pct,Tgt_pct_open
15460 !IF Ac_mission=1 THEN INPUT "WHAT IS THE SEED",R3
15470 CALL Check_var("A/C TYPE",Ac_type,1,4)
15480 CALL Check_var("AC MISSION",Ac_mission,1,5)
15490 CALL Check_var("A/C BREAKPOINT %",Ac_brkpt_pct,0,100)
15500 CALL Check_var("TGT % IN OPEN",Tgt_pct_open,0,100)
15510   !
15520 PRINT
15530 PRINT "ENTER: TYPE OF STRIKE -- CAS OR BAI (INPUT 1 OR 2)"
15540 INPUT Cas_bai
15550 CALL Check_var("TYPE OF STRIKE (CAS OR BAI)",Cas_bai,1,2)
15560 PRINT
15570 PRINT "ENTER: EXPECTED DENSITY OF AD -- HIGH OR LOW (INPUT 1 OR 2)"
15580 INPUT High_low
15590 CALL Check_var("EXPECTED DENSITY OF AD",High_low,1,2)
15600   !
15610 PRINT

```


Table 5-3. Air attack/Air defense code.

```

15620 PRINT "ENTER: TGT LENGTH, TGT WIDTH, TGT POSTURE, TGT TYFE. # OF TGT UNITS"
15630 INPUT Tgt_length,Tgt_width,Tgt_posture,Tgt_type,Nm_units
15640 CALL Check_var("TGT FOSTURE",Tgt_posture,1,4)
15650 CALL Check_var("TGT TYPE",Tgt_type,0,9)
15660 CALL Unit_read(Frc_clr$,Nm_units,Unit_id(*),Terr(*))
15670 !
15680 IF Nm_units>0 THEN
15690 PRINT
15700 PRINT "ENTER: PERCENT OF UNIT IN TARGET AREA FOR EACH UNIT_ID"
15710 INPUT Tgt_expsr_pct(*)
15720 FOR I=1 TO Nm_units
15730 CALL Check_var("% TARGETED",Tgt_expsr_pct(I),0,100)
15740 NEXT I
15750 END IF
15760 !
15770 IF Ac_mission=1 AND Tgt_type=8 THEN INPUT "ENTER RANDOM NUMBER".RS
15780 FOR I=Nm_units+1 TO 5
15790 Tgt_expsr_pct(I)=0
15800 NEXT I
15810 !
15820 Fmtsi:IMAGE 31A,2X,4(3D,D,2X)
15830 RETURN
15840 !
15850 !*****
*
15860 !
15870 Strike_output:!
15880 !
15890 GOSUB Select_prmtrs
15900 !
15910 PRINT USING "///"
15920 PRINT "THE FOLLOWING ARE THE INPUTS SELECTED FOR THE ":Frc_clr$:" AIR STR
KE:"
15930 PRINT
15940 PRINT " # OF A/C, A/C TYPE, A/C MISSION, A/C BREAKPOINT, TGT % IN OPEN"
15950 PRINT USING Fmtt01;Nm_ac_input,Acprint$,Flt$,Ac_brkpt_pct,Tgt_pct_open
15960 !
15970 PRINT
15980 SELECT Cas_bai
15990 CASE 1
16000 PRINT "Aircraft performing CAS."
16010 CASE 2
16020 PRINT "Aircraft performing BAI."
16030 END SELECT
16040 PRINT
16050 SELECT High_low
16060 CASE 1
16070 PRINT "In a perceived high-density AD environment."
16080 CASE 2
16090 PRINT "In a perceived low-density AD environment."
16100 END SELECT

```

Table 5-3. Air attack/Air defense code.

```

16110 !
16120 PRINT
16130 PRINT "TGT LENGTH, TGT WIDTH, TGT ACTIVITY, TGT TYPE, # OF TGT UNITS"
16140 PRINT USING Fmtto2;Tgt_length,"m",Tgt_width,"m",Activity$.Tgt_type$.Nm_un
ts
16150 PRINT
16160 PRINT USING Fmtto3;"TARGET UNIT-ID'S CHOSEN:",Unit_id(*)
16170 PRINT USING Fmtto3;" TERRAIN:",Terr(*)
16180 PRINT
16190 PRINT USING Fmtto3;"PERCENT OF UNIT TARGETED:",Tgt_expsr_pct(*)
16200 !
16210 PRINT
16220 Fmtto1:IMAGE 7D,5X,5A, 7X,6A,13X,3D,12X,3D
16230 Fmtto2:IMAGE 9D,1A,10D,1A,7X,7A,2X,8A,14X,2D
16240 Fmtto3:IMAGE 25A,5(2X,3D)
16250 !
16260 RETURN
16270!
16280!*****
*
16290!
16300 Strike_profile: !
16310!
16320 File$=Wpn_ld_template$(Ac_load)
16330 ON ERROR GOSUB File_error_1
16340 ASSIGN @Path TO File$&&Disk$
16350 OFF ERROR
16360 ENTER @Path,1;Stk_profile(*)
16370 ASSIGN @Path TO *
16380 !
16390 Wpn_load_code=Stk_profile(1)
16400 Ac_area_prn_tgt=Stk_profile(2)
16410 Min_ac_passes=Stk_profile(3)
16420 Nm_ac_rnds_eng=Stk_profile(4)
16430 Nm_ac_rnd_bs_ld=Stk_profile(5)
16440 Prn_tgt_wds_frc=Stk_profile(160)
16450 Prsnl_fxhl_frc=Stk_profile(161)
16460 FOR I=1 TO 4
16470 Ac_pdtc_prn_tgt(I)=Stk_profile(5+I)
16480 Ac_plos_prn_tgt(I)=Stk_profile(9+I)
16490 NEXT I
16500 FOR I=1 TO 7
16510 Min_ada_alt(I)=Stk_profile(161+I)
16520 Max_ada_alt(I)=Stk_profile(168+I)
16530 Ada_range(I)=Stk_profile(175+I)
16540 Ada_prtcptn(I)=Stk_profile(182+I)
16550 Ada_rnd_bs_ld(I)=Stk_profile(189+I)
16560 Ada_rnd_wt(I)=Stk_profile(196+I)
16570 Ada_rnd_frd_eng(I)=Stk_profile(203+I)
16580 Ada_psa_ac(I)=Stk_profile(210+I)
16590 Ada_psk_ac(I)=Stk_profile(217+I)
16600 NEXT I

```

Table 5-3. Air attack/Air defense code.

```

16610 FOR I=1 TO 72
16620   Ac_tgt_pk(I)=Stk_profile(13+I)
16630   Ac_tgt_area(I)=Stk_profile(86+I)
16640 NEXT I
16650   !
16660 RETURN
16670!
16680!*****
16690!
16700 Update_results:!
16710!
16720 REPEAT
16730   PRINT
16740   PRINT "UPDATE MENU:  SELECT OPTION"
16750   PRINT "      (1)  UPDATE CURRENT RESULTS"
16760   PRINT "      (2)  PURGE CURRENT RESULTS"
16770   PRINT "      (3)  EXIT"
16780   INPUT Nm_option
16790 UNTIL Nm_option=1 OR Nm_option=2 OR Nm_option=3
16800   !
16810 IF Nm_option=1 THEN
16820   GOSUB Cumulate_totals
16830   GOSUB Update_storage
16840 END IF
16850 IF Nm_option<>3 THEN
16860   GOSUB Init_totals
16870 END IF
16880   !
16890 RETURN
16900!
16910!*****
*
16920!
16930 Update_storage:!
16940!
16950 ASSIGN @Path TO " UNITFILE:HP9134,701"
16960 Cnt=0
16970 REPEAT
16980   Cnt=Cnt+1
16990   FOR I=1 TO 150
17000     Unit_info(I)=Unitstore_20_15(Cnt,I)
17010   NEXT I
17020   OUTPUT @Path,Unit_id_20_150(Cnt);Unit_info(*)
17030 UNTIL Cnt>=Nm_units_played
17040 ASSIGN @Path TO *
17050 PRINT
17060 PRINT "UPDATE COMPLETED"
17070   !
17080 RETURN
17090!
17100!*****
*

```

Table 5-3. Air attack/Air defense code.

```

17110!
17120 END
17130!
17140! *****
*
17150!
17160 SUB Check_var (Var_name$,Variable,Min_value,Max_value)
17170!
17180     WHILE Variable<Min_value OR Variable>Max_value
17190         BEEP
17200         PRINT
17210         PRINT "** ERROR: ";Variable;" IS INVALID FOR ";Var_name$
17220         PRINT "     INPUT: ";Min_value;" THROUGH ";Max_value;" ONLY"
17230         INPUT Variable
17240     END WHILE
17250     !
17260 SUBEND
17270!
17280! *****
*
17290!
17300 SUB Unit_read (Frc_clr$,Nm_units,Unit_id(*),Terr (*))
17310!
17320     CALL Check_var ("# UNITS",Nm_units,0,5)
17330     IF Frc_clr$="RED" THEN
17340         Min_value=1
17350         Max_value=191
17360     ELSE
17370         Min_value=192
17380         Max_value=400
17390     END IF
17400     PRINT
17410     IF Nm_units>0 THEN
17420         FOR I=1 TO Nm_units
17430             INPUT "ENTER: UNIT-ID , TERRAIN",Unit_id(I),Terr (I)
17440             CALL Check_var ("UNIT-ID",Unit_id(I),Min_value,Max_value)
17450             CALL Check_var ("TERRAIN",Terr (I),1,4)
17460         NEXT I
17470     END IF
17480     !
17490     FOR I=Nm_units+1 TO 5
17500         Unit_id(I)=0
17510         Terr (I)=0
17520     NEXT I
17530     !
17540 SUBEND
17550!
17560! *****
*
17570!
17580 DEF FNMin (A,B)
17590!

```

Table 5-3. Air attack/Air defense code.

```
17600 IF A<=B THEN
17610   C=A
17620 ELSE
17630   C=B
17640 END IF
17650 RETURN C
17660 '
17670 FNEND
17680 '
17690 '*****'
17700 '
17710 DEF FNMax (A,B)
17720 '
17730 IF A>=B THEN
17740   C=A
17750 ELSE
17760   C=B
17770 END IF
17780 RETURN C
17790 '
17800 FNEND
17810 '
17820 '*****'
```

CHAPTER 6

GROUND COMBAT

1. PURPOSE.

The purpose of the DIME ground combat program (P4) is to determine the number of systems destroyed and ammunition expended during combat between ground forces. The program also displays a battle chronology describing significant maneuver events and designates either the Blue or Red force as terminating the battle through disengagement of direct-fire forces.

2. GENERAL.

A. The survival and effectiveness of a lightly armored force is dependent on its mobility. The force must be able to locate the enemy, move quickly to contact, strike, and then break contact before the enemy is able to respond by tailoring his mission to bring effective firepower into play against the more agile force. In a general sense, this is true of any force attempting to use surprise as a tactical multiplier. However, one usually thinks of a heavily armored force with a simpler tactical objective of containing the enemy and thus developing sufficient firepower to engage and defeat him.

B. This problem faced the DIME development team: how does one structure a division combat model which will fairly represent the light force tactics which seek to avoid decisive engagement, while at the same time fairly representing the advantages and disadvantages of a Soviet force seeking decisive engagement? Low-resolution corps/division models have classically played attrition scenarios representing an attacking force assaulting a defender in a prepared defense. They have not represented various missions and resulting force postures available to both attacker and defender. Nor have they represented the time-phased transition of a force from one posture to another (i.e., from a hasty to a prepared defense).

C. The DIME combat program attempts to represent this change in posture as a surprised unit, attacked in a vulnerable posture, which moves to a hardened posture. This process is simulated using the DIME missions available to each unit. The missions are as follows:

<u>Mission Number</u>	<u>Description</u>
0	Meeting engagement
1	Indirect fire
2	Movement
3	Frontal attack
4	Envelopmental attack
5	Delay

<u>Mission Number</u>	<u>Description</u>
6	Hasty defense
7	Prepared defense
8	Reserve/rear area
9	Ambush

Associated with each mission is a set of templates. The templates are used to represent the lethality and vulnerability of the unit and contain the following information:

- (1) The percent of unit available to fire.
- (2) The percent of unit available as targets.
- (3) The percent of targetable unit fully exposed.
- (4) The percent of targetable unit in hull defilade.

As the battle progresses, these templates are modified by a time-phased increment representing the change in unit vulnerability and lethality. The template structure gives the low-resolution DIME program the flexibility to represent units in various missions/postures engaged by attacking units in various postures. Although the templates represent the natural tendency for a unit to harden its position under fire, it was also necessary to structure the ground combat program to provide the gamer with the flexibility to select conditions which he believes will favorably initialize and terminate the battle.

D. The ground combat program simulates three phases of battle: phase I, movement to contact; phase II, the direct fire battle; and phase III, the withdrawal from direct fire contact. The program requires the gamer to input a set of parameters which essentially represent his battle plan or scenario. The program then executes the plan of both Blue and Red gamers determining the resulting attrition and also determining which side is forced to initiate and sustain a more vulnerable withdrawal posture in phase III. Figures 6-1 through 6-3 show a stylized depiction of the DIME battle geometry in each of the three phases.

(1) Phase I, Movement to Contact. This is essentially an artillery battle. During this period, the forces are beyond the opening range for direct fire (3000 m) and closing toward their objective. The principal scenario parameters input by the Red and Blue gamers describing this phase of the battle are:

- (a) Opening range for artillery (beginning of phase I).
- (b) Percent of force forward in covering action.
- (c) Opening range for direct fire (ending of phase I).


BLUE ATTACKER SCENARIO

MISSION: ASSAULT
OPEN RANGE ARTILLERY: 5 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 10
WITHDRAWAL RANGE: 0
PERCENT LOSS WITHDRAWAL: 40

RED DEFENDER SCENARIO

MISSION*: RESERVE
OPEN RANGE ARTILLERY: 4 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 0
WITHDRAWAL RANGE: 1 KM
PERCENT LOSS WITHDRAWAL: 60

BATTLE TIME: 0:30



*Red regiment in Reserve caught by flanking attack by Blue Battalion.

Figure 6-1. Phase I, Blue force movement to contact.


BLUE ATTACKER SCENARIO

MISSION: ASSAULT
OPEN RANGE ARTILLERY: 5 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 10
WITHDRAWAL RANGE: 0
PERCENT LOSS WITHDRAWAL: 40

RED DEFENDER SCENARIO

MISSION*: RESERVE
OPEN RANGE ARTILLERY: 4 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 0
WITHDRAWAL RANGE: 1 KM
PERCENT LOSS WITHDRAWAL: 60

BATTLE TIME: 9:30



*Although forces tend to harden, BLUE does not allow Red to change mission throughout battle.

Figure 6-2. Phase II, direct fire battle.


BLUE ATTACKER SCENARIO

MISSION: ASSAULT
OPEN RANGE ARTILLERY: 5 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 10
WITHDRAWAL RANGE: 0
PERCENT LOSS WITHDRAWAL: 40

RED DEFENDER SCENARIO

MISSION: RESERVE
OPEN RANGE ARTILLERY: 4 KM
OPEN RANGE DIRECT FIRE: 3 KM
PERCENT FORCES COVERING: 0
WITHDRAWAL RANGE: 1 KM
PERCENT LOSS FORCING WITHDRAWAL: 60

BATTLE TIME: 10:30



*Although forced to withdraw, Red's overall mission remains constant.

Figure 6-3. Phase III, Red force withdrawal to new reserve position.

It should be noted Blue has placed 10 percent of his forces forward in a covering action in Figure 6-1.

(2) Phase II, The Direct Fire Battle. In this phase, direct fire systems of both forces engage available targets. In the example scenario (Figure 6-2), both Blue and Red have chosen 3 km as an opening range. Hence, all available firing systems which can perform at that range will begin to fire. Note that the DIME ground combat program has inflicted attrition on elements in both forces and moved the elements into less exposed positions to artillery and direct fire weapons. The principal gamer inputs affecting phase II are:

- (a) Opening range for direct fire (beginning of phase II).
- (b) Withdrawal range (ending of phase II).
- (c) Percent of losses units will incur before withdrawing.
- (d) Mission (determines percent of forces fully exposed to artillery/direct fire).

(3) Phase III, The Withdrawal Phase. In this phase (Figure 6-3) Blue and/or Red forces break contact with enemy direct fire weapons. The combat program also increases the vulnerability of the withdrawing force by increasing the percent of fully exposed targets. This increase is dependent on the mission of the withdrawing force. The gamer inputs which impact this phase are:

- (a) Withdrawal range, if violated by either of the forces will cause the beginning of phase III.
- (b) Withdrawal percent loss, if sustained by either force, will cause the beginning of phase III.
- (c) Withdrawal time, time required to move out of direct fire range, determines the ending of phase III.
- (d) Mission, determines the percent of forces fully exposed during withdrawal.

(4) Omission of battle phases. It should be noted that the DIME program does not require the gamer to use all of the battle phases. By carefully structuring the scenario input parameters, the gamer can delete any battle phase(s). For example, by making the "opening range for direct fire" equal to the "withdrawal range for direct fire," the DIME ground combat program will move directly from phase I to phase III, thereby simulating a standoff battle consisting primarily of artillery with one force withdrawing to avoid direct contact.

3. DATA FLOW.

The data flow structure for the ground combat program is shown in Figure 6-4. The data are divided into four categories: game parameters, unit status file ("UNITFILE") entries, weapon system parameters, and logistic parameters.

A. Game parameters. The game parameters are input through the terminal. These parameters describe both the tactical scenario and the environmental scenario.

(1) Tactical scenario. These inputs describe which units will fight and their initial missions and deployment postures. Tactical parameters also determine the criteria for shifting from one battle phase to the next and the planned allocation of available artillery and mortar tubes to the missions of prep/counterprep, close support, counterfire, suppression of air defense (SEAD), interdiction, and defensive smoke. DIME will attempt to honor the artillery allocations until it becomes obvious that the tactical situation demands a reallocation of resources. At this point, the program will automatically redistribute the indirect fire resources. The dimensions of the area occupied by both forces are also part of the tactical scenario. This area serves as a basis for computing target density in the artillery and mortar effectiveness algorithms and has significant impact on these algorithms. The tactical scenario represents the pace of battle desired by both Blue and Red gamers. The weapon system parameters, logistic parameters, and attrition algorithms ultimately drive the game in a favorable direction for one of the players.

(2) Environmental scenario. These parameters describe the battle terrain, weather, and the battle initiation time. The terrain type consists of one of four types:

- (a) Open.
- (b) Rolling.
- (c) Hilly.
- (d) Mountainous.

Both the exposure rates of vehicles and personnel to direct fire, and the movement rates for vehicles and personnel, are also keyed on the terrain. The meteorological visibility affects the ranges at which direct fire systems can detect and engage ground targets. Cloud height has a similar degrading effect on laser-seeking artillery projectiles. Battle start time determines the ambient light (day or night) conditions under which the battle will be played with night conditions resulting in degraded movement rates and detection ranges.




Figure 6-4. Information flow for the ground combat program.

B. DIME "UNITFILE". Following the entry of the tactical scenario, the ground combat program structures the forces for battle from the DIME "UNITFILE". Selecting the units indicated in the tactical scenario, the program retrieves the number of weapons from each unit record (located on the hard disk) and forms both the Blue and the Red forces. The tons of ammunition for air defense, direct fire, and indirect fire are also obtained from the "UNITFILE". The attrition program then moves through 30-minute battle time steps calculating element losses and ammunition consumption to both forces. When direct fire contact between the forces has been broken, thus completing the battle, the attrition program distributes the element and ammunition losses among each unit and updates their records on the DIME "UNITFILE."

C. Weapon system parameters. The weapon system parameter files contain the data describing the lethality and vulnerability characteristics of each weapon system being played in the program. The files are randomly accessed by the combat program as engagements occur during the battle. As noted in Figure 6-4, the files contain system information of six types:

(1) Mine systems. The ground combat mine module considers one type of minefield. The data representing the attrition effects against the 70 weapon systems are maintained in data statements as part of the mine module. The data describe kills per armored column and are based on the tactic (bull or breach) being used to cross the minefield. Refer to Chapter 6, Section I for more information.

(2) Indirect fire systems. The DIME ground combat artillery module uses algorithms from the Super Quickie II model to assess kills through artillery, mortars, or multiple launch rocket systems (MLRS for Blue)/multiple rocket launchers (MRL for Red). Data supporting these algorithms are found on the hard disk and consist of artillery delivery errors and lethal areas for each munition against the 70 target elements. Section II of this chapter describes the indirect fire module in greater detail.

(3) Smoke Parameters. Artillery-delivered white phosphorus smoke can be employed by a withdrawing unit during battle phase III. The smoke module calculates the percent of both forces screened by the smoke and then calculates the associated reductions in direct fire kills. Data describing the percent of targets visible to various direct fire sensor systems are found on the hard disk. The smoke file is accessed when the tactical scenario indicates that a retreating force wishes to deploy screening smoke. For more on smoke, see Section III of this chapter.

(4) Direct fire parameters. These files are located on the hard disk and accessed as targets close from 3000 meters. The records are structured to represent engagements in each 500-meter band and contain firing rates and probabilities of kill for each weapon engaging twenty target categories.

Other information describing individual weapon fire control systems (principal sensor, basic load) are also contained in these files. See Section IV of this chapter for greater detail of direct fire data flow and file structures.

(4) Helicopter/air defense systems. This file is also located on the hard disk and is accessed during helicopter engagements of ground targets. The ground combat program assumes that helicopters engaging forces will attempt to stand off at maximum range while still employing their weapons effectively. Consequently, the file contains records describing the helicopter's ability to detect, engage, and kill ground targets depending on the optimal range for various delivery (missile or gun) profiles. Also contained in the record is the ability of each air defense system to engage the helicopter as it stands off at its engagement range. See Section V of this chapter for a more explicit description on helicopter data flow and file structures.

(5) Precision-guided munitions. The ground combat program plays two types of precision-guided munitions (PGM). These consist of cannon-launched guided projectiles (CLGP) and guided antiarmor mortar projectiles (GAMP). Data necessary for these include single shot kill probabilities toward each of the 70 targets and designator degradation factors for each PGM. These data are held internally within the PGM attrition module. For greater detail, see Section VI of this chapter.

(6) Dismounted infantry personnel losses. If a final assault by dismounted infantry is part of the tactical scenario, the ground combat program will allow infantry to dismount during the last 500 meters of closure. Data describing losses to infantry personnel during this phase are maintained as data statements in the infantry module. See Section VII of this chapter for more information.

D. Logistic parameters. The ground combat program calculates the tonnages of ammunition consumed by both Blue and Red forces during the battle. The data base supporting these calculations consists of basic loads and the packaged round weights for each of the 70 weapon systems on the "UNITFILE". This data base is held in the ground combat program in the form of data statements.

E. DIME attrition output.

(1) The principal output from the combat program is the number of weapon systems lost in battle. Figure 6-5 shows an example of Blue system losses following a 2 1/2-hour battle. The losses are not provided in the classic weapon-to-weapon killer/victim sense; rather, the program provides losses inflicted by a functional group of weapons, i.e., direct fire (DF), indirect fire (IF), attack helicopters (A/H), infantry (INF), precision-guided munitions (PGMs), and mines (MIN). If it is necessary to obtain killer/victim tables by weapon type, this can be done for direct fire systems by applying the individual firer/target probabilities of kills developed by subroutine Df_cbt. However, the user is reminded that DIME is a low-resolution model designed primarily for analysis of brigade/battalion tactics and not for analysis of individual weapon systems.

(2) Other output from the program consists of a report produced every 30 minutes describing the location of the forces, the artillery and mortar volleys fired, and the current strengths of both forces. Figure 6-6 shows an example of the 30-minute battle updates produced by the program.

4. FILE STRUCTURE.

The DIME ground combat program (P4) accesses the following external files on the hard disk.

A. Sys_eff(I,J) contains numerical effectiveness values assigned to each of the 70 weapon elements. The effectiveness is determined by the element's firepower capability.

I is 1 = Blue
2 = Red
J is 1-70 for the weapon types.

B. Wpn_type(I,J) contains a number (1-3) which places the weapon elements into the ammunition categories of:

1 = Direct fire
2 = Indirect fire
3 = Air defense.

I and J represent the same as above.

RED KILLER--BLUE VICTIM TABLE

VICTIM	KILLER							
SYS	START	D/F	I/F	PGM	A/H	INF	MIN	END
M551	12.3	.3	.4	0.0	.1	0.0	0.0	11.5
FAV40	24.8	.4	.7	0.0	.6	0.0	0.0	23.1
HMV-G	2.2	0.0	.1	0.0	.1	0.0	0.0	2.0
DRAGN	5.3	0.0	.8	0.0	.1	0.0	0.0	4.3
CMD-V	20.4	.2	1.2	0.0	.5	0.0	0.0	18.4
HMV40	44.7	.5	2.2	0.0	1.1	0.0	0.0	40.9
ARTY	21.5	0.0	.8	0.0	0.0	0.0	0.0	20.7
MORTR	.1	0.0	0.0	0.0	0.0	0.0	0.0	0.0
INF	8.3	0.0	2.1	0.0	.2	0.0	0.0	6.0
VULCN	5.0	0.0	.6	0.0	.1	0.0	0.0	4.3
AVNGR	9.5	0.0	.2	0.0	0.0	0.0	0.0	9.3
STING	1.6	0.0	.2	0.0	0.0	0.0	0.0	1.3
F-TRK	5.7	0.0	.1	0.0	0.0	0.0	0.0	5.6
CGO-T	98.3	0.0	2.6	0.0	0.0	0.0	0.0	95.7

BLUE KILLER--RED VICTIM TABLE

VICTIM	KILLER							
SYS	START	D/F	I/F	PGM	A/H	INF	MIN	END
T55	9.2	.2	0.0	1.5	1.0	0.0	0.0	6.5
BMP73	2.5	0.0	0.0	.6	.3	0.0	0.0	1.6
BRDM3	6.3	.1	0.0	1.3	.5	0.0	0.0	4.3
AT-75	15.3	.6	.3	0.0	0.0	0.0	0.0	14.3
AGS17	10.3	.4	.1	0.0	0.0	0.0	0.0	9.7
CMD-V	17.7	.4	.3	0.0	.3	0.0	0.0	16.7
BTR	111.5	2.4	.9	4.3	1.8	0.0	0.0	102.1
ARTY	138.9	0.0	.3	0.0	0.0	0.0	0.0	138.6
MORTR	17.6	0.0	.5	0.0	0.0	0.0	0.0	17.1
MRL	15.3	0.0	.1	0.0	0.0	0.0	0.0	15.2
INF	180.6	3.7	2.2	7.0	2.7	0.0	0.0	165.0
ZSU-X	3.2	.1	0.0	0.0	.3	0.0	0.0	2.8
SA-13	3.9	0.0	0.0	0.0	0.0	0.0	0.0	3.9
SA-6	11.2	0.0	0.0	0.0	0.0	0.0	0.0	11.2
SA-14	37.0	1.4	1.2	0.0	0.0	0.0	0.0	34.4
F-TRK	132.9	0.0	.2	0.0	0.0	0.0	0.0	132.7
CGO-T	512.1	0.0	1.0	0.0	0.0	0.0	0.0	511.1
ENGR	26.8	.6	0.0	0.0	.4	0.0	0.0	25.8

ATTACK HELICOPTER RESULTS:

TYPE	#COMMITTED	#KILLED	#SORTIES
LCH	3.0	1.5	3.0
AH1S	5.0	.1	5.0
SCTS	0.0	0.0	0.0
HIND	12.0	3.6	10.4
HIP	0.0	0.0	0.0
SCTS	0.0	0.0	0.0

Figure 6-5. An example of system losses following a 2.5 hour battle.

 : SIGNIFICANT BATTLE EVENTS FROM 1500 TO 1530 :

BLUE HELICOPTERS ATTACKING RED FORCE

LCH 3.0
 AHIS 5.0
 SCT 0.0

RED HELICOPTERS ATTACKING BLUE FORCE

HIND 6.0
 HIP 0.0
 SCT 0.0

RED WITHIN BLUE MORT CS RANGE : REMAINING BLUE PREP AMMO AVAILABLE FOR CS

BLUE WITHIN RED MORT CS RANGE : REMAINING RED PREP AMMO AVAILABLE FOR CS

RED WITHIN BLUE ARTY CS RANGE : REMAINING BLUE PREP AMMO AVAILABLE FOR CS

BLUE WITHIN RED ARTY CS RANGE : REMAINING RED PREP AMMO AVAILABLE FOR CS

BLUE ARTILLERY VOLLEYS FIRED

	P/CP	CS	SEAD	CF	INT	TOTAL	Tons CONSUMED	Tons AVAILABLE
ARTY	0	21	0	3	3	26	11.6	19.3
MORT	0	0	0	0	0	0	0.0	11.2

BLUE PGM ROUNDS:

	CLGF	GAMP
FIRED	20.0	0.0
AVAILABLE	0.0	0.0

RED ARTILLERY VOLLEYS FIRED

	P/CP	CS	SEAD	CF	INT	TOTAL	Tons CONSUMED	Tons AVAILABLE
ARTY	0	116	49	97	97	360	175.4	391.6
MORT	0	27	0	0	0	27	4.1	59.7
MRL	0	0	0	4	4	9	38.5	213.6

CLOSE DF BATTLE UNDERWAY 1530 HRS B/EFF: 1.00 R/EFF: 1.00
 INITIAL RANGE: 4000 CURRENT RANGE: 2500

BOTH FORCES IN CONTACT FOR 30 MINUTE PERIOD.

	BLUE			RED		
	HELO 1	HELO 2	HELO 3	HELO 1	HELO 2	HELO 3
S1 NDOFF RANGE:	3000	2500	0	3000	0	0
HELO MSN:	1	2	0	3	0	0
ATK_PROF:	5	7	0	7	0	0
* HELOS:	3.00	5.00	0.00	6.00	0.00	0.00

BLUE HELICOPTER MISSION 1 ABORTED DUE TO EXCESSIVE LOSSES.

NO MORE AIR MISSILES AVAILABLE FOR BLUE HELO 2 . WILL RETURN TO BASE.

RED HELICOPTER MISSION 1 ABORTED DUE TO EXCESSIVE LOSSES.

Figure 6-6. An example of the 30 minute battle updates.

C. Ammo_wt(I,J) contains the ammunition expenditure per engagement for each of the 70 elements. I and J are the same as above.

D. Basic_ld(I,J) contains the total number of engagements for each of the 70 elements. I and J represent the same as above.

E. Arty_30min_wt(I,J) contains the total ammunition in tons that can be allocated to artillery during a 30-minute timestep.

I is: 1 = Blue
2 = Red

J is: 1 = Arty
2 = MLRS/MRL
3 = Mortar.

F. A_wt(I,J) contains the weight in tons for six batteries firing one burst of artillery ammunition. I and J are the same as in E above.

G. Bf_mask(J) and Rf_mask(J) contain a one, meaning element J may take part in battle, or a zero indicating that element J may not be involved in the battle. J represents the 1-70 system elements.

H. Bdf_mask(I,J) and Rdf_mask(I,J) contain a one for being a part of the direct fire battle, or a zero meaning element J is not involved in the battle.

I is: 1 = Conventional battle
2 = Attack on a command post
3 = Attack on a forward arming and refueling point (FARP)
4 = Attack on a log point

I is: 5 = Attack on a field artillery.

J is (1-70) for the weapon elements. Note: If Blue is attacking a log point and Red is defending, the Bdf_mask(1,J) and Rdf_mask(4,J) would be used.

I. Ds_start(I) contains the starting range in meters for close support in terrain I.

I is: 1 = Open
2 = Rolling
3 = Hilly
4 = Mountainous

J. Barty_30min(I,J) and Rarty_30min(I,J) contain tonnages per tube delivered per 30 minutes by supporting artillery. The descriptions for I and J are as follows:

I is the mission:

- 1 = Movement to contact
- 2 = Indirect fire
- 3 = Movement
- 4 = Frontal attack
- 5 = Envelop attack
- 6 = Delay
- 7 = Hasty defense
- 8 = Preparatory defense
- 9 = Rear area
- 10 = Ambush.

J is:

- 1 = Arty
- 2 = MLRS/MRL
- 3 = Mortar.

(Note: I = The mission value input, plus one, for array accessing.)

K. "UNITFILE". This file consists of 400 records, each containing 150 elements. The assignment of records consists of records 1-191 for Blue units and records 192-400 for Red units. Elements used within each record consist of 1-70, 78, 131 - 133, 80, 139 - 141. A description of these elements may be found in Chapter 1, Table 1-1.

L. Advance rate file. This file contains the maximum rate of advance for a force in meters advanced per minute. The file consists of 16 records.

- Record 1. Blue, day, open terrain
- Record 2. Blue, day, rolling terrain
- Record 3. Blue, day, hilly terrain
- Record 4. Blue, day, mountainous terrain
- Record 5. Blue, night, open terrain
- Record 6. Blue, night, rolling terrain
- Record 7. Blue, night, hilly terrain
- Record 8. Blue, night, mountainous terrain
- Record 9. Red, day, open terrain
- Record 10. Red, day, rolling terrain
- Record 11. Red, day, hilly terrain
- Record 12. Red, day, mountainous terrain
- Record 13. Red, night, open terrain
- Record 14. Red, night, rolling terrain
- Record 15. Red, night, hilly terrain
- Record 16. Red, night, mountainous terrain.

The appropriate record is read into the array Advance_rate(I,J), where:

I is battle phase: 1 = Mounted in Phase I
 2 = Dismounted in Phase I
 3 = Mounted in Phase III
 4 = Dismounted in Phase III

and

J is mission: 1 = Movement to contact
 2 = Indirect fire
 3 = Movement
 4 = Frontal attack
 5 = Envelopment attack
 6 = Delay
 7 = Hasty defense
 8 = Preparatory defense
 9 = Reserve/rear area
 10 = Ambush

M. Operational mission templates. These files contain the percentage of participants in a battle and target vulnerabilities. There are eight files for the Blue force and eight files for Red.

1. The files defining the number of target participants are:

- (a) "BIFTARG" - Blue targets vs. indirect fire.
- (b) "BDFTARG" - Blue targets vs. direct fire.
- (c) "RIFTARG" - Red targets vs. indirect fire.
- (d) "RDFTARG" - Red targets vs. direct fire.

2. Delta files contain the rate of change representing the percent of elements that can be introduced/extracted from battle per a 30-minute interval, while maintaining the same mission. These files are:

- (a) "BIFDT" - Delta Blue target vs. indirect fire.
- (b) "BDFDT" - Delta Blue target vs. direct fire.
- (c) "RIFDT" - Delta Red target vs. indirect fire.
- (d) "RDFDT" - Delta Red target vs. direct fire.

3. Firer files for direct fire contain the percent of participating firers and the corresponding delta files show the firer's rate of change.

- (a) "BFIRE" - Blue firers for direct fire.
- (b) "RFIRE" - Red firers for direct fire.
- (c) "BDFIRE" - Delta Blue firers for direct fire.
- (d) "RDFIRE" - Delta Red firers for direct fire.

4. Vulnerability files exist to represent the fraction of fully exposed systems to direct fire. They, too, have corresponding delta files which represent the percent increase/decrease to a system's vulnerability.

- (a) "BVUL" - Blue vulnerabilities to direct fire.
- (b) "RVUL" - Red vulnerabilities to direct fire.
- (c) "BDVUL" - Delta Blue vulnerabilities.
- (d) "RDVUL" - Delta Red vulnerabilities.

5. All of the template files contain 10 records each. These records represent the possible missions:

- 1 = Movement to contact
- 2 = Indirect fire
- 3 = Movement
- 4 = Frontal attack
- 5 = Envelop attack
- 6 = Delay
- 7 = Hasty defense
- 8 = Preparatory defense
- 9 = Rear area
- 10 = Ambush

The array used in accessing data from a record is in the form:

M(J)

where J is unit type and unit echelon and where echelon = 0 (Blue battalion/Red regiment) or 1 (Blue company/Red battalion).

- 11/01 = Combat unit
- 12/02 = Artillery unit
- 13/03 = ADA unit
- 14/04 = Helicopter site/FARP
- 15/05 = Command post/headquarters (CP/HQ)
- 16/06 = Engineer unit
- 17/07 = Fuel/ammunition (POL/AMMO) supply point
- 18/08 = Maintenance point
- 19/09 = Surface-to-air missile (SAM) site
- 20/10 = Communication/radar/electronic warfare (EW) site

N. For more information on any data, refer to Volume III of the DIME documentation.

5. ALGORITHMS.

A. Logic flow. Figure 6-7 presents a generalized logic flow for the processes occurring in the DIME ground combat program. The purpose of this diagram is to provide a framework for discussion of the algorithms supporting each of these processes. The DIME ground combat program is a timestep, deterministic model using expected value techniques for calculating losses to both forces.

B. Force structuring/tactical template initialization. The ground combat program begins processing by reading both tactical and environmental scenarios and structuring the opposing forces. This initialization is done in subprogram Set_battle (see Figure 6-8 for a generalized logic flow of Set_battle and Table 6-5 for a description of its principal variables).

The initialization process continues by accumulating the total tonnages of indirect fire (IF), direct fire (DF), and air defense (AD) ammunition available to both forces. After accepting a gamer description of the environmental scenario, the program then establishes the exposure/lethality templates for each force using the following equations:

(1) Exposure to indirect fire. Initial percentages exposed to indirect fire are:

$$Ift_{jm} = \sum_{i=1}^n P_{ij} * If_{im} \quad (\text{Eq. 6-1})$$


where:

Ift_{jm} = the percent of the j^{th} element type exposed to indirect fire at the beginning of the battle with the force in mission m ($j = 1$ to 70 element types in the force).

n = number of units in the entire force involved in the sector battle.

P_{ij} = percent of force from unit i and element type j .

If_{im} = percent of elements exposed to indirect fire for unit i in mission m . Note that unit i is of a specific unit type such as combat, artillery, ADA, etc.



*Block is given in greater detail on the following page.

Figure 6-7. DIME ground combat generalized logic flow.




Figure 6-7. DIME ground combat generalized logic flow (concluded).




Figure 6-8. Generalized logic flow for initialization of force structure in subroutine Set_battle.

The delta changes which occur to the percentage each 30 minutes is also calculated.

$$\text{Dift}_{jm} = \sum_{i=1}^n P_{ij} * \text{Dif}_{im} \quad (\text{Eq. 6-2})$$

where:

Dift_{jm} = the change in the percent of elements of type j exposed to indirect fire every 30 minutes with force in mission m. This increment is applied to Ift_{jm} each 30 minutes by DIME.

Dif_{im} = the change in the percent of elements of unit i exposing themselves to indirect fire each 30 minutes when the unit is operating under mission m. Note that unit i is of a specific unit type such as combat, artillery, ADA, etc.

(2) Exposure/vulnerability to direct fire. The following variables describing exposure and vulnerability to direct fire are also initialized in subroutine Set_battle using weighing procedures identical to those shown in equations 6-1 and 6-2.

- Dft_{jm} = the percent of elements of type j in the force initially exposed to direct fire with force in mission m.
- Ddft_{jm} = the change in the percent of elements of type j exposed to direct fire each 30-minute period with force in mission m.
- Dff_{jm} = the percent of elements of type j in the force which can initially fire in a direct fire battle with force in mission m.
- Ddff_{jm} = the change in the percent of elements of type j able to fire each 30-minute period with force in mission m.
- Fet_{jm} = the percent of target and firer elements of type j which are fully exposed with force in mission m.
- Dfet_{jm} = the percent of targets and firers of type j which move from fully exposed to hull defilade each 30 minutes with the force in mission m.

It should be noted that the values If_{im} and Dif_{im} are taken from the DIME vulnerability/lethality templates discussed in paragraphs 2C and 4M(1 - 5) of this chapter. One of the primary functions of Set_battle is to initialize the vulnerability templates based on the unit echelon, type and

mission for use by the attrition program. An example of the values used by DIME for I_{im} and D_{im} are shown in Table 6-1. For a complete listing of all values used in DIME, see Chapter 4, Volume III, of the data documentation. The option exists to change the template values based on the level of deployment the gamer wants to portray.

C. Initialization of battle plan.

(1) Following the structuring of both forces, the combat program continues preparation for the battle by allocating indirect fire resources among eight tasks. The allocation occurs in subroutine Set_conditions. See Figure 6-9 for a logic flow of Set_conditions and Table 6-5 for a list of principal variables. The combat program allows allocation of indirect fire resources among eight tasks which are shown in Table 6-2 with possible allocations for artillery, mortars, and MLRS/MRL. The actual allocations made by DIME are dependent on gamer inputs from the tactical scenario. These inputs consist of the tactical fire plan describing the percent of available indirect firing systems which are to be applied to each task. Subroutine Set_conditions responds to this plan by earmarking the indirect fire ammunition for use in each task using the percentages input in the tactical fire plan. The earmarked tonnages serve as an upper bound to the ground combat program as it attempts to execute the fire plan during each 30-minute step in the battle. As an example, consider a unit having 50 tons of artillery ammunition to fire during a battle. Note that a 20 percent allocation for prep/counterprep will cause no more than 10 tons to be fired in this activity. This will be fired only if sufficient tubes survive in the 30-minute battle steps to fire it.

(2) Subroutine Set_conditions completes the development of the indirect fire plan by establishing tactical range lines. These lines represent the locations at which the indirect fire tasks will be initiated or cancelled by the program. The execution of the indirect fire tasks (i.e., the shift from prep/counterprep to close support) is governed by these phase lines and the battle range between the forces. Although the actual lines are established using inputs from the tactical scenario, the limits on these ranges for each task and the rules causing the program to reallocate resources from one task to another is shown in Table 6-3. The tactical scenario thresholds bounding the DIME ground combat battle phases are also initialized in Set_conditions.

D. Battle timestep loop. Following the initial allocations of maximum battle tonnages for indirect fire, the program moves into a timestep loop representing 30 minutes of battle time. The program will move through this loop until the tactical scenario criteria for phases I, II, and III have been satisfied. The 30-minute step is begun by comparing loss and range criteria for both forces with the tactical scenario threshold. If it is necessary to change phases, the program increments the phase counter and allocates the helicopters and indirect fire rounds for both forces for this 30-minute period. Principal variables affecting the process are listed in Table 6-5 under battle phase criteria.

Table 6-1. Blue target indirect fire templates (If_{jm}) and indirect fire delta templates (Dif_{jm}).

Unit type	Mission									
	0	1	2	3	4	5	6	7	8	9
Combat	.400	.160	.333	.600	.280	.200	.600	.800	.750	.050
Artillery	1.000	.160	.350	1.000	1.000	.400	1.000	1.000	1.000	1.000
Air defense	.400	.160	.333	.600	.280	.200	.600	.800	.750	.050
FARP	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000
CP/HQ	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000
Engineer	.133	.053	.111	.200	.093	.067	.200	.267	.250	.050
Supply	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000
Maintenance	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000
SAM site	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000
Commo/radar	1.000	1.000	.500	1.000	1.000	1.000	1.000	1.000	.750	1.000

Unit type	Mission									
	0	1	2	3	4	5	6	7	8	9
Combat	.100	.140	.111	.067	.120	.133	.067	.033	.042	.010
Artillery	0.000	.140	.108	0.000	0.000	.100	0.000	0.000	0.000	0.000
Air defense	.100	.140	.111	.067	.120	.133	.067	.033	.042	.158
FARP	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000
CP/HQ	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000
Engineer	.144	.158	.148	.133	.151	.156	.133	.122	.125	.158
Supply	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000
Maintenance	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000
SAM site	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000
Commo/radar	0.000	0.000	.083	0.000	0.000	0.000	0.000	0.000	.042	0.000




Figure 6-9. Generalized logic flow for initialization of battle parameters and 6-hour artillery ammunition allocation in subroutine Set_conditions.

Table 6-2. Possible allocations for blue and red indirect fire (IF) volleys.

<u>Blue IF</u>	<u>TASKS*</u>									
	<u>Prep/CP</u>	<u>C/S</u>	<u>SEAD</u>	<u>CF</u>	<u>Int</u>	<u>Smoke</u>	<u>PGM</u>	<u>FPF</u>		
Artillery	X	X	X	X	X	X	X	X	X	X
MRS	X	0	X	X	X	0	0	0	0	0
Mortar	X	X	X	0	0	X	X	X	X	X
<u>Red IF</u>										
Artillery	X	X	X	X	X	X	0	X	X	X
MRL	X	0	X	X	X	0	0	0	0	0
Mortar	X	X	X	0	0	X	0	X	X	X

X = possibility of allocation.

0 = cannot allocate in this task.

*TASKS

- Prep/CP
- C/S
- SEAD
- CF
- Int
- Smoke
- PGM
- FPF
- Preparatory/counterpreparatory
- Close Support
- Suppression and engagement of air defense
- Counterfire
- Interdiction
- White phosphorous defensive smoke
- Precision-guided munitions
- Final protective fire

Table 6-3. Firing range conditions for various tasks in DIME indirect fire allocation module.

Task	Blue Artillery		Blue MLRS		Blue Mortar	
	Begin	End	Begin	End	Begin	End
Prep/CP	Blue prep time* and 12.0 km	Blue CS begins	Blue prep time* and 25.0 km	Blue CS begins	Blue prep time and 5.7 km	Blue CS begins
CS	5.0 km	Blue break less 100m	Does not fire	Does not fire	5.0 km**	Blue break
SEAD	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges
CF	12.0 km*	Blue FPF begins	25.0 km*	Blue break	Does not fire	Does not fire
INT	12.0 km*	Blue FPF begins	25.0 km*	Blue break	Does not fire	Does not fire
CLGP	Blue CS begins less 500m	Blue break	Does not fire	Does not fire	Does not fire	Does not fire
GAMP	Does not fire	Does not fire	Does not fire	Does not fire	Blue CS begins less 500m	Blue break
FPF	Blue break plus 1.5 km	Blue break	Does not fire	Does not fire	Blue break plus 1.5 km	Blue break
SNOKE	Blue break and range < 3.2 km	Blue break	Does not fire	Does not fire	Blue break and range < 3.2 km	Blue break

* This is max range; gamer specification may allow to begin at closer ranges. However, battle time must have passed the attackers opening prep time.

** Terrain dependent: open - 6.0 km; rolling - 5.0 km; hilly - 4.00 km; mountainous - 4.0 km.

Table 6-3. Firing range conditions for various tasks in DIME indirect fire allocation module (concluded).

Task	Red Artillery		Red MRL		Red Mortar	
	Begin	End	Begin	End	Begin	End
Prep/CP	Red prep time* and 14.0 km	Red CS begins	Red prep time* and 14.0 km	Red CS begins	Red prep time* and 14.0 km	Red CS begins
CS	5.0 km	Red break less 100m	Does not fire	Does not fire	5.0 km**	Red break
SEAD	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges	Allocated at all ranges
CF	14.0 km*	Red FPF begins	25.0 km	Red break	Does not fire	Does not fire
INT	14.0 km*	Red FPF begins	25.0 km	Red break	Does not fire	Does not fire
FPF	Red break plus 1.5 km	Red break	Does not fire	Does not fire	Red break plus 1.5 km	Red break
SMOKE	Red break and range < 3.2 km	Red break	Does not fire	Does not fire	Red break and range < 3.2 km	Red break

* This is max range; gamer specification may allow to begin at closer ranges. However, battle time must have passed the attackers opening prep time.

** Terrain dependent: open - 6.0 km; rolling - 5.0 km; hilly - 4.00 km; mountainous - 4.0 km.

E. Allocation of helicopters (Helo arrive). This ground combat subroutine allocates the number of helicopters to be flown against the opposing force for any 30-minute period using a cell methodology. Figure 6-10 provides a logic flow of this methodology contained in subroutine Helo_arrive.

(1) Helicopter battle entry. The subroutine checks three criteria to determine if Blue helicopters can be scheduled for on battle site action.

(a) Are current force ranges less than Blue helicopter tactical entry range?

(b) Is current time less than Blue helicopter tactical entry time?

(c) Is meteorological visibility greater than or equal to 2 km?

The meteorological criteria must always be satisfied. Helicopters will not fly on less than 2-km/days. Satisfying (c), if either (a) or (b) is satisfied, then the subroutine proceeds to calculate the number of helicopters available at the battle site. A similar check is made for Red helicopters.

(2) Helicopters available on site. The subroutine divides all surviving helicopters into battle cells. The number of battle cells are specified by the gamer and may vary from one to four. The cells allow the gamer to apply constant pressure on the opposing ground forces by using four cells or a 30-minute period of heavy helicopter pressure followed by 90 minutes of no helicopters on site using one cell. Two or three cells may also be selected. The cells are also used to simulate the periodic vacating of the battle site for refuel and rearmament by helicopters. The subroutine considers a cell to be on site for 30 minutes and off site for 90 minutes to refuel and rearm. Consequently, the subroutine schedules the presence of a cell based on Table 6-4. This scheduling table shows the number of cells at the battle site over five consecutive 30-minute periods for various cell configurations. A force of 12 helicopters is used in this table. For example, with three cells, the helicopters are divided into groups of four per cell. Cell one arrives on site at the time designated by the gamer with four helicopters. After 30 minutes, it returns to refuel and rearm and is followed by cell two with four new helicopters. Cell three relieves cell two and then, as it moves off site, there are no helicopters in the battle from 91 to 120 minutes past helicopter entry time until cell one returns at 121 minutes past helicopter entry time.




Figure 6-10. DIME logic flow for helicopter allocation found in subprogram Helo_arrive.

Table 6-4. On-site scheduling table for various numbers of helicopter cells.

Cells desired	Minutes following helicopter battle entry time			
	<u>0-30</u>	<u>31-60</u>	<u>61-90</u>	<u>91-120</u>
1	1/12	0/0	0/0	0/0
2	1/6	0/0	2/6	0/0
3	1/4	2/4	3/4	0/0
4	1/3	2/3	3/3	4/3

Table contains X/Y where:

X = the helicopter cell on side
(example: number 1 of 3, number 2 of 3, etc.).

Y = the number of helicopters on site assuming 12 helicopters were allocated for this sector battle.

(3) Scouts available for Blue attack helicopters (AHs). If scouts are available, they are also divided among the number of cells. The actual number of scouts accompanying a Blue AH cell is given by:

$$Sc = \begin{cases} \text{MIN } (0.6 * Ah, S * Ro/C); & \text{if } S > 0.4 * Ah \\ 0; & \text{otherwise} \end{cases} \quad (\text{Eq. 6-3})$$

where:

- Sc = number of scouts per cell.
- Ah = number of attack helicopters per cell.
- Ro = an operational reliability factor for scouts (currently set to 0.83).
- C = number of cells desired by the gamer.
- S = total number of scouts in the force.

Note that this essentially models the allocation of scouts along a criteria which will allow no more than three scouts to five AHs (a 3/5 mix) while assuring that the scout mix will be at least 2/5. If the 2/5 mix cannot be achieved, the subroutine discards the scouts (see Figure 6-8) and the Blue attack helicopters proceed alone.

(4) Following allocation of Blue helicopters, the subroutine then allocates Red helicopters using the cell methodology described for Blue. Note that the subroutine does not allocate scouts for the Red helicopter cells. Principal variables for the helicopter allocation process are described under Helo_arrive in Table 6-5.

F. Allocation of indirect fire volleys for 30 minutes.

(1) The number of volleys of artillery, mortars, and MLRS/MLR for both Blue and Red to be fired during the 30-minute period is calculated in subroutine Arty_arrive. The logic flow diagram for Arty_arrive is in Figure 6-11 with the subroutine's principal variables found in Table 6-5. The flow diagram shows the subroutine moving through four areas of allocation each 30 minutes.

- (a) Allocation of smoke.
- (b) Allocation of prep/counter prep, CLGP, and GAMP.
- (c) Allocation of close support volleys.
- (d) Allocation of counterfire and interdictive volleys.




Figure 6-11. Logic flow for 30-minute allocation of artillery, MLRS/MRL and mortar volleys in subroutine Arty_arrive.




Figure 6-11. Logic flow for 30-minute allocation of artillery, MLRS/MRL and mortar volleys in subroutine Arty_arrive (continued).




Figure 6-11. Logic flow for 30-minute allocation of artillery, MLRS/MRL and mortar volleys in subroutine Arty_arrive (continued).




Figure 6-11. Logic flow for 30-minute allocation of artillery, MLRS/MRL and mortar volleys in subroutine Arty_arrive (concluded).

(2) The number of volleys allocated for each task depends upon the most restrictive of the following constraints:

(a) The number of tubes surviving to fire a particular task.

(b) The amount of ammunition available for use in a particular task for this 30-minute period.

(3) The subroutine uses the following equation for allocations by artillery, mortars, and MLRS/MRL:

$$V_{ij} = \text{MIN} (A_{ij}/W_{tj}, T_{ij} * R_j/W_{tj}) \quad (\text{Eq. 6-4})$$

where:

V_{ij} = the number of volleys from indirect fire system type j fired in response to requests for task i support.

T_{ij} = surviving tubes of type j assigned to task i .

R_j = operational 30-minute firing rate of system type j (tons per 30 minutes).

W_{tj} = weight (tons) of one round from indirect system of type j .

A_{ij} = tons of ammunition of type j available for task i .

For all tasks other than close support, the A_{ij} value is simply the amount of ammo initially allocated by subroutine Set_conditions. This amount has been decremented by consumptions which occurred during all previous 30-minute periods. However, for close support, the subroutine attempts to limit the amount of ammunition available each 30-minute period in an effort to keep constant pressure on the enemy. Figure 6-12 provides a graphic description of this process.

As the enemy advances at a constant rate, each 30-minute time step, the subroutine allocates a constant 10 percent of all ammunition available for close support. The subroutine maintains a reserve of 50 percent of all close support ammunition for use in the final protective fire (FPF) phase of the battle beginning at 1.5 km. Normally, a force does not advance at a constant rate. The force will move forward and then, suffering the effects of suppression from attrition and incoming fire, will slow during subsequent 30-minute advance periods. In this case, the indirect fire module sets as its goal the even allocation of all close support ammunition against an advancing force while maintaining a significant percent of the ammunition as an FPF reserve.

Referring again to Figure 6-12, it will be noted that the program allocates the close support ammunition for the 30-minute period before calculating force movement for that period. Consequently, the movement distance of the previous 30 minutes is used assuming that the advancing force will continue





Figure 6-12. Graphical depiction of procedure for close support (CS) indirect fires. Graphs represent allocations against a force advancing at constant and variable rates.

at that rate during this 30-minute period. The following simple linear approximation is used to guide the uniform allocation of close support ammunition against the enemy as it moves to FPF range:

$$F_{ij} = \begin{cases} \frac{(1 - F_p)(R_s - R_t)}{R_s - R_p} - \frac{X_{t_{ij}}}{X_{a_{ij}}} & ; \text{if } R_t > R_p \\ \left(1 - \frac{X_{t_{ij}}}{X_{a_{ij}}}\right) * \left(\frac{R_t' - R_t}{R_t - R_b}\right) & ; \text{if } R_b < R_t < R_p \\ 1 - \frac{X_{t_{ij}}}{X_{a_{ij}}} & ; \text{if } R_t < R_b \end{cases} \quad (\text{Eq. 6-5})$$

$$F_{a_{ij}} = \text{MAX}(F_{\text{min}}, F_{ij}) \quad (\text{Eq. 6-6})$$

$$A_{ij} = \text{MIN}(F_{a_{ij}} * X_{a_{ij}}, X_{a_{ij}} - X_{t_{ij}}) \quad (\text{Eq. 6-7})$$

where:

- F_{ij} = the fraction of indirect fire ammunition tonnage for system j allocated for close support (i) for this 30-minute timestep with strict maintenance of FPF reserves.
- F_p = the fraction of close support ammo held in reserve for use in final protective fires. Values currently used for both artillery and mortars are Blue 0.5 and Red 0.3.
- R_s = tactical phase line open fire range of artillery close support.
- R_t = range of target at beginning of this 30-minute period.
- R_p = phase line range at which final protective fire (FPF) will begin.
- R_b = range at which defender direct fire forces will break.

$X_{t_{ij}}$ = total tonnage of type j consumed in close support (i) in all previous 30-minute timesteps.
 $X_{a_{ij}}$ = total tonnage of type j available for close support (i) including FPF tonnage.
 $R_{t'}$ = range of target at beginning of 30-minute period just prior to current period.
 $F_{a_{ij}}$ = fraction of ammunition type j available for close support task (i).
 F_{min} = factor representing lower bound for close support allocations on targets of opportunity. $F_{min}=0.083$ for lower bound or 0.20 if target is in minefield.
 A_{ij} = is as described in equation 6-4 with i as the close support tasks.

G. Force movement.

(1) The DIME ground combat program calculates the movement of the attacker force every 30 minutes. The program assumes that only the attacker force moves with the defender remaining fixed. Figure 6-13 provides a flow diagram of the procedure used to determine movement in subroutines Calc_movement and Mine_encounter. Principal variables for these subroutines can be found in Table 6-5.

(2) Subroutine Calc_movement selects the unsuppressed velocity for the attacking force based on the terrain, mission, day/night, and whether the force is primarily mounted or dismounted. It then calculates three suppression factors affecting the movement.

(a) Suppression from Calc_movement for a 30-minute period can be suppressed up to 40 percent based on casualties from artillery, direct fire, and helicopters sustained in the previous 30 minutes. The following equations are used to represent movement suppression from casualties:

$$P_{sc} = \text{MIN} \left(.4, .4 * \left[\frac{E_{fp} - E_{fc}}{E_{ff}} \right] / .06 \right) \quad (\text{Eq. 6-8})$$

where:

P_{sc} = the fraction of force movement suppressed this 30 minutes due to casualties.
 E_{fp} = the force effectiveness score at the beginning of the previous 30-minute period.
 E_{fc} = the force effectiveness score at the end of the previous 30-minute period (i.e., current score at the beginning of this period).
 E_{ff} = the force effectiveness score at the beginning of this battle.




Figure 6-13. Logic flow for 30-minute movement calculation found in subroutines Calc_movement and Mine_encounter.

Note that the force effectiveness (Eft) at any time in the battle is calculated by:

$$Eft = \sum_{i=1}^n N_i * W_i \quad (\text{Eq. 6-9})$$

where:

N_i = the number of surviving elements of type i .
 W_i = the effectiveness weight assigned to element i .
 n = 70; the number of different system elements.

(b) Movement suppression from indirect fire. Calc_movement also considers suppression from indirect fire. The suppression is directly proportional to the average number of indirect fire missions directed toward each company of the attacking force. The subroutine calculates the number of companies surviving in the attacking force and then determines the average number of indirect fire (artillery, mortar, and MLRS/MRL) missions being sustained by the advancing companies. A maximum suppression level of 40 percent degradation in movement can be achieved by an average of six missions in 30 minutes falling on a maneuver company. The following equation is used to calculate movement suppression from indirect fire:

$$Ceqt = \left(\sum_{i=1}^{20} M_i * Nt_i + \sum_{i=36}^{47} M_i * Nt_i / 8 \right) / 28 \quad (\text{Eq. 6-10})$$

where:

$Ceqt$ = the number of company equivalents in the attacking force at a particular time.
 M_i = mask set to 1, if the i th element is found in a maneuver company; 0 otherwise.
 Nt_i = the number of attacker elements of type i surviving at a particular time.
 28 = the number of direct fire elements ($i = 1$ to 20) plus infantry ($i = 36-47$) approximating a DIME company unit.

The number of indirect fire missions is given by:

$$I_{dm} = \frac{\sum_{i=1}^7 (A_{i,1} + A_{i,2})_{ARTY}}{1.8} + \frac{\sum_{i=8}^{11} (A_{i,1} + A_{i,2})_{MORT}}{1.2} + \frac{\sum_{i=12}^{15} (A_{i,1})_M}{1.8}$$

(Eq. 6-11)

where:

- I_{dm} = the number of indirect fire missions falling on the attacking force this 30 minutes.
- $(A_{i,1} + A_{i,2})_{ARTY}$ = the total tonnage for artillery missions of prep and close support falling on the attacker during these 30 minutes. Note that 1.8 tons fired represents one artillery mission.
- $(A_{i,1})_M$ = the total tonnage for multiple rocket launcher missions of prep fired at the attacker during these 30 minutes. Note that 1.8 tons fired represents one MRL mission. To calculate I_{dm} for Blue, replace tonnages with Blue amounts.
- $(A_{i,1} + A_{i,2})_{MORT}$ = the total tonnage for mortar missions of prep and close support fired at the attacker during these 30 minutes. Note that 1.2 tons represents one mortar mission.
- A_{ij} = is as defined by Eq. 6-7.

The suppressive effects on movement by indirect fire is given by:

$$P_{sid} = R_{bf} * \text{MIN} (I_{dm}/C_{eqt} * 6, 1) \quad (\text{Eq 6-12})$$

where:

- P_{sid} = the fraction of force movement suppressed these 30 minutes due to indirect fire.
- R_{bf} = the maximum fraction of movement suppression due to indirect fire for the attacking force (Blue attacker 0.4; Red attacker 0.3).

(c) Movement suppression from attack helicopter. Movement is also suppressed by attack helicopters. The subroutine considers a maximum suppression of 30 percent of the force movement rate if one helicopter has been allocated to each 12 vehicles of the attacking force. The movement degradation is determined by the following expression:

$$V_a = \sum_{i=1}^{20} N_{t_i} \quad (\text{Eq. 6-13})$$

where:

V_a = the number of maneuver vehicles in the attacking force which are potential targets for helicopter engagement.
 N_{t_i} = number of elements i in the attacking force surviving at a particular time.

$$P_{sh} = 0.3 * \text{MIN} (12 * H_n/V_a, 1) \quad (\text{Eq. 6-14})$$

where:

P_{sh} = the fraction of the advance rate suppressed by the helicopters.
 H_n = The number of defender helicopters currently attacking the defensive force.

The effective movement rate for this 30-minute period then becomes:

$$R_{30} = (1 - P_{sc} - P_{sid} - P_{sh}) * R_m \quad (\text{Eq. 6-15})$$

where:

R_{30} = the movement rate for these 30 minutes (meters per 30 minutes).
 R_m = the unsuppressed movement rate. This rate is a function of mounted/dismounted, day/night, mission, and terrain. Given in meters per 30 minutes.

(3) The actual distance moved by the force during the next 30-minute period is determined in subroutine Mine_encounter. This code projects the unimpeded force movement and then determines which, if any, minefields will be encountered by the attacking force as it advances this 30-minute period. If a minefield is encountered, the subroutine delays the force at the edge

of the minefield until it has opened the minefield. The force uses two tactics to open the minefield. The more cautious breach tactic is used when the trapped force finds itself under the following conditions:

(a) The attacking unit is beyond direct fire range, i.e., still in the phase I artillery battle (30-minute maximum delay).

(b) The attacking unit has suffered attrition to within five percent of its tactical break point (45-minute maximum delay).

The bolder bull tactic occurs only if the attacker finds himself delayed within direct fire range of the defender. In this case, the maximum delay time is only 10 minutes. However, the choice of the bull tactic penalizes the attacker more heavily in systems lost to mines. After selecting the proper clearing tactic, subroutine Mine_encounter assesses the actual delay using the following expression:

$$D_m = M_d * M_w * F_d / S_w \quad (\text{Eq. 6-16})$$

where:

D_m = the delay (minutes) of the attacking force as it clears the minefield.

M_d = maximum delay to clear a minefield affecting the entire force (minutes).

M_w = width of the minefield (km).

S_w = width of the maneuverable sector channelizing the attack (km).

F_d = fraction of the force entering the minefield.

After assessing the mine delay in Mine_encounter, subroutine Calc_movement then determines the actual advancement for this 30-minute period using the following set of equations:

$$D = 30 - \text{MIN} (D_m + D_m', 30) \quad (\text{Eq. 6-17a})$$

$$M_m = \begin{cases} R_{30} * D ; \text{ for Phases I or III} \\ \text{MAX} \left(2, \left[\frac{R_{30} * D + 250}{500} \right]_I \right) ; \text{ For Phase II} \end{cases} \quad (\text{Eq. 6-17b})$$

$$M_{30} = M_m * 500 \quad (\text{Eq. 6-17c})$$

where:

- M_{30} = the movement for this 30-minute period (meters).
 D_m = any mine delay from the previous 30 minutes extending into this 30-minute period (minutes)
 $(R_{30} * D + 250)/500_I$ = indicates truncation to integer form.

Note that equations 6-17 have two implications for the attacking force finding itself in phase II:

- (1) The force can advance no more than 1 km during a 30 minute period.
- (2) If the force cannot move 250 meters or more, it is considered stationary.

6. "UNITFILE" IMPACT.

The ground combat program takes the kills associated with mines, indirect fire, direct fire, helicopters, PGMs, and infantry and deducts them from "UNITFILE" positions 1 to 70. Associated ammunition/fuel consumption is updated within the "UNITFILE". Ground combat attrition modules (discussed in following sections) return kills and ammunition consumption to this ground combat driver and are then updated to the "UNITFILE".

7. CODE.

A. Following the allocation and movement calculations discussed in paragraph 5 of this chapter, the ground combat program moves to one of three subroutines which drive the attrition algorithms for each phase. Although the methodology used in the code for the selection of a battle phase is not complex, it should be noted that this point represents a critical transfer of control in the DIME code structure. Once the phase is selected, the phase drivers (subroutines Phase1_bt1, Phase2_bt1, and Phase3_bt1) are structured as shown in Figure 6-7. They have been written with considerable redundancy which was designed for ease of phase modification and debugging. The phase driver subroutines are as follows:

(1) Phase1_bt1. The movement to contact phase, found in the code in Table 6-14, drives the attrition algorithms for this part of the battle. See paragraph 2D(1) for a description of phase I. Attrition available to this phase is as follows:

- (a) Minefield attrition.
- (b) Indirect fire (artillery) attrition.
- (c) Direct fire attrition (15-minute contact).
- (d) Helicopter attrition.
- (e) Precision-guided munition (PGM) attrition.

The order of attrition does not change. If a type of attrition does not take place, it is skipped and attrition proceeds in order.

(2) Phase2_bt1. The direct fire phase drives the attrition algorithms for this portion of the battle. See paragraph 2D(2) for a description of phase II. Attrition available to this phase is similar to phase I with the following exceptions:

(a) Direct fire occurs for 30 minutes in phase II.

(b) The infantry attrition module is engaged after PGMs if forces are within 500 meters of each other.

(3) Phase3_bt1. The withdrawal phase drives the attrition algorithms for this part of the battle. See paragraph 2D(3) for a description of the withdrawal phase. Attrition available to this phase is as follows:

- (a) Indirect fire.
- (b) Delivery of smoke for withdrawal.
- (c) Direct fire.
- (d) Helicopter attrition.
- (e) Precision-guided munitions (PGMs).
- (f) Infantry attrition if within 500 meters.

B. Each type of attrition exists as separate modules within the ground combat code.

(1) In order to prepare for the minefield attrition module, subroutine Run_mine is called by the phase driver (Phase1_bt1 or Phase2_bt1). Subroutine Run_mine mounts or dismounts troops, corrects the number of dismounted infantry, and keeps track of infantry kills on carriers as it sends needed parameters to the minefield attrition module (Mines). For more information on the minefield module, see Section I of this chapter.

(2) Indirect fire module preparation begins with the calling of subroutine Arty_sub by the phase driver (Phase1_bt1, Phase2_bt1, or Phase3_bt1). Arty_sub prepares and sends needed parameters to the artillery attrition module while keeping track of current mounted and dismounted troops. The artillery module, Arty_atrit, is a module of Arty_sub. A complete description of the module and subroutine Arty_sub may be found in Section II of this chapter.

(3) Artillery/mortar-delivered white phosphorous smoke may be allocated to degrade the visibility of the withdrawing force. Degradation of visibility reduces the amount the withdrawing force can be seen as targets in direct fire combat. The smoke is allocated during the artillery allocation discussed in paragraph 5. The percent of frontage visible through a smoke screen is calculated by the smoke module and later used by the direct fire module during withdrawal. For a complete discussion of the smoke allocation, smoke module, and its effects in the direct fire module, refer to Section III of this chapter.

(4) Section IV of this chapter is devoted to direct fire attrition. The phase driver, after preparing some of the parameters, calls subroutine Df_cbt. This subroutine prepares more parameters, including the current number of mounted and dismounted troops, and sends them to the Df_attrition module.

(5) The helicopter module is called directly from the phase driver. This means all parameter preparation (including mounted/dismounted troops) is included in the phase driver subroutines. The duplication in each phase should be noted and remembered in case of code changes. The helicopter module, itself, is discussed thoroughly in Section V of this chapter.

(6) In order to prepare for the PGM attrition module, subroutine Clgp_gamp_atrit is called by the phase driver (Phase1_btl, Phase2_btl, or Phase3_btl). Subroutine Clgp_gamp_atrit mounts or dismounts troops, corrects the number of dismounted infantry, and keeps track of infantry kills on carriers as it sends needed parameters to the Pgm_atrit module. A complete description of the PGM module may be found in Section VI of this chapter.

(7) Preparing for the infantry attrition module, subroutine Infantry_cbt is called by the phase driver (Phase2_btl, or Phase3_btl). Subroutine Infantry_cbt helps keep track of the current number of dismounted infantry and sends needed parameters to the infantry module. For more information on the infantry module, see Section VII of this chapter.

C. During the preparation for each module, excluding smoke, the current number of mounted and dismounted troops is calculated. To do this, two other modules are accessed. The Dismounted module is called during the preparatory phase of attrition module calling. This module, in turn, calls the Load_infantry module.

(1) Dismounted. This module checks the force's mission and distance from opponent. When in a defensive mission (hasty, prepared, reserve, or ambush), all troops are dismounted. A frontal attack mission within 600 meters of the enemy also calls for dismounted troops. If mounted troops are possible, the Load_infantry module is called to determine the number of infantry personnel per carrier. The number of mounted troops is calculated by multiplying the total number of carriers times the personnel per carrier. The remaining troops (the beginning infantry minus the number of mounted) are left to be dismounted.

(2) Load_infantry. In order to calculate the number of personnel per carrier, a check is made for the mission. A defensive mission has a load factor of zero, so that all the troops remain dismounted. If the force has an attacking mission, the load factor is the minimum of the total number of infantry divided by the number of carriers, or eight, which is the maximum load factor.

(3) The subroutines which prepare the parameters for the attrition modules save the original number of infantry. This is then replaced by the number of dismounted troops before the number of system elements are sent to the modules. Upon return from the modules, the load factor times the number of personnel carriers killed is added to the total number of infantry killed. The saved number of infantry minus the total number of infantry killed now becomes the current number of infantry personnel.

D. The ground combat driver's subroutines and their primary variables are contained in Table 6-5. A listing of P4 code appears in Table 6-14.

Table 6-5. Subroutine table for ground combat/driver routine

Functional area(s): <u>Ground combat attrition program (P4)</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read_data	Reads small arrays into programs from data statements.	A. Sys_eff (I,J)	Firepower score for system J (1-70) of side I (1 = Blue, 2 = Red)
		B. Wpn_typ (I)	Contains the weapon type for weapon I (1-70). (1 = DF, 2 = IF, 3 = AD)
		C. Ammo_wt (I,J)	Packaged weight (in tons) of individual round /burst of ammo I - 1 = Blue, 2 = Red J - 1 - 70 elements
		D. Arty_30min_wt (I,J)	Contains the weight in short tons that one gun can deliver firing at a sustained rate for 30 minutes (packaged ammo). I - 1 = Blue, 2 = Red J - 1 - 7 = artillery, 8 - 11 = mortars, 12 - 15 = MLRS/MLR
		E. A_wt (I,J)	Weight of artillery round/ packaged weight I - 1 = Blue, 2 = Red J - 1 - 7 = artillery, 8 - 11 = mortars, 12 - 15 = MLRS/MLR
		F. Bf_mask (I) Rf_mask (I)	Mask for selecting forward elements. I = 1-70; If value is 1, element used; if 0, not used
		G. Rdf_mask (I) Rdf_mask (I)	Mask for elements in DF battle. I = 1 - 70, value is 1 or 0.
		H. Ds_start	Start range for artillery DS (close SPT). I = 1 - 4.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<u>Functional area(s):</u>	<u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Zero_out (continued)					
				J. Sys_tot (I,J)	Keeps the current status of the forces in combat for element J. If I = 1 - Initial Blue system. = 2 - Final Blue system. = 3 - Initial Red system. = 4 - Final Red system.
				K. B_init (I,J) R_init (I,J)	Initial unit systems by unit I, system J. (I = 1-12; J = 1-70.)
				L. B_init (I3,J) R_init (I3,J)	Holds total weapons for this flight. (J = 1-70.)
				M. Minefield (I,J)	I = 1 to 3 minefields. J = 1 - minefield range = 2 - width of minefield (km) = 3 - width of sector (km) = 4 - % bypassed = 5 - % entering minefield = 6 - minefield assessment 0 = unused minefield 1 = used minefield
				N. Time_seg	Number of the current 30 minute time segment.
				O. Last_bahl_seg Last_bah2_seg Last_bsct_seg Last_rah1_seg Last_rah2_seg Last_rsct_seg	Time segment when helicopter was last flown.
				P. Bahl_seg Bah2_seg Bsct_seg Rah1_seg Rah2_seg Rsc2_seg	Number of helicopter missions flown when 3 cells are used.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s):	Ground combat attrition program (P4)		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Zero_out (concluded)		Q. B_dsarty_fire (I) R_dsarty_fire (I)	Number of tons of artillery ammo fired in CS mission (I = 1 - 7).
		R. B_dsmort_fire (I) R_dsmort_fire (I)	Number of tons of mortar ammo fired in CS mission (I = 1 - 4).
		S. Barty_fire Rarty_fire	Number of 30 minute segments Red has been under Blue artillery fire.
		T. Mine_delay	Time delay due to mines.
		U. Bif_msn_tons (I,J) Rif_msn_tons (I,J)	Contains tons of ammo available this 30 minute segment by weapon type I (1 - 15) on mission type J (1 - 5).
		V. B_con (I,J) R_con (I,J)	Percentage of total number of elements of system J (1 - 70) provided by unit I (1 - 12).
Set_battle	Allows input of the sector worksheet Determines Blue element percentages. Calculates Red target parameters.	A. B_msn (I) R_msn (I)	Blue mission Red mission.
		B. Mift (I)	Percent of systems in unit I that can be engaged by combat systems in the indirect fire battle (I = 1 - 20).
		C. Mdft (I)	Percent of systems in unit I that can be engaged by combat systems in the direct fire battle (I = 1 - 20).
		D. Mifdt (I)	Rate of change representing percent of elements of unit I that can be introduced/extracted from the IF battle per 30 minute interval while maintaining the same mission (I=1-20)

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): <u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Set_battle (continued)		E. Mdfdt (I)	Rate of change representing the percent of elements of unit I that can be introduced/extracted from the direct fire battle per 30 minute interval, while maintaining the same mission (I = 1 - 20).	
		F. Mfire (I)	Percent of systems in unit I that can effectively fire in battle (I = 1-20).	
		G. Mdfire (I)	Rate of change representing the percent of elements of unit I that can effectively fire and which can be introduced into the battle every 30 minutes (I = 1-20).	
		H. Mvul (I)	The fraction (0 - 1.0) of a system in unit I that is fully exposed to direct fire. (I = 1-20).	
		I. Mdvul (I)	Percent increase/decrease in the vulnerability of a system in unit I on a particular mission (I = 1-20).	
		J. B_if_t (I,E) R_if_t (I,E)	The percent of systems that can be engaged by combat systems in the indirect fire battle for unit E on a mission for 3 hour segment I.	
		K. B_df_t (I,E) R_df_t (I,E)	The percent of systems that can be engaged by combat systems in the direct fire battle for unit E on a mission for 3 hour segment I.	

Table 6-5. Subroutine table for ground combat/driver routine (continued)

'Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Set_battle (concluded)		L. B_if_dt (I,E) R_if_dt (I,E)	The rate of change representing the number of elements engaged in combat and under indirect fire for unit E on a mission for 3 hour segment I.
		M. B_df_dt (I,E) R_df_dt (I,E)	The rate of change representing the number of elements engaged in combat and under direct fire for unit E on a mission for 3 hour segment I.
		N. B_f (I,E) R_f (I,E)	Percent of systems of unit E on mission I that can effectively fire in battle.
		O. B_df (I,E) R_df (I,E)	Rate of change representing the percent of elements of unit E on mission I that can effectively fire in battle.
		P. B_v (I,E) R_v (I,E)	Percent of unit E fully exposed while on mission I.
		Q. B_dv (I,E) R_dv (I,E)	Change in percent of unit E fully exposed while on mission I.
		R. B_type (I) R_type (I)	Unit type (I = 1-12).
Ready_load	Ready infantry and direct fire loads.	A. Sum_inf B. Sum_df	Sum of infantry which will be mounted. Sum of the direct fire carriers designated as infantry carriers.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s):	Ground combat attrition program (P4)	
<u>Subroutine called</u>	<u>Subroutine function(s)</u> <u>Primary variables</u> <u>Variable descriptions</u>	
L1	Enters the first line of data for starting the battle.	
L2	Sets up the Blue units fighting the battle; calculates Blue ammo available.	<p>A. Bada_hnd (I) Fraction of Blue hand-held AD elements suppressed in unit I.</p> <p>B. Bada_veh (I) Fraction of Blue vehicular AD elements suppressed in unit I.</p> <p>C. If_ammo (J) Number of tons of ammo available for current battle for: J = 1 - 7 artillery 8 - 11 mortar 12 - 15 MLRS/MRL</p>
L3	Sets up the Red units committed to battle; calculates Red ammo available.	<p>A. Rada_hnd (I) Fraction of Red hand-held AD elements suppressed in unit I.</p> <p>B. Rada_veh (I) Fraction of Red vehicular AD elements suppressed in unit I.</p>
Ad_sup	Calculates percentages of air defense elements suppressed; calculates Red and Blue target parameters.	<p>A. Bhnd_sup Fraction of all Blue/Red hand-held AD elements suppressed.</p> <p>B. Bveh_sup Fraction of all Blue/Red vehicular AD elements suppressed.</p> <p>C. Tot_init_1 Initial total number of vehicle type AD weapons for a certain sector unit.</p> <p>D. Tot_init_13 Initial total number of vehicle type AD weapons for the battle.</p>

Table 6-5. Subroutine table for ground combat/driver routine (continued)

'Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
L4	Enter battle parameters	A. Init_rg B. Df_rg C. No_minefields	Initial range (in meters). Direct fire range (in meters). Number of minefields.
L5	Enter weather conditions		
L6	Enter side attacking		
L7	Enter Blue mission data	A. B_terr B. B_rg_break C. B_pct_fwd D. B_mopp E. T_length (I) F. T_width (I) G. B_break_t (I) H. B_cas_break	Blue terrain type (1-5) Range (m) at which Blue must break. Percent of Blue force forward. Mopp fatigue degradation. Length of sector Width of sector. Amount of time Blue will fight before breaking. Percent of casualties at which Blue will break.
L8	Enter Red mission data	A. R_terr B. R_rg_break C. R_pct_fwd	Red terrain type (1-5). Range (m) at which Red must break. Percent of Red force forward.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
L8 (concluded)		D. R_mopp E. T_length (I) F. T_width (I) G. R_break_t (I) H. R_cas_break	Mopp fatigue degradation. Length of sector Width of sector. Amount of time Red will fight before breaking. Percent of casualties at which Red will break.
L9	Enter Blue helicopter data	A. B_helo (I,J)	Data of type J = 1 # of helo = 3 # of cells for helicopter I = 1 Blue type 1 attack helo = 2 Blue type 2 attack helos = 3 Blue Scouts
		B. B_helo_atkprof(I)	Blue helo type I (I=1-2) attacker profile where 1 = missiles 2 = missiles and guns 3 = guns 4 = air-to-air missiles 5 = air-to-air and ground missiles 6 = air-to-air, ground missiles & guns 7 = air-to-air missiles and guns
		C. B_helo_delay	Time helicopter is at large from start of battle until it enters the battle.
		D. B_helo_rg_delay	Range at which helicopters are to enter battle (0= none, otherwise input in m).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<p>'Functional area(s): <u>Ground combat attrition program (P4)</u> L9 (Concluded)</p>		<p>E. B_helo_msn(I) Mission for Blue helo of type I (I = 1-2): 1 = air-to-ground mission 2 = air-to-air mission 3 = SEAD mission</p>
<p>L10</p>	<p>Enter Red helicopter data</p>	<p>F. B_atk_rg(I) Standoff range (meters) of Blue helicopter type I (I=1-2)</p> <p>A. R_helo (I,J) Data of type J = 1 - # of helos = 2 - # of helo cells. for helicopter I = 1 - Red type 1 attack helo = 2 - Red type 2 attack helos = 3 - Red Scouts</p>
	<p>B. R_helo_atkprof(I)</p>	<p>Red helo type I (I=1-2) attacker profile</p>
	<p>C. R_helo_delay</p>	<p>Time helicopter is at large from start of battle until it enters the battle.</p>
	<p>D. R_helo_rg_delay</p>	<p>Range at which helicopters are to enter battle (0= none, other- wise input in m).</p>
	<p>E. R_helo_msn(I)</p>	<p>Mission for Blue helo of type I (I = 1-2): 1 = air-to-ground mission 2 = air-to-air mission 3 = SEAD mission</p>
	<p>F. R_atk_rg(I)</p>	<p>Standoff range (meters) of Blue helicopter type I (I=1-2)</p>

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
L11	Enter Blue artillery data	A. Bif_msn (I)	Contains the percent of IF tonnage to be allocated to individual mission I.
		B. B_prep_time	Time Blue will begin preparation for battle. Input as hhmm, with hh = the hour and mm - the minutes after start time the preparation begin.
		C. No_gamp	Number of GAMP available.
		D. No_clgp	Number of CLGP available.
		E. Perc_gamp	Percentage of all IF tonnage filled by GAMP.
		F. Perc_clgp	Percentage of all IF tonnage filled by CLGP.
L12	Enter Red artillery data	A. Rif_msn (I)	Contains the percent of IF tonnage to be allocated to individual mission I.
		B. R_prep_time	Amount of time after start time that Red will begin preparation for attack.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s):	Ground combat attrition program (P4)		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Laines	Enter minefield data	Minefield (I,J)	Contains minefield information where: I: (1-3) minefields J: 1 = minefield range 2 = minefield width 3 = sector width 4 = percent of forces entering minefields.
Set_print	Prints out initial battle data, including who is attacking, the type of mission, the type of terrain, helicopter information and other pertinent data.		
Set_conditions	Set up battlefield conditions. Set indirect fire mission tonnages for 6 hour battle. Set direct support artillery/mortar parameters.	A. B_cbt_eff R_cbt_eff B. Btl_time C. Max_btl_time	Current Blue/Red firepower score. Current time on the battlefield (in 30 minute intervals). The latest possible time for the battle to stop.
		D. Btl_rg	Current range between forces on the battlefield.
		E. First_bnd	Initial range band (1-6) for DF.
		F. Gamp_avail	Number of GAMP available for the current battle.
		G. Clgp_avail	Number of CLGP available for the current battle.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): <u>Ground combat attrition program (P4)</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Set_conditions (concluded)			
	H. B_dsmort_brkrgr R_dsmort_brkrgr		End range for CS mortar support.
	I. B_dsarty_brkrgr R_dsarty_brkrgr		End range for CS artillery support.
	J. B_dsmort_start R_dsmort_start		Start range for CS mortar support.
	K. B_dsarty_start R_dsarty_start		Start range for CS artillery support.
	L. B_ds_conc_pt R_ds_conc_pt		Point (meters) to begin concentrated artillery fire prior to break
	M. B_mo_conc_pt R_mo_conc_pt		X-point at knee of CS curve
	N. B_mo_conc_level B_ds_conc_level R_mo_conc_level R_ds_conc_level		Y-point at knee of CS curve.
	O. B_p30_artyrgr R_p30_artyrgr B_p30_mortrgr R_p30_mortrgr		Battle range at end of previous 30 minute period.
	P. Advance_rate (I,J)		Maximum rate of advance (meters per minute for force on mission J and advance type: I = 1 advance mounted during phase I. = 2 advance dismounted during phase I. = 3 withdraw mounted during phase III. = 4 withdraw dismounted during phase III.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Print_sys_out	Prints out data on specified system	S (I)	Array used to print out data on weapon system elements (I = 1-70).
Control_battle	Calculates attrition assessments for ground battle. Update battle time. Set attack helicopter arrivals.	A. Saty (I) B. Tot_volley (I) C. Volley (I,J) D. Amt_of_advance	Tons of ammo available this 30 minute segment by weapon type I (1-15) on all missions. Total number of rounds fired by weapon type I for all missions. (I = 1-15). Number of rounds fired by weapon type I on mission J. (I = 1-15). Distance moved in meters.
Print_eff	Prints the current effectiveness of Blue and Red forces.	A. B_eff_pt R_eff_pt	The current effectiveness of the entire Blue/Red force.
Print_volleys	Prints data on amount of ammunition used.		
Print_init_res	Prints out initial unit status.		
Print_fin_res	Prints out final battle results.		

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<u>Functional area(s):</u> <u>Ground combat attrition program (P4)</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Subroutine called</u>			
Chk_brk_pt	Checks for battle breakpoints.		
Tally_cbt_eff	Calculates the adjusted firepower score.	A. Prev30_b_eff Prev30_r_eff	Firepower scores for the previous 30 minute segment for entire Blue/Red force in combat.
Apport_wri_loss	Writes unit status to history file.	A. Bif_left Rif_left	Contains total tons of ammo left available for all weapon types and missions.
		B. Bif_ammou_used Rif_ammou_used	Total tons of ammo used this 30 minute segment by all weapon types for all missions.
		C. N (*)	Represents the 150 elements from 1 record of the UNITFILE.
		D. B_df_ammou_used R_df_ammou_used	Tons of direct fire ammo used in this 30 minute segment of battle.
		E. B_ad_used R_ad_used	Tons of air defense ammo used in this 30 minute segment of battle.
		F. Ci_kv_b (I,J) Ci_kv_r (I,J)	Cumulative killer/victim matrix for entire game with killer J and victim I.
		G. Ci_helo_b (I,J) Ci_helo_r (I,J)	Cumulative data on helicopters for entire game (same format as B_helo).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo_arrive	Calculates the attack helicopters available this period.	A. Bahl B. Bah2 C. Bsct	Number of Blue type 1 attack helos attacking this segment. Number of Blue type 2 attack helos attacking this segment. Number of Blue scouts attacking this segment.
		D. Rah1 E. Rah2 F. Ract	Number of Red attack helicopters in cell 1 attacking this segment. Number of Red attack helicopters in cell 2 attacking this segment. Number of Red scouts attacking this segment.
		G. Earliest_time H. Helo	Earliest possible arrival time of helicopters. The number of helicopters which will arrive on station.
Chk_delay_time	Calculates delay times for helicopters.		
Ammo_breakdown	Apportions ammunition for use by weapon systems.	A. Sys_amm (I)	Ammo weight for each indirect element per 30 minutes. J = 1 - 7 artillery 8 - 11 mortar 12 - 15 MLRS/MRL

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Arty_arrive	Calculates incoming artillery. Updates artillery capacity for tonnage not used. Schedule incoming prep fires. Allocate mortar fires for prep. Allocate prep fires for artillery pieces. Allocate prep fires for MLRS pieces. Allocate CLGP missions. Schedule incoming direct support fires. Schedule incoming counter fire missions. Schedule incoming interdiction missions.	A. B_vis (I) R_vis (I) B. B_arty_cap (I,J) R_arty_cap (I,J) C. B_mlrs_cap (I,J) R_mlrs_cap (I,J) D. B_mort_cap (I,J) R_mort_cap (I,J) E. Int_bmort Int_rmort F. Tot_arty (I,J) G. B_clgp_cap (I) H. B_gamp_cap (I)	Visibility percent (0-1.0) for weapon type I. Total weight of ammo which can be shot by artillery (I) in the current 30 minute segment for mission J (J=1-5; I=1-4). Total weight of ammo that can be shot by MLRS/MLR (I) in the current 30 minute segment for mission J (J=1-5; I=1-4). Total weight of ammo which can be shot by mortars (I) in the current 30 minute segment for mission J (J=1-5; I=1-4). Tons of ammunition available to mortars at beginning of segment. Subtotal of amount of ammo delivered per 30 minutes (I=1-2; J=1-15). Weight of ammo available to CLGP in this 30 minute segment (I = 1-7). Weight of ammo available to GAMP in this 30 minute segment (I = 1-4).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): <u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Arty_arrive (continued)			I. Tot_clgp	Total weight of ammo available to CLGP in current 30 minute segment.
			J. Tot_gamp	Total weight of ammo available to GAMP in current 30 minute segment.
			K. Cloud_ht	Cloud height over battle area (in meters).
			L. B_smk_cap (I) R_smk_cap (I)	Total weight of ammo which can be shot for smoke in current 30 minute for weapon type I where I = 1 - 7 artillery 8 - 11 mortar
			M. B_smk_tons(I) R_smk_tons(I)	Total weight of ammo which can be shot for smoke in current 30 minute for weapon type I where I = 1 - 7 artillery 8 - 11 mortar
			N. A_ammo_ton	Total artillery ammo tonnage for smoke.
			O. M_ammo_ton	Total mortar ammo tonnage for smoke.
			P. B_asmk_used (I) B_msmk_used (J)	Tons of artillery/mortar ammo actually fired for smoke in current 30 minute segment by Blue (I=1-7; J=1-4).
			Q. R_asmk_used (I) R_msmk_used (J)	Tons of artillery/mortar ammo actually fired for smoke in current 30 minute segment by Red (I=1-7; J=1-4).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Arty_arrive (continued)			
R. Smoke_used			Total arty or mortar tonnage actually used to emplace smoke.
S. Prep_time			The amount of time after start time that the attacker will begin preparation.
T. Int_fire_time			Time the fire can begin in the battle.
U. Prep_fire_time			The Int_fire_time, rounded off to the nearest 30 minutes.
V. Bif_fired (I,J) Rif_fired (I,J)			Tons of ammo fired this 30 minute segment by weapon type I on mission J.
W. B_dsarty_avail (I) R_dsarty_avail (I)			Tons of arty ammo available for CS arty support (I=1-7).
X. B_dsmort_avail (I) R_dsmort_avail (I)			Tons of mortar ammo available for CS mortar support (I=1-4).
Y. Tot_ds_avail			Total tons of artillery ammo available for CS artillery support.
Z. Clgp_msns			Number of CLGP missions flown.
AA. Camp_msns			Number of CAMP missions flown.
BB. Frac_arty (I)			Fraction of artillery ammo available that was fired (I = 1-7).
CC. Tons_avail			Total tons of ammo available this 30 minute segment.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Arty_arrive (concluded)		DD. Arty_bound	Maximum percentage of artillery ammo that can be fired on this mission.
		EE. Mine_hit	Number of minefields encountered that had not been assessed before.
		FF. Ds_attempted (I)	Tons of artillery fired in an attempt to provide direct support (I=1-7).
		GG. Frac_mort (I)	Fraction of mortars available which were fired (I=1-4).
		HH. Mort_bound	Maximum percentage of mortar ammo that can be fired on this mission.
		II. Mo_attempted (I)	Tons of mortar fired in an attempt to provide mortar support (I=1-4).
Calc_movement	Calculates attacker movement distances during the designated 30 minute period.	A. Move_minutes B. Mission C. Phase D. M_per_minute E. Unsupp_advance	Minutes of unsuppressed advance movement. Pointer for which side is attacking. Phase of the battle. Unsuppressed advance rate for this mission. Distance of unsuppressed advance (= Move_minutes times M_per_minute).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calc_movement (continued)			
F. Casualty_level			Level of casualties for previous 30 minutes.
G. Prev30_r_eff			Level of Red effectiveness for previous 30 minutes.
H. Prev30_b_eff			Level of Blue effectiveness for previous 30 minutes.
I. Cas_suppr			Suppression from casualties.
J. Tot_systems			The total number from 10 elements, of forces in contact for one side.
K. Incoming_arty (I)			Amount of incoming artillery (I=1-7).
L. Incoming_mlrs (I)			Amount of incoming MLRS (I=1-4).
M. Incoming_mort (I)			Amount of incoming mortars (I=1-4).
N. Arty_equiv			The 155mm mission equivalent of incoming artillery.
O. Mort_equiv			The 155mm mission equivalent of incoming mortars.
P. Mlrs_equiv			The 155mm mission equivalent of incoming MLRS.
Q. Tot_incom_msn			Total amount of incoming mission (sum of Arty_equiv, Mort_equiv Mlrs_equiv).
R. Arty_level			Level of the artillery.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calc_movement (concluded)		S. Company_equiv T. Arty_suppr U. Tot_vehicles V. Atk_helos W. Atk_helo_level X. Atk_helo_suppr Y. Tot_move_suppr	Number of company equivalents. Amount of artillery suppression. Total number of vehicles. Number of attack helicopters attacking this segment. Attack level of helicopters. Suppression level of helicopters. Total level of suppression of movement (the sum of Las_suppr, Arty_suppr and Atk_helo_suppr).
Mine_encounter	Checks for mine activation	A. Bul_bch B. Max_delay	= 1 bull tactic, pushing through forcefully, minimizing time. = 2 breach tactic, clearing passage-way, minimizing losses. Maximum time of delay.
Phase1_bt1	Conducts the attrition assessment for the Phase 1 battle.	A. Blue_aty B. Red_aty C. A_pct_fwd D. D_pct_fwd E. D_fp	Fireflag for Blue artillery (0= no Blue arty this 30 minutes; 1= Blue arty this 30 minutes). Fireflag for Red artillery. Percentage of attackers forward. Percentage of defenders forward. Defender's percent of effectiveness.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Phase1_bt1 (continued)			
		F. Sys(I,J)	A work array passing J = 1-70 elements to the subroutines. Sys (1,J) = Initial number of Blue targets. Sys (2,J) = Final number of Blue targets. Sys (3,J) = Initial number of Red targets. Sys (4,J) = Final number of Red targets. Sys (5,J) = Initial number of Blue fires. Sys (6,J) = Final number of Red fires.
		G. Blue_vul (I)	Array containing Blue vulnerability.
		H. Red_vul (I)	Array containing Red vulnerability.
		I. Rng_band	Range band: = 1 engagement at 1 - 500 m. = 2 engagement at 1000 m. = 3 engagement at 1500 m. = 4 engagement at 2000 m.
		J. Terrain	Terrain type; dependent on the attacker's terrain.
		K. Num_bands	Number of range bands.
		L. P_def (I)	Array containing percent of elements defending (I = 1-70).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): Ground combat attrition program (P4)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Phase btl (continued)			
		M. Cell (1,J)	Array containing initial number of element J helicopters.
		Cell (2,J)	Array containing remaining number of element J helicopters.
		N. Arty	Pointer for artillery type.
		O. Time_step	Interval of time in this phase in minutes.
		P. Adside	Pointer to AD side (1 = Blue; 2 = Red).
		Q. Ad_ammo	Total tons of ammo for AD.
		R. Ad_helo	Number of AD helicopters.
		S. Sided	Pointer to side (1 = Blue; 2 = Red).
		T. Target (1,J)	Array containing initial number of target systems of type J.
		Target (2,J)	Array containing remaining number of target systems of type J.
		U. H_targ (1,J)	Array containing initial number of helicopter targets of type J (J = 1-70).

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s): <u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>	
Phase1_bt1 (concluded)	V. R_dmount			Number of Red dismounted infantry.	
	W. Sys_helo (I,J)			Array containing element losses to helicopters (I = 1 - Blue killed; 2 - Red killed).	
	X. R_ld_fact			Number of Red personnel in carrier.	
	Y. B_ld_fact			Number of Blue personnel in carrier.	
	Z. Inf_surv (I)			Number of mounted infantry which survived (I = 1-5).	
	AA. B_ms			Pointer to current Blue mission.	
	BB. B_dmount			Number of Blue dismounted infantry.	
	CC. Gamp_fact (I)			Array containing percent of the 70 elements at which GAMP may fire.	
	DD. Clgp_fact (I)			Array containing percent of the 70 elements at which CLGP may fire.	
	Phase2_bt1	A. Del_30	Assesses attrition rate in Phase 2, direct fire		Delay flag for 30 minute delay.
		B. Red_fct			Red factor for element I, involving the percent of Red forces which are firers, and the change in that percent every 30 minutes.
		C. Blue_fct			Same as Red_fct, but for Blue.
		D. Red_ft(*)			Array containing fraction of Red force which is a target for this 30 minutes.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s)	Subroutine function(s)	Primary variables	Variable descriptions
Phase2_bt1 (concluded)		E. Blue_f_t(*)	Array containing fraction of Blue force which is a target for this 30 minutes.
		F. Rdf_mask(*)	Mask for Red elements in DF battle.
		G. R_ms	Pointer to current Red mission (value 1 or 2).
		H. Cur_bnd	Current band entering.
		I. Num_bands	Number of range bands.
		J. T_conflict	Infantry conflict time (hours).
Phase3_bt1	Conducts attrition assessments for Phase 3, withdrawal.		
Phase_int	Initializes systems to zero	A. Sys_direct (I,J) B. Sys_pgm (I,J) C. Sys_inf(*)	Array containing participants and results of direct fire battle. (I = 1 - Blue killed; 2 - Red killed. J = 1-70 elements.) Array containing elements and results of pgm battle (J= 1 - 70 elements). Array containing elements of infantry battle.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

Functional area(s):	Ground combat attrition program (P4)	Subroutine function(s)	Primary variables	Variable descriptions
Phase_int (concluded)			D. Sys_mine (I,J)	Array containing elements entering and surviving minefields. I = 1 - Blue elements under attack. 2 - Blue elements surviving 3 - Red elements under attack. 4 - Red elements surviving. J = 1 - 70 elements.
			E. Sys_art (I,J)	Array containing elements in artillery battle. I = 1 - Blue elements under attack. 2 - Blue elements surviving 3 - Red elements under attack. 4 - Red elements surviving. J = 1 - 70 elements.
Updatek_v		Updates the killer-victim arrays for Blue and Red forces.		
Run_mine		Calculates the percent of force in the minefield	A. Mounted B. Dismounted	Number of mounted artillery. Number of dismounted artillery.
Arty_sub		Calculates Blue and Red elements target-able. Calculates artillery losses for Red and Blue.	A. R_dismounted B. B_dismounted	Number of Red dismounted infantry. Number of Blue dismounted infantry.
Df_cbt		Calculates Red and Blue losses due to DF combat. Updates amount of ammunition for Red and Blue DF.	A. Prnt_rg B. R_ammo_lst	Range at which present attackers must break. Amount of Red ammo used.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<u>Functional area(s):</u> <u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>	
Dbf_cbt (concluded)			C. B_ammo_list	Amount of Blue ammo used.	
			D. B_ammo_load	The load of ammo for Blue, involving the packed weight of the ammo and the number of Blue engagements.	
			E. R_ammo_load	The load of ammo for Red, involving the packed weight of the ammo and the number of Red engagements.	
			F. B_engagements (I)	Array containing the number of Blue engagements for direct fire element I (I = 1 - 20).	
			G. R_engagements (I)	Array containing the number of Red engagements for direct fire element I (I = 1 - 20).	
			H. B_inf_save (I) R_inf_save (I)	Array containing the number of infantry on direct fire carriers. (I = 1-5).	
			I. B_fire_sv (I) R_fire_sv (I)	Contains initial number of fires from the work array Sys. (I = 1-70).	
	W_smoke		Establishes the dimensions of the desired screen. Calls the Smk_emp routine. Returns the visibility through the screen and the amount of ammo used to emplace the screen.	A. S_time	Amount of time the screen will last. It equals 1.1 times the maximum amount of time before the side will break.
				B. B_msmk_left	Amount of smoke left fired by Blue mortars.
				C. B_asmk_left	Amount of smoke left fired by Blue artillery.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<u>Functional area(s):</u>	<u>Ground combat attrition program (P4)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>W_smoke</u> (concluded)				D. R_msmk_left	Amount of smoke left fired by Red mortars.
				C. R_asmk_left	Amount of smoke left fired by Red artillery.
<u>Infantry_cbt</u>			Calculates losses to Red and Blue infantry due to infantry combat.	A. Bstat (I) B. Attacker	1 = Blue mission; 2 = Red mission. Pointer to attacker. 1 = Blue; 2 = Red.
				C. Lossblue	Blue infantry losses in this combat.
				D. LossRed	Red infantry losses in this combat.
				E. Sum_inf_b Sum_inf_r	Total number of small arms.
<u>Clgp_gamp_attrit</u>			Attrition of CLGP and GAMP elements.	A. N_rnds (I)	Array containing the number of rounds. I = 1 - number CLGP rounds. = 2 - number GAMP rounds.
				B. Sens_type (I)	Array containing sensor type. I = 1 - CLGP = 2 - GAMP
				C. Fir_type (I)	Array containing fire type. I = 1 - CLGP = 2 - GAMP
				D. C_t (I,J) C_targ (I,J)	Array containing the number of targets at which CLGP and GAMP may fire.

Table 6-5. Subroutine table for ground combat/driver routine (continued)

<u>Functional area(s):</u>	<u>Ground combat attrition program (P4)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>		
Dump_input	Prints out information on Red and Blue units.		
Close_files	Closes the files to the main program.		

Section I. Minefield Attrition

1. PURPOSE.

The purpose of the DIME ground combat minefield attrition module is to calculate losses to 70 types of elements due to an encounter with a minefield in a sector battle.

2. GENERAL.

A. Minefield attrition is assessed for an attacking force encountering a minefield during phase I (pre-closure) and phase II (direct fire) of the sector battle.

B. The defender may emplace a maximum of three minefields per sector battle, simply by indicating the location (battle range) and the percent of the attacking force entering the minefield.

C. The minefield is emplaced using a ground-emplaced mine-scattering system (GEMSS) of two strips of mines each with a depth of 60 meters and a density of 0.007.

D. Two tactics may be used by the attacker in crossing the minefield in which the percentage of expected kills varies accordingly.

(1) Bull tactic, pushing through forcefully, minimizing time. This tactic occurs if the minefield is within direct fire range.

(2) Breach tactic, clearing passageway minimizing losses. This tactic occurs if the minefield is outside of direct fire range.

E. The formation of systems varies according to the phase of battle.

(1) Phase I (pre-closure). The systems entering have time to disperse and become less dense, forming more columns upon entering the minefield.

(2) Phase II (direct fire). The systems are more densely situated, forming fewer columns upon entering the minefield.

(3) Phase III (withdrawal). Minefield attrition does not occur in this phase.

3. DATA FLOW.

All needed information is received from the ground combat mainline except for the internal data of expected kills. The information flow is represented in Figure 6-14.

4. FILE STRUCTURE.

The only files associated with the minefield subroutine are held as internal data statements. These contain the percentage of expected losses to the attacker according to the bull/breach tactic and whether Red or Blue units are attacking.

5. ALGORITHMS.

A. Figure 6-15 shows a generalized logic flow of the processes in the ground combat mine attrition subroutine. Minefield attrition is figured by calculating the minefield coverage fraction, a column number for the force density, and then calculating the losses accordingly using the percentage of expected kills. The following paragraphs provide a more detailed description of the algorithms used in the attrition process.

(1) Calculate minefield coverage fraction. The width of the minefield and the sector width, as input at the beginning of the ground combat module, are used to calculate the coverage fraction as follows:

$$Mcf = Mw/Sw \quad (\text{Eq. 6-18})$$

where:

Mcf = minefield coverage fraction.
Mw = minefield width.
Sw = sector width.

(2) Calculate columns. Columns represent the deployment density of systems according to the current battle phase as discussed in paragraph 2E.

$$C = \text{Totsys}/N \quad (\text{Eq. 6-19})$$

where:

C = columns.
Totsys = total number of all systems entering minefield.
N = 3 for battle phase I .
6 for battle phases II & III .




Figure 6-14. Minefield attrition information flow.




Figure 6-15. Minefield attrition logic flow.

(3) Calculate losses.

$$L_i = \frac{Mcf * Sys_i}{Totsys} * C * Eki \quad (\text{Eq. 6-20})$$

where:

L_i = number of losses.
 Sys_i = the number of type systems entering the minefield.
 Eki = percentage of expected kills per system.

6. "UNITFILE" IMPACT.

This subroutine does not directly impact the unit status file ("UNITFILE"). Kills calculated in this subroutine are returned to the ground combat driver which in turn decrements all kills from the "UNITFILE".

7. CODE.

A. Introduction. This section contains information on the minefield attrition code. The functional areas discussed in the following paragraph are represented in Figure 6-16.

B. Mine attrition functional areas.

(1) The low resolution data are received from the ground combat mainline and consist of the systems entering the minefield, the minefield width and sector width, the attacker (Red/Blue force), whether the attacker will bull or breach the minefield, and the current battle phase.

(2) The array containing the number of kills is initialized to zero before any attrition is made.

(3) The low-resolution data and other minefield characteristics are checked. If inappropriate information has been passed, attrition calculations will not take place and an array of zero kills will be returned to the mainline. The appropriate characteristics should consist of:

- (a) Minefield width not equal to zero.
- (b) Sector width not equal to zero.
- (c) Percentage of forces entering minefield not equal to zero.
- (d) Minefield must be unused.
- (e) Bull/breach flag equals 1 or 2.




Figure 6-16. Minefield attrition functional flow.

(4) If the minefield characteristics are appropriate, the expected kill data are then loaded from internal data statements.

(5) The minefield coverage fraction is now calculated from the low-resolution data.

(6) The density of the forces is calculated according to the current battle phase which is referred to as the columns.

(7) Losses to the attacking force are then calculated using the expected kills, minefield coverage fraction, and columns per the 70 systems.

(8) A flag is then set to show that the minefield has been assessed, so as not to be used again.

(9) The number of kills per system is then returned to the ground combat mainline.

C. Primary variables. The primary variables of each functional area of the minefield attrition subroutine are shown in Table 6-6. Each variable is accompanied with a short description. Table 6-14 contains a code listing of the ground combat program.

Table 6-6. Minefield attrition subroutine table.

<u>Functional area(s): Minefield Attrition</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Mines	Mine subroutine.	A. Atk_def	Represents attacker: 0 = Red 1 = Blue
		B. Bul_bch	Bull/breach minefield tactic flag: 1 = Bull 2 = Breach
		C. Columns	Deployment density of systems according to current battle phase
		D. Mcf	Minefield coverage fraction
		E. Mine_frct (I,J)	Minefield expected kill fraction where: I = 1 - Blue bull 2 - Blue breach 3 - Red bull 4 - Red breach J = 1 - 70 weapon systems
		F. Mine_hit	Represents one of the possible three minefields currently being assessed

Table 6-6. Minefield attrition subroutine table (continued).

<u>Functional area(s):</u> Minefield Attrition	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Mines (concluded)			
	G. Minefield (I,J)		Minefield information containing: I = 1 to 3, where 1 - First minefield 2 - Second minefield 3 - Third minefield J = 1 to 6, where 1 - Location of minefield in meters (range) 2 - Minefield width 3 - Sector width 4 - Percent of force entering minefield 5 - Vacant 6 - Assessed flag; 0 is not assessed, 1 is assessed
	H. Phase		Current battle phase 1 - Preclosure 2 - Direct fire 3 - Withdrawal
	I. Sys_mine (I,J)		Contains systems entering minefield and attrited systems. I = 1 to 4 where, 1 - Blue systems entering 2 - Blue systems attrited 3 - Red systems entering 4 - Red systems attrited J = 1 to 70 are the elements on the unit file

Section II. Artillery Attrition

1. PURPOSE.

The purpose of the DIME indirect fire subroutine, Arty_atrit, is to determine the losses to each of the 70 element types resulting from the delivery of artillery, rockets, multiple launch rocket systems (MLRS for Blue)/multiple rocket launchers (MRL for Red), and mortar munitions during the 30-minute interval.

2. GENERAL.

A. Interface with the main ground combat program. Arty_atrit is called from each of the three battle phase drivers discussed in the introduction of this chapter. Figure 6-17 provides an overview of the interface between the phase drivers and Arty_atrit. The interface subroutine, Arty_sub, prepares both the vehicular and personnel target arrays. It also maintains a counter of the successive number of 30-minute intervals that the targeted force has been subjected to indirect fire. Following the attrition calculations by Arty_atrit, Arty_sub posts the vehicular and personnel losses before returning to the battle phase driver.

B. Arty_atrit structure. Since DIME is low-resolution, target acquisition is represented implicitly in two ways. First, indirect fire use is structured around five fire support tasks (prep, counterprep, close support, SEAD, and interdiction). Associated with each task is an implied target acquisition. Second, there are, in essence, four steps used in the assessment of attrition to indirect fire: set-up target area, determine elements targeted, determine ammunition fired, and assess damages.

(1) Set-up target area. The total area of the targeted force, input by the gamer, is reduced based upon the associated fire support task. This represents that portion of the total area occupied by the elements targeted for a specific fire support task, as well as the likelihood of acquiring them. This area is then further modified based upon the ability of the targeted force to disperse. The ability of the targeted force to disperse is determined by two factors: dispersion mask and whether the force is mounted (R=1) or dismounted (R=0). The dispersion mask is a 3 X 10 boolean array consisting of three battle phases and 10 missions. The dispersion mask may permit the force to increase its battle area radius if the given battle phase and mission are 1. If the force can disperse, the increase in the radius of the equivalent circle is 1200m if mounted (R=1) and 200m if dismounted (R=0) for a 30-minute timestep, thus diluting the density of the targeted elements. See Figure 6-18 for a graphical representation.




Figure 6-17. Logic flow of indirect fire subroutine Arty_sub (showing principal functions in calling the indirect fire attrition module Arty_attrit).




Figure 6-18. Schematic of notionalized artillery target. Shows bands for concentrating indirect fires in mission roles of prep, interdiction, close support, suppression of air defense and counterfire.

(2) Determine elements targeted. Though the quantity of each target element is passed into Arty_atrit in the Sys_arty(*) array, it is further modified to allow for selective targeting for each fire support task.

(3) Determine ammunition fired. The weight of ammunition fired is passed into Arty_atrit in the Bif_fired(*) and Rif_fired(*) arrays. It is then converted into the number of standard fire unit volleys fired.

(4) Assess damages. The majority of Arty_atrit deals with this function. Given the items discussed above, it determines the losses to the targeted force in each of the 70 elements using the methodology given in the Joint Technical Coordinating Group for Munitions Effectiveness (JTTCG/ME) document and the Super Quickie II model.

3. DATA FLOW.

The Arty_atrit subroutine has three basic sources of data: the DIME host, munitions description from external files and target profile from external data structures. See Figure 6-19 for a graphical presentation.

A. DIME host data. These data are passed to Arty_atrit as calling arguments. They include:

(1) Tonnages of ammunition expended by artillery, rockets, and mortars for both Red and Blue.

(2) Target elements potentially available to be attacked by indirect fire for both Red and Blue.

(3) Target dimensions of entire force engaged in the battle for both Red and Blue.

(4) Mission and battle phase of the target unit for both Red and Blue.

(5) Cumulative time under indirect fire attack for both Red and Blue.

B. Target profile. These data are structured externally and include:


(1) Target band sizes for each fire support task.

(2) Dispersion mask for each phase and mission of the targeted force.

(3) Target mask array for each fire support task and targeted element, thus allowing selective targeting for each task.

(4) Round packaged weight (in short tons).

(5) Personnel (infantry) profile which permits the hardening of this element over time.



* Indicates internal data structure.

Figure 6-19. Data flow for the indirect fire attrition module, Arty_atrit.

C. Munitions descriptions. These are accessed from external files and include:

(1) Artillery, rocket, and mortar round (or submunition) effects against each of 72 target elements. It should be noted that personnel (infantry) are further divided into prone and prone-protected postures.

(2) Ballistic delivery error for each type of fire support and system (artillery, rockets, and mortars) for both Red and Blue at some fixed range (normally 1/2 or 2/3 maximum range). These include precision mean point of impact (MPI) errors.

(3) Volley pattern descriptors which describe the standard volley pattern of the fire unit for each type of fire support system for Red and Blue.

(4) Round reliability.

(5) Target location error (TLE) which represents the error associated with a generic target acquisition device for each fire support task (e.g., forward observer for close support).

4. FILE STRUCTURE.

Two sets of external files are used by Arty_atrit: lethal areas and fire delivery parameters.

A. Fire delivery files. Each file consists of fifteen records, seven for artillery, four for rockets and four for mortars. Each record includes:

<u>Index</u>	<u>Description</u>
1	Length of damage pattern.
2	Length of damage pattern factor which is determined by the angle of fall for the range used.
3	Probability of damage factor determined by number of submunitions, submunition reliability, length, and width of submunition pattern.
4	Precision error range for range used.
5	Precision error in deflection for range used.
6	Length of volley factor for one fire unit volley in range.

<u>Index</u>	<u>Description</u>
7	Width of volley factor for one fire unit volley in deflection.
8	Individual round reliability.
9	MPI error in deflection for range used.
10	MPI error in range for range used.

B. Lethal area files. Each file, dependent on Red or Blue, consists of fifteen records, seven for artillery, four for rockets, and four for mortars. Each record contains 72 items, one for each of 70 weapon elements plus one for prone personnel and one for protected prone personnel.

5. ALGORITHMS.

The primary algorithm used in Arty_attrit is the Super Quickie II. This algorithm requires a definition of the target area elements targeted, and volleys fired. These are used to calculate the losses to targeted elements due to indirect fire.

$$Ps_i = \prod_{j=1}^5 (1 - Fd_{ij}) \quad (\text{Eq. 6-21a})$$

where:

Ps_i = probability of survival of element i from direct fire.
 i = target element
 j = fire support task
 Fd_{ij} = calculated as follows:

$$Fd_{ij} = Ecr_{ij} * Ecd_{ij} * Pnv_{ij} \quad (\text{Eq. 6-21b})$$

where:

Fd_{ij} = expected fractional damage to target element i from indirect fire support task j .
 Ecr_{ij} = expected fraction of target covered by pattern in range (see Eq. 6-23).

Ecd_{ij} = expected fraction of target covered by pattern in deflection (see Eq. 6-25).

Pnv_{ij} = calculated as follows:

$$Pnv_{ij} = 1 - \left[1 - (Al_i * Nr * Rr) / (Avp_i * Of_i) \right]^{Vollies_j * Of_j} \quad (\text{Eq. 6-22})$$

where:

Pnv_{ij} = the probability of damage within pattern for vollies; fired by an indirect fire type for a specific task.

Al_i = the lethal area of the complete round against target element i.

Nr = the number of rounds in the volley.

Rr = the reliability of the round.

Avp_i = volley damage pattern area.

Of_i = the volley overlap factor.

The expected fraction of target covered by pattern in range (used in Eq. 6-21b) is calculated as follows:

$$Ecrij = 2.96 * Reptm_j * Fl_{ij} / Lt_j \quad (\text{Eq. 6-23})$$

where:

Reptm_j = total mean point of impact error in range for fire support task j.

Lt_j = target length for task j.

Fl_{ij} = calculated as follows:

$$Fl_{ij} = Fla_{ij} - Flb_{ij} \quad (\text{Eq. 6-24a})$$

where:

$$Fla_{ij} = (Al_{ij}/2) \left[1 - e^{-0.63 * Al_{ij}^2} \right]^{1/2} +$$

$$\left[e^{-Al_{ij}^2 / 2} / (2\pi) \right]^{1/2} \quad (\text{Eq. 6-24b})$$

$$Flb_{ij} = (A2_{ij}/2) \left[1 - e^{-0.63 * A2_{ij}^2} \right]^{1/2} + \left[e^{-A2_{ij}^2 / 2} / (2 \pi) \right]^{1/2} \quad (\text{Eq. 6-24c})$$

and,

$$A1_{ij} = (Lvp_i + Lt_j) / (2.96 * Reptm_j) \quad (\text{Eq. 6-24d})$$

$$A2_{ij} = |Lvp_i - Lt_j| / (2.96 * Reptm_j) \quad (\text{Eq. 6-24e})$$

where:

Lvp_j = the length of the volley pattern of the standard fire unit.

The expected fraction of target covered by pattern in deflection (used in Eq. 6-21b) is calculated as follows:

$$Ecd_{ij} = 2.96 * Deptm_j * Fw_{ij}/Wt_j \quad (\text{Eq. 6-25})$$

where:

$Deptm_j$ = total mean point of impact error in deflection.

Wt_j = target width for task j.

Fw_{ij} = calculated as follows:

$$Fw_{ij} = Fwa_{ij} - Fwb_{ij} \quad (\text{Eq. 6-26a})$$

where:

$$Fwa_{ij} = (B1_{ij}/2) \left[1 - e^{-.63 * B1_{ij}^2} \right] + \left[e^{-B1_{ij}^2 / 2} / (2 \pi)^{1/2} \right] \quad (\text{Eq. 6-26b})$$

$$Fwb_{ij} = (B2_{ij}/2) \left[1 - e^{-.63 * B2_{ij}^2} \right] + \left[e^{-B2_{ij}^2 / 2} / (2 \pi)^{1/2} \right] \quad (\text{Eq. 6-26c})$$

and,

$$B1_{ij} = (Wvp_i + Wt_j) / (2.96 * Dept_{mj}) \quad (\text{Eq. 6-26d})$$

$$B2_{ij} = | Wvp_i - Wt_j | / (2.96 * Dept_{mj}) \quad (\text{Eq. 6-26e})$$

where:

Wvp_j = the width of the volley pattern of the standard fire unit.

6. "UNITFILE" IMPACT.

Arty_atrit does not directly affect the "UNITFILE"; rather it returns to the main battle devices the losses to each of the 70 elements due to indirect fire.

7. CODE.

Figure 6-20 represents the functional flow of Arty_atrit. The subroutine is divided into two separate (but identical) sections: Blue firing on Red and Red firing on Blue. Each section has the four portions discussed in paragraph 2B above.

A. Calculate target area. Arty_atrit begins processing by calculating the total area that each of five fire support tasks are targeted against. These tasks are: preparatory fires, close support, suppression of air defense (SEAD), counterfire, and interdiction. One of two equations is used to determine target area. The equation selected is dependent upon the target's ability to disperse. The ability to disperse is in turn contingent upon the battle phase and the mission of the target.

(1) Target area excluding dispersion factor.

$$A = L * W * B \quad (\text{Eq. 6-27})$$

where:

- A = total area that the indirect fire task is targeted against.
- L = total length in meters of the target area in the range direction.
- W = dimension (total width in meters) of the target area in the deflection direction.
- B = percentage of total area that indirect fire task is targeted against.

(2) Target area including dispersion factor. When a target is allowed to disperse, it is necessary to first calculate the increase in target area due to dispersion and the original radius of the target area before determining the final target area for each of the indirect fire tasks.




Figure 6-20. Generalized functional flow of Arty_atrit

(a) Calculate the increase in the target radius.

$$I_r = M * (F - 1) \quad (\text{Eq. 6-28})$$

where:

I_r = increase in target area due to target dispersion in meters.

M = meters moved per 30-minute interval where:
1000 if a Red target is mounted and attacking
1200 if a Blue target is mounted and attacking
200 if either a Red or Blue target is dismounted or defending.

$F-1$ = number of consecutive 30-minute intervals less one in which the target has been receiving indirect fire.

(b) Calculate radius of original target area.

$$R = (A/PI)^{.5} \quad (\text{Eq. 6-29})$$

where:

R = radius of original target area.

A = area that indirect fire task is targeted against excluding the dispersion factor (see Eq. 6-27).

PI = the symbol designating the ratio of the circumference of a circle to its diameter; approximately 3.1415927.

(c) Calculate target area including the dispersion factor.

$$A_d = PI * (R + I_r)^2 \quad (\text{Eq. 6-30})$$

where:

A_d = area that the indirect fire task is targeted against including the dispersion factor.

R = radius of original target area in meters, as calculated in Eq. 6-29 above.

I_r = increase in target area due to target dispersion, in meters, as calculated in Eq. 6-28 above.

B. Calculate volleys to fire. The number of volleys fired is calculated for each combination of the three indirect fire types (artillery, MLRS/MRL, mortars) and the five indirect fire tasks (preparatory fire, close support, SEAD, counterfire, interdiction). The type of indirect fire determines the number of tubes fired in the volley as well as the individual round or launcher load packaged weight (in tons).

(1) The weight of all ammunition fired in a single volley is determined by:

$$W_f = T * R_{wf} \quad (\text{Eq. 6-31})$$

where:

W_f = weight of ammunition, in tons, fired in a single volley by weapon type f.
 T = number of tubes firing in each volley.
 R_{wf} = individual round or launcher load packaged weight, in tons, of weapon type f.

(2) The number of volleys to fire is computed from the following equations.

$$V_f = A_f / W_f \quad (\text{Eq. 6-32})$$

where:

V_f = number of volleys fired by weapon type f under a specific firing task where:
 f = Type:
 1 Artillery
 2 MLRS/MRL
 3 Mortars
 A_f = total number of tons of ammunition fired by weapon type f under a specific firing task.
 W_f = weight of ammunition, in tons, fired in a single volley as calculated in Eq. 6-31.

C. Calculate fractional damage and total probability of survival indirect fire losses.

(1) The expected fractional damage for each DIME element, excluding the VIPER/infantry and for personnel in both standing and prone positions, is computed by $Arty_atrit$. The equations determining fractional damage are set forth in paragraph 5. above.

(2) The fractional damages computed by Arty_atrit are conditioned by the targeted force (Red or Blue) and the type of indirect fire (artillery, rockets, mortars). The fractional damage is used to determine losses to both Red and Blue from indirect fire and is passed back to the battle drivers.

D. Subroutine table and primary variables are listed in Table 6-7. Table 6-14 contains a listing of the ground combat code.

Table 6-7. Artillery subroutine table.

Functional area(s): Arty atrit: Artillery attrition	Subroutine function(s)	Primary variables	Variable descriptions
Main	Sets up targets for artillery fire.	A. Area_band (I)	Percentage of total area that task I (1-5) is targeted against.
		B. T_length(I)	The dimension (total length in meters) of the target area in the deflection direction.
		C. T_width(I)	The dimension (total width in meters) of the target area in the deflection direction.
		D. Area (I)	Area that task I is targeted against (square meters).
		E. Dispersion_mask (I,J)	A switch (0 or 1) determining if target can disperse when receiving fire on mission J, phase I.
		F. Increase_radius	Amount of radius the target area is increased (meters) due to target dispersion.
		G. Radius	Radius (meters) of original target area.
		H. Length (I)	Length (meters) of new target area after possible dispersion for task I.
		I. Width (I)	Width (meters) of new target area after possible dispersion for task I.

Table 6-7. Artillery subroutine table.

Functional area(s):	<u>Arty attrit: Artillery attrition</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main (continued)			
J.	B_tgt_mask (I,J) R_tgt_mask (I,J)		Target mask (0 or 1) for task I and target element J (1-72).
K.	A1 (I,J)		Lethal area (square meters) of weapon type I (1-15) against target type J: 1 - 70 = DIME elements 71 = Infantry standing 72 = Infantry prone
L.	Ps (I)		Joint probability of survival of element I (1-72) against all indirect fire elements.
M.	Tubes_per_vol		Number of tubes firing per volley.
N.	Throw_wt		Weight (tons) of ammo fired per volley.
O.	Volleys (I,J)		Number of volleys to fire by weapon type I (1-15) under task J (1-5).
P.	Bif_fired (I,J)		Total number of tons of ammo fired by Blue weapon type I on task J.
Q.	Psnl_posture (I,J)		Percent of personnel in prone position for: I = 1 - Defense = 2 - Attack J = 1 - First volley = 2 - Subsequent volley.
R.	Posture		Percent of personnel currently in prone position.
S.	Barty_fire		Number of consecutive 30-minute intervals in which Blue uses indirect fire on Red.

Table 6-7. Artillery subroutine table.

Functional area(s): Arty attrit: Artillery attrition	Subroutine function(s)	Primary variables	Variable descriptions
Main (continued)			
	T. Rarty_fire		Number of consecutive 30-minute intervals in which Red uses indirect fire on Blue.
	U. Rd_wt (I)		Individual round or launcher load packaged weight (tons) of weapon type I (1-15).
	V. Sys_tot (I,J)		I = 1 - initial number of Blue element J (1-70) = 2 - current number of Blue element J = 3 - initial number of Red element J = 4 - current number of Red element J
	W. Sys_artly(I,J)		I = 1 - initial number of Blue element J (1-70) targetable = 2 - current number of Blue element J targetable = 3 - initial number of Red element J targetable = 4 - current number of Red element J targetable
	X. B_afire		Number of consecutive 30-minute intervals in which Blue uses indirect fire on Red.
	Y. R_afire		Number of consecutive 30-minute intervals in which Red uses indirect fire on Blue.
	Z. R		Flag for whether infantry is mounted.
	AA. Type		Loop counter indexing type of IF. 1 = Artillery 2 = MLRS 3 = Mortars.

Table 6-7. Artillery subroutine table.

Functional area(s): <u>Arty atrit: Artillery attrition</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main (concluded)			
	BB. Task		Loop counter indexing one of 5 tasks.
	CC. Atk_def		0 = Blue attacking, Red defending 1 = Red attacking, Blue defending
	DD. Attacker		1 = Blue attacking 2 = Red attacking.
	EE. B_msn		Pointer to Blue mission.
	FF. R_msn		Pointer to Red mission.
	GG. B_phase		Pointer to Blue phase.
	HH. Element		Loop counter for target type.
	II. Index		Loop counter for target type.
	JJ. L_vp		Total length (meters) of the adjusted volley pattern in the range direction.
	KK. Rif_fired(I,J)		Array containing total number of tons of ammo fired by Red weapon type I for task J.
	LL. Del_par (I,J)		Array containing information from an external file which is assigned to fire delivery variables.

Table 6-7. Artillery subroutine table.

<u>Functional area(s):</u> <u>Arty attrit:</u> <u>Artillery attrition.</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Compute	Computes the probability of survival for a weapon system to go into the Ps(*) array. Computes for Blue firing on Red.	A. F_d (I,J) B. N_r C. L_v D. W_v E. W_dp F. L_dp G. L_dp_F H. P_dp I. P_dp_f J. A_el	Designed or expected fractional damage to element J (1-72) under task I (1-5). Number of rounds per volley. Total length (meters) of the volley pattern in the range direction. Total width (meters) of the volley pattern in the deflection direction. Width (meters) of the damage pattern of a single round in the deflection direction. Length (meters) of the damage pattern of a single round in the range direction. L_dp factor. Determined by the angle of fall for the range selected. Probability of damage within a single round pattern. P_dp factor. Determined by the number of submunitions, submunitions reliability and single round submunition pattern in the range direction. Lethal area (square meters) of target damage per single round. Determined by length and width of damage pattern and probability of damage within single round pattern.

Table 6-7. Artillery subroutine table.

Functional area(s): <u>Arty attrit: Artillery attrition</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Compute (concluded)		K. L_v_fac L. W_v_fac	Length of the volley pattern in the range direction for a single volley pattern. Width of the volley pattern in the deflection direction of a single volley round pattern.
Compute_red	Computes the probability of survival for a weapon system to go into the Ps(*) array. Computes for Red firing on Blue.		
Calculate_fd	Calculates the expected fractional damage (used to compute the probability of survival).	A. L_ap B. W_ap C. A_vp D. A_ap E. Of F. Tle(I)	Adjusted damage pattern (meters) of a single round in the range direction. Adjusted damage pattern (meters) of a single round in the deflection direction. Volley pattern damage area. Single round adjusted damage area. Overlap factor. Determined by the number of rounds in each volley, the adjusted damage pattern and the volley damage pattern. Target location error for task I.

Table 6-7. Artillery subroutine table.

Functional area(s): <u>Arty attrit: Artillery attrition</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calculate <u>fd</u> (continued)			G. Rep_m	Mean point of impact probable error in range direction (excluding target location error).
			H. Dep_mac	Mean point of impact probable error the deflection direction (excluding target location error).
			I. P_nv	Probability of damage for a number of volleys. Used as a factor in the expected fractional damage, $F_d(*,*)$.
			J. Rep_tm	Mean point of impact probable error in range direction (including target location error).
			K. Dep_tm	Mean point of impact probable error in deflection direction (including target location error).
			L. R_r	Reliability of the round.
			M. A_1	Factor used to determine F_{1a} . Determined by the length of volley damage, the length of the new target area after dispersion and the probable error in range.
			N. A_2	Factor used to determine F_{1b} . Determined by the length of volley damage, the length of the new target area after dispersion and the probable error in range.
			O. F_1a	Positive factor in F_{1a} . Determined by A_1 .

Table 6-7. Artillery subroutine table.

<u>Functional area(s): Arty attrit:</u>	<u>Artillery attrition</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calculate fd (continued)			
		P. F _{1b}	Negative factor in F ₁ . Determined by A ₂ .
		Q. F ₁	Factor in the expected fraction of target covered by pattern in range direction, Ec _r .
		R. Ec _r	Expected fraction of target covered by pattern in range direction. Used to determine the expected fractional damage, F _d (*,*).
		S. B ₁	Factor used to determine F _{wa} . Determined by the width of volley damage, the width of the new target area after possible dispersion and probable error in dispersion.
		T. B ₂	Factor used to determine F _{wb} . Determined by the width of volley damage, the width of the new target area after possible dispersion and probable error in dispersion.
		U. F _{wa}	Positive factor in F _w . Determined by B ₁ .
		V. F _{wb}	Positive factor in F _w . Determined by B ₂ .
		W. F _w	Factor in the expected fraction of target covered by pattern in the deflection direction.
		X. Ec _d	Expected fraction of target covered by pattern in deflection direction. Used to determine the expected fractional damage, F _d (*,*).

Table 6-7. Artillery subroutine table.

<u>Functional area(s): Arty atrit: Artillery attrition</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Calculate_fd (concluded)		Y. Kdep_p Z. Krep_p	The pattern adjustment factor. The precision probable error in deflection (excluding target location error). The pattern adjustment factor. The precision probable error in range (excluding target location error).
Re_read	Assigns values to fire delivery variables.	AA. W_vp	Total width (meters) of the adjusted volley pattern in the deflection direction.
Sub_end	Closes the files for the subroutine.		

Section III. Smoke

1. PURPOSE.

The purpose of the smoke module is to return the percent of frontage visible through a screen to a firer using optic, crew-served, and thermal sensors.

2. GENERAL.


The DIME smoke module provides coverage for the withdrawing force. The withdrawing force can request mortar and/or artillery-delivered smoke, provided smoke ammunition has been allocated. The smoke module returns the percent of frontage visible through a screen to a firer using optic, crew-served, and thermal sensors and the tonnage used to emplace the screen which is subtracted from the withdrawing force's stockpile. The percent of frontage visible is used by the direct fire attrition module of DIME to determine the total number of systems available to be engaged as targets for the withdrawal phase (phase III) of the DIME battle. In turn, these targets are used to determine the attrition suffered by both forces.

3. DATA FLOW.

The smoke module is a portion of the ground combat attrition program. The data flow and the logic flow involve passing information through four routines. Figure 6-21 indicates the data flow through the four smoke subroutines. In addition to the input and/or output parameters, smoke ammunition weight in pounds per one round and the rate of fire used to build the screen are contained in external data files. Additional data is accessed from an auxiliary file containing the probabilities of detection through specific screens. This file will be discussed in greater detail in paragraph 4. The following discussion will include the data flow as it pertains to the general flow of the DIME smoke module.

A. The DIME smoke module employs a four-step methodology:

- (1) Provides coverage for the withdrawing force.
- (2) Provide mortar and/or artillery-emplaced smokescreen.
- (3) Returns the percent of frontage visible to a firer using optics, crew-served, and thermal sensors.
- (4) Depletes the ammunition stockpile of the force emplacing the screen.



INPUTS

- A. BATTLE PHASE, NEW SMOKE CAPACITY, TOTAL SYSTEMS WITHIN RANGE.
- B. POSITION ALLOCATION (TOWNSHIP), ARTILLERY ALLOCATION (TOWNSHIP), WITHDRAWAL TIME.
- C. UNIT EMPLOYING SMOKE, POSITION TOWNSHIP, ARTILLERY TOWNSHIP, FRONTAGE LENGTH, SCREEN TYPE, VISIBILITY CATEGORY, BATTLE RANGE.
- D. UNIT EMPLOYING SMOKE, SMOKE TOWNSHIP, FRONTAGE LENGTH, SCREEN TYPE, VISIBILITY CATEGORY, BATTLE RANGE.
- E. SMOKE TYPE (1. OPTICS, 2. CROW SERVED, 3. THERMAL), RELATIVE HUMIDITY, VISIBILITY CATEGORY, RANGE.

OUTPUTS

- F. EXPECTED PROBABILITY OF DETECTION FOR AN OBSERVER USING (1) OPTICS, (2) CROW SERVED, AND (3) THERMAL SENSORS.
- G. PERCENT OF FRONTAGE SCREENED BY POSITION EMPLOYED SMOKE, POSITION TOWNSHIP USED, EXPECTED PROBABILITY OF DETECTION THROUGH A POSITION EMPLOYED SMOKE FOR OPTICS, CROW SERVED, AND THERMAL SENSORS. PERCENT OF FRONTAGE SCREENED BY ARTILLERY EMPLOYED SMOKE, ARTILLERY TOWNSHIP USED, EXPECTED PROBABILITY OF DETECTION THROUGH AN ARTILLERY EMPLOYED SMOKE FOR OPTICS, CROW SERVED, AND THERMAL SENSORS.
- H. POSITION TOWNSHIP USED, ARTILLERY TOWNSHIP USED.
- I. POSITION TOWNSHIP USED, ARTILLERY TOWNSHIP USED, NEW NEW AND NEW VISIBILITY BY SENSOR TYPE.
- J. PERCENT OF FRONTAGE VISIBLE TO A FINDER WITH (1) OPTICS, (2) CROW SERVED, AND (3) THERMAL SENSORS. POSITION AND ARTILLERY TOWNSHIP AVAILABLE AFTER SMOKE MISSION.

Figure 6-21. Data flow for smoke routines

B. The DIME smoke module divides these four steps into four routines: Allocate_smoke, W_smoke, Smk_emp, and Smoke.

(1) During the withdrawal phase of the battle, DIME calls the Allocate_smoke routine to determine if a percent of the close support ammunition has been allocated for smoke. If an allocation has been determined, the tonnage of ammunition is forwarded to the W_smoke routine as mortar tonnage and artillery tonnage designated for smoke.

(2) These tonnages, along with the range between the units, the visibility category, the unit's width, and the withdrawal time, are used by the W_smoke routine to determine the dimensions of the smokescreen.

(3) Once the dimensions of the screen have been determined, this information is passed to the Smk_emp routine which will attempt to emplace a screen with mortar-delivered smoke. The screen's length is determined from the unit's width passed in by the W_smoke routine. If the mortars cannot produce a screen which completely covers the unit, then the Smk_emp routine will complete the desired screen by emplacing the remainder of the screen with artillery-delivered smoke.

(4) Once the screen is emplaced, the Smk_emp routine calls the Smoke routine to determine the probability of detection through "holes" in the screen as a function of the smoke round, relative humidity, visibility category, and the range between units for an observer using an optic, crew-served, or thermal sensor.

(5) Using these probabilities of detection, the Smk_emp routine determines the percent of frontage a firer can see through "holes" in the screen, plus any unsmoked frontage, as a function of sensor type. In addition, Smk_emp calculates the mortar tonnage and/or artillery tonnage used to emplace the screen.

(6) The direct fire attrition module uses the percent of frontage visible by sensor type to determine the total number of targets available to be engaged during the withdrawal phase.

4. FILE STRUCTURE.

The smoke module accesses an auxiliary file containing the probabilities of detection through specific screens.

A. The probability of detection values are stored on a file consisting of six records.

(1) Record 1 contains the probability of detection values for an observer using an optic sensor in relative humidity of less than 50 percent for four visibility categories (1 km, 2 km, 4 km, > 4 km) and in seven range categories (0 - .5 km, .5 - 1.0 km, 1.0 - 1.5 km, 1.5 - 2.0 km, 2.0 - 2.5 km, 2.5 - 3.0 km, 3.0 - 3.5 km).

(2) Record 2 contains the probability of detection values for an observer using an optic sensor in relative humidity of 50 percent or greater for four visibility categories and seven range categories.

(3) Record 3 and record 4 contain the probability of detection values for an observer using a crew-served sensor.

(4) Record 5 and record 6 contain the probability of detection values for an observer using a thermal sensor.

B. The probability of detection values are stored on five files: three for mortar-delivered and two for artillery-delivered screens emplaced using white phosphorous (WP) smoke.

(1) Blue mortars,

(a) 107mm

(b) 181mm.

(2) Blue artillery, 155mm.

(3) Red mortar, 120mm.

(4) Red artillery, 152mm.

5. ALGORITHMS.

The smoke module uses two major algorithms: calculation of the percent of frontage visible to a firer, as a function of sensor type and smoke round; and calculation of total number of systems available to be engaged as targets in the battle.

A. The algorithm used to calculate the percent of frontage visible to a firer, as a function of sensor type and smoke round, uses the following formula:

$$P_{see_s} = (1 - T_{cov}) + \left[\sum_{r=1}^{nr} (P_{dect_{sr}}) * P_{ftcov_r} \right] \quad (\text{Eq. 6-33})$$

where:

P_{see_s} = percent of frontage visible to firer using sensor type s.
 $P_{dect_{sr}}$ = expected probability of detection through a screen, as a function of sensor type and smoke round.

Pftcov_r = percent of frontage covered by a screen, as a function of the smoke round used to emplace the screen.
Tcov = total percent of frontage covered by all smoke rounds.
nr = number of smoke rounds used to emplace the screen.

B. The algorithm used in the direct fire module to calculate the total number of systems available to be engaged as targets in the battle uses the following formula:

$$T_{\text{systems}} = \sum_{s=1}^{70} T_{\text{wpns}_s} * P_{\text{see}_s} \quad (\text{Eq. 6-34})$$

where:

T_{systems} = total number of systems available to be engaged as targets in battle.
T_{wpns_s} = total number of systems within range.
P_{see_s} = percent of frontage visible to a firer, as a function of sensor type and smoke round.

6. "UNITFILE" IMPACT.

The smoke module has no direct impact on the "UNITFILE". For the indirect impact discussion, refer to the ammunition allocation discussion in the introduction to this chapter.

7. CODE.

The smoke module code is contained as a submodule in the ground combat attrition program. The smoke module code is divided into four subroutines: Allocate_smoke, W_smoke, Smk_emp and Smoke. Note that Allocate_smoke and W_smoke are held as a portion of the ground combat mainline whereas Smoke_emp and Smoke are entirely separate modules in the ground combat code.

A. During artillery allocation in the ground combat driver, Allocate_smoke determines if a percent of the close support ammunition has been allocated for smoke. If a smoke allocation has been indicated, Allocate_smoke forwards this smoke tonnage to the W_smoke routine.

B. W_smoke uses the tonnages from Allocate_smoke combined with the range between units, the visibility category, the unit's width, and the withdrawal time to determine the dimensions of the desired smokescreen. W_smoke then sends necessary parameters to the Smk_emp module.

C. Smk_emp uses the dimensions received from W_smoke to emplace a smoke screen which will provide coverage for the withdrawing force. Smk_emp will attempt to emplace a screen over the entire withdrawing force (defined by the unit's length) by firing mortar ammunition. If the mortar smoke allocation is insufficient to cover the entire frontage, then the artillery smoke allocation is fired to cover any remaining frontage. The total mortar and/or artillery smoke tonnage used to emplace the screen is returned to the W_smoke routine where it is subtracted from the stockpile of the force that requested the smoke. Once the screen is emplaced, Smk_emp determines the total percent of frontage visible through the screen using the Equation 6-33. This total percent of frontage visible is sent to the direct fire attrition module routine where it is used in Equation 6-34 to determine the total number of systems available to be engaged as targets in the withdrawal phase of the DIME battle.

D. The Smoke routine determines the probability of detection through "holes" in the screen by accessing the off-line data file containing the expected probabilities of detection for a screen emplaced by a specific smoke round under certain meteorological conditions for a specified range. Smoke returns this probability of detection for an observer using an optics, crew-served, and a thermal sensor.

E. Figure 6-22 shows the general flow of the smoke module as it relates to the ground combat attrition module. Figures 6-23, 6-24, 6-25, and 6-26 indicate the specific flow diagrams for the four routines involved with smoke.

F. Table 6-8 indicates the primary variables and their functions as they relate to each subroutine. See Table 6-14 for a listing of the ground combat code.




Figure 6-22. Generalized flow of smoke module.




Figure 6-23. Generalized flow of Allocate_smoke routine.




Figure 6-24. Generalized flow of W_smoke routine.




Figure 6-25. Generalize flow of Smk_emp routine.




Figure 6-26. Generalized flow of routine Smoke.

Table 6-8. Smoke subroutine table.

Functional area(s): A. Provides coverage for withdrawing force; depletes the requesting unit's ammunition stockpile.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Allocate_smoke	Determines if a percent of close support ammunition was allocated to smoke by the withdrawing force. Forewards smoke tonnage to W_smoke routine. Updates ammo stockpile for smoke tonnage used to emplace screen.	A. Break_point B. B_smok_tons (I) C. R_smok_tons (I)	An integer value which indicates which force requested smoke during withdrawal phase. An array containing the Blue allocated ammunition tonnage: I = 1-7 - Artillery capacity 8-11 - Mortar capacity. An array containing the Red allocated ammunition tonnage: I = 1-7 - Artillery capacity 8-11 - Mortar capacity.
		D. Bif_msn_tons (I,J)	An array containing the Blue indirect fire ammunition allocation (I) as a function of mission (J). Contains adjusted tonnage after smoke mission. I = 1-11; J = 1-5.
		E. Rif_msn_tons (I,J)	An array containing the Red indirect fire ammunition allocation (I) as a function of mission (J). Contains adjusted tonnage after smoke mission. I = 1-11; J = 1-5.

Table 6-8. Smoke subroutine table.

Functional area(s): B. Prepares the dimensions of the smoke screen.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>W_smoke</u>	Establishes the dimensions of the desired screen. Calls the Smkemp routine to emplace screen. Returns the percent of frontage visible through a screen as a function of sensor type.	A. Iunt B. Ielem	Flag which indicates the unit which emplaced the screen 1 = Blue - Light force 2 = Blue - Heavy force 3 = Red Flag indicating whether the screen is emplaced by artillery or mortars. 1 = artillery emplacement 8 = mortar emplacement.
		C. T_width (I)	An array containing the width of the units in contact: I = 1 - Blue unit's width = 2 - Red unit's width.
		D. S_time	Total screen time base on withdrawal time indicated by gamer.
		E. Vis	Visibility category flag. 1 = >4 km day 2 = 4 km day 3 = 2 km day 4 = 1 km day.
		F. Btl_rg	Range (kilometers) between units in contact.
		G. B_msmk_used (I)	Blue mortar smoke tonnage used to emplace screen (I = 1 - 4).
		H. B_asmk_used (I)	Blue artillery smoke tonnage used to emplace screen (I = 1 - 7).

Table 6-8. Smoke subroutine table.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>W_smoke</u> (concluded)			
		I. R_msmk_used (I)	Red mortar smoke tonnage used to emplace screen (I = 1 - 4).
		J. R_asmk_used (I)	Red artillery smoke tonnage used to emplace screen (I = 1 - 7).
		K. B_vis (I)	The percent of frontage visible through a smoke screen emplaced by the Blue force as a function of sensor type I. I = 1 - Optics = 2 - Crew served = 3 - Thermal.
		L. R_vis (I)	The percent of frontage visible through a smoke screen emplaced by the Red force as a function of sensor type I. I = 1 - Optics = 2 - Crew served = 3 - Thermal.
<u>Functional area(s): B.</u>	<u>Prepares the dimensions of the smoke screen.</u>		
<u>Functional area(s): C.</u>	<u>Emplaces desired screen. Determines total percent of frontage visible through screen.</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Sskemp	Attempts to cover entire frontage with mortar allocated tonnage. Covers any unsmoked frontage with artillery allocated tonnage. Calculates	A. Amovt (I)	Mortar and artillery tonnage allocated for smoke. I = 1-7 - artillery = 8-11 - mortar.
		B. Bnotsmok	Percent of frontage not covered by smoke.

Table 6-8. Smoke subroutine table.

Functional area(s): C. Emplaces desired screen. Determines total percent of frontage visible through screen.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Smkemp (continued)	percent of frontage visible through a screen as a function of sensor type. Calls Smoke routine to determine percent of frontage visible through "holes" in the screen.	C. Pmorto D. Amwt E. Partyo	Percent of frontage visible through mortar emplaced smoke when viewer is using an optic sensor. Total weight of mortar/artillery ammunition available to fire for smoke. Percentage of frontage visible through artillery-emplaced smoke when viewer is using an optic sensor.
		F. Pvopt	Total percent of frontage visible through mortar and/or artillery emplaced smoke when viewer is using an optic sensor.
		G. Pmortc	Percent of frontage visible through mortar emplaced smoke when viewer is using a crew served sensor.
		H. Partyc	Percent of frontage visible through artillery emplaced smoke when viewer is using a crew served sensor.
		I. Pvcs	Total percent of frontage visible through mortar and/or artillery emplaced smoke when viewer is using an crew served sensor.
		J. Pmortt	Percent of frontage visible through mortar emplaced smoke when viewer is using a thermal sensor.

Table 6-8. Smoke subroutine table.

Functional area(s): C. Emplaces desired screen. Determines total percent of frontage visible through screen.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Smkemp (continued)			
K. Partyt			Percent of frontage visible through artillery emplaced smoke when viewer is using a thermal sensor.
L. Pvth			Total percent of frontage visible through mortar and/or artillery emplaced smoke when viewer is using a thermal sensor.
M. Mleng (I)			Percent of frontage covered by mortar emplaced smoke. (I = 1 - 4).
N. Aleng (I)			Percent of frontage covered by artillery emplaced smoke. (I = 1 - 7).
O. Tot_mleng			Total length of mortar emplaced smoke.
P. Tot_aleng			Total length of artillery emplaced smoke.
Q. Fwldt			Total frontage to be screened.
R. Mton (I)			Total mortar tonnage used to emplace screen (I = 1 - 4).
S. Aton (I)			Total artillery tonnage used to emplace screen (I = 1 - 7).
T. Flwldt			Percent of frontage remaining unscreened after mortar emplaced smoke tonnage is expended.

Table 6-8. Smoke subroutine table.

Functional area(s):	<u>Emplaces desired screen. Determines total percent of frontage visible through screen.</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Smkemp (concluded)	U. Apseeopt (I) Apseecs (I) Apseeth (I)		Percent of artillery emplaced smoke frontage visible through "holes" in the screen as a function of optics, crew served or thermal sensors respectively (I=1-7).
	V. Mpseeopt (I) Mpseeccs (I) Mpseeeth (I)		Percent of mortar emplaced smoke frontage visible through "holes" in the screen as a function of optics, crew served or thermal sensors respectively (I=1-4).
Functional area(s):	<u>D. Determines the probability of detection through desired screen.</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Smoke	Accesses the probability of detection files for screens emplaced by mortar or artillery rounds. Returns percent of frontage visible through "holes" in an mortar or artillery emplaced screen.	A. Amowt (I)	The total amount of ammunition (tons) allocated to emplace screen.
		B. Amwtpp (I,J)	A real value containing the weight (pounds) of one round. The weight is a function of the unit (I) and the smoke round (J) used to emplace the screen (I = 1-3; J = 1-11).
		C. Irof (I,J)	A real value containing the rate of fire used to build the screen (I=1-3; J=1-11).
		D. Amwtpp	A real value containing the amount of ammunition (pounds) allocated to emplace the smoke screen.
		E. Nrd	An integer value containing the number of rounds used to emplace the screen.

Table 6-8. Smoke subroutine table.

<u>Functional area(s):</u> D. <u>Determines the probability of detection through desired screen.</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Variable descriptions</u>		
Smoke (continued)		
	F. Snrd (I)	The number of rounds used to emplace the screen for each type of indirect fire (I).
	G. Ton (I)	Ammunition tonnage allocated, but not used to emplace the screen.
	H. Sleng (I)	Length of screen actually produced by smoke tonnage allocated.
	I. Tot_sleng	Total length of screen which was produced by artillery or mortar.
	J. Smkdat(*)	Real array containing the prob- ability of detection.
	K. Irh	A flag indicating the relative humidity category. 1 = Rel. humid. less than 50% 2 = Rel. humid. 50% or greater.
	L. Fwidth	A real value containing the total width (battle frontage) between units.
	M. Pseopt (I)	Percent of smoked frontage visible through "holes" in the screen by an optics sensor.
	N. Pseecs (I)	Percent of smoked frontage visible through "holes" in the screen by a crew served sensor.
	O. Pseethm (I)	Percent of smoked frontage visible through "holes" in the screen by a thermal sensor.

Table 6-8. Smoke subroutine table.

Functional area(s): <u>D. Determines the probability of detection through desired screen.</u>	<u>Subroutine called</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Smoke (concluded)	P. Irg		The range band flag, an integer from 1 - 7 where: 1 = 0 - .5 km 2 = .5 - 1.0 km 3 = 1.0 - 1.5 km 4 = 1.5 - 2.0 km 5 = 2.0 - 2.5 km 6 = 2.5 - 3.0 km 7 = 3.0 - 3.5 km

Section IV. Direct Fire Attrition

1. PURPOSE

The purpose of the direct fire module is to portray opposing ground forces exchanging volleys during direct fire combat.

2. GENERAL

A. The direct fire module is a time step deterministic model. It calculates attrition for a 30 minute period of direct fire contact. However, during the pre-closure phase of battle (phase I) forces are only in contact for a 15 minute period. To represent this pre-closure, the expected number of completed firings are multiplied by one half.

B. Attrition is calculated using 20 firers per side (elements 1 through 20 of the unit status file or "UNITFILE"). There are 70 target elements per side which are grouped into 17 out of 20 target categories for calculations. The first 17 target categories consist of ground elements, and target categories 18-20 consist of helicopter elements.

3. DATA FLOW

A. Information is received from the ground combat mainline program. This information consists of:

(1). Variables used to read appropriate data such as flags for terrain, day/night, visibility, attacker and rangeband.

(2). Ammunition, in tons, available for Red and Blue.

(3). Percent of systems vulnerable and percent of systems visible through smoke.

(4). The number of 500 meter range bands the forces move within the 15 or 30 minute period.

(5). An array containing the status for ground systems entering the battle. It contains the number of targets entering the battle, the number of firers entering the battle, and blank positions which will later contain the losses for the direct fire battle.

(6). An array containing the number of target helicopters entering the battle.

(7). Ranges, in meters, between target helicopters and direct fire systems.

B. External data consisting of sensor files, fire distributions, ammunition weights, expected number of completed firings (ECF), and probability of kill (PK) files are necessary. If more than one 500 meter range band is moved during a 30 minute period, then new ECF and PK files are needed for each new range band. This data flow is represented in Figure 6-27.

4. FILE STRUCTURE

A. External Files.

(1). Sensor files hold the sensor type values 1-3: 1 = optics, 2 = crew served and 3 = thermal. The arrays $B_sen_d(J)$, $B_sen_n(J)$, $R_sen_d(J)$, and $R_sen_n(J)$ represent the sensors during the day and night where $J = 1 - 70$ for each of the 70 target elements. $B_vis(I)$ and $R_vis(I)$ are internal data arrays which contain the percentage of targets visible through smoke for each of the three sensor types ($I = 1$ to 3). $B_vis(I)$ and $R_vis(I)$ are accessed through the values found in the sensor arrays.

(2) Category files are needed to place the 70 target elements into the target categories for attrition calculations. The $B_cat(I)$ and $R_cat(I)$ arrays contain a value between 1 and 17, which represent the target category they fall into. (Categories 18-20 are reserved for the 3 types of enemy helicopters.)

(3) Fire distribution files contain weighted factors (a value from 1 to 10) which each firer applies to one of the twenty target categories when firing. The higher value indicates a higher preference in firing at that target. The arrays $B_fire_d(I,J)$ and $R_fire_d(I,J)$ represent the weighted factor in the following manner:

$I = (1-20)$ is the firer
 $J = (1-20)$ is the target category.

(4) Weight, engagement, and pointer files. Ammunition weights are kept within the $B_ammo_wt(I)$ and $R_ammo_wt(I)$ arrays for each firer. $B_engagements(I)$ and $R_engagements(I)$ are the number of engagements for each firer. Array $Df_sen_ptr(S,I)$ contains the direct fire sensor pointers (value 1 = optical ground or 2 = thermal ground) and array $Df_muni_ptr(S,I)$ contains the munitions pointers (value 1 = ground missile or 2 = ground kinetic energy round), where:

$S = (1-2)$ for each side (1 = blue, 2 = red)
 $I = (1-20)$ for each firer




Figure 6-27. Direct fire data flow.

(5) Expected number of completed firing (ECF) files contain the expected number of completed firings for each of the twenty firers during a 30 minute period. ECF's are dependent upon day/night, defending/attacking and terrain represented within the file name for both Blue and Red. Dependent also on the range, the 6 different direct fire range bands are represented by different records within each file. Weather visibility is also an important factor for ECF's and is designated in the arrays $B_{ecf_vis}(I,J)$ and $R_{ecf_vis}(I,J)$ where:

I = (1-20) the twenty firers
 J = (1-4) the visibility categories
 (1) greater than 5 km
 (2) 5 km
 (3) 2 km
 (4) 1 km.

(6) Probability of kill (PK) files are available for two types of target postures, hull defilade and fully exposed, which are represented by the file name. Dependent on range, the 6 records of each file represent the range band for the direct fire combat. The arrays containing the PK's are:

$B_{pk_fe}(I,J)$, $B_{pk_hd}(I,J)$, $R_{pk_fe}(I,J)$, $R_{pk_hd}(I,J)$

where: I = (1-20) the firers
 J = (1-20) the target categories.
 J = (18-20) are helicopter target categories

5. ALGORITHMS

A. Figure 6-28 presents a generalized logic flow of the processes in the ground combat direct fire subroutine. Direct fire attrition involves calculating the fire distribution factor, rounds available and the attrition calculations. The following paragraphs provide a more detailed description of the algorithms used in the attrition process.

(1) Calculate the fire distribution factor (Fdf_{ij}).

$$Fdf_{ij} = (T_j * D_{ij} * Pkfe_{ij}) / \sum_{j=1}^{20} (T_j * D_{ij} * Pkfe_{ij}) \quad (\text{Eq. 6-35})$$

where:

T_j = number of targets in category j being fired upon.
 D_{ij} = a weighted factor to represent preferred distribution of fire for firer i vs. target j.
 $Pkfe_{ij}$ = probability of kill for fully exposed targets (j) being fired on by i and where: i = (1-20) the firers and j = (1-20) target categories.




Figure 6-28. Direct fire logic flow.

At this point the Fdf_{ij} and Pk_{ij} of helicopter target categories $i = 18-20$ are saved and used in the helicopter attrition portion (see section V of this chapter) of P4.

The following direct fire calculations are based on the ground target categories ($j = 1-17$); the helicopter target categories ($j = 18-20$) are ignored.

(2) Calculate rounds available. The rounds available to each firer for each of its target categories is calculated in the following manner:

$$Rnds_{ij} = Fdf_{ij} * Nf_i * \text{MIN}(Ecf_i, \text{Ammo}_i) \quad (\text{Eq. 6-36})$$

where:

$Rnds_{ij}$ = rounds available to each firer (i) per ground target category (j).
 Nf_i = number of firers of type i.
 Ecf_i = expected number of completed firings for firer i.
 Ammo_i = ammunition available for firer i.

(3) Slice methodology. Attrition during the 30 minute period is broken into 15 slices of attrition calculations. This methodology brings about a more accurate representation of exchanging fire during battle. It allows the attrition to occur in 15 sections during a 30 minute period rather than one large mass of fire in one moment for a 30 minute period. Before each slice a new value for firers and targets is used which represents deducted kills from the previous slice.

Before this slice methodology may be used to calculate attrition, the rounds available must be broken down into the number of rounds fired per slice. The calculation is done as follows:

$$Erij = Rnds_{ij} / Nf_i / Ns \quad (\text{Eq. 6-37})$$

where:

$Erij$ = expected number of rounds per slice for each firer at each ground target category.
 Ns = number of slices.
 $Rnds_{ij}$ = rounds available to each firer per ground target category.
 Nf_i = number of firers.

For each slice k, the attrition calculations involve the probability of survival for each target category being fired on by each firer:

$$P_{ijk} = \frac{((1 - (Pv_j * Pkfe_{ij} + Pnv_j * Pkhd_{ij}))}{Nt_j} \uparrow (Nf_i * Er_{ij}) \quad (\text{Eq. 6-38})$$

where:

- P_{ijk} = the probability of survival for the jth ground target category being fired upon by the ith firer.
- Pv_j = percent of vulnerable targets for the jth ground target category.
- $Pkfe_{ij}$ = probability of kill for fully exposed targets in the jth ground target category being fired upon by the ith firer.
- Pnv_j = percent of targets not vulnerable for the jth ground target category.
- $Pkhd_{ij}$ = probability of kill for hull defilade targets in the jth ground target category being fired upon by the ith firer.
- Nt_j = total number of targets of type j.

The value of P_{ijk} is accumulated for all firers firing on each ground target category for slice k by:

$$P_{jk} = \prod_{i=1}^{17} P_{ijk} \quad (\text{Eq. 6-38a})$$

The value P_{jk} is also accumulated for all slices by:

$$Ps_j = \prod_{k=1}^{Ns} P_{jk} \quad (\text{Eq. 6-38b})$$

giving one probability of survival per ground target category over all slices and over all firers.

(4) Losses per target category are then calculated using the following:

$$L_j = T_j * V_j * (1 - Ps_j) \quad (\text{Eq. 6-39})$$

where:

- L_j = losses in the jth ground target category.
- T_j = number of targets being fired upon in the jth target category.
- V_j = percent of visible targets through smoke in the jth ground target category.

6. "UNITFILE" IMPACT

This subroutine does not directly impact the "UNITFILE". Kills calculated in this subroutine along with the amount of ammunition used is returned to the ground combat mainline and then decremented from the "UNITFILE".

7. CODE

A. Introduction. This section contains information on the direct fire attrition code. The functional areas discussed in the following paragraph are represented in Figure 6-29.

B. Direct fire attrition functional areas.

(1) The data received from the ground combat mainline consists of terrain, day/night, weather visibility, the percent of targets fully exposed, the number of 500 meter range bands the force is to move, the beginning range, whether red or blue is the attacker, sensor visibilities through smoke, ammunition available and the number of targets and fires on both sides.

(2) Set_call. This portion of the code saves the original range and initial targets. If the number of range bands is 1/2, one attrition loop with half the ECF's are utilized to represent pre-closure battle.

(3) Init_reads. Reads external sensor data, category files, fire distributions and ammunition weights which do not change by range.

(4) The following calculations are necessary for each 500 meter range covered by the forces:

(a) Read_files. The PK and ECF files are read for a specific range.

(b) Categorize. This code calculates the total number of targets per target category and the percent in which each target is fully exposed.

(c) Smokes. This code calculates the total number of systems available to be engaged as targets in the battle.




Figure 6-29. Direct fire functional flow.

(d) Calc_fdf. This portion of the code calculates the fire distribution factor being the distribution of rounds fired at the twenty target categories.

(e) Ammo_available. Determines the number of rounds available for firing per single weapon from the tons available sent from the mainline.

(f) Calc_rnd. Rounds fired by one of each of the twenty firers is determined by the minimum of rounds available and expected number of completed firings. These rounds per single weapon must then be multiplied by the total of each system type firing. These rounds must then be distributed between each of the ground target categories by using the fire distribution factor.

(g) Update_ammo. Accumulates the amount of ammo used and is returned to the mainline to be decremented from "UNITFILE" ammo.

(h) Calc_loss. Using the slice methodology discussed in the algorithm portion of direct fire attrition, the number of slices are set to 15 in this portion of the code. Before actual attrition is calculated, the number of rounds fired per slice must be calculated from the previous rounds per category. Occurring within the actual slice loop calculations are the following.

1. Firers are recalculated at the beginning of each slice to discard any killed during the previous slice(s).

2. Probability of survival is accumulated for all firers firing upon each ground target category. This, in turn, is accumulated for all slices as discussed in the algorithm portion of the direct fire documentation.

Having calculated the overall probability of survival for each ground target category, the losses are then determined by multiplying the number of targets in each category by their probability of kill (one minus the probability of survival) and their percent visible through smoke. This portion of the code is more explicitly displayed in Figure 6-30.

(i) Decat_losses. This apportions the losses within the first 17 target categories to losses within the 70 systems.

(j) Set_next_loop. This portion of the code decrements the appropriate losses from the firers, and the targets available along with adding in losses all contained in the array Sys(*). The range band is decremented to prepare for the following attrition calculations in another range.

(5) Set_return. Restores the range band and initial targets before returning the direct fire losses and ammunition used to the ground combat mainline.

Calculate average number of rounds per slice



Slice Loop:

Calculate current
number of firers



Accumulate probability
of survival for each
ground target category

End Slice Loop

Calculate kills
to each ground
target category

Figure 6-30. Direct fire functional flow of Calc_losses.

C. The primary variables of each functional area of the direct fire attrition subroutine are shown in Table 6-9. Each variable is accompanied by a short description. Table 6-14 contains a listing of the ground combat code.

Table 6-9. Direct fire subroutine table.

<u>Functional area(s):</u>	<u>Df attrition:</u>	<u>Direct fire attrition.</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>
<u>Variable description</u>		
Main	Main driver for Df attrition.	A. Band_loop B. Loops
		Loop counter; counts number of bands Number of attrition loops necessary for the number of range bands and length of battle.
Set_call	Saves the original range and initial targets.	A. Rng_band B. Rng_band_save
		The current range band Save value of Rng_band
		C. Init_b_targets(I) D. Init_r_targets(I)
		Array containing the initial number of Blue type I targets; I = 1 - 70 Array containing the initial number of Red type I targets; I = 1 - 70
		E. Num_bands F. Partial
		Number of 500 meter range bands If the number of range bands is less than 1, Partial = number of bands; otherwise, Partial = 1
		G. Sys(1,I) Sys(3,I)
		Array containing the remaining number of Blue targets of type I for the next range band Array containing the remaining number of Red targets of type I for the next range band; I from 1 to 70
		Sys(2,I)
		Array containing the number of losses to Blue targets of type I; I = 1 - 70

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition: Direct fire attrition.</u>		
<u>Subroutine called</u>	<u>Subroutine function(s)</u> <u>Primary variables</u> <u>Variable description</u>	
Set_call (concluded)	Sys(4,I) Sys(5,I) Sys(6,I)	Array containing the number of losses to Red targets of type I; I = 1 - 70 Array containing the number of remaining Blue firers of type I; I = 1 - 70 Array containing the number of remaining Red firers of type I; I = 1 - 70
Init_reads	A. Day_night B. B_sen(I) C. R_sen(I) D. Atk_def E. Terrain	0 = Day 1 = Night Array containing sensor data for Blue target I visible through smoke; I = 1 - 70 Array containing sensor data for Red target I visible through smoke; I = 1 - 70 0 = Blue attacking/Red defending 1 = Red attacking/Blue defending 1 = Open 2 = Rolling 3 = Hilly 4 = Mountainous
	Reads internal sensor data, external category files, fire distributions, and arms weights which do not change by range.	

Table 6-9. Direct fire subroutine table.

<u>Functional area(s):</u>	<u>Df attrition:</u>	<u>Direct fire attrition.</u>	
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Read_files	The probability of kill (PK) files and the expected number of completed firing (ECF) files are read for a specific range.	A. B_ecf_vis(I,J)	Array containing the expected number of completed firings for Blue firer I; I = 1 - 20; J = 1 for >5 km = 2 for 5 km = 3 for 2 km = 4 for 1 km
		B. R_ecf_vis(I,J)	Array containing the expected number of completed firings for Red firer I; I = 1 - 20; J same as for B_ecf_vis(I,J)
		C. B_ecf(I)	Array containing the expected number of completed firings for a fixed visibility category for Blue firer type I; I = 1 - 20
		D. R_ecf(I)	Array containing the expected number of completed firings for a fixed visibility category for Red firer type I; I = 1 - 20
		E. B_pk_fe (I,J) R_pk_fe (I,J)	Probability of kill for fully exposed target J being fired on by firer I. (I=1-20; J=1-20)
		F. B_pk_hd (I,J) R_pk_hd (I,J)	Probability of kill for hull defilade target J being fired on by firer I. (I=1-20; J=1-20)

Table 6-9. Direct fire subroutine table.

Functional area(s): Df attrition; Direct fire attrition.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Categorize	Calculates the total number of targets per target category and the percent in which each category is fully exposed.	A. B_cat(I)	Array containing the type of ground category for Blue element I. I = 1 - 70. There are 17 types of ground categories.
		B. R_cat(I)	Array containing the type of ground category for Red element I. I = 1 - 70. Types of categories are the same as for B_cat(I)
		C. B_targ(I)	Array containing the number of Blue targets of category I; I = 1 - 20
		D. R_targ(I)	Array containing the number of Red targets of category I; I = 1 - 20
		E. B_vul_t(I)	Array containing the total vulnerability of Blue targets of category I. I = 1 - 20. Determined by the number of remaining type I elements and their vulnerability, as given by B_vua(I)
		F. B_vua(I)	Array containing the vulnerability of Blue target I; I = 1 - 70

Table 6-9. Direct fire subroutine table.

Functional area(s): Df attrition; Direct fire attrition.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Categorize (continued)			
		G. R_vul_t(I)	Array containing the total vulnerability of Red targets of category I, I = 1 - 20. Determined by the number of remaining type I elements and their vulnerability, as given by R_vua(I).
		H. R_vua(I)	Array containing the vulnerability of Red target I; I = 1 - 70
		I. B_vul(I)	Array containing the vulnerability of Blue category I. I = 1 - 20. Determined by dividing B_vul_t(I) by the number of Blue targets of category I.
		J. R_vul(I)	Array containing the vulnerability of Red category I. I = 1 - 20. Determined by dividing R_vul_t(I) by the number of Red targets of category I.

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition; Direct fire attrition.</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Smokes	A. R_vis(I)	Calculates the total number of systems available to be engaged as targets in the battle.	A. R_vis(I)	Array containing the percent of frontage visible through a smoke screen employed by the Blue forces as a function of sensor type I: I = 1 Optics = 2 Crew served = 3 Thermal
	B. B_vis(I)		B. B_vis(I)	Array containing the percent of frontage visible through a smoke screen employed by the Red force as a function of sensor type I
	C. B_targ_vis(I)		C. B_targ_vis(I)	Array containing the number of Blue type I targets which are visible to Red; I = 1 - 20. Determined by the number of Red firers and the percent of frontage visible through a smoke screen employed by Blue forces. This is divided by the number of Blue firers of type I.
	D. R_targ_vis(I)		D. R_targ_vis(I)	Array containing the number of Red type I targets which are visible to Blue; I = 1 - 20
	E. B_look(I)		E. B_look(I)	Array containing the number of Blue firers of type I (I=1-20).
	F. R_look(I)		F. R_look(I)	Array containing the number of Red firers of type I (I=1-20).

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition; Direct fire attrition.</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Calc_fdf	Calculates the fire distribution factor; i.e., the distribution of rounds fired at the 20 target categories.	A. B_fire_d(I,J)	Array containing the fire distribution factor of Blue firer I on Red target J. Data accessed from data file. I = 1 - 20; J = 1 - 20.
		B. R_fire_d(I,J)	Array containing the fire distribution factor of Red firer I on Blue target J. Data accessed from data file. I = 1 - 20; J = 1 - 20.
		C. B_sum(I)	Array containing the sum of the fire of Blue firer of type I. I = 1 - 20. Determined by the number of Red targets, the preference factor of firer I against the Red target, and the probability of Blue firer I killing the Red target.
		D. R_sum(I)	Array containing the sum of the fire of Red firer of type I
		E. B_fdf(I,J)	Array containing the fire distribution factor of Blue firer I on Red target category J (I = 1 - 20; J = 1 - 20.) Determined by the number of Red targets of category J, the preference factor of Blue firer I against Red target J and the probability of Blue firer I killing fully exposed target J. This is divided by B_sum(I).

Table 6-9. Direct fire subroutine table.

<u>Functional area(s): Df attrition; Direct fire attrition.</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Calc_fdf (concluded)		F. R_fdf(I,J)	Array containing the fire distribution factor of Red firer I on Blue target category J. I = 1 - 20; J = 1 - 20.
Ammo_available	Determine the number of rounds available for firing per single weapon from the tons available sent from the mainline.	A. B_ammo_wt(I)	Array containing the ammunition weight in pounds for firing per single weapon for Blue type I firer; I = 1 - 20
		B. R_ammo_wt(I)	Array containing the ammunition weight in pounds for firing per single weapon for Red type I firer; I = 1 - 20
		C. B_tons(1,I) B_tons(2,I)	Array containing tons of ammunition initially available for Blue firer I sent from the mainline; I = 1 - 20 Array containing tons of ammunition used by Blue firer I
		D. R_tons(1,I) R_tons(2,I)	Array containing tons of ammunition initially available for Red firer I sent from the mainline; I = 1 - 20 Array containing tons of ammunition used by Red firer I; I = 1 - 20
		E. B_ammo(I)	Array containing number of rounds available for firing per single weapon for Blue type I firer; I = 1 - 20

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition; Direct fire attrition.</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Ammo available (concluded)		F. R_ammo(I)	Array containing number of rounds available for firing per single weapon for Red type I firer; I = 1 - 20
Calc_rnd	Calculates the number of rounds fired by each of the twenty firers.	A. B_rnds_wep(I)	Array containing the number of rounds fired by Blue firer I; I = 1 - 20. Determine by taking the minimum value of the number of rounds available and the expected number of completed firings.
		B. R_rnds_wep(I)	Array containing the number of rounds fired by Red firer I; I = 1 - 20
		C. Tot_b_rnds(I)	Array containing the total number of rounds fired by all of the Blue firers of type I; I = 1 - 20. Determined by the number of Blue firers of type I and B_rnds_wep(I).
		D. Tot_r_rnds(I)	Array containing the total number of rounds fired by all of the Red firers of type I; I = 1 - 20. Determined by the number of Red firers of type I and R_rnds_wep(I).

Table 6-9. Direct fire subroutine table.

Functional area(s): Df attrition; Direct fire attrition.

Subroutine called Subroutine function(s) Primary variables Variable description

Calc_rnd
(concluded)

E. B_rnds_cat(I,J)

Array containing the number of rounds fired from Blue firer I against Red target category J. I = 1 - 20; J = 1 - 20. Determined by the fire distribution factor of firer I against target J, and the total number of rounds fired by I.

F. R_rnds_cat(I,J)

Array containing the number of rounds fired from Red firer I against Blue target category J. I = 1 - 20; J = 1 - 20.

Update_ammo

Accumulates the amount of ammunition used, in tons.

Calc_loss

Calculates the average number of rounds fired per slice. Calculates the number of firers which survive for Red and Blue.

A. B_ex_r(I,J)

Array containing the average number of rounds fired per slice by Blue firer I against Red target category J. I = 1 - 20; J = 1 - 20.

B. R_ex_r(I,J)

Array containing the average number of rounds fired per slice by Red firer I against Blue target category J. I = 1 - 20; J = 1 - 20.

Table 6-9. Direct fire subroutine table.

Functional area(s): Df attrition; Direct fire attrition.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Calc_loss (continued)			
C. B_firers			Number of Blue firers surviving. Determined by the probability of survival of type I firer, and the number of type I firers.
D. R_firers			Number of Red firers surviving
E. Ps_r_ps			Probability of Red target J being killed by Blue firer I. Determined by the vulnerability of target J, the probability of firer I killing the fully exposed target J, and the probability of firer I killing the hull defilade target J.
F. Ps_b_ps			Probability of Blue target J being killed by Red firer I
G. R_ps(I,J)			Array containing the probability of Red target category J surviving against Blue firer I. I = 1 - 20; J = 1 - 20. Determined by Ps_r_ps, the number of Blue firers surviving, and the average number of rounds fired per slice by Blue firer I against Red target category J.
H. B_ps(I,J)			Array containing the probability of Blue target category J surviving against Red firer I. I = 1 - 20; J = 1 - 20.

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition; Direct fire attrition.</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Calc_loss (continued)	I. B_psuvs	(I)	Accumulated probability of Blue target categories surviving against all Red firers (I=1-20).
	J. R_psuvs	(I)	Accumulated probability of Red target categories surviving against all Blue firers (I=1-20).
	K. Lossr		Number of losses to Red category J targets. Determined by the number of J type targets which are visible to Blue, and R_ps(I,J).
	L. Lossb		Number of losses to Blue category J targets
	M. Lo_r_cat	(I,J)	Array containing the number of losses of Red type J targets, due to Blue type I firers. I = 1 - 20; J = 1 - 20.
	N. Lo_b_cat	(I,J)	Array containing the number of losses of Blue type J targets, due to Red type I firers. I = 1 - 20; J = 1 - 20.
	O. Lo_r_cats	(J)	Number of losses of Red type J targets; J = 1 - 20
	P. Lo_b_cats	(J)	Number of losses of Blue type J targets; J = 1 - 20
	Q. Loss_r_cat	(J)	Array containing the number of losses of Red category J targets

Table 6-9. Direct fire subroutine table.

Functional area(s): <u>Df attrition; Direct fire attrition.</u>			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
Calc_loss (concluded)	R. Loss_b_cat(J)	Array containing the number of losses of Blue category J targets	
	S. Red_target	A weighting factor for Ps_r_ps	
	T. Blue_target	A weighting factor for Ps_b_ps	
Decat_losses	A. Loss_blue (I) Loss_red (I)	Number of losses to each element (I=1-70).	
Set_next_loop	Apportions the losses within the 17 target categories to losses within the 70 target categories.		
	Decrements the appropriate losses from the firers and targets available.		
Set_return	Restores the range band and initial targets.		
	Returns the direct fire losses and ammunition used to the ground combat mainline.		

Section V. Helicopter Operations

1. PURPOSE

The purpose of the helicopter operations section of the DIME ground combat program is to realistically game air-to-ground, ground-to-air, and air-to-air interactions at variable ranges and missions between helicopters and the 20 target categories described in Section IV. These interactions take place during ground combat operations and are separate from air operations (ingress, egress, or strike) as in the DIME air defense program.

2. GENERAL

A. Both Red and Blue forces are played with capabilities and limitations which can mirror current and future equipment, vehicles, weapons, munitions, and helicopters.

B. Program characteristics include:

(1) Two types of attack helicopters and one scout helicopter are played for the Red and Blue forces.

(2) Seven possible air defense (AD) types may be played.

(3) Twenty possible direct fire types may be played.

(4) Losses to ground targets and helicopters are calculated by using various algorithms available within the module. These losses are a function of:

(a) Visibility (day or night)

(b) Terrain (mountainous, hilly, rolling, open)

(c) Target profile (fully exposed or hull defilade)

(d) Helicopter munitions (missiles, guns and missiles, guns/rockets or air to air missiles).

3. DATA FLOW

The helicopter module receives data from the main driver routine and auxiliary stored files. These data are used by the Helo_kills module to calculate the total elements killed by the helicopters and the total helicopters killed by the air defense and direct fire elements. See the data flow shown in Figure 6-31.

A. Inputs. The helicopter module receives the following data through a call statement from the main driver routine.

(1) Cell (S,I). An array which contains the cell size where:

S = 1 = Blue side
2 = Red side

I = 1 = the number of helicopter type 1
2 = the number of helicopter type 2
3 = the number of helicopter type 3

(2) Target (S,I,J). An array which contains the target matrix where:

S = Pointer to side

I = 1 = original number of systems
2 = surviving number of systems

J = 1 to 70 systems

(3) Ad_ammo(S). The ammunition available in short tons (2000 lbs) where:

S = Pointer to side

(4) Terr. An integer value of 1 to 4 which identifies the defender's terrain where:

1 = Open
2 = Rolling
3 = Hilly
4 = Mountainous

(5) Atk_prof (S,I). An integer value of 1 to 7 which identifies the helicopter's attacker profile:

1 = Missiles only
2 = Missiles and guns
3 = Guns and rockets
4 = Air to Air Missile




Figure 6-31. Data flow of helicopter attrition module.

- 5 = Air to Air Missile with Missiles
- 6 = Air to Air Missile with Missiles and Guns
- 7 = Air to Air Missile with Guns and Rockets

where:

- S = pointer to side
- I = helicopter type

(6) Helo_mis (S,I). An integer value of 1 to 3 which identifies the attacker's mission:

- 1 = Air to ground
- 2 = Air to air
- 3 = Suppression of Enemy Air Defense (SEAD)

where:

- S = pointer to side
- I = helicopter type

(7) Day_nite. An integer value representing the light visibility category, where:

- 0 = Day
- 1 = Night

(8) Time_step. The on-site time of a helicopter cell in minutes.

(9) P_def (S,I). Percent of the targets in hull defilade. The remaining targets are in the fully exposed posture where:

- S = pointer to side
- I = 1 to 70 systems

(10) Arty (S). An integer value of 1 or 2 which identifies the presence or absence of artillery fires, where:

- 1 = Yes, under artillery attack
- 2 = No, not under artillery attack

(11) Veh_ada (S). Percentage of vehicular AD Systems suppressed
where:

- S = pointer to side

(12) Hnd_ada(S). Percentage of hand-held AD systems suppressed where:

S = pointer to side

(13) Stnd_off_rg (S,I). A variable integer value indicating the attacker's standoff range to the opposing target in meters where:

S = pointer to side

I = helicopter type

(14) Vis. An integer value of 1-4 indicating the atmospheric visibility where:

1 = > 5 km

2 = 5 km

3 = 2 km

4 = 1 km

B. The helicopter module also receives input data through the common block area called "Helo_info".

(1) Btl_rg. The current range between the two forces on the battle field.

(2) Rg_avg (S,I,J). The range between the helicopter I (I = 1 - 3) and the target category J (J = 1 - 20) for side S (S = 1 - 2) in meters. The ranges are calculated in subprogram Helo_range and are illustrated in Tables 6-Va, 6-Vb, and 6-Vc.

(3) Df_ammo (S). Direct fire ammunition available to shoot at helicopter targets for side S.

(4) Df_fire_dist (S,I,J). Fire distribution factor of each direct fire type I shooting at target helicopter J (J = 1-3).

(5) Df_pk_helo (S,I,J,M). Direct fire probability of kill of helicopters J, mast mounted (M=1) and non-mast mounted (M=2).

(6) Df_sen_ptr (S,I). Pointer to type of sensor (value 1 = optical ground, 2 = thermal ground) for direct fire type I (I = 1-20) on side S (S = 1-2).

(7) Df_muni_ptr (S,I). Pointer to type of munition (value 1 = ground missile, 2 = ground kinetic energy round) for direct fire type I (I = 1- 20) on side S (S = 1-2).

C. Other inputs required by the helicopter module are read in from auxiliary storage files, such as the: helicopter characteristics files; helicopter sensor files; helicopter munitions files; helicopter vulnerability files; AD vulnerability files; AD ammunition files; helicopter target preference file; direct fire sensor files; direct fire munitions files. This data is stored in common block area "Helo_attrite" for later retrieval in the Helo_kills module.

D. Outputs. The helicopter module returns to the main driver routine the number of elements in a target category killed by the helicopters and the number of helicopters killed by AD elements, ground elements and other helicopters.

4. FILE STRUCTURE

DIME helicopter files are used by the ground combat (P4) program to supply statistical performance/preference data and physical characteristics data (basic load, weight/round, etc.). Figure 6-32 is an example of the interaction between the file structures.

A. Helicopter characteristics files.

There is one helicopter characteristics file for each force. Each file contains three records, one for each helicopter type. Each helicopter record contains eight elements. The structure of each record is as follows:

<u>Index</u>	<u>Description</u>
1	Pointer to unique sensor type (value 1-10).
2	Pointer to unique missile type (value 1-15).
3	Pointer to unique gun type (value 1-15).
4	Pointer to unique air to air missile (value 1-15).
5	Basic load for the unique missile above
6	Basic load for the unique gun above
7	Basic load for the unique air to air missile above
8	Sensor location (0= non-mast mounted, 1= mast mounted)




Figure 6-32. Helicopter file hierarchy.

In this figure, record 2 of the Blue Characteristics file is shown in detail. Each record describes a helicopter type plus sensor and munition pointers. The sensor pointer points to record 3 of the Sensor Performance File which describes a unique type of sensor (contains probability of detection data). The missiles, gun and air-to-air pointers respectively point to records 1, 4 and 15 of the Helicopter Performance File. These records describe a munition type (contain probability of kill data, tactical number of rounds, fire and guide time and time masked and exposed).

B. Helicopter sensor performance files.

There is one helicopter sensor performance file for each force. Each file contains ten records for unique types of sensors. Each sensor record contains seventy-seven elements used to represent the probability of detection (P_{∞}) and the average time to detect (\bar{T}) for each target. Record entries represent fitted coefficients in the equation

$$P_{\infty} = ar^2 + br + c \text{ and } \bar{T} = a'r^2 + b'r + c' \text{ where}$$

r = range in meters to target.

The structure of each record is as follows:

<u>Index</u>	<u>Description</u>
1	Sensor description string (eight characters).
2	Probability of detection (P_{∞}) coefficient [a] of target category personnel, fully exposed
3	Probability of detection (P_{∞}) coefficient [a] of target category personnel, hull defilade
4	Probability of detection (P_{∞}) coefficient [a] of target category light vehicles, fully exposed
5	Probability of detection (P_{∞}) coefficient [a] of target category light vehicles, hull defilade
6	Probability of detection (P_{∞}) coefficient [a] of target category heavy vehicles, fully exposed
7	Probability of detection (P_{∞}) coefficient [a] of target category heavy vehicles, hull defilade
8	Probability of detection (P_{∞}) coefficient [a] of target category artillery, fully exposed
9	Probability of detection (P_{∞}) coefficient [a] of target category artillery, hull defilade
10	Probability of detection (P_{∞}) coefficient [a] of target category helicopters, fully exposed
11	Probability of detection (P_{∞}) coefficient [a] of target category helicopters, hull defilade

- 12-21 Probability of detection (P_{∞}) coefficient [b] with the same format as 2-11.
- 22-31 Probability of detection (P_{∞}) coefficient [c] with the same format as 2-11.
- 32-41 Average time to detect (\bar{T}) coefficient [a'] with the same format as 2-11.
- 42-51 Average time to detect (\bar{T}) coefficient [b'] with the same format as 2-11.
- 52-61 Average time to detect (\bar{T}) coefficient [c'] with the same format as 2-11.
- 62-69 Probability of detection range minimum [r_{min_a}] for each atmospheric condition. (Day/Night and Visibility) (e.g., 62-Day, >5 KM, 63-Day, 5 KM, 64-Day, 2 KM, 65-Day, 1 KM, 66-Night, >5 KM, etc)
- 70-77 Probability of detection range maximum [r_{max_a}] for each atmospheric condition. (Day/Night and Visibility) (e.g., 70-Day, >5 KM, 71-Day, 5 KM, 72-Day, 2 KM, 73-Day, 1 KM, 74-Night, >5 KM, etc)

C. Helicopter performance against targets files.

There is one helicopter performance file for each force. Each file contains fifteen records for unique types of munitions. These records contain data describing munition lethalties (Pk's) and the performance parameters of the helicopters used in the tactics of munition delivery. Record entries for Pk's represent fitted coefficients in the equation

$$Pk = ar^2 + br + c \text{ where } r = \text{range in meters}$$

Each munition record contains 131 elements. The structure of each record is as follows:

<u>Index</u>	<u>Description</u>
1	Munition description string (eight characters).
2-41	Probability of kill (Pk) coefficient [a] for each of the 20 target categories, fully exposed and hull defilade. (e.g., 2-Target Category 1 Fully Exposed, 3-Target Category 1 Hull Defilade, 4-Target Category 2 Fully Exposed, etc.)

<u>Index</u>	<u>Description</u>
42-81	Probability of kill (Pk) coefficient [b] for each of the 20 target categories, fully exposed and hull defilade. (e.g., 42-Target Category 1 Fully Exposed, 43-Target Category 1 Hull Defilade, 44-Target Category 2 Fully Exposed, etc.)
82-121	Probability of kill (Pk) coefficient [c] for each of the 20 target categories, fully exposed and hull defilade. (e.g., 82-Target Category 1 Fully Exposed, 83-Target Category 1 Hull Defilade, 84-Target Category 2 Fully Exposed, etc.)
122	Probability of kill (Pk) range minimum [rmin]
123	Probability of kill (Pk) range maximum [rmax]
124	Tactical number of rounds fired per pop up
125	Fire and guide time [fm].
126-128	Time masked [Tm _j] for each mission in the pop up / pop down cycle. (e.g., 126-air to ground, 127-air to air, 128-SEAD)
129-131	Time exposed [Te _j] for each mission in the pop up / pop down cycle. (e.g., 129-air to ground, 130-air to air, 131-SEAD)

D. Helicopter target preference files.

There is one helicopter target preference file for each force. Each file contains three records, one for each mission, with record 1 = air to ground, record 2 = air to air, and record 3 = SEAD. Each mission record contains 28 elements. The files contain numeric weights representing helicopter preferences for targets and the parameters α , β used to approximate line of sight between helicopters and their targets. The parameters α , β are used in the following form

$$P_{los} = \alpha (e^{-\beta r})$$

The structure of each record is as follows:

<u>Index</u>	<u>Description</u>
1-20	Preferences for each target category [D _{ijk}].
21-24	Probability of line of sight alpha [α] for each terrain (open, rolling, hilly, mountainous)

<u>Index</u>	<u>Description</u>
25-28	Probability of line of sight beta [β] for each terrain. (open, rolling, hilly, mountainous)

E. Helicopter vulnerability against air defense files.

There is one helicopter vulnerability file for each force. Each file contains seven records; one for each air defense weapon. Each air defense weapon record contains thirty-nine elements describing the ability of the AD weapon to detect and kill the helicopters. Detection parameters include probability of detection and time to detect. The lethality parameters represent PKs. The parameters in the file represent fitting coefficients and are as described under the helicopter lethality file. The structure of each record is as follows:

<u>Index</u>	<u>Description</u>
1-2	Probability of detection (P_{∞}) coefficient [a] for mast mounted and non-mast mounted.
3-4	Probability of detection (P_{∞}) coefficient [b] for mast mounted and non-mast mounted.
5-6	Probability of detection (P_{∞}) coefficient [c] for mast mounted and non-mast mounted.
7-8	Average time to detect \bar{T} coefficient [a'] for mast mounted and non-mast mounted.
9-10	Average time to detect \bar{T} coefficient [b'] for mast mounted and non-mast mounted.
11-12	Average time to detect \bar{T} coefficient [c'] for mast mounted and non-mast mounted.
13-20	Probability of detection range minimum [r_{min_a}] for each atmospheric condition. (Day/Night and Visibility) (e.g., 13-Day, >5 KM, 14-Day, 5 KM, 15-Day, 2 KM, 16-Day, 1 KM, 17-Night, >5 KM, etc)
21-28	Probability of detection range maximum [r_{max_a}] for each atmospheric condition. (Day/Night and Visibility) (e.g., 21-Day, >5 KM, 22-Day, 5 KM, 23-Day, 2 KM, 24-Day, 1 KM, 25-Night, >5 KM, etc)
29-30	Mast mounted and non-mast mounted probability of kill coefficient [a].

<u>Index</u>	<u>Description</u>
31-32	Mast mounted and non-mast mounted probability of kill coefficient [b].
33-34	Mast mounted and non-mast mounted probability of kill coefficient [c].
35	Probability of kill range minimum [rmin].
36	Probability of kill range maximum [rmax].
37-39	Preferences of AD weapon for each enemy helicopter [H].

F. Air defense miscellaneous files.

There is one air defense miscellaneous file for each force. Each file contains seven records, one for each air defense weapon. Each air defense weapon record contains 3 elements. The structure for each record is as follows:

<u>Index</u>	<u>Description</u>
1	Weight per round (lbs).
2	Rounds per engagement.
3	Flyout velocity of the munition [Fad] in meters/sec.

G. Direct fire sensor performance files.

There is one direct fire sensor performance file for each force. Each file contains two records, the first for optical ground sensors and the second for thermal ground sensors. Each sensor record contains 28 elements representing the probability of detection P and the average time to detect T. The parameters in the file represent fitting coefficients and are as described under the helicopter sensor performance files. The structure of each file is as follows.

<u>Index</u>	<u>Description</u>
1-2	Probability of detection (P_{∞}) coefficient [a] for mast mounted and non-mast mounted helicopters.

<u>Index</u>	<u>Description</u>
3-4	Probability of detection (P_{∞}) coefficient [b] for mast mounted and non-mast mounted helicopters.
5-6	Probability of detection (P_{∞}) coefficient [c] for mast mounted and non-mast mounted helicopters.
7-8	Average time to detect \bar{T} coefficient [a'] for mast mounted and non-mast mounted helicopters.
9-10	Average time to detect \bar{T} coefficient [b'] for mast mounted and non-mast mounted helicopters.
11-12	Average time to detect \bar{T} coefficient [c'] for mast mounted and non-mast mounted helicopters.
13-20	Probability of detection range minimum [r_{min_a}] for each atmospheric condition (Day/Night and Visibility - e.g., 13-day, > 5 km, 14-day, 5 km, 15-day, 2 km, 16-day, 1 km, 17-night, > 5 km, etc.)
21-28	Probability of detection range maximum [r_{max_a}] for each atmospheric condition (same format as probability of detection range minimum above).

I. Direct fire miscellaneous files.

There is one direct fire miscellaneous file for each force. Each file contains two records, the first for ground missile data, and the second for ground kinetic energy round data. Each record contains two elements. The structure for each record is as follows:

<u>Index</u>	<u>Description</u>
1	Rounds fired per engagement
2	Flyout velocity of the munition [Fvdf] in meters/second

5. ALGORITHMS

A. Figure 6-33 presents a generalized logic flow of the processes occurring in the P4 helicopter module. The diagram provides a framework for the algorithms used in the module.

B. The geometry for the helicopter module is assumed to be as follows:

(1) For air to ground missions, the helicopters will play in-line with the ground forces.

(2) For SEAD missions, the attacking helicopters will flank the ground forces.

(3) For air to air missions, the attacking helicopter will maximize the range to opposing ground forces.

The following definitions are used:

R_R = The input range by the Red Helicopter player

R_B = The input range by the Blue Helicopter player

R_f = The range between the forces

B = Centroid of the Blue Force

R = Centroid of the Red Force

r = range used by the model when calculating P_k , P_{∞} , \bar{T} , etc. for helicopter to helicopter engagements (Table 6-Va) and helicopter vs ground engagements (Tables 6-Vb & 6-Vc).

The range calculations used in the helicopter module are illustrated in tables 6-Va through 6-Vc.

C. The following paragraphs provide a detailed description of the algorithms used for the attrition of target elements due to helicopters. Attrition to helicopters from air defense and direct fire elements is also calculated.




Figure 6-33. Generalized logic flow of helicopter attrition module.

Helicopter to Helicopter (r)

BLUE MISSION










		BLUE MISSION		
		Direct Support	Helo to Helo	SEAD
RED MISSION	Direct Support	 $ABS(R_e + R_e - R_r)$	 R_e	 $\sqrt{(R_e - R_r)^2 + R_e^2}$
	Helo to Helo	 R_e	 $\frac{R_e + R_e}{2}$	 R_e
	SEAD	 $\sqrt{(R_e - R_r)^2 + R_e^2}$	 R_e	 $\frac{1}{2} R_r \sqrt{R_r^2 + (R_e + R_e)^2}$

TABLE 6-Va

Blue Ground to Red Helo Ranges (r










		RED MISSION		
		Direct Support	Helo to Helo	SEAD
BLUE MISSION	Direct Support	 R_e	 $\sqrt{(R_s - R_f)^2 + R_e^2}$	 R_e
	Helo to Helo	 R_e	 $\frac{R_f}{2} + \frac{R_e + R_s}{4}$	 R_e
	SEAD	 R_e	 $R_f + \sqrt{R_e^2 - R_s^2}$	 R_e

TABLE 6-Vb

Red Ground to Blue Helo Ranges










		BLUE MISSION		
		Direct Support	Helo to Helo	SEAD
RED MISSION	Direct Support	 R_g	 $\sqrt{(R_g - R_f)^2 + R_b^2}$	 R_g
	Helo to Helo	 R_g	 $\frac{R_f + R_g + R_b}{2 + \frac{R_b}{4}}$	 R_g
	SEAD	 R_g	 $R_f + \sqrt{R_g^2 - R_b^2}$	 R_g

TABLE 6-Vc

(1) Number of helicopter munitions fired during the time step.

The number of rounds fired during the timestep per helicopter are:

$$R_{ij} = \bar{R}_{p_{ij}} * Put_i * Fdf_{ij} \quad (\text{Eq. 6-40})$$

where:

- $\bar{R}_{p_{ij}}$ = Average rounds fired at target category j per pop-up by helicopter i
 Put_i = Number of pop-ups by helicopter i during the assessment interval
 Fdf_{ij} = Fire distribution factor of rounds from firer i to target j

(i) For air to ground:

$$\bar{R}_{p_{ij}} = Pdt(r,t)_{ij} * Plos(r,ga)_k * Np \quad (\text{Eq. 6-41})$$

(ii) For air to air:

$$\bar{R}_{p_{ij}} = P(\text{engage})_{ij} * Np \quad (\text{Eq. 6-41a})$$

where:

- $Pdt(r,t)_{ij}$ = Probability of detection of target j which falls into detection category t by the firer i. The detection category is described under equation 6-42.
 $Plos(r,ga)_k$ = Probability that the helicopter has line of sight to the opposing force in terrain type k at range r. The target may be either ground or air (ga).
 Np = Tactical number of rounds fired by a helicopter when engaging a target.
 $P(\text{engage})_{ij}$ = Probability that helicopter i will engage target helicopter j

(i) Both $Pdt(r,t)_{ij}$ and $Plos(r,ga)_k$ are functions of range. They have the following forms.

$$Pdt(r,t)_{ij} = Pdfe(r,t)_a * Pfe + Pdhd(r,t)_a * Phd \quad (\text{Eq. 6-42})$$

where:

$Pdfe(r,t)_a$ = Probability of helicopter i detecting a fully exposed target of type t at range r under atmospheric conditions a . The target categories are personnel, light vehicles, heavy vehicles, artillery, and helicopters. The subscript a represents the atmospheric conditions. Eight conditions can be played: 1 km, 2 km, 5 km, >5 km for both day and night.

If $r_{min_a} \leq r \leq r_{max_a}$:

$$Pdfe(r,t)_a = P_{\infty}(r,t) \left(1 - e^{(-Ut(r)/\bar{T}(r,t))} \right) \quad (\text{Eq. 6-43})$$

Otherwise, $Pdfe(r,t)_a = 0$.

where $P_{\infty}(r,t) = a_t r^2 + b_t r + c_t$ is the probability of detecting the target of category t at range r when searching infinite time. a_t, b_t, c_t are fit parameters for target type t .
 $T(r,t) = a_t r^2 + b_t r + c_t$ is the average time to detect a target. a_t, b_t, c_t are fit parameters for target type t .
 $Ut(r) =$ the time the helicopter is exposed (te_{ik}) minus its fire and guide time. $te_{ik} = r / fm$ (fm is munition dependent for a missile, gun or air defense)

r_{min_a} and r_{max_a} are bounds based on the day, night and atmospheric type.

$Pdhd(r,t)_a =$ probability of detection for hull defilade targets. The definition of the structure is analogous to $Pdfe(r,t)_a$.
 $Pfe =$ percent of the targeted force fully exposed.
 $Phd =$ percent of the targeted force in hull defilade.

$$Plos(r,ga)_k = \alpha (e^{-\beta r}) \quad (\text{Eq. 6-44})$$

where:

α and β are fitting factors for probability of line of sight in four different types of terrain k for helicopters searching for ground targets and helicopters searching for air targets and in SEAD missions.

Popups for this time interval can be described as

$$Put_i = \frac{ts}{tm_{ik} + te_{ik}} \quad (\text{Eq. 6-45})$$

where:

- Put_i = number of pop-ups this time interval for firer i
 ts = seconds represented in the attrition step
 tm_{ik} = the average time masked per firing cycle for helicopter i for mission k
 te_{ik} = the average time exposed for helicopter i for mission k
 $k =$ 1 air to ground
 2 air to air
 3 SEAD for helicopter type j

The tm_{ik} and te_{ik} values that are used in calculations are determined by helicopter i's primary mission. If helicopter i is on an air to ground or SEAD mission, the tm_{ik} and te_{ik} of the conventional munitions (guns or missiles) are used. If it is on an air to air mission, the tm_{ik} and te_{ik} of the air munitions are used.

(ii) Equation 6-41a is basically the same as equation 6-41 with

$$P(\text{engage})_{ij} = \frac{P(\text{Exposure time}_i > \phi(r)) * P(\text{Detection time}_{ij} < \text{Exposure time}_i - \phi(r))}{P(\text{Detection time}_{ij} < \text{Exposure time}_i - \phi(r))} \quad (\text{Eq. 6-46})$$

where:

$$\phi(r) = r/f_i \quad (\text{Eq. 6-47})$$

r is the target range and f_i is the firer munition pinpoint and flyout time in meters/second.

The difference in the equations arises because the target and firer are popping up and down with their own frequencies. To solve the equations, the following assumptions are made:

- (a) The pop-up, pop-down process is an alternating Markov process with the durations of the alternating up, down states negative exponential random variables.
- (b) The time to acquire a target given it is continuously visible is an exponentially distributed random variable.

(c) The line of sight process between each target-firer pair is independent of all other pairs.

(d) Once a firer helicopter i has begun an engagement of a helicopter target j , it will continue until the engagement is complete, regardless if any other helicopter is firing at the same target.

$P(\text{Exposure})$ then becomes the exponentially distributed density function:

$$P(t) = \xi_i * e^{-\xi_i t} \quad \text{where } 0 < t \quad (\text{Eq. 6-48})$$

and

$$\xi_i = 1 / \bar{t}_{eik} \quad (\text{Eq. 6-49})$$

where \bar{t}_{eik} = the exposure time for firer i while it is performing mission k .

$DET_{ij}(t)$ is the probability that firer i will have detected target helicopter j after searching (t) seconds. $DET_{ij}(t)$ has the following form under the assumption of completed firing engagement (from "Vector-2 System of Theater Level Combat" DDC number ADB037799):

$$DET_{ij}(t) = 1 - \left[1 - (Z_{ij} / (\mu_j - Z_{ij})) (e^{-Z_{ij}t} - e^{-\mu_j t}) \right]^{N_j} \quad (\text{Eq. 6-50})$$

where:

N_j = number of target helicopters j on site
 Z_{ij} = the rate firer i detects target j , with j moving in and out of the line of sight of i .

$$Z_{ij} = \frac{\lambda_{ij} * \eta_{ij}}{\eta_j + \mu_j} \quad (\text{Eq. 6-51})$$

$$\eta_j = (1 / \bar{t}_{mjk}) \quad (\text{Eq. 6-52})$$

$$\mu_j = (1 / \bar{t}_{ejk}) \quad (\text{Eq. 6-53})$$

Note that \bar{t}_{mj} and \bar{t}_{ej} are the mask and exposure times of the target helicopter j and are determined by the same rules as in equation 6-45.

λ_{ij} = the rate at which helicopter i detects helicopter j

$$\lambda_{ij} = \frac{P_{\infty}(r,t) \left[1 - e^{-\frac{(t_{eik} - r / fm)}{\bar{T}(r,t)}} \right]}{\bar{T}(r,t)} \quad (\text{Eq. 6-54})$$

Where $P_{\infty}(r,t)$ and $\bar{T}(r,t)$ are as described in equation 6-43.

Also note that the dividend of λ_{ij} is the same calculation as $Pdfe(r,t)_a$ (equation 6-43).

Then:

$$P(\text{engage})_{ij} = \int_{\phi(r)}^{\infty} \xi_i * e^{-\xi_i t} * \text{DET}_{ij}(t - \phi(r)) dt$$

Substituting in equation 6-50 we get:

$$P(\text{engage})_{ij} = \int_{\phi(r)}^{\infty} \xi_i * e^{-\xi_i t} \left[1 - \left[1 - (z_{ij} / (\mu_j - z_{ij})) * \left(e^{-z_{ij}(t - \phi(r))} - e^{-\mu_j(t - \phi(r))} \right) \right] \right] N_j$$

The approximation used to numerically solve this equation is:

$$P(\text{engage})_{ij} = \sum_{t=\phi(r)}^{\frac{\ln 1}{\xi_i}} \xi_i * e^{-\xi_i t} * \text{DET}_{ij}(t - \phi(r))$$

(Eq. 6-55)

(This will account for at least 90% of the density of the firer exposure time.)

(2) Probability of kill for Target j by Helicopter i.

The probability of kill for this timestep is given by:

$$P_{k_{ij}} = P_{kd_{ij}}(r) * P_{hd} + P_{ke_{ij}}(r) * P_{fe} \quad (\text{Eq. 6-56})$$

where:

- $P_{kd_{ij}}(r)$ = the probability of kill for target category j by helicopter i for defilade targets at range r. Note that the target category (1-20) has been used.
- $P_{ke_{ij}}(r)$ = probability of kill for target category j by helicopter i for fully exposed targets at range r. Again the target category (1-20) has been used.

$P_{kd_{ij}}(r)$ and $P_{ke_{ij}}(r)$ have the following forms: If $r_{min} \leq r \leq r_{max}$, then

$$P_{kd_{ij}}(r) \text{ and } P_{ke_{ij}}(r) = ar^2 + br + c \quad (\text{Eq. 6-57})$$

Otherwise they equal 0.

The variables r_{min} and r_{max} are a function of target category and helicopter munition combination. (Each helicopter can be equipped with a maximum load of two air to ground munitions, and one air to air munitions. It can be loaded explicitly with fewer munitions.)

P_{hd} and P_{fe} are respectively the percent of the target force in hull defilade or fully exposed. Note that these are the same percentages as described under probability of detection.

(3) Fire Distribution Factor for Target j by Helicopter i.

The fire distribution factor, Fdf_{ij} , of rounds fired by helicopter i at target category j can be calculated using the following:

$$Fdf_{ij} = \frac{Pdt(r,t)_{ij} * tgt_j * Pke_{ij}(r) * D_{ijk}}{\sum_{j=1}^{20} Pdt(r,t)_{ij} * tgt_j * Pke_{ij}(r) * D_{ijk}} \quad (\text{Eq. 6-58})$$

all target categories

where:

D_{ijk} = a weighted factor representing the preferred distribution of firer i vs category j for mission k .

tgt_j = number of target elements in category j being engaged by firer i .

$Pdt(r,t)_{ij}$ and $Pke_{ij}(r)$ are as described in previous paragraphs.

(4) Determine Actual Number of Air and Conventional Rounds Fired Based on Ammunition Constraints.

$$(a) P_{g_i} = \sum_{j=1}^{17} Fdf_{ij} \quad (\text{Eq. 6-59})$$

$$P_{a_i} = \sum_{j=18}^{20} Fdf_{ij}$$

where:

P_{g_i} = desired percent of time firing at ground targets

P_{a_i} = desired percent of time firing at air targets.

Fdf_{ij} is as described in Equation 6-58.

(b)

$$Cnvpop_i = \sum_{j=1}^{17} (\bar{R}_{p_{ij}} * Fdf_{ij}) / P_{gi} \quad (\text{Eq. 6-60})$$

$$Airpop_i = \sum_{j=18}^{20} (\bar{R}_{p_{ij}} * Fdf_{ij}) / P_{ai}$$

where:

$Cnvpop_i$ = total number of conventional munitions fired per popup by firer i at all ground targets.

$Airpop_i$ = total number of air missiles fired per popup by firer i at all air targets.

$\bar{R}_{p_{ij}}$ and Fdf_{ij} are as described in Equations 6-41 and 6-58, respectively.

Note that the tradeoff rate of air to air/ground is $Airpop_i / Cnvpop_i$.

(c)

$$R_{gi} = \sum_{j=1}^{17} \bar{R}_{p_{ij}} * Put_i * Fdf_{ij} \quad (\text{Eq. 6-61})$$

$$R_{hi} = \sum_{j=18}^{20} \bar{R}_{p_{ij}} * Put_i * Fdf_{ij}$$

where:

R_{gi} = total number of rounds fired at ground targets by firer i.

R_{hi} = total number of air missiles fired at air targets by firer i.

$\bar{R}_{p_{ij}}$, Put_i , and Fdf_{ij} are as described in Equations 6-41, 6-45, and 6-58, respectively.

These equations can also be written as:

$$R_{g_i} = \sum_{j=1}^{17} R_{ij} \quad (\text{Eq. 6-61a})$$

$$R_{h_i} = \sum_{j=18}^{20} R_{ij}$$

Where R_{ij} is as described in Equation 6-40.

(d) Determine rounds based on ammunition constraints.

R_{ab_i} = basic load of air munitions for firer i.

R_{cb_i} = basic load of conventional munitions for firer i.

Case I: Enough air and ground rounds on board to fire the desired number of rounds:

$$R_{h_i} \leq R_{ab_i} \text{ and } R_{g_i} \leq R_{cb_i}$$

then:

$$R_{air_i} = R_{h_i} \text{ and } R_{conv_i} = R_{g_i}$$

where:

R_{air_i} = actual total number of air rounds fired based on ammo constraints.

R_{conv_i} = actual total number of ground rounds fired based on ammo constraints.

Case II: Not enough air rounds on board:

$$R_{h_i} > R_{ab_i}$$

$$R'_{g_i} = (R_{h_i} - R_{ab_i}) * (C_{nvpop_i} / A_{irpop_i}) \quad (\text{Eq. 6-62})$$

where R'_{g_i} = amount of conventional rounds needed to make up insufficient air rounds.

IIa.

If there are enough conventional rounds on board:

$$R'g_i + Rg_i \leq Rcb_i$$

then:

$$\begin{aligned} Rair_i &= Rab_i \\ Rconv_i &= R'g_i + Rg_i \end{aligned}$$

IIb.

If there are not enough conventional rounds on board:

$$R'g_i + Rg_i > Rcb_i$$

then

$$\begin{aligned} Rair_i &= Rab_i \\ Rconv_i &= Rcb_i \end{aligned}$$

and the number of popups is reduced:

$$Put_i = Put_i * ((Rair_i + Rconv_i * (Airpop_i / Cnvpop_i)) / (Rh_i + Rg_i * Airpop_i / Cnvpop_i)) \quad (\text{Eq. 6-63})$$

Case III: Not enough ground rounds on board:

$$Rg_i > Rcb_i$$

$$R'h_i = (Rg_i - Rcb_i) * (Airpop_i / Cnvpop_i) \quad (\text{Eq. 6-62a})$$

where $R'h_i$ = amount of air missiles needed to make up insufficient ground rounds.

IIIa.

If there are enough air munitions on board:

$$R'h_i + Rh_i \leq Rab_i$$

then

$$\begin{aligned} Rair_i &= R'h_i + Rh_i \\ Rconv_i &= Rcb_i \end{aligned}$$

IIIb.

If there are not enough air munitions on board:

$$R'h_i + Rh_i > Rab_i$$

then

$$\begin{aligned} Rair_i &= Rab_i \\ Rconv_i &= Rcb_i \end{aligned}$$

and the number of popups is reduced.

$$Put_i = Put_i * \left(\frac{(Rair_i * (Cnvpop_i / Airpop_i) + Rconv_i)}{(Rh_i * (Cnvpop_i / Airpop_i) + Rg_i)} \right) \quad (\text{Eq. 6-63a})$$

Rair_i and Rconv_i are then used to scale down the actual number of rounds fixed at each target j, if needed.

(5) Number of Rounds Fired by the Air Defense Elements During the Time Step (R_{ij}).

The rounds fired during the time step per air defense element are

$$R_{ij} = \overline{Rap}_{ij} * Put_j * Fdad_{ij} \quad (\text{Eq. 6-64})$$

where:

- \overline{Rap}_{ij} = the rounds fired by the AD element at helicopter j each time the helicopter pops up
- Put_j = the number of pop ups for helicopter j during this time period
- $Fdad_{ij}$ = fire distribution factor of rounds from AD firer i to target type j.

Note that:

$$\overline{Rap}_{ij} = Pad(r,t)_{ij} * Plos(r,ga)_k \quad (\text{Eq. 6-65})$$

- $Pad(r,t)_{ij}$ = the probability that the air defense element i can detect and engage a helicopter of type j in time T with mission ga.
- $Plos(r,ga)_k$ = probability that AD element at range r will have line of sight to the helicopter in mission ga in terrain k

If $r_{\min a} \leq r \leq r_{\max a}$:

$$P_{ad}(r,t)_{ij} = P_{\infty}(r,j) \left(1 - e^{-(T(r) / \bar{T}(r,t))} \right) \quad (\text{Eq. 6-66})$$

where:

$P_{\infty}(r,j)$ = the probability that air defense weapon n can detect helicopter j at range r given it can search for an infinite period under atmospheric conditions a.

Note that:

$$P_{\infty}(r,j) = ar^2 + br + c \quad (\text{Eq. 6-67})$$

where a, b, c are fitting parameters and r is the range in meters

$\bar{T}(r,j)$ = the average time to detect helicopter type j at range r.

$$\bar{T}(r,j) = a\bar{T}r^2 + b\bar{T}r + c\bar{T}$$

where $a\bar{T}$, $b\bar{T}$, $c\bar{T}$ are fitting parameters and are as described above.

$T(r)$ is the time the AD system has to detect the helicopter given an engagement will occur following detection.

$$T(r) = t_{ej} - r / f_{adi} \quad (\text{Eq. 6-68})$$

where:

t_{ej} = the exposure time for helicopter j
 f_{adi} = the flyout velocity of the air defense munition (m/sec).

$$P_{\text{los}}(r, g_a)_k = \alpha (e^{-\beta * r}) \quad (\text{Eq. 6-69})$$

where:

α, β are fitting factors for probability of line of sight in 4 different terrains.

(6) Probability of Kill for Helicopter j by AD element i.

The probability of kill against helicopter j if $r_{\text{min}} \leq r \leq r_{\text{max}}$ is

$$P_{k_{ij}}(r) = a_{ij}r^2 + b_{ij}r + c_{ij} \quad (\text{Eq. 6-70})$$

Otherwise, it is 0.

Variables a_{ij} , b_{ij} and c_{ij} are fitting parameters for P_k 's of an AD element. Variables r_{min} and r_{max} also represent the effective range envelope of the munition.

(7) Fire Distribution Factor for Helicopter j by AD element i.

$$F_{\text{dad}_{ij}} = \frac{P_{\text{ad}}(r, t)_{ij} * T_{\text{gt}_j} * P_{k_{ij}}(r) * H_{ij}}{\sum_{\text{all } j}^{\text{Helicopter types}} P_{\text{ad}}(r, t)_{ij} * T_{\text{gt}_j} * P_{k_{ij}}(r) * H_{ij}} \quad (\text{Eq. 6-71})$$

where:

T_{gt_j} = number of helicopter j targets being engaged by AD i.
 H_{ij} = a preference of AD element i for helicopter type j.

$P_{\text{ad}}(r, t)_{ij}$ and $P_{k_{ij}}(r)$ are as described in previous paragraphs.

(8) Number of Rounds Fired by the Direct Fire Elements During the Time Step (R_{ij}).

The rounds fired during the time step per direct fire element are:

$$R_{ij} = \overline{Rdp}_{ij} * Put_j * Fdf_{ij} \quad (\text{Eq. 6-72})$$

where:

\overline{Rdp}_{ij} = the rounds fired by the direct fire element i at helicopter j per popup.
 Put_j = the number of popups for helicopter j during this time step.
 Fdf_{ij} = fire distribution factor from direct firer i to helicopter target j . These factors are calculated in the direct fire portion of ground combat (P4) and passed to the helicopter attrition module (Helo_kills) through the common block Helo_info.

Note that:

$$\overline{Rdp}_{ij} = Pdfdt_{ij} * Plos(r,ga)_k \quad (\text{Eq. 6-73})$$

where:

$Pdfdt_{ij}$ = the probability that direct fire element i can detect and engage helicopter j .

$Plos(r,ga)_k$ is as described in previous paragraphs.

If $r_{min_a} \leq r \leq r_{max_a}$:

$$Pdfdt_{ij} = P_{\infty}(r,j) (1 - e^{-\frac{Ut(r)}{\bar{T}(r,t)}}) \quad (\text{Eq. 6-74})$$

where:

$P_{\infty}(r,j)$ = the probability that direct fire elements can detect helicopter j at range r given it can search for an infinite period under atmospheric conditions a .

$$P_{\infty}(r, j) = ar^2 + br + c \quad (\text{Eq. 6-75})$$

where:

Variables a, b, c are fitting factors for a sensor type and r is the range between direct fire elements and helicopter j in meters.

$U_t(r) =$ the time the direct fire system has to detect the helicopter given an engagement does occur.

$$U_t(r) = te_j - r/fvdf \quad (\text{Eq. 6-76})$$

where:

te_j = helicopter j's exposure time.
 $fvdf$ = flyout velocity of the direct fire munition (m/sec).

(9) Probability of Kill for Helicopter j by Direct Fire i.

The probability of kill (Pk_{ij}) against helicopter j is retrieved from the direct firer's PK files. The PK values are dependent on range, with the 6 records in the PK files representing 500 meter range bands. The values in the range band within which the helicopter to ground range falls are the ones stored and used in the helicopter attrition section.

(10) Fire Distribution Factor for Helicopter j by DF element i.

The fire distribution factor, Fdf_{ij} from direct firer i to helicopter target j is calculated in the direct fire portion of the ground combat (P4) routine. See Equation 6-35 for more details. These values are then stored in the common block Helo_info and used in the helicopter attrition module.

(11) Attrition of Helicopters, Air Defense, and Direct Fire.

To determine the helicopter losses, first the probabilities of survival for helicopter target j being fired upon by enemy helicopters, air defense and direct fire elements are calculated separately:

$$P_{ij} = (1 - (Pk_{ij} / Tgt_j))^{R_{ij}} \quad (\text{Eq. 6-77})$$

where:

P_{ij} = the probability of survival for the j th target helicopter being fired upon by the i th firer, where firers are AD elements, DF elements and attack helicopters.

Pk_{ij} , Tgt_i , and R_{ij} are as described in previous paragraphs.

P_{ij} is then accumulated for all firers.

$$P_{sj} = \prod_{i=1}^7 P_{ij} * \prod_{i=1}^{20} P_{ij} * \prod_{i=1}^3 P_{ij} \quad (\text{Eq. 6-78})$$

all AD
all DF
all attack
elements
elements
helos

where:

P_{sj} = the probability of survival for the j th target helicopter over all AD elements, DF elements and attack helicopters of type i .

Losses per target category are then calculated.

$$\text{Loss}_j = (1 - P_{sj}) * Tgt_j \quad (\text{Eq. 6-79})$$

where

Loss_j = losses of target helicopter j .

The losses to the ground targets are calculated by:

$$\text{Loss}_{gj} = (1 - (1 - (Pk_{ij} / Tgt_j))^{R_{ij}}) * Tgt_j \quad (\text{Eq. 6-80})$$

where:

Loss_{gj} = losses of ground target category j .
 Tgt_j = number of target elements in category j .
 Pk_{ij} = probability of kill of target category j by firer type i
 R_{ij} = rounds fired by i against target category j during this timestep

6. "UNITFILE" IMPACT

The unit status file ("UNITFILE") is not directly affected by the helicopter module. The information is returned to the ground combat mainline where it then affects the "UNITFILE".

7. CODE.

The helicopter subroutine code is explicitly depicted in the flow diagram in Figure 6-34. Notice that the routine contains numerous loops, checks and subroutines.

A listing of major variables by subroutine is found in Table 6-10. Table 6-14 contains a listing of the ground combat code,




Figure 6-34. Functional flow of helicopter attrition module.




Figure 6-34. Functional flow of helicopter attrition module (continued).
6-V-37




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (continued).





Figure 6-34. Functional flow of helicopter attrition module (continued).




Figure 6-34. Functional flow of helicopter attrition module (concluded).

Table 6-10. Helicopter Subroutine table.

Functional area(s): A. Helicopter attrition variables held in common block Helo attrite.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Read_files</u>	Reads in data from files. Variables used in subroutine Helo_kills	A. Helo_load (S,I,M)	Basic load of helicopters I (1-3) on side S (1=Blue; 2=Red) with munition type M (1=missile; 2=gun; 3=air-to-air).
		B. Mast_mnt (S,I)	Integer value which identifies whether helicopter on side S is mast mounted or not (0=mast mounted; 1=not mast mounted).
		C. Pd_fe_inf_a(S,I,J)/ Pd_fe_inf_b(S,I,J)/ Pd_fe_inf_c(S,I,J)	A, B, and C coefficients of a quadratic equation used to calculate the probability of detecting a fully exposed target of category J (1-20) when searching infinite time (S=side; I=helicopter type).
		D. Pd_hd_inf_a(S,I,J)/ Pd_hd_inf_b(S,I,J)/ Pd_hd_inf_c(S,I,J)	Same as above for hull defilade targets.
		E. Pd_fe_tbar_a(S,I,J)/ Pd_fe_tbar_b(S,I,J)/ Pd_fe_tbar_c(S,I,J)	A, B, and C coefficients of a quadratic equation used to calculate the average time to detect a fully exposed target of category J (1-20) helicopter I of side S.
		F. Pd_hd_tbar_a(S,I,J)/ Pd_hd_tbar_b(S,I,J)/ Pd_hd_tbar_c(S,I,J)	Same as above for hull defilade targets.
		G. Pd_rmin(S,I,A)/ Pd_rmax(S,I,A)	Minimum and maximum probability of detection ranges based on helo type I and atmospheric conditions A (1-8) by side S.
		H. Pk_fe_a(S,I,M,J)/ Pk_fe_b(S,I,M,J)/ Pk_fe_c(S,I,M,J)	A, B, and C coefficients of a quadratic equation used to calculate the probability of kill of fully exposed targets of category J based on munition M, Side S, Helo type I.

Table 6-10. Helicopter Subroutine table.

Functional area(s): A. Helicopter attrition variables held in common block Helo attrite. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read_files (continued)			
	I.	Pk_hd_a(S,I,M,J)/ Pk_hd_b(S,I,M,J)/ Pk_hd_c(S,I,M,J)	Same as above for hull defilade targets.
	J.	Pk_rmin(S,I,M)/ Pk_rmax(S,I,M)	Minimum and maximum probability of kill ranges based on helo type I and munition type M by side S.
	K.	Np(S,I,M)	Tactical number of rounds per engagement fired by helo type I using munition M.
	L.	Fm(S,I,M)	Fire and guide time (m/sec) of munition M and helo type I.
	M.	Tm(S,I,M)/ Te(S,I,M)	The average time masked and exposed per firing cycle for helo I firing munition M based on helo's mission.
	N.	Tgt_pref(S,I,J)	Preference for targets of category J by helicopters flying mission I. Values 1 - 10, with 10 the highest preference.
	O.	Plos_alpha(S,M)/ Plos_beta(S,M)	Alpha and beta values of an exponential equation used to calculate the probability of line of sight for mission M (1-3) based on terrain.

Table 6-10. Helicopter Subroutine table.

Functional area(s): A. Helicopter attrition variables held in common block Helo attrite. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read_files (continued)			
P. Pd_inf_ad_a(S,I,J)/ Pd_inf_ad_b(S,I,J)/ Pd_inf_ad_c(S,I,J)			A, B and C coefficients of a quadratic equation used to calculate the probability of Ad type I (1-7) detecting a mast mounted (J=1) or non-mast mounted (J=2) helicopter when searching infinite time.
Q. Pd_tbar_ad_a(S,I,J)/ Pd_tbar_ad_b(S,I,J)/ Pd_tbar_ad_c(S,I,J)			A, B and C coefficients of a quadratic equation used to calculate the average time for Ad type I (1-7) to detect a mast mounted (J=1) or non-mast mounted (J=2) helicopter.
R. Pd_ad_rmin(S,I,A)/ Pd_ad_rmax(S,I,A)			Minimum and maximum AD type I probability of detection ranges based on atmospheric condition. - A (1-8), (S=side 1-blue; 2-red).
S. Pk_ad_a(S,I,A)/ Pk_ad_b(S,I,A)/ Pk_ad_c(S,I,A)			A, B and C coefficients used to calculate AD I's probability of kill of mast mounted (J=1) and non-mast mounted (J=2) helicopters.
T. Pk_ad_rmin(S,I)/ Pk_ad_rmax(S,I)			Minimum and maximum AD type I probability of kill ranges for side S.
U. Ad_pref(S,I,J)			Preference of AD element I for helicopter type J.
V. Rnd_wt(S,I)			Weight of AD element I's munition.
W. Rnds(S,I)			Number of rounds fired per engagement by AD element I.
X. Fad(S,I)			Flyout velocity of AD I's munition (m/sec).

Table 6-10. Helicopter Subroutine table.

Functional area(s): A. Helo attrition variables held in common block Helo attrite. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read files (continued)			
		Y. Pd_cat(S,I)	A value from 1-5 representing the probability of detection category to which target category I (1-20, S=1 or 2) belongs.
		Z. Pd_inf_df_a(S,I,M)/ Pd_inf_df_b(S,I,M)/ Pd_inf_df_c(S,I,M)	A, B, and C coefficients of a quadratic equation used to calculate the probability of detecting a mast mounted (M=1) or non-mast mounted (M=2) helicopter of side S when searching infinite time. I - direct fire sensor type (1=optical; 2=thermal).
		AA. Pd_tbar_df_a(S,I,M)/ Pd_tbar_df_b(S,I,M)/ Pd_tbar_df_c(S,I,M)	A, B, and C coefficients of a quadratic equation used to calculate the average time to detect a mast mounted (M=1) or non-mast mounted (M=2) helicopter of side S. I - direct fire sensor type (1=optical; 2=thermal).
		BB. Pd_df_rmin(S,I,A)/ Pd_df_rmax(S,I,A)	Minimum and maximum probability of detection ranges based on sensor type I and atmospheric conditions A (1-8) by side S.
		CC. Df_rnd_wt(S,M)	Weight of direct fire munition type M's round (M=1 - ground missile; M=2 - ground kinetic energy round).
		DD. Df_rnds_eng(S,M)	Number of rounds fired per engagement for munition type M (1-2) on side S (1-2).
		EE. F_df(S,M)	Flight velocity of DF munition type M (in m/sec).
		FF. Df_sen_ptr(S,I)	Sensor (1=optical; 2=thermal) that direct fire type I (1-20) of side S(1-2) uses.

Table 6-10. Helicopter Subroutine table.

Functional area(s): A. Helo attrition variables held in common block Helo attrite. (concluded)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read_files (concluded)		GG, Df_muni_ptr(S,I)	Munitions (1-ground missile; 2-kinetic energy round) that direct fire type I (1-20) of side S(1-2) uses.

Functional area(s): B. Helo attrition variables held in common block Direct fire

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Read_files	Reads in data from files	A. B_cat (I) R_cat (I)	A value (1-17) which represents the ground target category to which weapon system I (1-70) belongs.

Functional area(s): C. Helo attrition variables held in common block Helo info

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main	Main driver	A. Btl_rg B. Df_amm0 (S)	Current range between two forces on the battlefield. Amount of direct fire ammo (short tons) available for side S.
Hel0_range	Calculates the ranges from helo to helo and helo to ground	A. Rg_avg(S,I,J) B. Rg_avg_pd(S,I,J)	Average stand-off range between helo type I (1-3) and target category J (1-20) for Blue and Red helos. Average stand-off range between helicopter I on side S and the condensed probability of detection category J (1-5).

Table 6-10. Helicopter Subroutine table.

Functional area(s): C. Helo attrition variables held in common block Helo info (concluded)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Df_attrition	Direct fire attrition	A. Df_fire_dist(S,I,J)	Fire distribution factor of each direct fire type I on side S shooting at target helicopter J (1-3).
		B. Df_pk_helo(S,I,J,M)	Direct fire I's probability of kill of helicopter J, which is mast mounted (M=1) or not (M=2).

Functional area(s): D. Calculate kills between helicopters and ground elements, AD Elements and enemy helicopters.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo_kills (driver)	Inputs from driver and initialization	A. Helo_mis(S,I)	Mission for helicopter type I 1 = air to ground 2 = air to air 3 = SEAD
		B. Stnd_off_rg(S,I)	Stand-off range (meters) of helicopter type I on side S.
		C. Side	An integer which identifies the attacking helicopter's side. 1 = Blue 2 = Red
		D. Side_def	An integer which identifies the defending helicopter's side. 1 = Blue 2 = Red
		E. Day_night	An integer representing the light visibility category. 0 = Day 1 = Night
		F. Time_step	On-site time of helicopter cells.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo kills (continued)			
		G. Cell(S,I,J)	Initial (I=1) and remaining (I=2) number of helicopters of type J on side S.
		H. Atk_prof(S,I)	An integer (1-7) representing the attacker profile of helicopter I on side S. 1 = missiles 2 = missiles and guns 3 = guns 4 = air to air missiles 5 = air to air missiles and ground missiles 6 = air to air missiles with ground missiles and guns 7 = air to air missiles and guns
		I. Target(S,I,J)	Initial (I=1) and remaining (I=2) number of targets J (1-70) on side S.
		J. Vis	Visibility index. 1 = >5 km 2 = 5 km 3 = 2 km 4 = 1 km
		K. Atmos	Atmospheric conditions based on day/night and visibility.
		L. Ad_amm (S)	Amount (short tons) of AD ammo available for side S.
		M. Ad_wt_av1(S)	Amount (pounds) of AD ammo available for side S.
		N. Df_wt_av1	Amount (pounds) of DF ammo available.
		O. Totden	Total number of targets remaining.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (Continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo_kills (continued)			
	P. Totnum		Total number of fully exposed targets remaining.
	Q. P_def_ray(S,J)		An array containing the percentage of each target element J on side S that is fully exposed.
	R. Pct_force_fe(S)/ Pct_force_hd(S)		Percent of side S's force which is fully exposed and hull defilade.
	S. Pct_mm(S)/ Pct_non_mm(S)		Percent of side S's force which is mast mounted and non-mast mounted.
	T. Tot_en_helos		Total number of enemy helicopters flying this timestep.
	U. Helo_rnds_avl(S,I)		Number of rounds available for helicopter type I, side S.
	V. Air_rnds_avl(S,I)		Number of air missiles available for helicopter type I, side S.
	W. No_targets(S,I)		Number of elements on target category I (1-20) for side S.
	X. Pop_tstep(I)		Number of pupas per timestep for helicopter type I.
	Y. Muni(I)		Integer representing the munitions type used by helicopter I this timestep. 1 = ground missiles 2 = guns 3 = air to air missiles
	Z. En_muni(I)		Integer representing the munition type used by enemy helicopter I this timestep.
AA. Lase			Integer representing lasing helicopter. 1, 2 = self 3 = scout

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements, AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo kills (concluded)		BB. Target_psrv(S,J) CC. Helo_psrv(S,I) DD. Target_loss(S,J) EE. Helo_loss(S,I)	Probability of survival of target category J on side S. Probability of survival of helicopter I on side S. Number of targets of category J (1-20) lost for side S (1=Blue; 2=Red). Number of helicopters of type I lost for side S.
Line_of_sight	Probability of line of sight between helicopters and ground elements.	A. Plos(S,I)	Probability of line of sight for helicopter I on side S to enemy ground elements.
Helo_pd_targ	Calculates the probability of a helicopter detecting a target	A. Hdinf B. Feinf C. Hdtbar D. Fetbar	Probability of detecting hull defilade targets given infinite search time. Probability of detecting fully exposed targets given infinite search time. Average time to detect a hull defilade target. Average time to detect a fully exposed target.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements, AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo_pd_targ (concluded)		E. Ut(I)	Actual time available to helicopter I to search for a target.
		F. Pdt_fe	Actual probability of detecting a fully exposed target.
		G. Pdt_hd	Actual probability of detecting a hull defilade target.
		H. Helo_pd_tgt(J5)	Actual probability of the helicopter's detecting collapsed target category J5 (1-5).
		I. Helo_pd_targ(I,J)	Probability of helicopter I detecting target category J.
Helo_pk_targ	Calculates the probability of a helicopter killing a target	A. Pkhd B. Pkfe	Probability of killing a hull defilade target. Probability of killing a fully exposed target.
		C. Helo_pk_targ(I,J)	Probability of helicopter I killing a target in category J.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements, AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Ad_pd_helo	Calculate the probability of Air Defense systems to detect helicopters.	A. Adinf B. Adtbar C. Adteng D. Ad_pd_helo(I,J)	Probability of detecting targets given infinite time. Average time to detect helicopter. Time available to detect helicopter assuming an engagement will follow (munitions sensitive). Actual probability of Air Defense System I detecting helicopter J.
Ad_avg_fired	Calculate the amount of ammunition fired by the Air Defense systems as if each helicopter is by itself.	A. Ad_avg_fired(I,J)	Amount of ammunition fired by AD system I at helicopter J.
Ad_pk_helo	Calculate the probability of killing a helicopter at a given range.	A. Mc B. Ad_pk_helo(I,J)	Variable used as a subscript in probability of kill data. 1 = helicopter has mast mounted detection sensor (little exposure) 2 = helicopter must be exposed to accomplish detection. Probability of killing helicopter J by AD system I.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Helo_avg_fired	Calculate the amount of ammunition fired by a helicopter at a target (as if only one target is available).	A. Helo_avg_fired(I,J)	The amount of ammunition fired by helicopter I at target category J.
Helo_fire_dist	Calculate the distribution of fire against all target categories.	A. Helo_tot_dist B. Helo_grd_dist C. Helo_file_dist(I,J)	The sum of all fire distribution for each target. The sum of all fire distribution for ground targets only (J=1-17). The percentage of fire that helicopter I directs at target category J (total equals 1.0).
Helo_act_fired	Calculate the actual amount of ammunition fired by a helicopter against a target category.	A. Helo_act_fired(I,J) B. Tot_rnds_fired C. Helo_act_pp	Actual amount of ammunition fired by helicopter I at target category J. Total rounds fired at all targets. Rounds fired at all targets during 1 popup.
Target_psrv	Calculate the losses to targets as a result of helicopter fire.	A. Target_psrv(S,J)	Probability of survival of target J after all helicopters have fired.
Ad_fire_dist	Calculate the distribution of fire against all helicopters by Air Defense systems.	A. Ad_tot_dist B. Ad_fire_dist(I,J)	The sum of all fire distribution for each helicopter. The percentage of fire that Air Defense system I directs at helicopter J (total equals 1.0).

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Ad_act_fired</u>	Calculate the actual amount of ammunition fired by an Air Defense system against a helicopter.	A. Ad_act_fired(I,J) B. Tot_wt_fired	Actual amount of ammunition fired by AD system I against helicopter J. Total weight of rounds fired at all helicopters.
<u>Helo_psrv</u>	Calculate the losses to helicopters as a result of Air Defense system fire.	A. Mt	Mast type 1 = mast mounted 2 = non-mast mounted
<u>Air_avg_fired</u>	Calculate the average rounds fired by one helicopter against another.	A. Pdt_rate_los B. P_engage C. Helo_avg_fired(I,J)	The rate that firing helicopter I detects target helicopter J when both are popping up and down. The probability of engagement, given the flight time of the appropriate munitions. The average number of rounds fired by helicopter I at target helicopter J.
<u>Air_act_fired</u>	Calculate the actual rounds fired by one helicopter at another.	A. Helo_air_dist B. Grd_pp C. Helo_act_fired(I,J) D. Helo_actual E. Air_pp	The sum of all fire distribution for air targets only (J=18-20). Actual rounds fired per popup at all ground targets. Actual rounds fired by helicopter I at target helicopter J. Actual rounds fired by helicopter I at all ground targets. Actual rounds fired per popup at all air targets.

Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (continued)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Air_act_fired</u> (concluded)		F. Air_act_fired(I,J)	Actual rounds fired by helicopter I at helicopter J.
		G. Air_actual	Actual rounds fired by helicopter I at all helicopter targets.
		H. A_g_ratio	The ratio of actual rounds fired at air targets vs. ground targets per popup.
<u>Df_pd_helo</u>	Calculate the probability of Direct Fire (DF) systems detecting the target helicopter.	A. Dfinf B. Dftbar C. Mt	The probability of detecting the target given infinite time. The average time to detect a target. Variable used as a subscript in probability of kill data. 1 = helicopter has mast mounted detection sensor (little exposure) 2 = helicopter must be exposed to accomplish detection.
		D. Dfteng	Time available to detect helicopter assuming an engagement will follow (munitions sensitive).
<u>Df_avg_fired</u>	Calculate the average ammunition fired by Direct Fire systems at helicopters.	A. Df_avg_fired(I,J)	Average number of rounds fired by DF system I at helicopter J.



Table 6-10. Helicopter Subroutine table.

Functional area(s): D. Calculate kills between helicopters and ground elements.
AD Elements and enemy helicopters. (concluded)

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Df_act_fired	Calculate the actual amount of ammunition fired by a Direct Fire system against helicopters.	A. Df_act_fired(I,J) B. Tot_rnds_fired C. Tot_wt_fired	Actual number of rounds fired by DF system I against helicopter J. Total number of rounds fired at all helicopters. Total weight of rounds fired at all helicopters.

Section VI. Precision Guided Munitions Attrition

1. PURPOSE.

The precision-guided munitions (PGM) attrition module calculates losses to target elements due to cannon-launched guided projectiles (CLGP) and guided antiarmor mortar projectiles (GAMP).

2. GENERAL.

A. CLGP are Blue indirect fire weapon systems that fire at point targets. Guidance for the CLGP rounds is assumed to be provided by a ground locator laser designator (GLLD) or may be specified to have remotely piloted vehicle (RPV) guidance. Smoke does not degrade the allocation of targets to CLGP. GAMP attrition is applied in a similar manner, but without the choice of guidance. Smoke is also assumed not to degrade the allocation of targets to GAMP. Both PGMs fire only under close support artillery munitions.

B. Currently, only Blue PGMs are used against Red targets in DIME.

3. DATA FLOW.

A. Data received from the ground combat driver program include which PGMs fire, number of rounds to be fired, visibility range, terrain type, PGM sensor types, cloud height in meters, atmospheric (dust) degradation, and the targets available.

B. All other data are specified in external data files. This information includes weighted values for target preference, single-shot kill probabilities, masks displaying which targets may be fired upon, and designator degradation factors.

C. The data flow is represented in Figure 6-35.

4. FILE STRUCTURE.

External files are as follows:

A. The Tgt_value (I,J) file contains numbers from 0 to 10 (10 being highest preference) which represent the preference of the Ith PGM firing on the Jth target where:

Data from
ground combat
mainline:

PGM types firing
rounds to be used
visibility range
terrain type
sensor types
cloud height
dust degradation
targets

Results:

PGM
Attrition
Module

Kills
due to
PGMs

Internal
data:

target
preferences
single shot
kill probabilities
target masks
Designator
degradation
factors

Figure 6-35. PGM data flow.

I = 1 - CLGP
2 - GAMP
J = 1 to 70 system elements

B. The Sskp (I,J) file contains the single-shot kill probability (SSKP) for the Ith PGM firing on the Jth target. All CLGP SSKPs depend on the guidance system. Therefore, Sskp(1,J), for J=1 to 70, contain zeros. The array Sskp_clgp(J) is selected according to the guidance system.

C. Tgt_mask1(I,J) represents the firing ability of the Ith PGM to fire upon the Jth target. A zero means the target may not be fired upon; a 1 means the target may be fired upon.

D. The following data refers only to CLGP:

(1) Terr_factor(I) is CLGP's designator degradation factor based on terrain type where:

I = 1 - Open
2 - Rolling
3 - Hilly
4 - Mountainous.

(2) Prob_dustabort(I,J) is CLGP's designator degradation factor where:

I = 1 - Light atmospheric (dust) obscuration
2 - Medium atmospheric (dust) obscuration
3 - Heavy atmospheric (dust) obscuration

J = 1 - 7 km visibility
2 - 5 km visibility
3 - 2 km visibility
4 - 1 km visibility.

(3) Clgp_mask(J) partitions the combined mask of Tgt_mask1(*) into a mask which specifies the sensor designator. Clgp_mask(J) may be chosen to represent GLLD or RPV accordingly. J represents the 70 target types.

(4) Prob_desg(I,J) is the CLGP designator degradation factor where:

I = 1 - Up to 1500 feet
2 - 1500-2000 feet
3 - 2000-2500 feet
4 - 2500-3000 feet
5 - 3000-4500 feet
6 - Over 4500 feet

J = 1 - 7 km visibility
2 - 5 km visibility
3 - 2 km visibility
4 - 1 km visibility

5. ALGORITHMS.

A. Figure 6-36 represents a generalized logic flow of the processes occurring in the PGM attrition module. This module involves a slice methodology like that in Chapter 6, section IV, which is the direct fire attrition. This slice methodology is used to bring about a more accurate representation of fire during battle. It allows the attrition to occur in 15 slices during a 30-minute period rather than one large mass of fire in one moment for a 30-minute period. PGMs do not use range bands as does the direct fire algorithm.

B. Calculations occurring during each slice consist of the following:

(1) Calculate weighted sum.

$$W_p = \sum_{t=1}^T (Tv_{pt} * Ps_t * Nt_t * Tm_{pt} * Des) \quad (\text{Eq. 6-81})$$

where:

- W_p = the weighted target sum for the p^{th} PGM.
- T = total number of target systems.
- Tv_{pt} = the target value of the p^{th} PGM firing on the t^{th} target.
- Ps_t = the current probability of survival for the t^{th} target during the current slice.
- Nt_t = the number of targets in the t^{th} target element.
- Tm_{pt} = the target mask for the p^{th} PGM firing on the t^{th} target.
- Des = the designator discriminating factor for discriminating between high and low probability of kill (PK) targets.


(2) Calculate rounds fired per slice. These rounds are calculated per slice for each firer firing on one type target system. The formula below is used only if $Tm_{pt} * Ct_t$ is greater than zero:

$$R_{pt} = [(Ct_t * Tv_{pt} * Des) / W_p] * (Nr_p / Ns) \quad (\text{Eq. 6-82})$$

where:

- R_{pt} = the rounds fired by a PGM firing on one type target system.
- Ct_t = current number of targets available to fire upon for this slice.
- Nr_p = the number of rounds the p^{th} PGM is to fire.
- Ns = the number of slices; set to 15.

Slice Loop:



End Slice Loop.

Calculate kills

Figure 6-36. PGM logic flow.

These rounds are then multiplied by all degradation factors to represent the number of rounds which hit the targets. The number of rounds which hit the targets is shown as R_{hpt} below.

$$R_{hpt} = R_{pt} * T_d * P_d * P_{da} \quad (\text{Eq. 6-82a})$$

where:

- T_d = degradation due to terrain.
- P_d = designator degradation due to clouds and visibility.
- P_{da} = designator degradation due to dust and visibility.

(3) The probability of survival for each target being fired upon by each PGM is:

$$P_{pt} = (1 - P_{k_{pt}} * L_r/D) \uparrow R_{hpt} \quad (\text{Eq. 6-83})$$

where:

- P_{pt} = the probability of survival for the t^{th} target being fired upon by the p^{th} PGM.
- $P_{k_{pt}}$ = the single-shot kill probability of the p^{th} PGM firing on the t^{th} target.
- L_r = the laser designator reliability factor.
- D = the maximum of 1 and the current number of available targets for this slice (CT) multiplied by the smoke degradation factor which is set to 1.
- R_{hpt} = number of rounds which hit the targets.

The value P_{tk} is the probability of target t surviving the lethality of all PGMs for slice K .

$$P_{tk} = \prod_{p=1}^{N_p} P_{ptk} \quad (\text{Eq. 6-84})$$

The value P_{tk} is accumulated across all slices by:

$$P_{st} = \prod_{k=1}^{N_s} P_{tk} \quad (\text{Eq. 6-84a})$$

giving the probability of survival (P_{st}) per target over all slices (N_s) and over all PGMs.

(4) Now it is possible to calculate the losses to each target system. The formula is as follows:

$$L_t = (1 - P_{s_t}) * N_{t_t} \quad (\text{Eq. 6-85})$$

where:

- L_t = losses to target elements due to PGMs.
- P_{s_t} = the probability of survival per target element over all slices and over all PGMs.
- N_{t_t} = the number of targets in the t^{th} target element.

6. "UNITFILE" IMPACT.

This module does not directly impact the unit status file ("UNITFILE"). Kills calculated in this routine are returned to the ground combat mainline and then decremented from the "UNITFILE".

7. CODE.

A. Introduction. This section contains information on the PGM attrition code. The functional areas discussed in the following paragraphs are represented in Figure 6-37.

B. PGM attrition functional areas.

(1) The data received from the ground combat mainline include PGMs which fire, number of rounds to be fired, visibility range, terrain type, PGM sensor types, cloud height in meters, atmospheric (dust) degradation flag, and available targets.

(2) Data files are read for both CLGP and GAMP.

(3) Initialization of variables, such as the number of slices, the number of possible firers, and the number of possible target elements, occurs. Before accumulation of the probability of survival, it must be initialized to 1.

(4) Files specifically set up for CLGP are now read. To do this, flags are set to determine the guidance system so the appropriate data may be used.

(5) Due to the two sets of mask files and SSKP files set up for CLGP, it is necessary to combine the two sets of files into one set of usable files:




Figure 6-37. PGM functional flow.

The Tgt_mask1(1,J) and the Clgp_mask(J) files are combined giving Tgt_mask(1,J). At the same time, Tgt_mask1(2,J) is placed into Tgt_mask(2,J). Then the Sskp_clgp(J) replaces the zeros originally in Sskp(1,J). The J represents the 70 weapon elements.

(6) Using the slice methodology discussed in the algorithm portion of PGM attrition, the calculations occurring within the slice loop consist of the following:

- (a) Weighted sum of current targets for each firer.
- (b) Specific degradation factors determined for both CLGP and GAMP.
- (c) Current available targets. This represents the slice losses to all targets.
- (d) Rounds fired per slice. These are calculated within the slice loop. Degradation factors are then multiplied to the rounds fired. This is done to represent the number of rounds which hit targets. Actual rounds used are calculated in the ground combat mainline.
- (e) Probability of survival per slice for each firer firing on each target. This probability is then accumulated for all firers firing on each target over all slices.

(7) The accumulated probability of survival for each target is used to calculate losses due to PGMs.

C. The primary variables for the PGM attrition module are shown in Table 6-11. Each variable is accompanied by a short description. See Table 6-14 for the ground combat code listing.

Table 6-11. PGM subroutine table.

Functional area(s): A. PGM induced losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Pgm_attrit	Calculates attrition due to PGM's.	A. Cld_ndx	Cloud height category: 1 = up to 1500 ft. 2 = 1500 - 2000 ft. 3 = 2000 - 2500 ft. 4 = 2000 - 3000 ft. 5 = 3000 - 4500 ft. 6 = over 4500 ft.
		B. Clgp_mask (I)	Represents the firing ability of CLGP on the Ith target (I = 1-70): 1 = Can fire 2 = Can not fire.
		C. Cloud	Cloud height (feet).
		D. Cloud_ht	Cloud height (meters).
		E. Des	The designator discriminator, used to discriminate between high and low Pk targets. Used in calculation of rounds which hit targets.
		F. Dust_index	Atmospheric obscuration is: 1 = Light 2 = Medium 3 = Heavy.
		G. Fir_typ (I)	Flag, whose value: 1 = PGM is being fired 2 = PGM not fired indicates the play of PGM I, I = 1 - CLGP = 2 - GAMP.

Table 6-11. PGM subroutine table.

Functional area(s): A. PGM induced losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Pgm_atrit (continued)			
H. Lase_reliab			Designator reliability factor.
I. N_rnds (I)			The number of rounds available to be fired by the Ith firer where I = 1 - CLGP = 2 - GAMP.
J. N_rnds_fired (I)			The number of rounds fired by the Ith PGM where I = 1 - CLGP = 2 - GAMP.
K. N_tgtts			Number of surviving targets within this attrition loop.
L. Nfirers			Number of possible firers (set to 2 for CLGP and GAMP).
M. N_rnds			Rounds available after degradation factors.
N. Nslices			Number of slice loops (set to 15).
O. Ntargets			Number of system types which are targets (set to 70).
P. P_deag			Specific designator degradation factor according to the dust-index and the visibility-index.
Q. P_dustabort			Specific designator degradation factor according to the dust-index and the visibility-index.

Table 6-11. PGM subroutine table.

Functional area(s): A. PGM induced losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Pgm_attrit (continued)			
R. P_surv (I)			Cumulative probability of survival for the Ith target type.
S. Prob_desg (I,J)			CLGP designator degradation factor. I is the cloud index and J is the visibility index.
T. Prob_dustabort (I,J)			CLGP designator degradation factor. I is the dust index and J is the visibility index.
U. Psurv_tf (I,J)			Probability of survival for the Jth target being fired on by the Ith PGM.
V. Sens_typ (I)			Flag, with the following values for the Ith PGM. Flag = 0 - no sensors = 1 - for CLLD = 2 - RPV I = 1 - CLGP = 2 - GAMP.
W. Smk			Smoke degradation factor (set to 1 for PGMs).
X. Sskp (I,J)			Single shot kill probability for the Ith PGM firing on the Jth target. Note: CLGP SSPKs done separately.
Y. Sskp_clgp (I)			Single shot kill probability for Clgp firing on the Ith target.

Table 6-11. PGM subroutine table.

Functional area(s): A. PGM induced losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Pgm_atrit (continued)			
	Z. Targets (I,J)		Number of targets where: I = 1 - Red targets available = 2 - Red targets killed and J is the 70 target elements.
	AA. Terr_degrd		Specific terrain degradation factor, depending on the current terrain.
	BB. Terr_factor (I)		CLGP degradation factors for terrain type I, where: I = 1 - Open = 2 - Rolling = 3 - Hilly = 4 - Mountainous.
	CC. Terr_typ		The current terrain 1 - Open 2 - Rolling 3 - Hilly 4 - Mountainous.
	DD. Tgt_mask (I,J)		Final target mask, containing Tgt_maskl for GAMP and a combination of Tgt_maskl and Clgp_mask for CLGP. I is the PGM; J the target.
	EE. Tgt_maskl (I,J)		The firing ability of the Ith PGM on the Jth target.
	FF. Tgt_value (I,J)		Contains numbers from 0 to 10 representing the preference of the Ith PGM firing on the Jth target. The higher the value, the greater the preference.

Table 6-11. PGM subroutine table.

Functional area(s): A. PGM induced losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Pgm_strit (concluded)		GG. Vis_ndx	Current visibility category: 1 - 7 km day 2 - 5 km day 3 - 2 km day 4 - 1 km day.
		HH. Vis_rng	Same as Vis_ndx.
		II. W_sum (I)	A weighted sum of all targets on which the Ith PGM is firing.

Section VII. Infantry

1. PURPOSE.

The purpose of the infantry module is to calculate the Red and Blue direct fire infantry losses during a 30-minute interval.

2. GENERAL.

A. The infantry module combines gamer inputs passed in through the main driver routine with firepower scores and a force multiplier to compute a firepower ratio for each force.

B. The firepower ratio is used to compute the total infantry attrition suffered by each force during a 30-minute interval.

C. For each 30-minute interval, the main driver routine combines the infantry losses with all other losses to determine a total ground combat attrition suffered by each force for that period.

3. DATA FLOW.

A. The infantry module uses driver inputs passed from the ground combat driver program to access the appropriate firepower scores and force multipliers for each force.

(1) Driver inputs. The main driver routine passes the following data into the infantry module.

(a) Sys(I,J). A 6x70 array which contains the current status of all units in conflict, where:

I = 1 - Blue targets
2 - Blue losses
3 - Red targets
4 - Red losses
5 - Blue direct fire elements
6 - Red direct fire elements

J = 1 - 70 - weapon systems

NOTE: The only J used in this subroutine is when J = 36 - 47, since these elements on the weapons list contain the infantry position.

(b) Force. An integer value of 1 or 2 which identifies the force type, where:

- 1 - Light force
- 2 - Heavy force.

(c) Cstat(I). An integer value of 1 to 10 which identifies the mission for force I where:

- I = 1 - Blue force
- 2 - Red force

- Mission = 1 - Movement to contact
- 2 - Indirect fire
- 3 - Movement
- 4 - Frontal attack
- 5 - Envelopmental attack
- 6 - Delay
- 7 - Hasty defense
- 8 - Prepared defense
- 9 - Rear area
- 10 - Ambush.

(d) Attacker. An integer value of 1 or 2 which identifies the attacking force, where: 1 - Blue attacking 2 - Red attacking.

(e) Hr_{conflict}. A real value which contains the time, in hours, for assessment of infantry battle.

(2) Firepower scores. The firepower scores are simply numerical values assigned to weapon systems to quantify their potential to inflict damage.

(a) The firepower scores used in the DIME game were derived from the Concepts Analysis Agency's (CAA) Weapon Effectiveness Indices/Weighted Unit Values (WEI/WUV) methodology. The DIME firepower scores are classified and may be found in volume III of this report.

(b) The firepower scores file consists of two records containing the firepower score for the Blue (record 1) and the Red (record 2) forces. Each record is a three dimensional array, where:

I = 1 to 70 weapon systems

J = 1 - light force
2 - heavy force

K = 1 - Red attacking/Blue defending
2 - Blue attacking/Red defending.

(3) Force multiplier. A real value which reflects an adjustment factor for maneuver unit weapons is either an attack or defend posture. Table 6-12 contains a list of the force multipliers by battle posture and mission. These multipliers, dependent on attacker/defender and mission status, are established as equations within the code.

Table 6-12. Infantry force multipliers.

<u>Tactical Situation</u>	<u>Battle posture</u>	
	<u>Attacker</u>	<u>Defender</u>
Movement to contact	1.5	1.0
Indirect fire	1.5	1.0
Movement	1.5	1.0
Frontal attack	1.5	1.0
Envelopmental attack	1.5	1.0
Delay	1.5	1.0
Hasty defense	1.5	1.2
Prepared defense	1.3	1.5
Rear area	2.0	0.5
Ambush	1.0	4.5

B. The infantry module returns the total losses for both Blue and Red forces.

C. Figure 6-38 indicates the generalized data flow for the infantry module.




Figure 6-38. Infantry data flow.

4. FILE STRUCTURE.

The only data stored in an auxiliary file are the firepower scores. The firepower scores are read into two on-line data arrays, Fpsb(*) and Fpsr(*).

A. Fpsb (I,J,K). An array with dimensions (70,2,2) which contains the Blue firepower scores for the 70 weapon elements assigned to one of two force types, either attacking or defending.

I = 1 to 70 weapon systems

J = 1 - light force
2 - heavy force

K = 1 - Red attacking/Blue defending
2 - Blue attacking/Red defending.

B. Fpsr (I,J,K). An array containing the Red firepower scores. The definitions of I, J, and K are the same as above.

5. ALGORITHMS.

A. The infantry module combines the gamer inputs, force multiplier, and firepower scores discussed in paragraphs 3 and 4 with the generalized logic flow shown in Figure 6-39 to calculate the total losses suffered by each force.

(1) The program begins by calculating a firepower ratio.

(a) A firepower ratio is a measure of one force's capability to inflict damage relative to the capability of another force. In forming such a ratio, the tactical situation of the maneuver units of both the attacking and defending forces are considered, and the firepower scores are adjusted accordingly. For instance, a defending force would expect to be less vulnerable if it were occupying a fortified defensive position than if it were engaging the enemy in the open. Likewise, an attacking force would expect to inflict greater damage executing a frontal attack against a unit in a hasty defense, as a unit in a prepared defense.

(b) The unadjusted total firepower score for each force is multiplied by the appropriate tactical situation adjustment factor (see Table 6-12, infantry force multipliers). The attacker-to-defender firepower ratio is then calculated. The firepower ratio calculation is expressed algebraically as:




Figure 6-39. Generalized infantry logic flow.

$$Fpr = \frac{\left(\sum_{i=1}^{70} (As_i * Afps_i) \right) * Atsaf}{\left(\sum_{i=1}^{70} (Ds_i * Dfps_i) \right) * Dtsaf} \quad (\text{Eq. 6-86})$$

where:

- Fpr = the firepower ratio.
- Atsaf = the attacker tactical situation adjustment factor (see Table 6-12).
- Dtsaf = the defender tactical situation adjustment factor (see Table 6-12).
- Dfps_i = the firepower score of the defender's ith system.
- Afps_i = the firepower score of the attacker's ith system.
- As_i = the number of attacking systems (i)
- Ds_i = the number of defending systems (i)

(2) This calculated firepower ratio is used to compute the casualty rates for defending and attacking forces.

(a) Defending forces. The casualty rate for a defending force is a function of the combat force ratio (FPR) and the mission of the defending force. Figure 6-40 shows a graphical representation of the casualty rate for ground combat personnel in one of six defense missions. Combining the graphs with a curve fitting equation using the FPR, the casualty rate is calculated by:

$$Drate = A + B * Fpr + C * Fpr^2 \quad (\text{Eq. 6-87})$$

where:

- Drate = defending force casualty rate.
- Fpr = firepower ratio.
- A = Y-intercept.
- B, C = constants determined from curve fitting (see Figure 6-40).

Defending force coefficients have been calculated as follows:

1. Defending from prepared positions.

- A = .00919
- B = .004085
- C = .000097




Figure 6-40. Ground combat personnel casualty rate for defending forces.

2. Defending from hasty positions.

A = .01274
B = .0005
C = .001

3. Defending against an enemy fighting a meeting engagement.

A = .001257
B = .000857
C = .001143

4. Defending force delaying or withdrawing against attackers.

A = .003286
B = .0034286
C = 0.0

(b) Attacking forces. The casualty rate for an attacking force is a function of the combat force ratio (FPR) and the mission of the attacking force. Figure 6-41 shows the graphical representation of the attacking forces. Again, rate is calculated by combining the FPR with a curve-fitting equation:

$$\text{Arate} = A * \text{Fpr}^{-B} \quad (\text{Eq. 6-88})$$

where:

Arate = attack force casualty rate.
Fpr = firepower ratio.
A,B = constants determined from fitting curve (see Figure 6-41).

Attacking force coefficients have been calculated as follows:

1. Against a fortified or prepared position:

A = .0483
B = .251

2. Against a hasty position:

A = .0401
B = .237




Figure 6-41. Ground combat personnel casualty rate for attacking forces.

3. Against a delaying or withdrawing enemy or fighting a meeting engagement:

$$\begin{aligned} A &= .0384 \\ B &= .2383 \end{aligned}$$

(3) Finally, the total losses suffered by each force are calculated using the following formula:

$$\text{Loss}_i = \text{Pers}_i * \text{Frac_comtd} * \text{Rate}_i * \text{Hr_conflict} \quad (\text{Eq. 6-89})$$

where:

- i = 1 - Blue force
- 2 - Red force.
- Loss_i = total losses per battle.
- Pers_i = total personnel assigned to unit.
- Frac_comtd = percent of unit committed to fight battle, where value is defaulted to 1.0.
- Rate_i = casualty rate loss.
- Hr_conflict = time, in hours, for assessment of infantry battle.

B. These losses are returned to the main driver routine where they are combined with other losses to determine the total ground combat losses suffered by each force.

6. "UNITFILE" IMPACT.

The infantry module returns the infantry losses to the ground combat driver. The driver then deducts the personnel losses from the infantry elements of the "UNITFILE".

7. CODE.

A. The infantry module consists of a driver routine and two subroutines.

(1) Main driver. The main driver establishes the initial parameters and pointers for reading in the appropriate data files.

(2) Once the correct data has been read into the program, the main driver routine calculates the firepower ratio by multiplying the firepower scores by the force multiplier.

(3) The main driver then calls two subroutines: Rate and Losses.

(a) Rate. The Rate routine uses the firepower ratio to compute the casualty loss rate.

(b) Losses. The Loss routine uses the casualty loss rate to compute the total personnel losses by a force for a specified battle time.

(4) The personnel losses are returned to the ground combat attrition module where they are used to compute the total kills for the 30-minute battle phase being evaluated.

B. The primary variables for the infantry module are shown in Table 6-13. Each variable is accompanied by a short description. See Table 6-14 for the ground combat code listing.

Table 6-13. Infantry subroutine table.

Functional area(s): A. <u>Game Initialization.</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main Driver	Establishes initial pointers and parameters for reading in data.	A. Sys (*)	A 6 x 70 array containing the current status of all units in conflict.	
		B. Force	In integer value of 1 or 2 which identifies the force type. 1 = light force 2 = heavy force.	
		C. Cstat (I)	An integer value of 1 to 10 which identifies the mission for force I.	
		D. Attacker	An integer value identifying the attacking force. 1 = Blue attacking 2 = Red attacking.	
		E. Hr_conflict	A real value containing the time (hours) used to assess the infantry battle.	
		F. Converta (*)	A 10 x 10 array used to select the appropriate loss coefficient equation for the attacker.	
		G. Convertd (*)	A 10 x 10 array used to select the appropriate loss coefficient equation for the defender.	
		H. Defender	Flag identifying the defending force. 1 = Blue defending 2 = Red defending.	

Table 6-13. Infantry subroutine table.

Functional area(s): A. Game initialization.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main Driver (continued)	Accesses and reads in appropriate data files.	A. FPS1	A real file containing the firepower scores for Blue and Red forces.
		B. What (I)	An integer value of 11-16 or 21-23 which identifies the casualty loss equation/coefficient to use in calculating the casualty loss rate for each force. I = 1 - Attacking force = 2 - Defending force.
		C. Fpsb (I,J,K) Fpsr (I,J,K)	A 70 x 2 x 2 array containing the Blue/Red firepower score for the 70 elements (I). J = 1 - Light force = 2 - Heavy force K = 1 - Attacking = 2 - Defending.
Compute adjusted firepower score for the forces.		A. Fratio (I)	The total unadjusted firepower scores for the forces. I = 1 - Blue = 2 - Red.
		B. Top	The total adjusted firepower scores for the attacking force.
		C. Bottom	The total adjusted firepower scores for the defending force.

Table 6-13. Infantry subroutine table.

Functional area(s): A. Game initialization.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Main Driver (concluded)			
		D. Dmultiply	Adjustment factor multiplier for a defending force.
		E. Amultiply	Adjustment factor multiplier for an attacking force.
	Compute firepower ratio.	A. Fpr	A real value, containing the ratio of the adjusted firepower scores of the attacker to the defender.

Functional area(s): B. Calculate rate of casualty losses.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Rate	Accesses correct equation/coefficient for computing rate of casualty losses.	A. Brate (I)	The rate of casualty losses for forces on the attack (I=1) and defense (I=2).

Functional area(s): C. Calculate total losses per force.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Losses	Calculates loss to attacking and defending forces.	A. Pers (I)	Number of infantry personnel for the Blue (I=1) and Red (I=2) forces.
		B. Fract_comtd	Fraction of unit committed to infantry (default = 1.0).

Table 6-14. Ground combat code.

```

3  !!! "P4" IS THE GROUND ATTRITION MODULE FOR THE DIVISION MAP
6  ! DATA CHANGED ON 21 MARCH 1985. ROB BELFLOWER. BDM
9  ! EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
12 !     DECLASSIFIED -- AUG 7, 1986 -- BY OAO CORP.  ** DC **
15 ! HELICOPTER METHODOLOGY CHANGED -- JUNE 1987 -- BY OAO CORP.
18  OPTION BASE 1
21  DIM Sys_dfl(7),Sys_dfs(7),Sys_if(7),Svs_ad(7),Svs_sum(7)
24  DIM Sys_tot(4,70),Kv_r(6,70),Kv_b(6,70),Rif_amm(15)
27  DIM Ci_kv_r(8,70),Ci_kv_b(8,70),Sys(6,70),B_helo(3,6),R_helo(3,6)
30  DIM Ci_helo_b(3,6),Ci_helo_r(3,6),Ammo_wt(2,70),If_amm(15),Bif_amm(15)
33  DIM B_unit(12,74),R_unit(12,74),S(70),Wpn_type(70)
36  DIM Svs_eff(2,70),B_init(13,70),R_init(13,70),Sys_amm(15),Bif_msn(6)
39  DIM Rif_msn(6),Bif_msn_tons(15,5),Rif_msn_tons(15,5),Arty_30min_wt(2,15)
42  DIM Bif_fired(15,5),Rif_fired(15,5),Tot_arty(2,15),Ds_start(4),N(150)
45  DIM Advance_rate(4,10),Minefield(3,6),Mf(4),R_veh$(350),B_veh$(350)
48  DIM B_if_t(2,70),R_if_t(2,70),B_df_t(2,70),R_df_t(2,70)
51  DIM B_if_dt(2,70),R_if_dt(2,70),B_df_dt(2,70),R_df_dt(2,70)
54  DIM B_f(2,70),R_f(2,70),B_v(2,70),R_v(2,70),B_dv(2,70),R_dv(2,70)
57  DIM B_con(12,70),R_con(12,70),B_type(12),R_type(12)
60  DIM Mift(20),Mdft(20),Mifdt(20),Mdfdt(20),T_length(2),T_width(2)
63  DIM Mfire(20),Mdfire(20),Mvul(20),Mdvul(20),Target(2,70),Red_f_t(70)
66  DIM Phase_ct(3),Sys_mine(4,70),Sys_arty(4,70),Basic_ld(2,70),Blue_f_t(70)
69  DIM Sys_direct(2,70),Bf_mask(70),Rf_mask(70),Bdf_mask(5,70),Rdf_mask(5,70)
72  DIM Blue_vul(70),Red_vul(70),B_amm(2,70),R_amm(2,70),Bstat(2)
75  DIM Sys_helo(2,70),Sys_pgm(2,70),Svs_inf(2,70),B_fire_sv(70),R_fire_sv(70)
78  DIM B_break_t(12),R_break_t(12),B_df(2,70),R_df(2,70),B_msn(1),R_msn(1)
81  DIM Volley(15,5),Saty(15),A_wt(2,15),Tot_volley(15),Label$(75)
84  DIM B_arty_cap(7,5),B_mlr_cap(4,5),B_mort_cap(4,5),H_targ(4,70)
87  DIM R_arty_cap(7,5),R_mlr_cap(4,5),R_mort_cap(4,5)
90  DIM Clgp_fact(70),Gamp_fact(70),B_clgp_cap(7),B_gamp_cap(4)
93  DIM C_targ(2,70),C_t(4,70),R_vis(3),R_vis(3),R_inf_save(5),B_inf_save(5)
96  DIM B_engagements(20),R_engagements(20),Barty_30min(10,15)
99  DIM Rarty_30min(10,15),B_smok_tons(11),R_smok_tons(11),Inf_surv(5)
102 DIM B_smk_cap(11),R_smk_cap(11),Bada_hnd(12),Bada_veh(12),Rada_hnd(12)
105 DIM B_dsarty_avail(7),B_dsarty_fire(7),B_dsmort_avail(4),B_dsmort_fire(4)
108 DIM R_dsarty_avail(7),R_dsarty_fire(7),R_dsmort_avail(4),R_dsmort_fire(4)
111 DIM B_asmk_used(7),B_msmk_used(4),R_asmk_used(7),R_msmk_used(4)
114 DIM Frac_arty(7),Frac_mort(4),Ds_attempted(7),Mo_attempted(4)
117 DIM Fir_typ(2),Sens_typ(2),N_rnds(2),Rada_veh(12),B_inf(1,5),R_inf(1,5)
120 DIM Incoming_arty(7),Incoming_mlr(4),Incoming_mort(4),B_ech(12),R_ech(12)
123 DIM B_unit_no(12),R_unit_no(12),Hfile(2,12,10)
126 DIM B_helo_atkprof(2),R_helo_atkprof(2),B_helo_msn(2),R_helo_msn(2)
129 DIM B_atk_rg(2),R_atk_rg(2),H_d_$(64),H_msn$(32),Std_off_rg(2,3)
132 DIM Sides$(2)(2),Helo_char(3,8),Desc$(8),P_det_inf(3,5,2),P_det_tbar(3,5,2)
135 DIM Rmin(8),Rmax(8),Pk(3,20,2),Tim_me(6),Pref(20),Plos(8),Pd_inf_ad(3,2)
138 DIM Pd_tbar_ad(3,2),Pk_ad(3,2),Pref_ad(3),Cat20(20),Rg_msn$(3)(10)
141 DIM Atk_prof(2,3),Helo_mis(2,3),P_def(2,70),Arty(2),Ad_helo(2),Ad_sv(2)
144 DIM Veh_ada(2),Hnd_ada(2),Helo_tgt(2,2,70),Sen_ptr(20),Mun_ptr(20)
147 DIM Df_det_inf(3,2),Df_det_tbar(3,2)
150
153 INTEGER I,J,K,B_unit_pct(12),R_unit_pct(12),St_time,Minute,Earliest_time

```

Table 6-14. Ground combat code (continued).

```

156 INTEGER Delay_minute,R_minute,B_minute,R_prep_time,B_prep_time
159 INTEGER H_side,Muni,Jtarg,M,Iad,Jmast
162 !
165 COM /Mines/ Mine_frct(4,70)
168 COM /Infantry/ Convertd(10),Converta(10,10),Fpsb(70,2,2),Fpsr(70,2,2)
171 COM /Arty/ B_area_band(5),R_area_band(5),B_disprsn_mask(3,10),R_disprsn_c
k(3,10),B_tgt_mask(5,72),R_tgt_mask(5,72),B_rd_wt(15),R_rd_wt(15)
174 COM /Arty/ B_psnl_posture(2,2),R_psnl_posture(2,2),Tle(5)
177 COM /Smoke/ Amwtp(3,11),Irof(3,11)
180 COM /Pgm/ Tgt_value(2,70),Tgt_mask1(2,70),Terr_factor(4),Prob_dustabort(
),Clgp_msk_ns(70),Clgp_msk_gl(70),Clgp_msk_rp(70)
183 COM /Pgm/ Prob_dsg_ns(6,4),Prob_dsg_gl(6,4),Prob_dsg_rp(6,4),Sskp_ns(70),
kp_gl(70),Sskp_rp(70)
186 COM /Direct_fire/ B_cat(70),R_cat(70),B_sen_d(70),B_sen_n(70),R_sen_d(70)
_sen_n(70),B_ammo_wt(20),R_ammo_wt(20)
189 COM /No_helos/ Cell(2,2,3)
192 !
195 COM /Helo_attrite/ Helo_load(2,3,3),Pd_fe_inf_a(2,3,5),Pd_fe_inf_b(2,3,5)
d_fe_inf_c(2,3,5),Pd_hd_inf_a(2,3,5),Pd_hd_inf_b(2,3,5)
198 COM /Helo_attrite/ Pd_hd_inf_c(2,3,5),Pd_fe_tbar_a(2,3,5),Pd_fe_tbar_b(2,
5),Pd_fe_tbar_c(2,3,5),Pd_hd_tbar_a(2,3,5),Pd_hd_tbar_b(2,3,5)
201 COM /Helo_attrite/ Pd_hd_tbar_c(2,3,5),Pd_rmin(2,3,8),Pd_rmax(2,3,8),Pk_f
a(2,3,3,20),Pk_fe_b(2,3,3,20),Pk_fe_c(2,3,3,20),Pk_hd_a(2,3,3,20)
204 COM /Helo_attrite/ Pk_hd_b(2,3,3,20),Pk_hd_c(2,3,3,20),Pk_rmin(2,3,3),Pk_
ax(2,3,3),Np(2,3,3),Fm(2,3,3),Tm(2,3,3),Te(2,3,3)
207 COM /Helo_attrite/ Flos_alpha(2,3),Plos_beta(2,3),Pd_inf_ad_a(2,7,2),Pd_
_ad_b(2,7,2),Pd_inf_ad_c(2,7,2),Pd_tbar_ad_a(2,7,2),Pd_tbar_ad_b(2,7,2)
210 COM /Helo_attrite/ Pd_tbar_ad_c(2,7,2),Pd_ad_rmin(2,7,8),Pd_ad_rmax(2,7,8)
Pk_ad_a(2,7,2),Pk_ad_b(2,7,2),Pk_ad_c(2,7,2),Pk_ad_rmin(2,7),Pk_ad_rmax(2,7)
213 COM /Helo_attrite/ Rnd_wt(2,7),Rnds(2,7),Fad(2,7),Pd_inf_df_a(2,2,2),Pd_
f_df_b(2,2,2),Pd_inf_df_c(2,2,2),Pd_tbar_df_a(2,2,2),Pd_tbar_df_b(2,2,2)
216 COM /Helo_attrite/ Pd_tbar_df_c(2,2,2),Pd_df_rmin(2,2,8),Pd_df_rmax(2,2,
),Df_rnds_eng(2,2),F_d(2,2)
219 COM /Helo_attrite/ INTEGER Mast_mnt(2,3),Tgt_pref(2,3,20),Ad_pref(2,7,3)
d_cat(2,20)
222 !
225 COM /Helo_info/ Btl_rg,Rg_avg(2,3,20),Rg_avg_pd(2,3,5),Df_ammo(2),Df_fire
st(2,20,3),Df_pk_helo(2,20,3,2),INTEGER Df_sen_ptr(2,20),Df_muni_ptr(2,20)
229 !
231 DIM Disk${50},Disk3${50}
234 Df_1$=":9134,704,0"
237 Df_1M${16},N${16} !ROB
240 Disk3$=":9134,704,0"
243 Dcdisk$=":9134,704,0" ! ** DC **
246 ASSIGN @Unitpath TO "UNITFILE"&Disk$
249 ASSIGN @Kvpath TO "KVFILE"&Disk$
252 ASSIGN @Helopath TO "HELOFILE"&Disk$
255 ASSIGN @Ammopath TO "AMMOFILE"&Disk3$
258 ASSIGN @Advanpath TO "ADVANFILE"&Disk$
261 ASSIGN @Fname TO "NAMEFILE:9134,704,0" ! ROB
264 ASSIGN @Rname TO "NAMEFILE:9134,704,0" ! ROB
267 !

```

Table 6-14. Ground combat code (continued).

```

270 ! READ IN SMALL PERMANENT DATA FILES
273 GOSUB Read_data
276 !
279 Start_battle: ! START OF THE ATTRITION MODULE
282 PRINTER IS 1
285 PRINT USING "@,#"
288 PRINT TABXY(30,17),"GROUND COMBAT MODULE"
291 !
294 PRINTER IS 702
297 ! CONDUCT SECTOR ATTRITION ASSESSMENTS
300 !
303 GOSUB Zero_out ! INITIALIZE VARIABLES
306 GOSUB Set_battle ! INPUT BATTLE CONDITIONS
309 GOSUB Set_conditions ! SET ALL BATTLE CONDITIONS
312 GOSUB Control_battle ! CONTROLS BATTLE FLOW
315 GOSUB Print_fin_res ! PRINTS SECTOR BATTLE RESULT
318 !
321 PRINTER IS 1
324 ! LET GAMER ANALYZE RESULTS FOR PROPER BATTLE PORTRAYAL
327 INPUT "UPDATE THE HISTORY FILE WITH THESE RESULTS? (Y or N)",Q$
330 IF Q$<>"Y" AND Q$<>"N" THEN 327
333 !
336 ! WRITE SECTOR RESULTS TO THE HISTORY FILE
339 IF Q$="Y" THEN
342 GOSUB Apport_wri_loss
345 END IF
348 !
351 GOSUB Close_files
354 !
357 ! CHECK FOR MORE COMBAT
360 INPUT "MORE SECTORS TO PROCESS? (Y or N)",Q$
363 IF Q$<>"Y" AND Q$<>"N" THEN 360
366 IF Q$="Y" THEN LOAD "NEW_F4"&Disk$
369 !
372 ! IF COMBAT IS DONE, MAKE A FILE COPY. IF NOT, GO BACK TO MAIN MENU
375 INPUT "IS ALL COMBAT ASSESSED FOR THIS TURN? (Y or N)",Q$
378 IF Q$<>"Y" AND Q$<>"N" THEN 375
381 IF Q$="N" THEN
384 LOAD "DIME:9134,704,0"
387 DISP "GOING BACK TO DIME MENU"
390 GOTO Halt
393 ELSE
396 !OPTIONAL UNITFILE BACKUP MAY BE PLACED HERE.
399 LOAD "DIME:9134,704,0"
402 GOTO Halt
405 END IF
408 !
411 !***** END OF MAIN PROGRAM *****
414 !
417 Read_data: ! THIS SBR READS SMALL ARRAYS INTO THE PROGRAM
420 !
423 ! ** DC **

```


Table 6-14. Ground combat code (continued).

```

426 !
429 ASSIGN @Psyseff TO "SYS_EFF"&Dcdisk$
432 ENTER @Psyseff,1;Sys_eff(*)          ! FIREPOWER SCORE OF RED/BLUE WEAPON
435 ASSIGN @Psyseff TO *
438 !
441 ASSIGN @Pwpntyp TO "WPN_TYPE"&Dcdisk$
444 ENTER @Pwpntyp,1;Wpn_type(*)          ! 1=DF 2=IF 3=AD
447 ASSIGN @Pwpntyp TO *
450 !
453 ASSIGN @Pammowt TO "AMMO_WT"&Dcdisk$
456 ENTER @Pammowt,1;Ammo_wt(*)          ! PACKED WT OF INDIV RD/BURST OF AMMO
459 ASSIGN @Pammowt TO *
462 !
465 ASSIGN @Pbasld TO "BASIC_LD"&Dcdisk$
468 ENTER @Pbasld,1;Basic_ld(*)
471 ASSIGN @Pbasld TO *
474 !
477 ASSIGN @Partrt TO "ARTY_RATE"&Dcdisk$
480 ENTER @Partrt,1;Arty_30min_wt(*)
483 ASSIGN @Partrt TO *          ! RED & BLUE 30 MIN WT DEFINED AT THIS POINT FOR AN
DSTRBTN
486 !
489 ASSIGN @Partwt TO "ARTY_WT"&Dcdisk$
492 ENTER @Partwt,1;A_wt(*)          ! WT OF IF ROUND/PACKAGED WT - VOLLEY WT. FOR
BATTERIES
495 ASSIGN @Partwt TO *
498 !
501 ASSIGN @Pifmask TO "BFMASK"&Dcdisk$
504 ENTER @Pifmask,1;Bf_mask(*)
507 ASSIGN @Pifmask TO *
510 !
513 ASSIGN @Pifmask TO "RFMASK"&Dcdisk$
516 ENTER @Pifmask,1;Rf_mask(*)
519 ASSIGN @Pifmask TO *
522 !
525 ASSIGN @Pdfmask TO "BDF_MASK"&Dcdisk$
528 ENTER @Pdfmask,1;Bdf_mask(*)
531 ASSIGN @Pdfmask TO *
534 !
537 ASSIGN @Pdfmask TO "RDF_MASK"&Dcdisk$
540 ENTER @Pdfmask,1;Rdf_mask(*)
543 ASSIGN @Pdfmask TO *
546 ! ** END DC **
549 B_veh$[1,125]="DF FAV-TM551 FAV40HVM-GDF DRAGNLAW DF CMD-VDF DF
DF DF DF HVM40DF-ICDF-ICDF-ICDF-ICARTY ARTY ARTY ARTY "
552 B_veh$[126,250]="ARTY ARTY MORTRMORTRMORTRMORTRMRLRSTMLRSTMLRSTMLRSTINF I
INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSVULCNAVNGRIHAWK"
555 B_veh$[251,350]="ADA ADA STINGADAHF-TRKJ4TRKWATERCGO-TNATRK'EWTRK'EWTR' E
R DRSCÉAVLB PONBRENGEØENGØMATHEMATHEAATHE"
558 R_veh$[1,125]="T55 DF BMP73DF BRDM3BRDM5AT-75AGS17T12 CMD-VDF DF
DF DF DF BMPATHTR DF-ICDF-ICDF-ICARTY ARTY ARTY ARTY "
561 R_veh$[126,250]="ARTY ARTY MORTRMORTRMORTRMORTRMRL MRL MRL MRL INF I

```

Table 6-14. Ground combat code (continued).

```

INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSARMSSARMSS76LI-XSA-13SA-6 "
564 R_veh$(I251,350)="ADA ADA SA-14ADAHF-TRKJ4TRKWATERCGO-TNATRKEWTRKEWTRKEI
R OBSCEAVLB FONRENGEONGEOMATHEMATHEATHE"
567 '
570 ! ** DC **
573 !
576 ASSIGN @Pdsst TO "DS_START"&Dcdisk$
579 ENTER @Pdsst,1;Ds_start(*) !START RANGE FOR ARTY DS (CLOSE SPT)
582 ASSIGN @Pdsst TO *
585 !
588 ASSIGN @Partaloc TO "BARTYALLOC"&Dcdisk$
591 ENTER @Partaloc,1;Barty_30min(*)
594 ASSIGN @Partaloc TO *
597 !
600 ASSIGN @Partaloc TO "RARTYALLOC"&Dcdisk$
603 ENTER @Partaloc,1;Rarty_30min(*)
606 ASSIGN @Partaloc TO *
609 ! ** END DC **
612 RETURN
615 !
618 !-----
621 !
624 Zero_out: ! THIS SBR INITIALIZES VARIABLES USED IN THE COMBAT MODULE
627 !
630 Dc=0
633 !
636 FOR I=1 TO 12
639 B_unit_no(I)=0 ! UNIT# OF SECTOR UNITS
642 R_unit_no(I)=0
645 B_unit_pct(I)=0 ! % OF UNIT COMMITTED TO SECTOR
648 R_unit_pct(I)=0
651 NEXT I
654 Init_b_eff=0 ! BLUE INITIAL FIREPOWER SCORE
657 B_df_ammo=0 ! DIRECT FIRE AMMO AVAILABLE TO FIRE
660 B_ad_ammo=0 ! AIR DEFENSE AMMO AVAILABLE TO FIRE
663 Init_r_eff=0
666 R_df_ammo=0
669 R_ad_ammo=0
672 FOR I=1 TO 15
675 Bif_ammo(I)=0 ! INDIRECT FIRE AMMO AVAILABLE IN THIS SECTO
678 Rif_ammo(I)=0
681 NEXT I
684 FOR I=1 TO 3
687 Phase_ct(I)=0
690 NEXT I
693 FOR I=1 TO 12
696 FOR J=1 TO 74
699 R_unit(I,J)=0 ! CURRENT SYSTEMS ALIVE BY UNIT# AND SYSTEM
702 B_unit(I,J)=0
705 NEXT J
708 NEXT I
711 FOR I=1 TO 70

```

Table 6-14. Ground combat code (continued).

```

714   FOR J=1 TO 6
717     Kv_r(J,I)=0           ! KV TABLES FOR SECTOR BATTLE
720     Kv_b(J,I)=0
723     Sys(J,I)=0           ! SUBPROGRAM PASSING ARRAY FOR SYSTEMS
726   NEXT J
729   FOR J=1 TO 4
732     Sys_tot(J,I)=0       ! CUMULATIVE SYSTEM STATUS
735   NEXT J
738   FOR J=1 TO 12
741     B_init(J,I)=0        ! INITIAL UNIT SYSTEMS BY UNIT (J), SYS (I)
744     R_init(J,I)=0
747     R_con(J,I)=0
750     B_con(J,I)=0
753   NEXT J
756     B_init(13,I)=0
759     R_init(13,I)=0
762   NEXT I
765   FOR I=1 TO 3
768     FOR J=1 TO 6
771       R_helo(I,J)=0     ! HELICOPTER RESULTS
774       B_helo(I,J)=0
777       Minefield(I,J)=0 ! SECTOR MINEFIELD INFO
780     NEXT J
783   NEXT I
786     Time_seg=0          ! # OF THE CURRENT 30 MIN TIME SEGMENT
789     Last_bah1_seg=0
792     Last_bah2_seg=0     ! TIME SEGMENT WHEN HELICOPTER LAST FLOWN
795     Last_bsct_seg=0
798     Last_rah1_seg=0
801     Last_rah2_seg=0
804     Last_rsct_seg=0
807     Rah1_seg=0
810     Rah2_seg=0
813     Rsct_seg=0
816     Bah1_seg=0         ! # OF HELO MISSIONS FLOWN IN CELL=3 STATUS
819     Bah2_seg=0
822     Bsct_seg=0
825   FOR I=1 TO 7
828     B_dsarty_fire(I)=0
831     R_dsarty_fire(I)=0 ! # OF TONS OF AMMO FIRED FIRED IN CS M
ION
834   NEXT I
837   FOR I=1 TO 4
840     B_dsmort_fire(I)=0
843     R_dsmort_fire(I)=0
846   NEXT I
849     Barty_fire=0
852     Rarty_fire=0
855     Mine_delay=0       ! TIME DELAY DUE TO MINES
858     First_df=0        ! POINTER FOR 1ST ENTRY INTO DIRECT FIRE B
861     !
864   FOR I=1 TO 15

```

Table 6-14. Ground combat code (continued).

```

867   FOR J=1 TO 5
870     Rif_msn_tons(I,J)=0
873     Rif_msn_tons(I,J)=0
876   NEXT J
879   NEXT I
882   !
885   RETURN
888   !
891   !-----
894   !
897   Set_battle:   !   THIS SBR ALLOWS INPUT OF THE SECTOR WORK SHEET
900   !
903   PRINTER IS 1
906   Start_input:  !
909   GOSUB L1
912   GOSUB L2
915   GOSUB L3
918   GOSUB L4
921   GOSUB L5
924   GOSUB L6
927   GOSUB L7
930   GOSUB L8
933   GOSUB L9
936   GOSUB L10
939   GOSUB L11
942   GOSUB L12
945   Beg=1
948   End=No_minefields
951   GOSUB Lmines
954   Auto:PRINTER IS 1
957   PRINT "GROUND COMBAT INPUT:"
960   GOSUB Dump_input
963   REPEAT
966     INPUT "IS INPUT CORRECT? (Y/N)".Answer$
969   UNTIL Answer$="Y" OR Answer$="N"
972   IF Answer$="N" THEN
975     REPEAT
978       INPUT "NUMBER OF INCORRECT LINES?".Num
981     UNTIL Num>=0 AND Num<=15
984     IF Num=0 THEN Auto
987     FOR Nums=1 TO Num
990       INPUT "LINE TO BE CORRECTED? Note: line 2 is blue units. line 3 is red
".Num1
993       ON Num1 GOSUB L1,L2,L3,L4,L5,L6,L7,L8,L9,L10,L11,L12,L13,L14,L15
996     NEXT Nums
999     GOTO Auto
1002  END IF
1005  GOSUB Ad_sup
1008  REPEAT
1011    INPUT "DO YOU WANT A HARD COPY OF THE INPUT? (Y/N)".Answer$
1014  UNTIL Answer$="Y" OR Answer$="N"
1017  IF Answer$="Y" THEN

```

Table 6-14. Ground combat code (continued).

```

1020 PRINTER IS 702
1023 PRINT USING "@,#"
1026 PRINT "GROUND COMBAT INPUT:"
1029 GOSUB Dump_input
1032 PRINTER IS 1
1035 END IF
1038 PRINTER IS 1
1041 PRINT USING "@,#"
1044 PRINT TABXY(30,17),"GROUND COMBAT MODULE"
1047 PRINT
1050 PRINT "                ** BATTLE HISTORY **"
1053 PRINTER IS 702
1056 FOR I=1 TO 70
1059   Sys_tot(1,I)=B_init(13,I)
1062   Sys_tot(3,I)=R_init(13,I)
1065 NEXT I
1068 !
1071 ! DETERMINE INFANTRY LOAD FACTORS
1074 Side=1
1077 GOSUB Ready_load
1080 CALL Load_infantry(Sys_tot(*),B_msn(1),Side_pt,Sum_inf,Sum_df,B_ld_fact)
1083 Side=2
1086 GOSUB Ready_load
1089 CALL Load_infantry(Sys_tot(*),R_msn(1),Side_pt,Sum_inf,Sum_df,R_ld_fact)
1092 ! DETERMINE BLUE ELEMENT PERCENTAGES
1095 INPUT "DO YOU WANT TO CHANGE BLUE MISSION TEMPLATE FILES?".Chgbmt$
1098 Listop=0
1101 IF Chgbmt$="Y" THEN
1104   INPUT "DISPLAY VALUES TO 1=SCREEN ONLY, 2=SCREEN & PRINTER?".Listop
1107   IF Listop=2 THEN
1110     PRINTER IS 702
1113     PRINT USING "@ "
1116   END IF
1119 END IF
1122 Side=1
1125 FOR I=1 TO 2
1128 J=B_msn(1)
1131 ASSIGN @P TO "BIFTARG"&Disk3$
1134 ENTER @P,J;Mift(*)
1137 ASSIGN @P TO "BDFTARG"&Disk3$
1140 ENTER @P,J;Mdft(*)
1143 ASSIGN @P TO "BIFDT"&Disk3$
1146 ENTER @P,J;Mifdt(*)
1149 ASSIGN @P TO "BDFDT"&Disk3$
1152 ENTER @P,J;Mdftd(*)
1155 ASSIGN @P TO "BFIRE"&Disk3$
1158 ENTER @P,J;Mfire(*)
1161 ASSIGN @P TO "BDFIRE"&Disk3$
1164 ENTER @P,J;Mdfire(*)
1167 ASSIGN @P TO "BVUL"&Disk3$
1170 ENTER @P,J;Mvul(*)
1173 ASSIGN @P TO "BDVUL"&Disk3$

```

Table 6-14. Ground combat code (continued).

```

1176 ENTER @P,J;Mdvul(*)
1179 !
1182 FOR I=1 TO 2
1185   FOR K=1 TO No_b_unit
1188     T=B_type(K)+B_ech(K)*10
1191     Hfile(I,K,1)=Mift(T)
1194     Hfile(I,K,2)=Mdft(T)
1197     Hfile(I,K,3)=Mifdt(T)
1200     Hfile(I,K,4)=Mdfdt(T)
1203     Hfile(I,K,5)=Mfire(T)
1206     Hfile(I,K,6)=Mdfire(T)
1209     Hfile(I,K,7)=Mvul(T)
1212     Hfile(I,K,8)=Mdvul(T)
1215     IF Chgbmt$="Y" THEN
1218       CALL Missn_tmpls(Side,(I),(T),(K),B_unit_no(*),Hfile(*),Listop)
1221     END IF
1224     FOR E=1 TO 70
1227       B_if_t(I,E)=Hfile(I,K,1)*B_con(K,E)+B_if_t(I,E)
1230       B_df_t(I,E)=Hfile(I,K,2)*B_con(K,E)+B_df_t(I,E)
1233       B_if_dt(I,E)=Hfile(I,K,3)*B_con(K,E)+B_if_dt(I,E)
1236       B_df_dt(I,E)=Hfile(I,K,4)*B_con(K,E)+B_df_dt(I,E)
1239       B_f(I,E)=Hfile(I,K,5)*B_con(K,E)+B_f(I,E)
1242       B_df(I,E)=Hfile(I,K,6)*B_con(K,E)+B_df(I,E)
1245       B_v(I,E)=Hfile(I,K,7)*B_con(K,E)+B_v(I,E)
1248       B_dv(I,E)=Hfile(I,K,8)*B_con(K,E)+B_dv(I,E)
1251     NEXT E
1254   NEXT K
1257 NEXT I
1260 ! CALCULATE RED TARGET PARAMETERS
1263 INPUT "DO YOU WISH TO CHANGE RED MISSION TEMPLATE FILES?",Chgrmt$
1266 IF Chgrmt$="Y" AND Listop=0 THEN
1269   INPUT "DISPLAY VALUES TO 1=SCREEN ONLY, 2=SCREEN & PRINTER ?",Listop
1272   IF Listop=2 THEN
1275     PRINTER IS 702
1278     PRINT USING "@"
1281   END IF
1284 END IF
1287 Side=2
1290! FOR I=1 TO 2
1293 J=R_msn(1)
1296 ASSIGN @P TO "RIFTARG"&Disk3$
1299 ENTER @P,J;Mift(*)
1302 ASSIGN @P TO "RDFTARG"&Disk3$
1305 ENTER @P,J;Mdft(*)
1308 ASSIGN @P TO "RIFDT"&Disk3$
1311 ENTER @P,J;Mifdt(*)
1314 ASSIGN @P TO "RDFDT"&Disk3$
1317 ENTER @P,J;Mdfdt(*)
1320 ASSIGN @P TO "RFIRE"&Disk3$
1323 ENTER @P,J;Mfire(*)
1326 ASSIGN @P TO "RDFIRE"&Disk3$
1329 ENTER @P,J;Mdfire(*)

```

Table 6-14. Ground combat code (continued).

```

1332 ASSIGN @F TO "RVUL"&Disk3$
1335 ENTER @P,J:Mvul(*)
1338 ASSIGN @F TO "RDVUL"&Disk3$
1341 ENTER @P,J:Mdvul(*)
1344 ASSIGN @F TO *
1347 '
1350 FOR I=1 TO 2
1353   FOR K=1 TO No_r_unit
1356     T=R_type(K)+R_ech(K)*10
1359     Hfile(I,K,1)=Mift(T)
1362     Hfile(I,K,2)=Mdft(T)
1365     Hfile(I,K,3)=Mifdt(T)
1368     Hfile(I,K,4)=Mdftd(T)
1371     Hfile(I,K,5)=Mfire(T)
1374     Hfile(I,K,6)=Mdfire(T)
1377     Hfile(I,K,7)=Mvul(T)
1380     Hfile(I,K,8)=Mdvul(T)
1383     IF Chgrmt$="Y" THEN
1386       CALL Missn_tmpls(Side.(I),(T),(K),R_unit_no(*),Hfile(*),Listop)
1389     END IF
1392     FOR E=1 TO 70
1395       R_if_t(I,E)=Hfile(I,K,1)*R_con(K,E)+R_if_t(I,E)
1398       R_df_t(I,E)=Hfile(I,K,2)*R_con(K,E)+R_df_t(I,E)
1401       R_if_dt(I,E)=Hfile(I,K,3)*R_con(K,E)+R_if_dt(I,E)
1404       R_df_dt(I,E)=Hfile(I,K,4)*R_con(K,E)+R_df_dt(I,E)
1407       R_f(I,E)=Hfile(I,K,5)*R_con(K,E)+R_f(I,E)
1410       R_df(I,E)=Hfile(I,K,6)*R_con(K,E)+R_df(I,E)
1413       R_v(I,E)=Hfile(I,K,7)*R_con(K,E)+R_v(I,E)
1416       R_dv(I,E)=Hfile(I,K,8)*R_con(K,E)+R_dv(I,E)
1419     NEXT E
1422   NEXT K
1425 NEXT I
1428 End_input:RETURN
1431 '-----
1434 Ready_load: ' READY INFANTRY AND DIRECT FIRE LOADS
1437 Side_pt=2*Side-1
1440 Sum_inf=Sys_tot(Side_pt,36)+Sys_tot(Side_pt,37)+Sys_tot(Side_pt,38)+Sys_tot
(Side_pt,39)+Sys_tot(Side_pt,40)
1443 Sum_df=Sys_tot(Side_pt,16)+Sys_tot(Side_pt,17)+Sys_tot(Side_pt,18)+Sys_tot
Side_pt,19)+Sys_tot(Side_pt,20)
1446 RETURN
1449 '-----
1452 '
1455 L1: '
1458 INPUT "ENTER LINE 1:".Turn,Sector,No_b_unit,No_r_unit,St_time,End_time
1461 CALL CK_var("# BLUE UNITS","TO",No_b_unit,0,12)
1464 CALL CK_var("# RED UNITS","TO",No_r_unit,0,12)
1467 Minute=St_time MOD 100
1470 IF St_time<0 OR St_time>2345 OR Minute>45 THEN
1473   PRINT
1476   PRINT "*** ERROR: START TIME MUST BE BETWEEN 00-2345 HRS : RE-ENTER LINE
"
```

Table 6-14. Ground combat code (continued).

```

1479 GOTO Start_input
1482 END IF
1485 IF End_time<St_time THEN End_time=End_time+2400
1488 RETURN
1491 !
1494 !-----
1497 !
1500 L2: !
1503 FOR Ij=1 TO 12
1506 B_unit_no(Ij)=0
1509 B_unit_pct(Ij)=0
1512 NEXT Ij
1515 FOR Ii=1 TO 70
1518 B_init(13,Ii)=0
1521 NEXT Ii
1524 B_ad_ammo=0
1527 B_df_ammo=0
1530 FOR Jj=1 TO 15
1533 Bif_ammo(Jj)=0
1536 NEXT Jj
1539 ! INPUT BLUE UNITS
1542 !
1545 FOR I=1 TO No_b_unit
1548 INPUT "ENTER BLUE UNIT, PERCENT COMMITTED",B_unit_no(I),B_unit_pct(I)
1551 IF B_unit_no(I)<0 OR B_unit_no(I)>191 THEN
1554 PRINT
1557 PRINT "*** ERROR: UNIT # ",B_unit_no(I)," NOT ALLOWED, IT MUST BE 1-:
"
1560 GOTO 1548
1563 END IF
1566 IF B_unit_pct(I)<0 OR B_unit_pct(I)>100 THEN
1569 PRINT
1572 PRINT I,"** ERROR: PERCENT NOT ALLOWED, IT MUST BE 0-100. "
1575 GOTO 1548
1578 END IF
1581 NEXT I
1584 FOR I=1 TO No_b_unit ! READ BLUE UNITS
1587 ENTER @Unitpath,B_unit_no(I);N(*)
1590 B_ech(I)=N(76)
1593 !RESET DETECTION STATUS ROB
1596 N(91)=.2
1599 IF N(92)<3 THEN N(92)=3
1602 OUTPUT @Unitpath,B_unit_no(I);N(*)
1605 FOR J=1 TO 70
1608 B_unit(I,J)=N(J)*B_unit_pct(I)/100
1611 B_init(I,J)=B_unit(I,J)
1614 B_init(13,J)=B_init(13,J)+B_init(I,J)
1617 NEXT J
1620 B_unit(I,71)=INT(((N(78)-INT(N(78)))*10)+.01)
1623 B_unit(I,72)=N(131)*B_unit_pct(I)/100
1626 B_unit(I,73)=N(132)*B_unit_pct(I)/100
1629 B_unit(I,74)=N(133)*B_unit_pct(I)/100

```


Table 6-14. Ground combat code (continued).

```

1632 B_type(I)=B_unit(I,71)+1
1635 B_df_ammo=B_df_ammo+B_unit(I,72)
1638 B_ad_ammo=B_ad_ammo+B_unit(I,74)
1641 Bada_hnd(I)=INT(N(80))/100
1644 Bada_veh(I)=N(80)-(Bada_hnd(I)*100)
1647 Side=1
1650 !
1653 ! CALCULATE AMMO AVAILABLE
1656 GOSUB Ammo_breakdown
1659 FOR J=1 TO 15
1662 Bif_ammo(J)=Bif_ammo(J)+If_ammo(J)*B_unit_pct(I)/100
1665 NEXT J
1668 NEXT I
1671 Bdf_ammo_sv=B_df_ammo
1674 Bad_ammo_sv=B_ad_ammo
1677 RETURN
1680 !
1683 !-----
1686 !
1689 L3: !
1692 FOR Ij=1 TO 12
1695 R_unit_no(Ij)=0
1698 R_unit_pct(Ij)=0
1701 NEXT Ij
1704 FOR Ii=1 TO 70
1707 R_init(13,Ii)=0
1710 NEXT Ii
1713 R_ad_ammo=0
1716 R_df_ammo=0
1719 FOR Jj=1 TO 15
1722 Rif_ammo(Jj)=0
1725 NEXT Jj
1728 ! INPUT RED UNITS
1731 !
1734 FOR I=1 TO No_r_unit
1737 INPUT "ENTER RED UNIT, PERCENT COMMITTED",R_unit_no(I),R_unit_pct(I)
1740 IF R_unit_no(I)<192 OR R_unit_pct(I)>400 THEN
1743 PRINT
1746 PRINT "*** ERROR: UNIT # ",R_unit_no(I)," NOT ALLOWED, IT MUST BE 192-
0."
1749 GOTO 1737
1752 END IF
1755 IF R_unit_pct(I)<0 OR R_unit_pct(I)>100 THEN
1758 PRINT I,"** ERROR: PERCENT NOT ALLOWED, IT MUST BE 0-100."
1761 GOTO 1737
1764 END IF
1767 NEXT I
1770 !
1773 FOR I=1 TO No_r_unit ! READ RED UNITS
1776 ENTER @Unitpath,R_unit_no(I);N(*)
1779 'RESET DETECTION STATUS FOR
1782 N(91)=.2

```

Table 6-14. Ground combat code (continued).

```

1785 R_ech(I)=N(76)
1788 'RESET DETECTION STATUS ROE
1791 N(91)=.2
1794 IF N(92)<3 THEN N(92)=3
1797 OUTPUT @Unitpath,R_unit_no(I);N(*)
1800 FOR J=1 TO 70
1803   R_unit(I,J)=N(J)*R_unit_pct(I)/100
1806   R_init(I,J)=R_unit(I,J)
1809   R_init(13,J)=R_init(13,J)+R_init(I,J)
1812 NEXT J
1815 R_unit(I,71)=INT(((N(78)-INT(N(78)))*10)+.01)
1818 R_unit(I,72)=N(131)*R_unit_pct(I)/100
1821 R_unit(I,73)=N(132)*R_unit_pct(I)/100
1824 R_unit(I,74)=N(133)*R_unit_pct(I)/100
1827 R_type(I)=R_unit(I,71)+1
1830 R_df_ammo=R_df_ammo+R_unit(I,72)
1833 R_ad_ammo=R_ad_ammo+R_unit(I,74)
1836 Rada_hnd(I)=INT(N(80))/100
1839 Rada_veh(I)=N(80)-(Rada_hnd(I)*100)
1842 Side=2
1845 ! CALCULATE RED AMMO AVAILABLE
1848 GOSUB Ammo_breakdown
1851 FOR J=1 TO 15
1854   Rif_ammo(J)=Rif_ammo(J)+If_ammo(J)*R_unit_pct(I)/100
1857 NEXT J
1860 NEXT I
1863 !
1866 RETURN
1869 !
1872 !-----
1875 !
1878 Ad_sup: !
1881 ! CALCULATE PERCENTAGE OF AIR DEFENSE SUPPRESSED
1884 Bhnd_sup=0
1887 Bveh_sup=0
1890 Rhnd_sup=0
1893 Rveh_sup=0
1896 FOR I=1 TO No_b_unit
1899   IF B_init(13,53)+B_init(13,54)<=.1 THEN Bveh_ada
1902   Bhnd_sup=Bhnd_sup+Bada_hnd(I)*(B_init(I,53)+B_init(I,54))/(B_init(13,53)
B_init(13,54))
1905 Bveh_ada: !
1908   Tot_init_13=B_init(13,48)+B_init(13,49)+B_init(13,50)+B_init(13,51)+B_i
t(13,52)
1911   IF Tot_init_13<=.1 THEN End_supb
1914   Tot_init_1=B_init(I,48)+B_init(I,49)+B_init(I,50)+B_init(I,51)+R_init(I
2)
1917   Bveh_sup=Bveh_sup+Bada_veh(I)*Tot_init_1/Tot_init_13
1920 End_supb:NEXT I
1923 FOR I=1 TO No_r_unit
1926 Rhnd_ada: IF R_init(13,53)+R_init(13,54)<=.1 THEN Rveh_ada
1929   Rhnd_sup=Rhnd_sup+Rada_hnd(I)*(R_init(I,53)+R_init(I,54))/(R_init(13,53)

```

Table 6-14. Ground combat code (continued).

```

R_init(13,54))
1932 Rveh_ada: '
1935 Tot_init_13=R_init(13,48)+R_init(13,49)+R_init(13,50)+R_init(13,51)+R_
t(13,52)
1938 IF Tot_init_13<=.1 THEN End_supr
1941 Tot_init_i=R_init(I,48)+R_init(I,49)+R_init(I,50)+R_init(I,51)+R_init(
2)
1944 Rveh_sup=Rveh_sup+Rada_veh(I)*Tot_init_i/Tot_init_13
1947 End_supr:NEXT I
1950 !
1953 Rdf_ammo_sv=R_df_ammo
1956 Rad_ammo_sv=R_ad_ammo
1959 ! CALCULATE BLUE TARGET PARAMETERS
1962 FOR I=1 TO No_b_unit
1965 FOR J=1 TO 70
1968 IF B_init(13,J)=0 THEN B_dem_0
1971 B_con(I,J)=B_unit(I,J)/B_init(13,J)
1974 B_dem_0:NEXT J
1977 NEXT I
1980 ! CALCULATE RED TARGET PARAMETERS
1983 FOR I=1 TO No_r_unit
1986 FOR J=1 TO 70
1989 IF R_init(13,J)=0 THEN R_dem_0
1992 R_con(I,J)=R_unit(I,J)/R_init(13,J)
1995 R_dem_0:NEXT J
1998 NEXT I
2001 RETURN
2004 !
2007 !-----
2010 !
2013 L4: !
2016 ! ENTER BATTLE PARAMETERS
2019 INPUT "ENTER LINE 4:",Atk_def,Init_rg,Df_rg,No_minefields,Ride,Dis_inf
2022 CALL Ck_var("BL/R ATKR","OR",Atk_def,0,1)
2025 CALL Ck_var("INIT RG(m)","THRU",Init_rg,0,40000)
2028 IF Init_rg<=3000 THEN
2031 Limit_df_rg=Init_rg
2034 ELSE
2037 Limit_df_rg=3000
2040 END IF
2043 CALL Ck_var("DF RG(m)","THRU",Df_rg,0,Limit_df_rg)
2046 CALL Ck_var("# OF MINEFIELDS","TO",No_minefields,0,3)
2049 CALL Ck_var("MTD/DISM","OR",Ride,0,1)
2052 CALL Ck_var("INF DISM","OR",Dis_inf,0,1)
2055 FOR Ii=No_minefields+1 TO 3
2058 FOR Jj=1 TO 6
2061 Minefield(Ii,Jj)=0
2064 NEXT Jj
2067 NEXT Ii
2070 RETURN
2073 !
2076 !-----

```

Table 6-14. Ground combat code (continued).

```

2079 !
2082 L5: !
2085 INPUT "ENTER LINE 5: ",Vis,Cloud_ht,Irh
2088 CALL Ck_var("VISIBILITY","TO",Vis,1,4)
2091 CALL Ck_var("CLOUD HT(m)","THRU",Cloud_ht,0,999999999)
2094 CALL Ck_var("REL HUMID","OR",Irh,1,2)
2097 Vis_bound$=" "
2100 SELECT Vis
2103 CASE 1
2106 ! Visib=7
2109 Visibility=5
2112 Vis_bound$=">"
2115 CASE 2
2118 ! Visib=5
2121 Visibility=5
2124 CASE 3
2127 ! Visib=2
2130 Visibility=2
2133 CASE 4
2136 ! Visib=1
2139 Visibility=1
2142 CASE ELSE
2145 PRINT " NO VISIBILITY "
2148 STOP
2151 END SELECT
2154 IF Vis=3 OR Vis=4 THEN !SUPPRESS ALL HAND HELD ADA
2157 Rhnd_sup=1
2160 Rhnd_sup=1
2163 END IF
2166 RETURN
2169 !
2172 !-----
2175 !
2178 L6: !
2181 INPUT "ENTER LINE 6: ".Ialb
2184 CALL Ck_var("ATTACKER SPECIAL TASK","TO",Ialb,0,4)
2187 Balb=1
2190 Ralb=1
2193 SELECT Atk_def
2196 CASE 0 !RED ATTACKER
2199 Balb=Ialb+1
2202 CASE 1 !BLUE ATTACKER
2205 Ralb=Ialb+1
2208 END SELECT
2211 !
2214 RETURN
2217 !
2220 !-----
2223 !
2226 L7: !
2229 INPUT "ENTER LINE 7: ".B_msn(1),B_terr,B_rg_break,B_pct_fwd,B_mopp,T_lengt
1),T_width(1),B_break_t(1),B_cas_break

```

Table 6-14. Ground combat code (continued).

```

2232 CALL Ck_var("BLUE MISSION","TO",B_msn(1),0,9)
2235 CALL Ck_var("BLUE TERRAIN","TO",B_terr,1,4)
2238 CALL Ck_var("BL RG BRK/PT","THRU",B_rg_break,0,Init_rg-.001)
2241 CALL Ck_var("BLUE ADV. GUARD","THRU",B_pct_fwd,0,1)
2244 CALL Ck_var("BLUE MOFF/FATIGUE","THRU",B_mopp,0,100)
2247 !CALL Ck_var("BLUE SECTOR LENGTH","THRU",T_length(1),0,25)
2250 !CALL Ck_var("BLUE SECTOR WIDTH","THRU",T_width(1),0,25)
2253 CALL Ck_var("BLUE W/DRAW TIME","THRU",B_break_t(1),0,30)
2256 CALL Ck_var("BLUE CAS BRK/PT","THRU",B_cas_break,0,1)
2259 !
2262 !T_length(1)=T_length(1)*1000
2265 !T_width(1)=T_width(1)*1000
2268 B_msn(1)=B_msn(1)+1
2271 !
2274 RETURN
2277 !
2280 !-----
2283 !
2286 L8: !
2289 INPUT "ENTER LINE 8:",R_msn(1),R_terr,R_rg_break,R_pct_fwd,R_mopp,T_lengt
2) ,T_width(2),R_break_t(1),R_cas_break
2292 CALL Ck_var("RED MISSION","TO",R_msn(1),0,9)
2295 CALL Ck_var("RED TERRAIN","TO",R_terr,1,4)
2298 CALL Ck_var("RD RG BRK/PT","THRU",R_rg_break,0,Init_rg-.001)
2301 CALL Ck_var("RED ADV. GUARD","THRU",R_pct_fwd,0,1)
2304 CALL Ck_var("RED MOFF/FATIGUE","THRU",R_mopp,0,100)
2307 !CALL Ck_var("RED SECTOR LENGTH","THRU",T_length(2),0,25)
2310 !CALL Ck_var("RED SECTOR WIDTH","THRU",T_width(2),0,25)
2313 CALL Ck_var("RED W/DRAW TIME","THRU",R_break_t(1),0,30)
2316 CALL Ck_var("RED CAS BRK/PT","THRU",R_cas_break,0,1)
2319 !
2322 !T_width(2)=T_width(2)*1000
2325 !T_length(2)=T_length(2)*1000
2328 R_msn(1)=R_msn(1)+1
2331 !
2334 RETURN
2337 !
2340 !-----
2343 !
2346 L9: !
2349 PRINT TABXY(1,14),"** NOTE: Helicopter standoff ranges input on lines 9 &
0 are ranges from"
2352 PRINT TABXY(1,15),"** attack helicopters to primary mission targets."
2355 INPUT "ENTER LINE 9:",B_helo(1,1),B_helo(2,1),B_helo(3,1),B_helo(1,3),B_h
o(2,3),B_helo_atkprof(*),B_helo_delay,B_helo_rg_delay,B_helo_msn(*),B_atk_rg(*)
2358 IF B_helo(1,1)>0 AND B_helo(1,3)=0 THEN
2361 PRINT "** ERROR: CANNOT HAVE AH-64'S WITHOUT CELLS; RE-ENTER LINE 9"
2364 GOTO L9
2367 END IF
2370 IF B_helo(1,1)=0 AND B_helo(3,1)>0 AND B_helo_msn(1)=2 THEN
2373 !SCOUTS ARE LASING FOR AH1'S AND ON AN AIR MISSION? CAN'T DO THAT
2376 PRINT "** ERROR: SCOUTS CANNOT LASE ON AN AIR TO AIR MISSION. WILL IGN

```

Table 6-14. Ground combat code (continued).

```

SCOUTS"
2379 R_helo(3,1)=0 !ZERO OUT SCOUTS
2382 END IF
2385 IF B_helo(1,1)>0 THEN B_helo_atkprof(1)=1
2388 CALL Ck_var("# OF LCH","THRU",B_helo(1,1),0,99)
2391 CALL Ck_var("# OF AH1S","THRU",B_helo(2,1),0,99)
2394 CALL Ck_var("# OF SCOUTS","THRU",B_helo(3,1),0,99)
2397 CALL Ck_var(" LCH CELLS","TO",B_helo(1,3),0,4)
2400 CALL Ck_var("AH1S CELLS","TO",B_helo(2,3),0,4)
2403 CALL Ck_var("BLUE ATK PROF","TO",B_helo_atkprof(1),0,7)
2406 CALL Ck_var("BLUE ATK PROF","TO",B_helo_atkprof(2),0,7)
2409 CALL Ck_var("BLUE TIME DELAY","THRU",B_helo_delay,0,530)
2412 CALL Ck_var("BLUE ATK RG","THRU",B_helo_rg_delay,0,Init_rg)
2415 CALL Ck_var("BLUE HELO MSN","TO",B_helo_msn(1),0,3)
2418 CALL Ck_var("BLUE HELO MSN","TO",B_helo_msn(2),0,3)
2421 CALL Ck_var("BLUE STANDOFF RG","THRU",B_atk_rg(1),0,Init_rg)
2424 CALL Ck_var("BLUE STANDOFF RG","THRU",B_atk_rg(2),0,Init_rg)
2427 IF B_helo(3,1)>0 THEN
2430 B_helo(3,3)=B_helo(1,3)
2433 END IF
2436 RETURN
2439 !
2442 !-----
2445 !
2448 L10: !
2451 INPUT "ENTER LINE 10:",R_helo(1,1),R_helo(2,1),R_helo(3,1),R_helo(1,3),R_helo(2,3),R_helo_atkprof(*),R_helo_delay,R_helo_rg_delay,R_helo_msn(*),R_atk_rg(*)
2454 IF R_helo(1,1)>0 AND R_helo(1,3)=0 THEN
2457 PRINT "** ERROR: MUST SPECIFY # OF CELLS: RE-ENTER LINE 10"
2460 GOTO L10
2463 END IF
2466 IF R_helo(1,1)>0 AND R_helo(3,1)>0 AND R_helo_msn(1)=2 THEN
2469 !SCOUTS ARE LASING FOR AH1'S AND ON AN AIR MISSION? CAN'T DO THAT
2472 PRINT "** ERROR: SCOUTS CANNOT LASE ON AN AIR TO AIR MISSION. WILL IGNORE SCOUTS"
2475 R_helo(3,1)=0 !ZERO OUT SCOUTS
2478 END IF
2481 IF R_helo(2,1)>0 THEN R_helo_atkprof(2)=3
2484 CALL Ck_var("# OF HIND","THRU",R_helo(1,1),0,99)
2487 CALL Ck_var("HIND CELLS","TO",R_helo(1,3),0,4)
2490 CALL Ck_var("# OF AH2S","THRU",R_helo(2,1),0,99)
2493 CALL Ck_var("AH2 CELLS","TO",R_helo(2,3),0,4)
2496 CALL Ck_var("RED ATK PROF","TO",R_helo_atkprof(1),0,7)
2499 CALL Ck_var("RED ATK PROF","TO",R_helo_atkprof(2),0,7)
2502 CALL Ck_var("RED TIME DELAY","THRU",R_helo_delay,0,530)
2505 CALL Ck_var("RED ATK RG","THRU",R_helo_rg_delay,0,Init_rg)
2508 CALL Ck_var("RED HELO MSN","TO",R_helo_msn(1),0,3)
2511 CALL Ck_var("RED HELO MSN","TO",R_helo_msn(2),0,3)
2514 CALL Ck_var("RED STANDOFF RG","THRU",R_atk_rg(1),0,Init_rg)
2517 CALL Ck_var("RED STANDOFF RG","THRU",R_atk_rg(2),0,Init_rg)
2520 IF R_helo(3,1)>0 THEN R_helo(3,3)=R_helo(1,3)
2523 PRINT TABXY(1,14),"
```

Table 6-14. Ground combat code (continued).

```

2526 PRINT TABXY(1,15).
2529 RETURN
2532 !
2535 !-----
2538 !
2541 L11: !
2544 INPUT "ENTER LINE 11: ".Bif_msn(*),B_prep_time,No_gamp,Perc_gamp,No_clgp,F
c_clgp,Clgp_rpv
2547 Total_pct=0
2550 FOR Tot_pct=1 TO 5 ! SMOKE WILL COME OUT OF CLOSE SUPPORT
2553 Total_pct=Bif_msn(Tot_pct)+Total_pct
2556 NEXT Tot_pct
2559 Total_pct=Total_pct+Perc_gamp+Perc_clgp
2562 IF Total_pct=100 OR Total_pct=0 THEN
2565 GOTO End_tot_pct_ch1
2568 ELSE
2571 PRINTER IS 1
2574 PRINT
2577 PRINT "*** ERROR: %'S DO NOT EQUAL 100 OR 0 : RE-ENTER LINE 11"
2580 GOTO L11
2583 END IF
2586 End_tot_pct_ch1: !
2589 CALL Ck_var("SMOKE % ". "THRU",Bif_msn(6).0,100)
2592 !CALL Ck_var("TIME DELAY". "THRU",B_prep_time,0,2400)
2595 CALL Ck_var("# GAMP". "THRU",No_gamp.0,999)
2598 CALL Ck_var("# CLGP". "THRU",No_clgp.0,999)
2601 CALL Ck_var("RVP". "OR".Clgp_rpv.0,1)
2604 B_prep_time=B_prep_time+30
2607 B_minute=B_prep_time MOD 100
2610 SELECT B_minute
2613 CASE 16 TO 45
2616 B_minute=30
2619 CASE <16
2622 B_minute=0
2625 CASE >45
2628 B_minute=100
2631 END SELECT
2634 B_prep_time=INT(B_prep_time/100)*100+B_minute
2637 RETURN
2640 !
2643 !-----
2646 !
2649 L12: !
2652 INPUT "ENTER LINE 12: ".Rif_msn(*),R_prep_time
2655 Total_pct=0
2658 FOR Tot_pct=1 TO 5 ! SMOKE WILL COME OUT OF CLOSE SUPPORT
2661 Total_pct=Rif_msn(Tot_pct)+Total_pct
2664 NEXT Tot_pct
2667 IF Total_pct=100 OR Total_pct=0 THEN
2670 GOTO End_tot_pct_ch2
2673 ELSE

```

Table 6-14. Ground combat code (continued).

```

2676 PRINTER IS 1
2679 PRINT
2682 PRINT "** ERROR: %'S DO NOT EQUAL 100 OR 0 ; RE-ENTER LINE 12"
2685 GOTO L12
2688 END IF
2691 End_tot_pct_ch2: !
2694 CALL Ck_var("SMOKE % ", "THRU", Rif_msn(6), 0, 100)
2697 !CALL Ck_var("TIME DELAY", "THRU", R_prep_time, 0, 2400)
2700 R_prep_time=R_prep_time+30
2703 R_minute=R_prep_time MOD 100
2706 SELECT R_minute
2709 CASE 16 TO 45
2712     R_minute=30
2715 CASE <16
2718     R_minute=0
2721 CASE >45
2724     R_minute=100
2727 END SELECT
2730 R_prep_time=INT(R_prep_time/100)*100+R_minute
2733 RETURN
2736 !
2739 !-----
2742 !
2745 Lmines: !
2748 IF No_minefields>0 THEN
2751     FOR I=Beg TO End
2754         INPUT "ENTER MINEFIELD DATA: ", Mf(*)
2757         FOR J=1 TO 4
2760             Minefield(I, J)=Mf(J)
2763         NEXT J
2766         Minefield(I, 5)=100 !***** NO LONGER USED
2769         CALL Ck_var("RANGE", "THRU", Minefield(I, 1), 0, Init_rg-.001)
2772         CALL Ck_var("WIDTH", "THRU", Minefield(I, 2), 1, 999)
2775         CALL Ck_var("SECTOR WIDTH", "THRU", Minefield(I, 3), 1, 999)
2778         CALL Ck_var("% ENTERED", "THRU", Minefield(I, 4), 0, 100)
2781     NEXT I
2784 END IF
2787 RETURN
2790 !
2793 !-----
2796 !
2799 L13: !
2802 IF No_minefields>=1 THEN
2805     Beg=1
2808     End=1
2811     GOSUB Lmines
2814 END IF
2817 RETURN
2820 !
2823 !-----
2826 !
2829 L14: !

```


Table 6-14. Ground combat code (continued).

```

2832 IF No_minefields=2 THEN
2835   Reg=2
2838   End=2
2841   GOSUB Lmines
2844 END IF
2847 RETURN
2850 !
2853 !-----
2856 !
2859 L15: !
2862 IF No_minefields=3 THEN
2865   Reg=3
2868   End=3
2871   GOSUB Lmines
2874 END IF
2877 RETURN
2880 !
2883 !-----
2886 !
2889 Set_print: !
2892 PRINT USING "//////.21A.4Z,2X,25A,6D";"BATTLE WILL BEGIN at ":St_time:"w
an INITIAL RANGE of ":Init_rg
2895 IF End_time<2400 THEN
2898   PRINT USING "19A.4Z";"BATTLE WILL END at ":End_time
2901 ELSE
2904   PRINT USING "19A.4Z";"BATTLE WILL END at ":End_time-2400
2907 END IF
2910 PRINT USING "/.6X,32A,6D";"DIRECT FIRE will begin at range ":Df_rg
2913 PRINT USING "/.6X,14A,1A,2D,22A,6D,1A";"Visibility is ":Vis_bound$:Visibi
ty;"km ; Cloud height is ":Cloud_ht;"m"
2916 PRINT USING "///"
2919 SELECT Atk_def
2922 CASE 0
2925   B_atk_def$="DEFENDER"
2928   R_atk_def$="ATTACKER"
2931 CASE 1
2934   B_atk_def$="ATTACKER"
2937   R_atk_def$="DEFENDER"
2940 END SELECT
2943 PRINT
2946 PRINT
2949 PRINT "          BLUE ":B_atk_def$:          ;          RED ":R
tk_def$
2952 PRINT USING "11X,13A,15X,1A,12X,13A";"-----":":":-----"
2955 PRINT USING "39X,1A";":":
2958 SELECT B_msn(1)
2961 CASE 1
2964   B_msn$="MvContact"
2967 CASE 2
2970   B_msn$="Indr Fire"
2973 CASE 3
2976   B_msn$=" Movement"

```

Table 6-14. Ground combat code (continued).

```

2979 CASE 4
2982   B_msn$=" Frnt Atk"
2985 CASE 5
2988   B_msn$="  Env Atk"
2991 CASE 6
2994   B_msn$="    Delay"
2997 CASE 7
3000   B_msn$="  Hast Def"
3003 CASE 8
3006   B_msn$="  Prep Def"
3009 CASE 9
3012   B_msn$="Rear Area"
3015 CASE 10
3018   B_msn$="  Ambush"
3021 END SELECT
3024 SELECT R_msn(1)
3027 CASE 1
3030   R_msn$="MvContact"
3033 CASE 2
3036   R_msn$="Indr Fire"
3039 CASE 3
3042   R_msn$=" Movement"
3045 CASE 4
3048   R_msn$=" Frnt Atk"
3051 CASE 5
3054   R_msn$="  Env Atk"
3057 CASE 6
3060   R_msn$="    Delay"
3063 CASE 7
3066   R_msn$="  Hast Def"
3069 CASE 8
3072   R_msn$="  Prep Def"
3075 CASE 9
3078   R_msn$="Rear Area"
3081 CASE 10
3084   R_msn$="  Ambush"
3087 END SELECT
3090 PRINT USING "6X.8A,6X.9A,10X.1A,7X.8A,6X.9A": "Mission ":B_msn$:"!": "Missi
";R_msn$
3093 SELECT B_terr
3096 CASE 1
3099   B_terr$=" OFEN"
3102 CASE 2
3105   B_terr$=" ROLL"
3108 CASE 3
3111   B_terr$=" HILL"
3114 CASE 4
3117   B_terr$="MOUNT"
3120 END SELECT
3123 SELECT R_terr
3126 CASE 1
3129   R_terr$=" OFEN"

```

Table 6-14. Ground combat code (continued).

```

3132 CASE 2
3135   R_terr$=" ROLL"
3138 CASE 3
3141   R_terr$=" HILL"
3144 CASE 4
3147   R_terr$="MOUNT"
3150 END SELECT
3153 PRINT USING "6X,7A,11X,5A,10X,1A,7X,7A,11X,5A": "Terrain": R_terr$: "!"; "Ter
in": R_terr$
3156 PRINT USING "6X,11A,6X ,6D,10X,1A, 7X,11A,6X ,6D": "Break Range": B_rg_brea
"!"; "Break Range": R_rg_break
3159 PRINT USING "6X,16A,4X ,3D,10X,1A, 7X,16A,4X ,3D": "% Casualty Break": B_ca
break*100: "!"; "% Casualty Break": R_cas_break*100
3162 PRINT USING "6X,9A,11X,3D,10X,1A, 7X,9A,11X,3D": "% Forward": B_pct_fwd*100
"!"; "% Forward": R_pct_fwd*100
3165 Set_pnt_fmt1: IMAGE 6X,10A,10X,3D,10X,1A, 7X,10A,10X,3D
3168   !
3171   !           PRINT HELICOPTER INFORMATION
3174   !
3177 PRINT USING "6X,12A,21X,1A,7X,12A": "Helicopters:": "!"; "Helicopters:"
3180 H_d_$="          MissilesMsl&guns      Guns Air-air Msl&AirMslGnAir Gun&Air"
!ATTACK PROFILE
3183 H_msn$="          Air-grnd Air-air      SEAD"          !HELO MISSION
3186 Rg_msn$(1)="Rg to D.F."
3189 Rg_msn$(2)="Rg to Helo"
3192 Rg_msn$(3)="Rg to SEAD"
3195 PRINT USING "9X,11A,  X,8A,10X,1A,10X,11A, X,8A": "Helo msn      ": H_msn$[B_h
o_msn(1)*8+1;8]; "!"; "Helo msn      ": H_msn$[R_helo_msn(1)*8+1;8]
3198 PRINT USING "21X          ,8A,10X,1A,22X          ,8A": H_msn$[B_helo_msn(2)*8+1
]; "!"; H_msn$[R_helo_msn(2)*8+1;8]
3201 PRINT USING "9X,11A,  X,8A,10X,1A,10X,11A, X,8A": "Atk profile": H_d_$[R_he
_atkprof(1)*8+1;8]; "!"; "Atk profile": H_d_$[R_helo_atkprof(1)*8+1;8]
3204 PRINT USING "21X          ,8A,10X,1A,22X          ,8A": H_d_$[B_helo_atkprof(2)*
1;8]; "!"; H_d_$[R_helo_atkprof(2)*8+1;8]
3207 FOR I=1 TO 2
3210   IF B_helo_msn(I)>0 AND R_helo_msn(I)>0 THEN
3213     PRINT USING "9X,10A,6X,4Z,10X,1A,10X,10A,6X,4Z": Rg_msn$(R_helo_msn(I)
B_atk_rg(I)): "!"; Rg_msn$(R_helo_msn(I)); R_atk_rg(I)
3216   ELSE
3219     IF B_helo_msn(I)>0 AND R_helo_msn(I)<=0 THEN
3222       PRINT USING "9X,10A,6X,4Z,10X,1A,10X,10A,6X,4Z": Rg_msn$(B_helo_msn(I)
): B_atk_rg(I): "!"; "Stndoff Rg": R_atk_rg(I)
3225     ELSE
3228       IF B_helo_msn(I)<=0 AND R_helo_msn(I)>0 THEN
3231         PRINT USING "9X,10A,6X,4Z,10X,1A,10X,10A,6X,4Z": "Stndoff Rg": B_at
rg(I): "!"; Rg_msn$(R_helo_msn(I)); R_atk_rg(I)
3234       ELSE
3237         PRINT USING "9X,10A,6X,4Z,10X,1A,10X,10A,6X,4Z": "Stndoff Rg": B_at
rg(I): "!"; "Stndoff Rg": R_atk_rg(I)
3240         END IF
3243       END IF
3246     END IF

```

Table 6-14. Ground combat code (continued).

```

3249 NEXT J
3252 PRINT USING "9X,5A,14X,D,10X,1A,10X,5A,14X,D";"Cells":B_helo(1,3);"!";"Ce
s":R_helo(1,3)
3255 PRINT USING "28X      ,D,10X,1A,29X      ,D";B_helo(2,3);"!";R_helo(2,3)
3258 PRINT USING "9X,11A, 5X,4Z,10X,1A,10X,11A,5X,4Z";"Entry time":B_helo_dela
"!";"Entry time":R_helo_delay
3261 PRINT USING "9X,11A, 3X,6D,10X,1A,10X,11A,3X,6D";"Entry range":B_helo_rg_
lay;!";"Entry range":R_helo_rg_delay
3264 PRINT USING "9X,6A,12X,2D,10X,1A,10X,6A,12X,2D";"# LCH":B_helo(1,1);"!";
HIND":R_helo(1,1)
3267 PRINT USING "9X,6A,12X,2D,10X,1A,10X,6A,12X,2D";"# AH1S":B_helo(2,1);"!";
HIP":R_helo(2,1)
3270 PRINT USING "9X,6A,12X,2D,10X,1A,10X,6A,12X,2D";"# SCT":B_helo(3,1);"!";
SCT":R_helo(3,1) !END OF CHANGES DWS
3273 !PRINT USING "9X,6A,12X,2D,10X,1A";"# AHIP":B_helo(3,1);"!"; !ROB
3276 !
3279 PRINT USING "39X,1A";"!";
3282 IF B_atk_def$="DEFENDER" THEN
3285 PRINT USING "6X,12A,10X,D,10X,1A";"# Minefields":No_minefields;!";
3288 IF No_minefields>0 THEN
3291 PRINT USING " 9X,6A,8X,6D,10X,1A";"Range:":Minefield(1,1);"!";
3294 IF No_minefields>1 THEN
3297 FOR Minflds=2 TO No_minefields
3300 PRINT USING "23X,6D,10X,1A";Minefield(Minflds,1);"!";
3303 NEXT Minflds
3306 END IF
3309 END IF
3312 ELSE
3315 PRINT USING "39X,1A, 7X,12A,10X,D";"!";"# Minefields":No_minefields
3318 IF No_minefields>0 THEN
3321 PRINT USING "39X,1A,10X,6A,8X,6D";"!";"Range:":Minefield(1,1)
3324 IF No_minefields>1 THEN
3327 FOR Minflds=2 TO No_minefields
3330 PRINT USING "39X,1A,24X,6D";"!";Minefield(Minflds,1)
3333 NEXT Minflds
3336 END IF
3339 END IF
3342 END IF
3345 PRINT " "
3348 PRINT " "
3351 FOR I=1 TO 12 !TEMP EXPERIMENT TO PRINT NAMES ROB
3354 M$=" "
3357 N$=" "
3360 IF I>No_b_unit THEN 3372
3363 ENTER @Pname,B_unit_no(I);M$
3366 ENTER @Unitpath,B_unit_no(I);N(*)
3369 Beff=N(79)
3372 IF I>No_r_unit THEN 3384
3375 ENTER @Rname,R_unit_no(I);N$
3378 ENTER @Unitpath,R_unit_no(I);N(*)
3381 Reff=N(79)
3384 IF I>No_b_unit AND I>No_r_unit THEN 3414

```

Table 6-14. Ground combat code (continued).

```

3387 IF I>No_b_unit THEN
3390 PRINT USING "4X,3D,2X,16A,2X,3D":R_unit_no(I):N$:R_unit_pct(I)*Reff
3393 GOTO 3414
3396 END IF
3399 IF I>No_r_unit THEN
3402 PRINT USING "6X,3D,2X,16A,2X,3D":B_unit_no(I):M$:R_unit_pct(I)*Reff
3405 GOTO 3414
3408 END IF
3411 PRINT USING "6X,3D,2X,16A,2X,3D,15X,3D,2X,16A,2X,3D":B_unit_no(I):M$:B_
it_pct(I)*Reff;R_unit_no(I):N$:R_unit_pct(I)*Reff
3414 NEXT I
3417 RETURN
3420 !
3423 !-----
3426 !
3429 Set_conditions: ! SETUP BATTLEFIELD CONDITIONS
3432 !
3435 ! SET BATTLE START TIME TO NEAREST 30 MINUTE BLOCK
3438 Minute=St_time MOD 100
3441 End_minute=End_time MOD 100
3444 SELECT Minute
3447 CASE 16 TO 45
3450 Minute=30
3453 CASE <16
3456 Minute=0
3459 CASE >45
3462 Minute=100
3465 END SELECT
3468 St_time=INT(St_time/100)*100+Minute
3471 End_time=INT(End_time/100)*100+End_minute
3474 IF St_time=2400 THEN St_time=0
3477 !
3480 !SET DAY/NIGHT STATUS
3483 IF St_time<600 OR St_time>2100 THEN
3486 Day_nite=1 NIGHT=1
3489 ELSE
3492 Day_nite=0 DAY=0
3495 END IF
3498 !
3501 ! SET FORCE EFFECTIVENESS
3504 FOR I=1 TO 70
3507 Init_b_eff=Init_b_eff+Sys_tot(1,I)*Sys_eff(1,I)
3510 Init_r_eff=Init_r_eff+Sys_tot(3,I)*Svs_eff(2,I)
3513 NEXT I
3516 !
3519 ! SET CURRENT FORCE EFFECTIVENESS
3522 B_cbt_eff=Init_b_eff
3525 R_cbt_eff=Init_r_eff
3528 !
3531 ! SET UP FORCE MATRIX
3534 FOR I=1 TO 70
3537 Sys_tot(2,I)=Sys_tot(1,I)

```

Table 6-14. Ground combat code (continued).

```

3540   Sys_tot(4,I)=Sys_tot(3,I)
3543   NEXT I
3546   !
3549   ! SET BATTLE TIME
3552   Btl_time=St_time
3555   !
3558   Max_btl_time=End_time
3561   ! SET BATTLE TERMINATION TIME
3564   !SELECT Btl_time
3567   !CASE 0 TO 599
3570     !Max_btl_time=600
3573   !CASE 600 TO 1199
3576     !Max_btl_time=1200
3579   !CASE 1200 TO 1799
3582     !Max_btl_time=1800
3585   !CASE 1800 TO 2400
3588     !Max_btl_time=2400
3591   !END SELECT
3594   !
3597   ! SET HOUR COUNTER
3600   St_hour=INT(Max_btl_time/100+.1)-6
3603   Battle_hour=INT(St_time/100+.1)
3606   Battle_min=St_time MOD 100
3609   Hh=(Battle_hour-St_hour)*2
3612   IF Battle_min>.1 THEN Hh=Hh+1
3615   !
3618   ! SET BATTLE RANGE
3621   Btl_rg=Init_rg
3624   !
3627   ! SET BATTLE PHASE
3630   IF Btl_rg>Df_rg THEN
3633     Btl_phase=1
3636   ELSE
3639     Btl_phase=2
3642   END IF
3645   !
3648   !SET FIRST BAND FOR DIRECT FIRE
3651   First_bnd=INT(Df_rg/500+.5)
3654   IF First_bnd>6 THEN First_bnd=6
3657   IF First_bnd<=0 THEN First_bnd=1
3660   !
3663   !SET UP HELO ATTACK PROFILE, MISSION & STANDOFF RANGE ARRAYS
3666   FOR I=1 TO 3
3669     J=I
3672     IF I=3 THEN
3675       IF B_helo(3,1)>0 THEN           !SCOUTS DO EXIST
3678         J=1                          !SET SCT'S ATK PROF, MSN AND RANGE FROM HELO 1'S
3681       ELSE                            !ZERO OUT SCT'S ARRAYS
3684         Atk_prof(1,3)=0
3687         Helo_mis(1,3)=0
3690         Stnd_off_rg(1,3)=0
3693         GOTO Rd_sct

```

Table 6-14. Ground combat code (continued).

```

3696     END IF
3699     END IF
3702     Atk_prof(1,I)=B_helo_atkprof(J)
3705     Helo_mis(1,I)=B_helo_msn(J)
3708     Stnd_off_rg(1,I)=B_atk_rg(J)
3711     Rd_sct:IF I=3 THEN
3714         IF R_helo(3,1)>0 THEN           !SCOUTS DO EXIST
3717             J=1                       !SET SCT'S ATK PROF. MSN AND RANGE FROM HELO 1'S
3720             ELSE                       !ZERO OUT SCT'S ARRAYS
3723                 Atk_prof(2,3)=0
3726                 Helo_mis(2,3)=0
3729                 Stnd_off_rg(2,3)=0
3732                 GOTO Nxt_setup
3735             END IF
3738     END IF
3741     Atk_prof(2,I)=R_helo_atkprof(J)
3744     Helo_mis(2,I)=R_helo_msn(J)
3747     Stnd_off_rg(2,I)=R_atk_rg(J)
3750     Nxt_setup:
3753     NEXT I
3756     !
3759     ! SET INDIRECT FIRE MISSION TONNAGES FOR 6-HOUR BATTLE
3762     !
3765     !SET FOR GAMP&CLGP
3768     Gamp_avail=No_gamp*.11
3771     Clgp_avail=No_clgp*.11
3774     !
3777     ! SET FOR ARTILLERY
3780     FOR J=1 TO 7
3783         FOR I=1 TO 5
3786             Bif_msn_tons(J,I)=Bif_ammo(J)*Bif_msn(I)/100
3789             Rif_msn_tons(J,I)=Rif_ammo(J)*Rif_msn(I)/100
3792         NEXT I
3795         B_dsarty_avail(J)=Bif_msn_tons(J,2)
3798         R_dsarty_avail(J)=Rif_msn_tons(J,2)
3801     NEXT J
3804     !
3807     ! SET FOR MLRS
3810     FOR I=1 TO 5
3813         IF I=2 THEN Next_mlrs           ! MLRS NOT A CS WEAPON
3816         IF Bif_msn(2)>=100 THEN Rif_mt
3819         FOR J=12 TO 15
3822             Bif_msn_tons(J,I)=Bif_ammo(J)*Bif_msn(I)/(100-Bif_msn(2))
3825         NEXT J
3828     Rif_mt:IF Rif_msn(2)>=100 THEN Next_mlrs
3831         FOR J=12 TO 15
3834             Rif_msn_tons(J,I)=Rif_ammo(J)*Rif_msn(I)/(100-Rif_msn(2))
3837         NEXT J
3840     Next_mlrs:NEXT I
3843     !
3846     ! SET FOR MORTARS
3849     Int_bmort=Bif_msn(1)+Bif_msn(2)+Bif_msn(3)      ' NO MORTARS IN CFIRE/INT

```

Table 6-14. Ground combat code (continued).

```

3852 Int_rmort=Rif_msn(1)+Rif_msn(2)+Rif_msn(3)
3855 FOR I=1 TO 5
3858   IF I=4 OR I=5 THEN Next_mort
3861   IF Int_bmort=0 THEN Next_mort_r
3864   FOR J=8 TO 11
3867     Bif_msn_tons(J,I)=Bif_ammo(J)*Bif_msn(I)/Int_bmort
3870   NEXT J
3873 Next_mort_r: !
3876   IF Int_rmort=0 THEN Next_mort
3879   FOR J=8 TO 11
3882     Rif_msn_tons(J,I)=Rif_ammo(J)*Rif_msn(I)/Int_rmort
3885   NEXT J
3888 Next_mort:NEXT I
3891 FOR J=8 TO 11
3894   B_dsmort_avail(J-7)=Bif_msn_tons(J,2)
3897   R_dsmort_avail(J-7)=Rif_msn_tons(J,2)
3900 NEXT J
3903 !
3906 ! ZERO SEAD AMMO. NOT EXPLICITLY USED
3909 !FOR I=1 TO 15 !ROB
3912 !Rif_fired(I,3)=0
3915 !Bif_fired(I,3)=0
3918 !NEXT I
3921 !
3924 Rif_ammo_sv=0
3927 Bif_ammo_sv=0
3930 FOR I=1 TO 15
3933   FOR J=1 TO 5
3936     Rif_ammo_sv=Rif_ammo_sv+Rif_msn_tons(I,J)
3939     Bif_ammo_sv=Bif_ammo_sv+Bif_msn_tons(I,J)
3942   NEXT J
3945 NEXT I
3948 !
3951 !SET ARTY MLRS AND MORT CAP FOR MISSION
3954 ! MAX FIRE RATES FOR THIS MISSION
3957 FOR I=1 TO 15
3960   Arty_30min_wt(1,I)=Barty_30min(B_msn(1),I)
3963   Arty_30min_wt(2,I)=Rarty_30min(R_msn(1),I)
3966 NEXT I
3969 !
3972 ! SET DIRECT SUPPORT ARTILLERY/MORTAR PARAMETERS
3975 B_dsmort_brkrng=B_rg_break-100
3978 R_dsmort_brkrng=R_rg_break-100
3981 B_dsarty_brkrng=B_rg_break ! END RANGE FOR CS ARTY SUPPORT
3984 R_dsarty_brkrng=R_rg_break
3987 B_dsarty_start=Ds_start(R_terr) ! START RANGE FOR CS ARTY SUPPORT
3990 R_dsarty_start=Ds_start(B_terr)
3993 !
3996 IF Ds_start(R_terr)<5700 THEN
3999   R_dsmort_start=Ds_start(R_terr)
4002 ELSE
4005   B_dsmort_start=5700

```


Table 6-14. Ground combat code (continued).

```

4008 END IF
4011 !
4014 IF Ds_start(B_terr)<5700 THEN
4017   R_dsmort_start=Ds_start(B_terr)
4020 ELSE
4023   R_dsmort_start=5700
4026 END IF
4029 B_ds_shift=0           ! STATUS OF RE-DEFINE OF FIRING LEVEL
4032 R_ds_shift=0         ! 0=NOT RE-DEFINED
4035 B_mo_shift=0         ! 1=RE-DEFINED
4038 R_mc_shift=0
4041 R_ds_conc_pt=R_dsarty_brkrq+1500
4044 B_ds_conc_pt=B_dsarty_brkrq+1500   ! X-PT AT KNEE OF CS CURVE
4047 B_mo_conc_pt=B_dsarty_brkrq+1500
4050 R_mo_conc_pt=R_dsarty_brkrq+1500
4053 B_ds_conc_level=.5
4056 R_ds_conc_level=.7           ! Y-PT AT KNEE OF CS CURVE
4059 B_mo_conc_level=.5
4062 R_mo_conc_level=.7
4065 B_p30_artyrq=B_dsarty_start
4068 R_p30_artyrq=R_dsarty_start   ! BATTLE RANGE AT END OF PREVIOUS 30 MIN F
4071 B_p30_mortrg=B_dsmort_start
4074 R_p30_mortrg=R_dsmort_start
4077 !
4080 IF Bt_time<600 OR Bt_time>2100 THEN
4083   Day_nite=1   ! CHECK THIS
4086 ELSE
4089   Day_nite=0
4092 END IF
4095 ! READ ADVANCE RATE DATA
4098 IF Atk_def=0 THEN
4101   File=B+4*Day_nite+R_terr
4104 ELSE
4107   File=4*Day_nite+B_terr
4110 END IF
4113 ENTER @Advanpath,File;Advance_rate(*)
4116 !
4119 RETURN
4122 !
4125 !-----
4128 !
4131 Print_sys_out: ! THIS SBR PRINTS OUT SPECIFIED SYSTEMS
4134 !
4137 FOR I=7 TO 70 STEP 7
4140   PRINT USING Fmt1;I-6,"":S(I-6),I-5,"":S(I-5),I-4,"":S(I-4),I-3,"":S
-3),I-2,"":S(I-2),I-1,"":S(I-1),I,"":S(I)
4143 NEXT I
4146 Fmt1:IMAGE 7(2D,1A,4D,1D,2X)
4149 RETURN
4152 !
4155 !-----
4158 !

```

Table 6-14. Ground combat code (continued).

```

4161 Control_battle: ! THIS SBR CONTROLS THE GROUND BATTLE
4164 !
4167 !!PRINT OUT INITIAL SECTOR CONDITIONS
4170 GOSUB Print_init_res
4173 !
4176 ! READ DATA FILES TO BE USED IN 30 MINUTE BATTLE
4179 !
4182 GOSUB Read_files
4185 !
4188 ! START ATTRITION ASSESSMENTS
4191 Start_30min_btl: ! START ATTRITION ASSESSMENTS FOR A 30 MINUTE TIME PERI
4194 !
4197 ! COMPUTE COMBAT EFFECTIVENESS
4200 GOSUB Tally_cbt_eff
4203 !
4206 ! CHECK BREAKPOINT CRITERIA
4209 GOSUB Check_brk_pt
4212 !
4215 ! SET PHASE FOR NEXT 30 MIN BATTLE
4218 IF Break_point=1 OR Break_point=2 THEN Btl_phase=3
4221 IF Break_point=3 THEN GOTO End_battle
4224 !
4227 Continue_btl: ! UPDATE BATTLE TIME.
4230 ! TIME IS SET TO END OF THE 30 MIN PERIOD.
4233 ! SETTING MISSIONS FOR RED AND BLUE
4236 B_ms=1
4239 R_ms=1
4242 !
4245 R_time_print=Btl_time
4248 !
4251 Btl_time=Btl_time+30
4254 Int_minute=Btl_time MOD 100
4257 IF Int_minute=60 THEN
4260 Btl_time=Btl_time+40 ! SET TIME TO NEXT WHOLE HOUR AT 60 MINS
4263 END IF
4266 IF Btl_time<600 OR Btl_time>2100 THEN
4269 Day_nite=1
4272 ELSE
4275 Day_nite=0
4278 END IF
4281 Time_seg=Time_seg+1
4284 !
4287 PRINT USING "@,#"
4290 PRINT USING "1X,45A";"-----"
4293 IF Btl_time<2430 THEN
4296 PRINT USING "33A,4Z,4A,4Z,2A";"! SIGNIFICANT BATTLE EVENTS FROM ";B_tir
print;" TO ";Btl_time;" !"
4299 ELSE
4302 PRINT USING "33A,4Z,4A,4Z,2A";": SIGNIFICANT BATTLE EVENTS FROM ";B_tir
print-2400;" TO ";Btl_time-2400;":"
4305 END IF
4308 PRINT USING "1X,45A";"-----"

```

Table 6-14. Ground combat code (continued).

```

4311 '
4314 ! SET ATTACK HELICOPTER ARRIVALS FOR RED/BLUE
4317 GOSUB Helo_arrive
4320 !
4323 PRINT USING "/"
4326 IF Vis=4 THEN
4329 PRINT " HELICOPTERS NOT FLYING ON 1km DAY"
4332 ELSE
4335 PRINT " BLUE HELICOPTERS ATTACKING RED FORCE"
4338 PRINT USING Fmt80;" LCH";Bah1
4341 PRINT USING Fmt80;"AH1S";Bah2
4344 PRINT USING Fmt80;" SCT";Bsct
4347 ! PRINT USING Fmt80;"AHIP";Bsct
4350 PRINT
4353 PRINT " RED HELICOPTERS ATTACKING BLUE FORCE"
4356 PRINT USING Fmt80;"HIND";Rah1
4359 PRINT USING Fmt80;" HIP";Rah2
4362 PRINT USING Fmt80;" SCT";Rsct
4365 END IF
4368 Fmt80:IMAGE 6X,4A,2X,3D.D
4371 ! SET INCOMING INDIRECT FIRE FOR RED/BLUE
4374 GOSUB Arty_arrive
4377 !
4380 !
4383 FOR I=1 TO 15
4386 Saty(I)=0
4389 Tot_volley(I)=0
4392 FOR J=1 TO 5
4395 Volley(I,J)=Bif_fired(I,J)/A_wt(1,I)
4398 Saty(I)=Saty(I)+Bif_msn_tons(I,J)
4401 NEXT J
4404 Tot_volley(I)=Tot_arty(1,I)/A_wt(1,I)
4407 NEXT I
4410 B_or_r_$="BLUE"
4413 B_or_r=1
4416 Label$="ARTY ARTY ARTY ARTY ARTY ARTY ARTY MORT MORT MORT MORT MLRS MLRS
RS MLRS"
4419 GOSUB Print_volleys
4422 PRINT
4425 PRINT " BLUE PGM ROUNDS: CLGP GAMP"
4428 PRINT USING "6X,9A,6X,6D.D,11X,6D.D";"FIRED ";Clgp_msns/.11;Gamp_msns:
mo_wt(1,28) !?? STILL USE 28
4431 PRINT USING "6X,9A,6X,6D.D,11X,6D.D";"AVAILABLE";Clgp_avail/.11;Gamp_ava1
Ammo_wt(1,28) !??STILL USE 28
4434 '
4437 IF B_ds_shift=1 AND Atk_def=0 THEN PRINT USING "/,70A";" BLUE FINAL PRO
CTIVE ARTILLERY BEING APPLIED"
4440 IF B_ds_shift=1 AND Atk_def=1 THEN PRINT USING "/,70A";" BLUE FINAL ART
LERY BARRAGE ON OBJECTIVE BEING APPLIED"
4443 IF B_mo_shift=1 AND Atk_def=0 THEN PRINT USING "/,67A";" BLUE FINAL PRO
CTIVE MORTAR BEING APPLIED"
4446 IF B_mo_shift=1 AND Atk_def=1 THEN PRINT USING "/,67A";" BLUE FINAL MOF

```

Table 6-14. Ground combat code (continued).

```

R BARRAGE ON OBJECTIVE BEING APPLIED"
4449 FOR I=1 TO 15
4452   Saty(I)=0
4455   Tot_volley(I)=0
4458   FOR J=1 TO 5
4461     Volley(I,J)=Rif_fired(I,J)/A_wt(2,I)
4464     Saty(I)=Saty(I)+Rif_msn_tons I,J)
4467   NEXT J
4470   Tot_volley(I)=Tot_arty(2,I)/A_wt(2,I)
4473 NEXT I
4476 B_or_r_$="RED"
4479 B_or_r=2
4482 Label$="ARTY ARTY ARTY ARTY ARTY ARTY ARTY MORT MORT MORT MORT MRL MRL
L MRL "
4485 GOSUB Print_volleys
4488 IF R_ds_shift=1 AND Atk_def=1 THEN PRINT USING "/,70A": " RED FINAL PRO
CTIVE ARTILLERY BEING APPLIED"
4491 IF R_ds_shift=1 AND Atk_def=0 THEN PRINT USING "/,70A": " RED FINAL ART
LERY BARRAGE ON OBJECTIVE BEING APPLIED"
4494 IF R_mo_shift=1 AND Atk_def=1 THEN PRINT USING "/,67A": " RED FINAL PRO
CTIVE MORTAR BEING APPLIED"
4497 IF R_mo_shift=1 AND Atk_def=0 THEN PRINT USING "/,67A": " RED FINAL MOF
R BARRAGE ON OBJECTIVE BEING APPLIED"
4500 ! CALCULATE AMOUNT OF ADVANCE BY ATTACKER
4503 GOSUB Calc_movement
4506 ! CHECK FOR MINEFIELDS
4509 GOSUB Mine_encounter
4512 !ADJUST MOVEMENT FOR MINES
4515 IF Mine_hit<>0 AND Amt_of_advance<>0 THEN
4518 !CALCULATE MOVEMENT TIME TO EDGE OF MINEFIELD
4521 Edge_time=(Btl_rg-Minefield(Mine_hit,1))/Amt_of_advance*30
4524 IF Edge_time+Mine_delay<30 THEN
4527   Amt_of_advance=(1-Mine_delay/30)*Amt_of_advance
4530   Mine_delay=0
4533 ELSE
4536   Amt_of_advance=Btl_rg-Minefield(Mine_hit,1)
4539   Mine_delay=Mine_delay-(30-Edge_time)
4542 END IF
4545 END IF
4548 !
4551 ! CHECK FOR DIRECT FIRE
4554 Check_dir_fire: !
4557 IF Btl_phase=3 THEN Calc_btl_rg
4560 IF Btl_rg-Amt_of_advance<=Df_rg THEN
4563   Btl_phase=2
4566   IF First_df=0 THEN
4569     Int_advance=Btl_rg-Df_rg
4572     Int_btl_rg=(Amt_of_advance-Int_advance)
4575     Cur_bnd=First_bnd
4578     SELECT Int_btl_rg
4581     CASE <250
4584       First_df=1

```

Table 6-14. Ground combat code (continued).

```

4587      Df_500_bds=1
4590      Amt_of_advance=Int_advance
4593      CASE 250 TO 750
4596          First_df=1
4599          Df_500_bds=1
4602          Amt_of_advance=Int_advance+500
4605      CASE >750
4608          First_df=1
4611          Df_500_bds=2
4614          Amt_of_advance=Int_advance+1000
4617      END SELECT
4620      ELSE
4623          Int_bt1_rg=Amt_of_advance
4626          SELECT Int_bt1_rg
4629          CASE <250
4632              Amt_of_advance=0
4635              Df_500_bds=1
4638          CASE 250 TO 750
4641              Amt_of_advance=500
4644              Df_500_bds=1
4647          CASE >750
4650              Amt_of_advance=1000
4653              Df_500_bds=2
4656          END SELECT
4659      END IF
4662      ELSE
4665          Btl_phase=1
4668      END IF
4671      !
4674      Calc_bt1_rg: !
4677      IF Btl_phase=3 THEN
4680          SELECT Atk_def
4683          CASE 0          ! RED ATK
4686              IF Break_point=2 THEN Amt_of_advance=0
4689          CASE 1          ! BLUE ATK
4692              IF Break_point=1 THEN Amt_of_advance=0
4695          END SELECT
4698      END IF
4701      !
4704      Btl_rg=MAX(Btl_rg-Amt_of_advance,0)
4707      !
4710      GOSUB Print_eff
4713      !
4716      !
4719      SELECT Btl_phase
4722      CASE 1
4725          IF Btl_time<2430 THEN
4728              PRINT USING Fmt11;"ATTACKER FORCES CLOSING",Btl_time," HRS","B/EFF: "
urr_b_pt,"R/EFF: ",Curr_r_pt
4731          ELSE
4734              PRINT USING Fmt11;"ATTACKER FORCES CLOSING",Btl_time-2400," HRS","B/F
: ",Curr_b_pt,"R/EFF: ",Curr_r_pt

```

Table 6-14. Ground combat code (continued).

```

4737 END IF
4740 PRINT USING "19X,15A,6D,5X,14A,6D":"INITIAL RANGE: ",Btl_rg+Amt_of_adva
e,"CURRENT RANGE: ",Btl_rg
4743 GOSUB Phase1_btl
4746 Flag_30min=1
4749 CASE 2
4752 IF Btl_time<2430 THEN
4755 PRINT USING Fmt11;"CLOSE DF BATTLE UNDERWAY",Btl_time," HRS","B/EFF:
Curr_b_pt,"R/EFF: ",Curr_r_pt
4758 ELSE
4761 PRINT USING Fmt11;"CLOSE DF BATTLE UNDERWAY",Btl_time-2400," HRS","B/
F: ",Curr_b_pt,"R/EFF: ",Curr_r_pt
4764 END IF
4767 PRINT USING "19X,15A,6D,5X,14A,6D":"INITIAL RANGE: ",Btl_rg+Amt_of_adva
e,"CURRENT RANGE: ",Btl_rg
4770 Fmt11:IMAGE /,3X,25A,2X,4Z,4A,4X,7A,1D.2D,3X,7A,1D.2D
4773 GOSUB Phase2_btl
4776 Flag_30min=1
4779 CASE 3
4782 GOSUB Phase3_btl
4785 Flag_30min=2
4788 END SELECT
4791 ! COMPUTE COMBAT EFFECTIVENESS
4794 !GOSUB Tally_cbt_eff
4797 !GOSUB Print_eff
4800 !PRINT " "; "BEFF: ";INT((Curr_b_pt+.005)*100);"%". "REFF: ";INT((Curr_r
t+.005)*100);"%
4803 GOTO Start_30min_btl
4806 !
4809 !
4812 End_battle:RETURN
4815 !
4818 !-----
4821 Print_eff: !
4824 R_eff_pt=0
4827 B_eff_pt=0
4830 FOR I=i TO 70
4833 B_eff_pt=B_eff_pt+Sys_tot(2,I)*Sys_eff(1,I)
4836 R_eff_pt=R_eff_pt+Sys_tot(4,I)*Sys_eff(2,I)
4839 NEXT I
4842 IF Init_b_eff=0 THEN
4845 Curr_b_pt=0
4848 ELSE
4851 Curr_b_pt=B_eff_pt/Init_b_eff
4854 END IF
4857 IF Init_r_eff=0 THEN
4860 Curr_r_pt=0
4863 ELSE
4866 Curr_r_pt=R_eff_pt/Init_r_eff
4869 END IF
4872 RETURN
4875 !

```

Table 6-14. Ground combat code (continued).

```

4878 !-----
4881 !
4884 Print_volleys: !
4887 PRINT
4890 PRINT
4893 PRINT USING Pv_f3;B_or_r_#;" ARTILLERY VOLLEYS FIRED ":"Tons":"Tons"
4896 Pv_f3:IMAGE 3X,4A,25A,29X,4A,8X,4A
4899 PRINT USING Pv_f1:"P/CP";" CS ":"SEAD";" CF ":" INT":"TOTAL":"CONSUMED":
AILE"
4902 Pv_f1:IMAGE 9X,5(4A,3X),2X,5A,8X,8A,4X,9A
4905 FOR Wv=1 TO 15
4908 IF Saty(Wv)+Tot_arty(B_or_r,Wv)>0 THEN !If tons consumed or avail not
then print out line
4911 PRINT USING Pv_f2;Label$(Wv*5-4,Wv*5),Volley(Wv,1),Volley(Wv,2),Volley
Wv,3),Volley(Wv,4),Volley(Wv,5),Tot_volley(Wv),Tot_arty(B_or_r,Wv),Saty(Wv)
4914 END IF
4917 NEXT Wv
4920 Pv_f2:IMAGE 3X,5A,5(5D,2X),2X,6D,7X,6D.D,4X,8D.D
4923 RETURN
4926 !
4929 !-----
4932 !
4935 Print_init_res: ! THIS SBR PRINTS OUT INITIAL UNIT STATUS
4938 !
4941 PRINT USING "@,#,13A,5X,11A,2D,6X,8A,3D":"GROUND COMBAT"."GAME TURN: ".T
,"SECTOR: ".Sector
4944 GOSUB Set_print
4947 RETURN ! TEMPORARY DISABLING OF THIS SUB-ROUTINE
4950 PRINT USING "//,11A,29X,10A":"BLUE UNITS:", "RED UNITS:"
4953 FOR I=0 TO 9 STEP 3
4956 FOR J=1 TO 3
4959 PRINT USING Fmt2;B_unit_no(I+J),B_unit_pct(I+J)
4962 NEXT J
4965 Fmt2:IMAGE 3D,1X,3D,3X,#
4968 PRINT USING "7X,#"
4971 FOR J=1 TO 3
4974 PRINT USING Fmt3;R_unit_no(I+J),R_unit_pct(I+J)
4977 NEXT J
4980 Fmt3:IMAGE 3X,3D,1X,3D,#
4983 PRINT USING "/"
4986 NEXT I
4989 PRINT USING "////,13A":"BLUE SYSTEMS:"
4992 FOR I=1 TO 70
4995 S(I)=Sys_tot(2,I)
4998 NEXT I
5001 GOSUB Print_sys_out
5004 PRINT USING "//,12A":"RED SYSTEMS:"
5007 FOR I=1 TO 70
5010 S(I)=Sys_tot(4,I)
5013 NEXT I
5016 GOSUB Print_sys_out
5019 GOSUB Set_print

```

Table 6-14. Ground combat code (continued).

```

5022 PRINT USING "@,*,2X,26A,///  
5025 RETURN  
5028 !  
5031 !-----  
5034 !  
5037 Print_fin_res: ! THIS SBR PRINTS OUT FINAL BATTLE RESULTS  
5040 PRINT  
5043 PRINT  
5046 PRINT  
5049 PRINT "-----"  
5052 IF Btl_time<2430 THEN  
5055 PRINT USING "17A,4Z,2A";"! BATTLE ENDS AT ":Btl_time;" !"  
5058 ELSE  
5061 PRINT USING "17A,4Z,2A";": BATTLE ENDS AT ":Btl_time-2400;": "  
5064 END IF  
5067 PRINT "-----"  
5070 !  
5073 PRINT USING "@,*,29A";"RED KILLER--BLUE VICTIM TABLE"  
5076 PRINT USING "///,6A,14X,48A";"VICTIM", "<----- KILLER -----  
----->"  
5079 PRINT USING Fmt30;" SYS", "START", "D/F", "I/F", "PGM", "A/H", "INF", "MIN", "END  
5082 Fmt30: IMAGE 4A,5X,5A,7(6X,3A)  
5085 FOR I=1 TO 70  
5088 IF Sys_tot(1,I)<=0 THEN Skip_prt1  
5091 PRINT USING Fmt31;B_veh*((I-1)*5+1;5],Sys_tot(1,I),Kv_b(1,I),Kv_b(2,I),  
_b(3,I),Kv_b(4,I),Kv_b(5,I),Kv_b(6,I),Sys_tot(2,I)  
5094 Skip_prt1:NEXT I  
5097 Fmt31: IMAGE 5A,8(3X,4D,1D)  
5100 PRINT USING "////,29A";"BLUE KILLER--RED VICTIM TABLE"  
5103 PRINT USING "///,6A,14X,48A";"VICTIM", "<----- KILLER -----  
----->"  
5106 PRINT USING Fmt30;" SYS", "START", "D/F", "I/F", "PGM", "A/H", "INF", "MIN", "END  
5109 FOR I=1 TO 70  
5112 IF Sys_tot(3,I)<=0 THEN Skip_prt2  
5115 PRINT USING Fmt31;R_veh*((I-1)*5+1;5],Sys_tot(3,I),Kv_r(1,I),Kv_r(2,I),  
_r(3,I),Kv_r(4,I),Kv_r(5,I),Kv_r(6,I),Sys_tot(4,I)  
5118 Skip_prt2:NEXT I  
5121 !  
5124 !!PRINT OUT HELICOPTER RESULTS (SORTIES,LOSSES,AMMO/FUEL EXPENDED)  
5127 !  
5130 PRINT USING "@,*,27A";"ATTACK HELICOPTER RESULTS:"  
5133 PRINT USING Fmt32;"TYPE", "#COMMITTED", "#KILLED", "#SORTIES"  
5136 PRINT USING Fmt33;" LCH", B_helo(1,1),B_helo(1,2),B_helo(1,6)  
5139 PRINT USING Fmt33;"AH1S", B_helo(2,1),B_helo(2,2),B_helo(2,6)  
5142 PRINT USING Fmt33;"SCTS", B_helo(3,1),B_helo(3,2),B_helo(3,6)  
5145 PRINT USING Fmt34;"HIND", R_helo(1,1),R_helo(1,2),R_helo(1,6)  
5148 PRINT USING Fmt33;"HIP ", R_helo(2,1),R_helo(2,2),R_helo(2,6)  
5151 PRINT USING Fmt33;"SCTS", R_helo(3,1),R_helo(3,2),R_helo(3,6)  
5154 Fmt32: IMAGE ///,4A,3X,10A,4X,7A,(4X,8A),//  
5157 Fmt33: IMAGE 4A,6X,3D,1D,2(7X,3D,1D)  
5160 Fmt34: IMAGE //,4A,6X,3D,1D,2(7X,3D,1D)  
5163 RETURN 'DISABLE LER PRINTOUT

```


Table 6-14. Ground combat code (continued).

```

5166 FOR J=1 TO 2
5169   Sys_dfl(J)=Sys_tot(J,5)
5172   FOR I=1 TO 3
5175     Sys_dfl(J)=Sys_dfl(J)+Sys_tot(J,I)
5178   NEXT I
5181   Sys_dfs(J)=Sys_tot(J,4)
5184   FOR I=7 TO 9
5187     Sys_dfs(J)=Sys_dfs(J)+Sys_tot(J,I)
5190   NEXT I
5193 NEXT J
5196 FOR J=3 TO 4
5199   Sys_dfl(J)=Sys_tot(J,6)+Sys_tot(J,7)+Sys_tot(J,9)
5202   FOR I=1 TO 3
5205     Sys_dfl(J)=Sys_dfl(J)+Sys_tot(J,I)
5208   NEXT I
5211   Sys_dfs(J)=Sys_tot(J,4)+Sys_tot(J,5)+Sys_tot(J,8)
5214 NEXT J
5217 FOR J=1 TO 4
5220   Sys_if(J)=Sys_tot(J,11)+Sys_tot(J,13)+Sys_tot(J,14)
5223   Sys_ad(J)=Sys_tot(J,12)+Sys_tot(J,15)+Sys_tot(J,16)+Sys_tot(J,17)
5226   Sys_sum(J)=Sys_dfl(J)+Sys_dfs(J)+Sys_if(J)+Sys_ad(J)
5229 NEXT J
5232 Sys_dfl(7)=Kv_b(4,1)+Kv_b(4,2)+Kv_b(4,3)+Kv_b(4,5)
5235 Sys_dfs(7)=Kv_b(4,4)+Kv_b(4,7)+Kv_b(4,8)+Kv_b(4,9)
5238 Sys_if(7)=Kv_b(4,11)+Kv_b(4,13)+Kv_b(4,14)
5241 Sys_ad(7)=Kv_b(4,12)+Kv_b(4,15)+Kv_b(4,16)+Kv_b(4,17)
5244 Sys_sum(7)=Sys_dfl(7)+Sys_dfs(7)+Sys_if(7)+Sys_ad(7)
5247 Sys_dfl(5)=Sys_dfl(1)-Sys_dfl(2)
5250 Sys_dfs(5)=Sys_dfs(1)-Sys_dfs(2)
5253 Sys_if(5)=Sys_if(1)-Sys_if(2)
5256 Sys_ad(5)=Sys_ad(1)-Sys_ad(2)
5259 Sys_sum(5)=Sys_sum(1)-Sys_sum(2)
5262 Sys_dfl(6)=Sys_dfl(3)-Sys_dfl(4)
5265 Sys_dfs(6)=Sys_dfs(3)-Sys_dfs(4)
5268 Sys_if(6)=Sys_if(3)-Sys_if(4)
5271 Sys_ad(6)=Sys_ad(3)-Sys_ad(4)
5274 Sys_sum(6)=Sys_sum(3)-Sys_sum(4)
5277 IF Sys_sum(1)=0 THEN
5280   Cfr_b=1
5283 ELSE
5286   IF Sys_sum(3)=0 THEN
5289     Cfr_b=1
5292   ELSE
5295     Cfr_b=Sys_sum(3)/Sys_sum(1)
5298   END IF
5301 END IF
5304 Cfr_r=1/Cfr_b
5307 Cfr_bwo=Cfr_b
5310 IF Sys_dfl(1)=0 THEN
5313   Cfr_bdf1=0
5316   Ler_bdf1=0
5319   Fer_bdf1=0

```

Table 6-14. Ground combat code (continued).

```

5322 ELSE
5325   Cfr_bdf1=Sys_dfl(3)/Sys_dfl(1)
5328   IF Sys_dfl(5)=0 THEN
5331     Ler_bdf1=0
5334   ELSE
5337     Ler_bdf1=Sys_dfl(6)/Sys_dfl(5)
5340   END IF
5343   IF Cfr_bdf1=0 THEN
5346     Fer_bdf1=0
5349   ELSE
5352     Fer_bdf1=Ler_bdf1/Cfr_bdf1
5355   END IF
5358 END IF
5361 IF Sys_dfs(1)=0 THEN
5364   Cfr_bdfs=0
5367   Ler_bdfs=0
5370   Fer_bdfs=0
5373 ELSE
5376   Cfr_bdfs=Sys_dfs(3)/Sys_dfs(1)
5379   IF Sys_dfs(5)=0 THEN
5382     Ler_bdfs=0
5385   ELSE
5388     Ler_bdfs=Sys_dfs(6)/Sys_dfs(5)
5391   END IF
5394   IF Cfr_bdfs=0 THEN
5397     Fer_bdfs=0
5400   ELSE
5403     Fer_bdfs=Ler_bdfs/Cfr_bdfs
5406   END IF
5409 END IF
5412 IF Sys_sum(5)=0 THEN
5415   Ler_b=0
5418 ELSE
5421   Ler_b=Sys_sum(6)/Sys_sum(5)
5424 END IF
5427 IF Ler_b=0 THEN
5430   Ler_r=0
5433 ELSE
5436   Ler_r=1/Ler_b
5439 END IF
5442 Sysum57=Sys_sum(5)-Sys_sum(7)
5445 IF Sysum57=0 THEN
5448   Ler_bwo=0
5451 ELSE
5454   Ler_bwo=Sys_sum(6)/(Sys_sum(5)-Sys_sum(7))
5457 END IF
5460 Fer_b=Ler_b/Cfr_b
5463 Fer_r=Ler_r/Cfr_r
5466 Fer_bwo=Ler_bwo/Cfr_bwo
5469 PRINT
5472 PRINT
5475 PRINT

```

Table 6-14. Ground combat code (continued).

```

5478 PRINT
5481 PRINT USING "20X,27A";"DIME SECTOR-BATTLE ANALYSIS"
5484 PRINT USING "/",22X,10A,2D,8A,3D";"GAME 2, CI".Turn.". SECTOR",Sector
5487 PRINT USING "/",24X,4A,19X,3A";"BLUE"."RED"
5490 IF Sys_sum(7)>0 THEN
5493 PRINT USING "34X,2A";"BY"
5496 PRINT USING "16X,5A,3X,3A,3X,10A,5X,18A";"START","END"."LOSS HIND"."ST
T END LOSS"
5499 PRINT USING Fmt35;"DFLR",Sys_dfl(1),Sys_dfl(2),Sys_dfl(5),Sys_dfl(7),Sy
dfl(3),Sys_dfl(4),Sys_dfl(6)
5502 PRINT USING Fmt35;"DFSR",Sys_dfs(1),Sys_dfs(2),Sys_dfs(5),Sys_dfs(7),Sy
dfs(3),Sys_dfs(4),Sys_dfs(6)
5505 PRINT USING Fmt35;" IF ",Sys_if(1),Sys_if(2),Sys_if(5),Sys_if(7),Sys_if
),Sys_if(4),Sys_if(6)
5508 PRINT USING Fmt35;" AD ",Sys_ad(1),Sys_ad(2),Sys_ad(5),Sys_ad(7),Sys_ad
),Sys_ad(4),Sys_ad(6)
5511 PRINT
5514 PRINT USING Fmt35;"SUM:",Sys_sum(1),Sys_sum(2),Sys_sum(5),Sys_sum(7),Sy
sum(3),Sys_sum(4),Sys_sum(6)
5517 PRINT USING "//,20X,8A,2X,10A";"W/D HIND","DFLR DFSR"
5520 PRINT USING Fmt37;"CFR = ",Cfr_b,Cfr_bwo,Cfr_bdf1,Cfr_bdfs,"CFR = ",Cfr
5523 PRINT USING Fmt37;"LER = ",Ler_b,Ler_bwo,Ler_bdf1,Ler_bdfs,"LER = ",Ler
5526 PRINT USING Fmt37;"FER = ",Fer_b,Fer_bwo,Fer_bdf1,Fer_bdfs,"FER = ",Fer
5529 ELSE
5532 PRINT USING "/",16X,5A,3X,3A,3X,4A,11X,18A";"START","END","LOSS","START
END LOSS"
5535 PRINT USING Fmt36;"DFLR",Sys_dfl(1),Sys_dfl(2),Sys_dfl(5),Sys_dfl(3),Sy
dfl(4),Sys_dfl(6)
5538 PRINT USING Fmt36;"DFSR",Sys_dfs(1),Sys_dfs(2),Sys_dfs(5),Sys_dfs(3),Sy
dfs(4),Sys_dfs(6)
5541 PRINT USING Fmt36;" IF ",Sys_if(1),Sys_if(2),Sys_if(5),Sys_if(3),Sys_if
),Sys_if(6)
5544 PRINT USING Fmt36;" AD ",Sys_ad(1),Sys_ad(2),Sys_ad(5),Sys_ad(3),Sys_ad
),Sys_ad(6)
5547 PRINT
5550 PRINT USING Fmt36;"SUM:",Sys_sum(1),Sys_sum(2),Sys_sum(5),Sys_sum(3),Sy
sum(4),Sys_sum(6)
5553 PRINT USING "//,30X,10A";"DFLR DFSR"
5556 PRINT USING Fmt38;"CFR = ",Cfr_b,Cfr_bdf1,Cfr_bdfs,"CFR = ",Cfr_r
5559 PRINT USING Fmt38;"LER = ",Ler_b,Ler_bdf1,Ler_bdfs,"LER = ",Ler_r
5562 PRINT USING Fmt38;"FER = ",Fer_b,Fer_bdf1,Fer_bdfs,"FER = ",Fer_r
5565 END IF
5568 Fmt35: IMAGE 10X,4A,2(1X,4D.1D),2(1X,3D.1D),4X,2(4D.1D.1X),3D.1D
5571 Fmt36: IMAGE 10X,4A,2(1X,4D.1D),1X,3D.1D,10X,2(4D.1D.1X),3D.1D
5574 Fmt37: IMAGE 8X,6A,3D.2D,3X,3D.2D,1X,3D.2D,1X,3D.2D,8X,6A,3D.2D
5577 Fmt38: IMAGE 8X,6A,3D.2D,9X,3D.2D,1X,3D.2D,8X,6A,3D.2D
5580 !
5583 RETURN
5586 !
5589 !-----
5592 Read_files: ! THIS SBR READS DATA FILES USED IN 30 MINUTE BATTLES
5595 Dcdisk$=":9134,704,0"

```

Table 6-14. Ground combat code (continued).

```

5598 !
5601 !*****!
5604 ! READ MINE FILE !
5607 !*****!
5610 IF No_minefields>0 THEN
5613 ASSIGN @Pmine TO "MINE_FRCT"&Dcdisk$
5616 ENTER @Pmine,1;Mine_frct(*)
5619 ASSIGN @Pmine TO *
5622 END IF
5625 !*****!
5628 ! READ INFANTRY FILES !
5631 !*****!
5634 ASSIGN @Pcond TO "CONVERT_D"&Dcdisk$
5637 ENTER @Pcond,1;Convertd(*)
5640 ASSIGN @Pcond TO *
5643 !
5646 ASSIGN @Pcona TO "CONVERT_A"&Dcdisk$
5649 ENTER @Pcona,1;Converta(*)
5652 ASSIGN @Pcona TO *
5655 !
5658 !LOAD CLASSIFIED FIREPOWER SCORES
5661 ASSIGN @P TO "FPSI"&Dcdisk$
5664 ENTER @P,1;Fpsb(*)
5667 ENTER @P,2;Fpsr(*)
5670 ASSIGN @P TO *
5673 !
5676 !*****!
5679 ! READ ARTILLERY FILES !
5682 !*****!
5685 ! THIS REDUCES TOTAL AREA TO ONLY THAT AREA TASK IS TARGETED AGAINST
5688 ASSIGN @Parband TO "RD_AR_BAND"&Dcdisk$
5691 ENTER @Parband,1;R_area_band(*) ! (task)
5694 ASSIGN @Parband TO *
5697 !
5700 ASSIGN @Parband TO "BL_AR_BAND"&Dcdisk$
5703 ENTER @Parband,1;B_area_band(*) ! (task)
5706 ASSIGN @Parband TO *
5709 !
5712 ASSIGN @Pdspmsk TO "RD_DSP_MSK"&Dcdisk$
5715 ENTER @Pdspmsk,1;R_disprsn_mask(*) ! (PHASE,MSN)
5718 ASSIGN @Pdspmsk TO *
5721 !
5724 ASSIGN @Pdspmsk TO "BL_DSP_MSK"&Dcdisk$
5727 ENTER @Pdspmsk,1;B_disprsn_mask(*) ! (PHASE,MSN)
5730 ASSIGN @Pdspmsk TO *
5733 !
5736 ! MASK FOR TARGETS
5739 ! THIS ALLOWS SELECTIVE TARGETING FOR EACH TASK
5742 ASSIGN @Ptgtmsk TO "RD_TGT_MSK"&Dcdisk$
5745 ENTER @Ptgtmsk,1;R_tgt_mask(*) ! (TASK,TGT ELM)
5748 ASSIGN @Ptgtmsk TO *
5751 !

```

Table 6-14. Ground combat code (continued).

```

5754 ASSIGN @Ptgtmsk TO "BL_TGT_MSK"&Dcdisk$
5757 ENTER @Ptgtmsk,1;B_tgt_mask(*)      (TASK,TGT ELM)
5760 ASSIGN @Ptgtmsk TO *
5763 !
5766 ! THIS IS INDIVIDUAL RD OR LCHR LOAD PKGD WT IN TONS
5769 ASSIGN @Pround TO "BL_ROUNDWT"&Dcdisk$
5772 ENTER @Pround,1;B_rd_wt(*)      ! (TYPE)
5775 ASSIGN @Pround TO *
5778 !
5781 ASSIGN @Pround TO "RD_ROUNDWT"&Dcdisk$
5784 ENTER @Pround,1;R_rd_wt(*)      ! (TYPE)
5787 ASSIGN @Pround TO *
5790 !
5793 ! PERCENT OF PERSONNEL PRONE
5796 ASSIGN @Ppsnpst TO "RD_PSN_PST"&Dcdisk$
5799 ENTER @Ppsnpst,1;R_psnl_posture(*)
5802 ASSIGN @Ppsnpst TO *
5805 !
5808 ASSIGN @Ppsnpst TO "BL_PSN_PST"&Dcdisk$
5811 ENTER @Ppsnpst,1;B_psnl_posture(*)      ! (%prone)(1st volley, later volley
5814 ASSIGN @Ppsnpst TO *
5817 !
5820 ASSIGN @Ptle TO "TLE"&Dcdisk$
5823 ENTER @Ptle,1;Tle(*)      ! Target Loc Error(task)
5826 ASSIGN @Ptle TO *
5829 !*****!
5832 ! READ SMOKE FILES !
5835 !*****!
5838 !
5841 ASSIGN @Pawpp TO "AMWTPP"&Dcdisk$
5844 ENTER @Pawpp,1;Amwtp(*)      !WT. IN LBS OF 1 ROUND FOR ARTY & MORT BY
IT TYPE
5847 ASSIGN @Pawpp TO *
5850 !
5853 ASSIGN @Pprof TO "IROF"&Dcdisk$
5856 ENTER @Pprof,1;Irof(*)      ! RATE OF FIRE FOR ARTY & MORT BY TYPE OF UN
5859 ASSIGN @Pprof TO *
5862 !*****!
5865 ! READ DIRECT FIRE FILES !
5868 !*****!
5871 !
5874 ! READS IN SENSOR DATA FOR 70 TARGETS VISIBLE THROUGH SMOKE
5877 ASSIGN @Psen TO "BL_SEN_DAY"&Dcdisk$
5880 ENTER @Psen,1;B_sen_d(*)
5883 ASSIGN @Psen TO *
5886 !
5889 ASSIGN @Psen TO "BL_SEN_NIT"&Dcdisk$
5892 ENTER @Psen,1;B_sen_n(*)
5895 ASSIGN @Psen TO *
5898 !
5901 ASSIGN @Psen TO "RD_SEN_DAY"&Dcdisk$
5904 ENTER @Psen,1;R_sen_d(*)

```

Table 6-14. Ground combat code (continued).

```

5907 ASSIGN @Psen TO *
5910 !
5913 ASSIGN @Psen TO "RD_SEN_NIT"&Dcdisk$
5916 ENTER @Psen,1;R_sen_n(*)
5919 ASSIGN @Psen TO *
5922 !
5925 !ENTER CATEGORY FILES
5928 ASSIGN @Path1 TO "BH_CAT"&Dcdisk$
5931 ASSIGN @Path2 TO "RD_CAT"&Dcdisk$
5934 ENTER @Path1,1;B_cat(*)
5937 ENTER @Path2,1;R_cat(*)
5940 !
5943 !ENTER AMMO WEIGHTS
5946 ASSIGN @Path1 TO "BH_DFAMO"&Dcdisk$
5949 ASSIGN @Path2 TO "RD_DFAMO"&Dcdisk$
5952 ENTER @Path1,1;B_ammo_wt(*)
5955 ENTER @Path1,3;Sen_ptr(*)          !READ BLUE SENSOR PTRS
5958 ENTER @Path1,4;Mun_ptr(*)        !READ BLUE MUNIT PTRS
5961 FOR I=1 TO 20
5964   Df_sen_ptr(1,I)=Sen_ptr(I)
5967   Df_muni_ptr(1,I)=Mun_ptr(I)
5970 NEXT I
5973 ENTER @Path2,1;R_ammo_wt(*)
5976 ENTER @Path2,3;Sen_ptr(*)        !READ RED  SENSOR PTRS
5979 ENTER @Path2,4;Mun_ptr(*)        !READ RED  MUNIT PTRS
5982 FOR I=1 TO 20
5985   Df_sen_ptr(2,I)=Sen_ptr(I)
5988   Df_muni_ptr(2,I)=Mun_ptr(I)
5991 NEXT I
5994 ASSIGN @Path1 TO *
5997 ASSIGN @Path2 TO *
6000 !*****!
6003 !  READ PGM FILES  !
6006 !*****!
6009 !
6012 ASSIGN @Ptgtval TO "TGT_VALS"&Dcdisk$
6015 ENTER @Ptgtval,1;Tgt_value(*)
6018 ASSIGN @Ptgtval TO *
6021 !
6024 ASSIGN @Ptgtmsk1 TO "TGT_MASK1"&Dcdisk$
6027 ENTER @Ptgtmsk1,1;Tgt_mask1(*)
6030 ASSIGN @Ptgtmsk1 TO *
6033 !
6036 ASSIGN @Pterr TO "TERR_FCT"&Dcdisk$
6039 ENTER @Pterr,1;Terr_factor(*)
6042 ASSIGN @Pterr TO *
6045 !
6048 ASSIGN @Pdust TO "DUST_ABRT"&Dcdisk$
6051 ENTER @Pdust,1;Prob_dustabort(*)
6054 ASSIGN @Pdust TO *
6057 !
6060 ASSIGN @Pclgpmsk TO "NS_CLGPMSK"&Dcdisk$

```

Table 6-14. Ground combat code (continued).

```

6063 ENTER @Pclgpmsk,1;Clgp_msk_ns(*)
6066 ASSIGN @Pclgpmsk TO *
6069 !
6072 ASSIGN @Pclgpmsk TO "GL_CLGPMSK"&Dcdisk$
6075 ENTER @Pclgpmsk,1;Clgp_msk_gl(*)
6078 ASSIGN @Pclgpmsk TO *
6081 !
6084 ASSIGN @Pclgpmsk TO "RV_CLGPMSK"&Dcdisk$
6087 ENTER @Pclgpmsk,1;Clgp_msk_rp(*)
6090 ASSIGN @Pclgpmsk TO *
6093 !
6096 ASSIGN @Pprbdes TO "NOS_PRBDES"&Dcdisk$
6099 ASSIGN @Pkpcclgp TO "NOS_KPCLGP"&Dcdisk$
6102 ENTER @Pprbdes,1;Prob_dsg_ns(*)
6105 ENTER @Pkpcclgp,1;Sskp_ns(*)
6108 ASSIGN @Pprbdes TO *
6111 ASSIGN @Pkpcclgp TO *
6114 !
6117 ASSIGN @Pprbdes TO "GLL_PRBDES"&Dcdisk$
6120 ASSIGN @Pkpcclgp TO "GLL_KPCLGP"&Dcdisk$
6123 ENTER @Pprbdes,1;Prob_dsg_gl(*)
6126 ENTER @Pkpcclgp,1;Sskp_gl(*)
6129 ASSIGN @Pprbdes TO *
6132 ASSIGN @Pkpcclgp TO *
6135 !
6138 ASSIGN @Pprbdes TO "RPV_PRBDES"&Dcdisk$
6141 ASSIGN @Pkpcclgp TO "RPV_KPCLGP"&Dcdisk$
6144 ENTER @Pprbdes,1;Prob_dsg_rp(*)
6147 ENTER @Pkpcclgp,1;Sskp_rp(*)
6150 ASSIGN @Pprbdes TO *
6153 ASSIGN @Pkpcclgp TO *
6156 !*****!
6159 ! READ HELICOPTER FILES AND STORE IN ARRAYS !
6162 !*****!
6165 Side$(1)="BL"
6168 Side$(2)="RD"
6171 FOR H_side=1 TO 2
6174   ASSIGN @Helo_file TO Side$(H_side)&"HELICHAR"&Dcdisk$
6177   ENTER @Helo_file;Helo_char(*)   !READ ALL 3 RECORDS AT THE SAME TIME
6180   ASSIGN @Helo_file TO *
6183   FOR I=1 TO 3
6186     FOR Muni=1 TO 3
6189       Helo_load(H_side,I,Muni)=Helo_char(I,Muni+4)   !BASIC LOAD
6192     NEXT Muni
6195     Mast_mount(H_side,I)=Helo_char(I,8)   ! 0-MAST MOUNT, 1-NON MAST MT
6198   NEXT I
6201 ! READ IN DATA FROM SENSOR FILE (PROB OF DETECTION DATA)
6204 ASSIGN @Helo_file TO Side$(H_side)&"HELISENS"&Dcdisk$
6207 FOR I=1 TO 3   !RETRIEVE SENSOR RECORD FOR HELO TYPE I
6210   IF Helo_char(I,1)>0 THEN
6213     ENTER @Helo_file,Helo_char(I,1);Desc$.P_det_inf(*).P_det_tbar(*).Rr
(*).Rmax(*)

```

Table 6-14. Ground combat code (continued).

```

6216     FOR J=1 TO 8
6219         Pd_rmin(H_side,I,J)=Rmin(J)
6222         Pd_rmax(H_side,I,J)=Rmax(J)
6225     NEXT J
6228     FOR Jtarg=1 TO 5     !LOOP ON DETECTION CATEGORIES
6231         Pd_fe_inf_a(H_side,I,Jtarg)=P_det_inf(1,Jtarg,1)
6234         Pd_fe_inf_b(H_side,I,Jtarg)=P_det_inf(2,Jtarg,1)
6237         Pd_fe_inf_c(H_side,I,Jtarg)=P_det_inf(3,Jtarg,1)
6240         Pd_hd_inf_a(H_side,I,Jtarg)=P_det_inf(1,Jtarg,2)
6243         Pd_hd_inf_b(H_side,I,Jtarg)=P_det_inf(2,Jtarg,2)
6246         Pd_hd_inf_c(H_side,I,Jtarg)=P_det_inf(3,Jtarg,2)
6249         Pd_fe_tbar_a(H_side,I,Jtarg)=P_det_tbar(1,Jtarg,1)
6252         Pd_fe_tbar_b(H_side,I,Jtarg)=P_det_tbar(2,Jtarg,1)
6255         Pd_fe_tbar_c(H_side,I,Jtarg)=P_det_tbar(3,Jtarg,1)
6258         Pd_hd_tbar_a(H_side,I,Jtarg)=P_det_tbar(1,Jtarg,2)
6261         Pd_hd_tbar_b(H_side,I,Jtarg)=P_det_tbar(2,Jtarg,2)
6264         Pd_hd_tbar_c(H_side,I,Jtarg)=P_det_tbar(3,Jtarg,2)
6267     NEXT Jtarg
6270     END IF
6273     NEXT I
6276     ASSIGN @Helo_file TO *
6279     READ HELICOPTER PERFORMANCE FILE (PROB OF KILL, TIME MASKED & EXPOSED)
6282     ASSIGN @Helo_file TO Side$(H_side)&"HELIPERF"&Dcdisk$
6285     FOR I=1 TO 2
6288         IF H_side=1 THEN Helo_mis(1,I)=B_helo_msn(I)
6291         IF H_side=2 THEN Helo_mis(2,I)=R_helo_msn(I)
6294     NEXT I
6297     Helo_mis(1,3)=0
6300     Helo_mis(2,3)=0
6303     IF H_side=1 AND B_helo(3,1)>0 THEN Helo_mis(1,3)=B_helo_msn(1)
6306     IF H_side=2 AND R_helo(3,1)>0 THEN Helo_mis(2,3)=R_helo_msn(1)
6309     FOR I=1 TO 3     !RETRIEVE MUNITION RECORD FOR HELO TYPE I
6312         FOR Muni=1 TO 3
6315             IF Helo_char(I,Muni+1)>0 THEN     !BE SURE THIS POINTS TO A RECOR
6318                 ENTER @Helo_file, Helo_char(I,Muni+1);Desc$,Pk(*),Pk_rmin(H_side,I
uni),Pk_rmax(H_side,I,Muni),Np(H_side,I,Muni),Fm(H_side,I,Muni),Tim_me(*)
6321                 FOR Jtarg=1 TO 20     !LOOP ON TARGET CATEGORIES
6324                     Pk_fe_a(H_side,I,Muni,Jtarg)=Pk(1,Jtarg,1)
6327                     Pk_fe_b(H_side,I,Muni,Jtarg)=Pk(2,Jtarg,1)
6330                     Pk_fe_c(H_side,I,Muni,Jtarg)=Pk(3,Jtarg,1)
6333                     Pk_hd_a(H_side,I,Muni,Jtarg)=Pk(1,Jtarg,2)
6336                     Pk_hd_b(H_side,I,Muni,Jtarg)=Pk(2,Jtarg,2)
6339                     Pk_hd_c(H_side,I,Muni,Jtarg)=Pk(3,Jtarg,2)
6342                 NEXT Jtarg
6345                 IF Helo_mis(H_side,I)>0 THEN
6348                     Tm(H_side,I,Muni)=Tim_me(Helo_mis(H_side,I))     !TIME MASKED
6351                     Te(H_side,I,Muni)=Tim_me(Helo_mis(H_side,I)+3)     !TIME EXPOSED
6354                 END IF
6357             END IF
6360         NEXT Muni
6363     NEXT I
6366     ASSIGN @Helo_file TO *

```


Table 6-14. Ground combat code (continued).

```

6369 ' READ HELICOPTER PREFERENCE FILES
6372 ASSIGN @Helo_file TO Side$(H_side)&"HELIPREF"&Dcdisk$
6375 IF H_side=1 THEN Terr=R_terr
6378 IF H_side=2 THEN Terr=B_terr
6381 FOR M=1 TO 3      !LOOP ON MISSIONS
6384   ENTER @Helo_file,M;Pref(*),Plos(*)
6387   FOR Jtarg=1 TO 20
6390     Tgt_pref(H_side,M,Jtarg)=Pref(Jtarg)
6393   NEXT Jtarg
6396   Plos_alpha(H_side,M)=Plos(Terr)      !PROB OF LOS ALPHA.BETA FOR THIS
6399   Plos_beta(H_side,M)=Plos(Terr+4)    !TYPE OF TERRAIN INPUT
6402 NEXT M
6405 ASSIGN @Helo_file TO *
6408 ' READ AD PERFORMANCE FILES
6411 ASSIGN @Helo_file TO Side$(H_side)&"ADPERF"&Dcdisk$
6414 FOR Iad=1 TO 7
6417   ENTER @Helo_file,Iad;Pd_inf_ad(*),Pd_tbar_ad(*),Rmin(*),Rmax(*),Pk_ad
),Pk_ad_rmin(H_side,Iad),Pk_ad_rmax(H_side,Iad),Pref_ad(*)
6420   FOR Jmast=1 TO 2      !LOOP ON MAST/NON-MAST
6423     Pd_inf_ad_a(H_side,Iad,Jmast)=Pd_inf_ad(1,Jmast)
6426     Pd_inf_ad_b(H_side,Iad,Jmast)=Pd_inf_ad(2,Jmast)
6429     Pd_inf_ad_c(H_side,Iad,Jmast)=Pd_inf_ad(3,Jmast)
6432     Pd_tbar_ad_a(H_side,Iad,Jmast)=Pd_tbar_ad(1,Jmast)
6435     Pd_tbar_ad_b(H_side,Iad,Jmast)=Pd_tbar_ad(2,Jmast)
6438     Pd_tbar_ad_c(H_side,Iad,Jmast)=Pd_tbar_ad(3,Jmast)
6441     Pk_ad_a(H_side,Iad,Jmast)=Pk_ad(1,Jmast)
6444     Pk_ad_b(H_side,Iad,Jmast)=Pk_ad(2,Jmast)
6447     Pk_ad_c(H_side,Iad,Jmast)=Pk_ad(3,Jmast)
6450   NEXT Jmast
6453   FOR J=1 TO 8      !LOOP ON ATMOSPHERES
6456     Pd_ad_rmin(H_side,Iad,J)=Rmin(J)
6459     Pd_ad_rmax(H_side,Iad,J)=Rmax(J)
6462   NEXT J
6465   FOR J=1 TO 3      !LOOP ON NO. OF HELOS
6468     Ad_pref(H_side,Iad,J)=Pref_ad(J)
6471   NEXT J
6474 NEXT Iad
6477 ASSIGN @Helo_file TO *
6480 ' READ AD MISCELLANEOUS FILES (HOLDS AMMO DESCRIPTION)
6483 ASSIGN @Helo_file TO Side$(H_side)&"ADAMMO"&Dcdisk$
6486 FOR Iad=1 TO 7
6489   ENTER @Helo_file,Iad;Rnd_wt(H_side,Iad),Rnds(H_side,Iad),Fad(H_side,I
)
6492 NEXT Iad
6495 ASSIGN @Helo_file TO *
6498 ' READ PROBABILITY OF DETECTION CATEGORY FILE
6501 ASSIGN @Helo_file TO Side$(H_side)&"PDCAT"&Dcdisk$
6504 ENTER @Helo_file,1;Cat20(*)
6507 FOR Jtarg=1 TO 20
6510   Pd_cat(H_side,Jtarg)=Cat20(Jtarg)
6513 NEXT Jtarg
6516 ASSIGN @Helo_file TO *

```

Table 6-14. Ground combat code (continued).

```

6519 !READ DIRECT FILE PROBABILITY OF DETECTION FILE
6522 ASSIGN @Helo_file TO Side$(H_side)&"_DF_SENS"&Dcdisk$
6525 FOR I=1 TO 2 !LOOP ON SENSOR TYPE 1-OPTICAL, 2-THERMAL
6528 ENTER @Helo_file,I;Df_det_inf(*),Df_det_tbar(*),Rmin(*),Rmax(*)
6531 FOR J=1 TO 2 !1-MAST MNT, 2-NON MAST MNT
6534 Pd_inf_df_a(H_side,I,J)=Df_det_inf(1,J)
6537 Pd_inf_df_b(H_side,I,J)=Df_det_inf(2,J)
6540 Pd_inf_df_c(H_side,I,J)=Df_det_inf(3,J)
6543 Pd_tbar_df_a(H_side,I,J)=Df_det_tbar(1,J)
6546 Pd_tbar_df_b(H_side,I,J)=Df_det_tbar(2,J)
6549 Pd_tbar_df_c(H_side,I,J)=Df_det_tbar(3,J)
6552 NEXT J
6555 FOR J=1 TO 8 !LOOP ON ATMOSPHERES
6558 Pd_df_rmin(H_side,I,J)=Rmin(J)
6561 Pd_df_rmax(H_side,I,J)=Rmax(J)
6564 NEXT J
6567 NEXT I
6570 ASSIGN @Helo_file TO *
6573 !DIRECT FIRE MISCELLANEOUS FILE (HOLDS MUNITION DESCRIPTION)
6576 ASSIGN @Helo_file TO Side$(H_side)&"_DF_MUNI"&Dcdisk$
6579 FOR I=1 TO 2 !LOOP ON MUNI TYPE 1-GRND MISSILE,2-GRND KINETIC ENRGY
6582 ENTER @Helo_file,I;Df_rnds_eng(H_side,I),F_df(H_side,I)
6585 NEXT I
6588 ASSIGN @Helo_file TO *
6591 NEXT H_side
6594 RETURN
6597 !-----
6600 !
6603 Check_brk_pt: ! THIS SBR CHECKS FOR BATTLE BREAKPOINTS
6606 !
6609 Break_point=0
6612 !
6615 ! CALCULATE CURRENT FORCE EFFECTIVENESS
6618 IF Init_b_eff=0 THEN
6621 Curr_b_eff=0
6624 ELSE
6627 Curr_b_eff=B_cbt_eff/Init_b_eff
6630 END IF
6633 IF Init_r_eff=0 THEN
6636 Curr_r_eff=0
6639 ELSE
6642 Curr_r_eff=R_cbt_eff/Init_r_eff
6645 END IF
6648 !
6651 ! CHECK TO SEE IF GAME TURN TIME IS EXCEEDED
6654 IF Btl_time>=Max_btl_time OR Btl_phase=3 THEN
6657 Break_point=3
6660 IF Btl_time<2430 THEN
6663 PRINT USING Fmt10:"SECTOR BATTLE ENDS",Btl_time," HRS","B/EFF: ",Curr
_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6666 ELSE
6669 PRINT USING Fmt10:"SECTOR BATTLE ENDS",Btl_time-2400," HRS","B/EFF: "

```

Table 6-14. Ground combat code (continued).

```

urr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6672   END IF
6675   GOTO End_brk_pt
6678   END IF
6681   Fmt10:IMAGE /,3X,25A,2X,4Z,4A,2X,7A,1D,2D,2X,7A,1D,2D,3X,7A,6D
6684   !
6687   ! CHECK TO SEE IF CASUALTY BREAKPOINT IS EXCEEDED
6690   IF Curr_b_eff<=B_cas_break THEN
6693     Break_point=1
6696     IF Btl_time<2430 THEN
6699       PRINT USING Fmt10:"BLUE BREAKS FOR LOSSES",Btl_time," HRS","B/EFF: ".
rr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6702     ELSE
6705       PRINT USING Fmt10:"BLUE BREAKS FOR LOSSES",Btl_time-2400," HRS","B/EF
",Curr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6708     END IF
6711   END IF
6714   IF Curr_r_eff<=R_cas_break THEN
6717     Break_point=2
6720     IF Btl_time<2430 THEN
6723       PRINT USING Fmt10:"RED BREAKS FOR LOSSES",Btl_time," HRS","B/EFF: ".C
r_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6726     ELSE
6729       PRINT USING Fmt10:"RED BREAKS FOR LOSSESS",Btl_time-2400," HRS","B/EF
",Curr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6732     END IF
6735   END IF
6738   !
6741   ! CHECK TO SEE IF RANGE BREAKPOINT IS EXCEEDED
6744   IF Btl_rg<=B_rg_break THEN
6747     Break_point=1
6750     IF Btl_time<2430 THEN
6753       PRINT USING Fmt10:"BLUE BREAKS FOR RANGE",Btl_time," HRS","B/EFF: ".C
r_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6756     ELSE
6759       PRINT USING Fmt10:"BLUE BREAKS FOR RANGE",Btl_time-2400," HRS","B/EFF
",Curr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6762     END IF
6765   END IF
6768   IF Btl_rg<=R_rg_break THEN
6771     Break_point=2
6774     IF Btl_time<2430 THEN
6777       PRINT USING Fmt10:"RED BREAKS FOR RANGE",Btl_time," HRS","B/EFF: ".Cu
_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6780     ELSE
6783       PRINT USING Fmt10:"RED BREAKS FOR RANGE",Btl_time-2400," HRS","B/EFF:
.Curr_b_eff,"R/EFF: ",Curr_r_eff,"RANGE: ",Btl_rg
6786     END IF
6789   END IF
6792   !
6795   End_brk_pt:
6798   RETURN

```

Table 6-14. Ground combat code (continued).

```

6801 !
6804 ! -----
6807 !
6810 Apport_wri_loss: ! THIS SBR WRITES UNIT STATUS TO HISTORY FILE
6813 !
6816 Rif_left=0
6819 Bif_left=0
6822 FOR I=1 TO 15
6825   FOR J=1 TO 5
6828     Rif_left=Rif_left+Rif_msn_tons(I,J)
6831     Bif_left=Bif_left+Bif_msn_tons(I,J)
6834   NEXT J
6837 NEXT I
6840 !
6843 IF Rif_left<=0 THEN Rif_left=0
6846 IF Bif_left<=0 THEN Bif_left=0
6849 Bif_ammo_used=Bif_ammo_sv-Bif_left
6852 Rif_ammo_used=Rif_ammo_sv-Rif_left
6855 !
6858 ! WRITE OUT BLUE UNIT DATA
6861 !
6864 FOR I=1 TO No_b_unit
6867   ENTER @Unitpath,B_unit_no(I);N'*)
6870   FOR J=1 TO 70
6873     N(J)=N(J)-(Sys_tot(1,J)-Sys_tot(2,J))*B_con(I,J)
6876   NEXT J
6879 !
6882   IF Bdf_ammo_sv=0 THEN
6885     GOTO B_if_ammo
6888   ELSE
6891     B_df_ammo_used=(Bdf_ammo_sv-B_df_ammo)*B_unit(I,72)/Bdf_ammo_sv
6894     N(131)=N(131)-B_df_ammo_used
6897     IF N(131)<0 THEN N(131)=0
6900     N(139)=N(139)+B_df_ammo_used
6903   END IF
6906 B_if_ammo: !
6909   IF Bif_ammo_sv<=0 THEN
6912     GOTO B_ad_ammo
6915   ELSE
6918     If_used=(Bif_ammo_used)*B_unit(I,73)/Bif_ammo_sv
6921     N(132)=N(132)-If_used
6924     IF N(132)<0 THEN N(132)=0
6927     N(140)=N(140)+If_used
6930   END IF
6933 B_ad_ammo: !
6936   IF Bad_ammo_sv<=0 THEN
6939     GOTO End_b_ammo
6942   ELSE
6945     B_ad_used=(Bad_ammo_sv-B_ad_ammo)*B_unit(I,74)/Bad_ammo_sv
6948     N(133)=N(133)-B_ad_used
6951     IF N(133)<0 THEN N(133)=0
6954     N(141)=N(141)+B_ad_used

```

Table 6-14. Ground combat code (continued).

```

6957 END IF
6960 End_b_ammo: !
6963 OUTPUT @Unitpath,B_unit_no(I);N(*)
6966 NEXT I
6969 !
6972 ! WRITE OUT RED UNIT DATA
6975 !
6978 FOR I=1 TO No_r_unit
6981 ENTER @Unitpath,R_unit_no(I);N(*)
6984 FOR J=1 TO 70
6987 N(J)=N(J)-(Sys_tot(3,J)-Sys_tot(4,J))*R_con(I,J)
6990 NEXT J
6993 !
6996 IF Rdf_ammo_sv<=0 THEN
6999 GOTO R_if_ammo
7002 ELSE
7005 R_df_ammo_used=(Rdf_ammo_sv-R_df_ammo)*R_unit(I,72)/Rdf_ammo_sv
7008 N(131)=N(131)-R_df_ammo_used
7011 IF N(131)<0 THEN N(131)=0
7014 N(139)=N(139)+R_df_ammo_used
7017 END IF
7020 R_if_ammo: !
7023 IF Rif_ammo_sv<=0 THEN
7026 GOTO R_ad_ammo
7029 ELSE
7032 If_used=(Rif_ammo_sv)*R_unit(I,73)/Rif_ammo_sv
7035 N(132)=N(132)-If_used
7038 IF N(132)<0 THEN N(132)=0
7041 N(140)=N(140)+If_used
7044 END IF
7047 R_ad_ammo: !
7050 IF Rad_ammo_sv=0 THEN
7053 GOTO End_red_ammo
7056 ELSE
7059 R_ad_used=(Rad_ammo_sv-R_ad_ammo)*R_unit(I,74)/Rad_ammo_sv
7062 N(133)=N(133)-R_ad_used
7065 IF N(133)<0 THEN N(133)=0
7068 N(141)=N(141)+R_ad_used
7071 END IF
7074 End_red_ammo: !
7077 OUTPUT @Unitpath,R_unit_no(I);N(*)
7080 NEXT I
7083 !
7086 ! UPDATE KILLER-VICTIM TABLES
7089 ENTER @Kvpath,1;Ci_kv_b(*)
7092 ENTER @Kvpath,2;Ci_kv_r(*)
7095 FOR I=1 TO 6
7098 FOR J=1 TO 70
7101 Ci_kv_b(I,J)=Ci_kv_b(I,J)+Kv_b(I,J)
7104 Ci_kv_r(I,J)=Ci_kv_r(I,J)+Kv_r(I,J)
7107 NEXT J
7110 NEXT I

```

Table 6-14. Ground combat code (continued).

```

7113 OUTPUT @Kvpath,1;Ci_kv_b(*)
7116 OUTPUT @Kvpath,2;Ci_kv_r(*)
7119 !
7122 ! UPDATE HELICOPTER FILES
7125 ENTER @Helopath,1;Ci_helo_b(*)
7128 ENTER @Helopath,2;Ci_helo_r(*)
7131 FOR I=1 TO 3
7134   FOR J=1 TO 6
7137     Ci_helo_b(I,J)=Ci_helo_b(I,J)+B_helo(I,J)
7140     Ci_helo_r(I,J)=Ci_helo_r(I,J)+R_helo(I,J)
7143   NEXT J
7146 NEXT I
7149 OUTPUT @Helopath,1;Ci_helo_b(*)
7152 OUTPUT @Helopath,2;Ci_helo_r(*)
7155 !
7158 RETURN
7161 !
7164 !-----
7167 !
7170 Tally_cbt_eff: ! THIS SBR CALCULATES THE ADJUSTED FIREPOWER SCORE
7173 !
7176 Prev30_b_eff=B_cbt_eff
7179 Prev30_r_eff=R_cbt_eff
7182 B_cbt_eff=0
7185 R_cbt_eff=0
7188 FOR I=1 TO 70
7191   B_cbt_eff=B_cbt_eff+Sys_tot(2,I)*Sys_eff(1,I)
7194   R_cbt_eff=R_cbt_eff+Sys_tot(4,I)*Sys_eff(2,I)
7197 NEXT I
7200 !
7203 RETURN
7206 !
7209 !-----
7212 !
7215 Helo_arrive: ! THIS SBR CALCULATES THE ATK HELOS AVAILABLE THIS PERIOD
7218 !
7221 ! THIS SBR ASSUMES AN ON-STATION TIME OF 30 MINUTES FOR ATK HELOS AND
7224 ! 90 MINUTE CYCLE TIME. A SINGLE AH CAN ATTACK ONLY ONCE EVERY 2 HOUR
7227 !
7230 ! INITIALIZE BOTH RED AND BLUE HELOS
7233 Bah1=0
7236 Bah2=0
7239 Bsct=0
7242 Rah1=0
7245 Rah2=0
7248 Rsct=0
7251 !
7254 Set_blue_helos: ! SCHEDULE BLUE ATTACK HELICOPTERS
7257 !
7260 ! CHECK DELAY FACTORS
7263 Earliest_time=0
7266 IF B_helo_delay>0 THEN

```

Table 6-14. Ground combat code (continued).

```

7269 Delay_time=B_helo_delay
7272 GOSUB Chk_delay_time
7275 END IF
7278 !
7281 ! IF DELAYS ARE IN EFFECT NO ATK HELOS ARRIVE
7284 IF Btl_time<=Earliest_time OR (Btl_rg>B_helo_rg_delay AND B_helo_rg_delay
0) OR Vis=4 THEN
7287 Bah1=0
7290 Bah2=0
7293 Bsct=0
7296 GOTO Set_red_helos
7299 END IF
7302 !
7305 Set_blue_ah1: ! SCHEDULE BLUE #1 ATK HELOS
7308 !
7311 Helo_alive=B_helo(1,1)-B_helo(1,2)
7314 IF Helo_alive<=0 THEN GOTO Set_blue_ah2
7317 Set_bah1_cell:Helo=Helo_alive#1/B_helo(1,3) ! OA RATE=0.83
7320 IF Helo<1 AND B_helo(1,3)>1 THEN !DECREASE # OF CELLS & TRY SETTING AGAI
7323 B_helo(1,3)=B_helo(1,3)-1
7326 B_helo(3,3)=B_helo(1,3) ! SCTS HAVE SAME CELL# AS AH#1
7329 GOTO Set_bah1_cell
7332 ELSE
7335 IF Helo<1 AND B_helo(1,3)=1 THEN !NO USE, NOT ENOUGH HELOS
7338 Bah1=0
7341 GOTO Set_blue_ah2
7344 END IF
7347 END IF
7350 !
7353 ! SCHEDULE THE ARRIVAL TIME OF THE CELL
7356 SELECT B_helo(1,3)
7359 CASE =1
7362 IF Last_bah1_seg=0 OR Time_seg-Last_bah1_seg=4 THEN
7365 Bah1=Helo
7368 Last_bah1_seg=Time_seg
7371 ELSE
7374 Bah1=0
7377 END IF
7380 CASE =2
7383 IF Last_bah1_seg=0 OR Time_seg-Last_bah1_seg=2 THEN
7386 Bah1=Helo
7389 Last_bah1_seg=Time_seg
7392 ELSE
7395 Bah1=0
7398 END IF
7401 CASE =3
7404 IF Last_bah1_seg=0 THEN
7407 Bah1=Helo
7410 Last_bah1_seg=Time_seg
7413 Bah1_seg=1
7416 GOTO Set_blue_ah2
7419 END IF

```

Table 6-14. Ground combat code (continued).

```

7422 IF Bah1_seg<3 THEN
7425   Bah1=Helo
7428   Bah1_seg=Bah1_seg+1
7431   Last_bah1_seg=Time_seg
7434 ELSE
7437   Bah1=0
7440   Bah1_seg=0
7443 END IF
7446 CASE =4
7449   Bah1=Helo
7452   Last_bah1_seg=Time_seg
7455 END SELECT
7458 !
7461 Set_blue_ah2: ! SCHEDULE BLUE #2 ATK HELOS
7464 !
7467 Helo_alive=B_helo(2,1)-B_helo(2,2)
7470 IF Helo_alive<=0 THEN GOTO Set_blue_sct
7473 Set_bah2_cell:Helo=Helo_alive*1/B_helo(2,3) ! OA RATE=0.83
7476 IF Helo<1 AND B_helo(2,3)>1 THEN
7479   B_helo(2,3)=B_helo(2,3)-1
7482   GOTO Set_bah2_cell
7485 ELSE
7488   IF Helo<1 AND B_helo(2,3)=1 THEN
7491     Bah2=0
7494     GOTO Set_blue_sct
7497   END IF
7500 END IF
7503 !
7506 ! SCHEDULE THE ARRIVAL TIME OF THE CELL
7509 SELECT B_helo(2,3)
7512 CASE =1
7515   IF Last_bah2_seg=0 OR Time_seg-Last_bah2_seg=4 THEN
7518     Bah2=Helo
7521     Last_bah2_seg=Time_seg
7524   ELSE
7527     Bah2=0
7530   END IF
7533 CASE =2
7536   IF Last_bah2_seg=0 OR Time_seg-Last_bah2_seg=2 THEN
7539     Bah2=Helo
7542     Last_bah2_seg=Time_seg
7545   ELSE
7548     Bah2=0
7551   END IF
7554 CASE =3
7557   IF Last_bah2_seg=0 THEN
7560     Bah2=Helo
7563     Last_bah2_seg=Time_seg
7566     Bah2_seg=1
7569     GOTO Set_blue_sct
7572   END IF
7575   IF Bah2_seg<3 THEN

```


Table 6-14. Ground combat code (continued).

```

7578     Bah2=Helo
7581     Bah2_seg=Bah2_seg+1
7584     Last_bah2_seg=Time_seg
7587     ELSE
7590     Bah2=0
7593     Bah2_seg=0
7596     END IF
7599     CASE =4
7602     Bah2=Helo
7605     Last_bah2_seg=Time_seg
7608     END SELECT
7611     !
7614     Set_blue_sct: ! SCHEDULE BLUE SCOUT HELOS      CHANGED 12/11/86 DWS
7617     !GOTO 9188
7620     !
7623     !IF Bah1=0 THEN                                ! NO SCOUTS FLOWN IF NO BLUE AH1 FLOW
7626     ! Bscct=0
7629     ! GOTO Set_red_helos
7632     !END IF
7635     Helo_alive=B_helo(3,1)-B_helo(3,2)
7638     IF Helo_alive=0 THEN Set_red_helos
7641     Set_bsct_cell:Helo=Helo_alive*1/B_helo(3,3)      ! OA RATE=0.83
7644     IF Bah1>0 THEN                                !SCOUTS LASING FOR AH1
7647     IF Helo<1 OR Helo<.4*Bah1 THEN
7650         Bscct=0
7653         PRINT
7656         PRINT "    INSUFFICIENT SCOUTS TO CONTINUE,  REMAINING AH64 WILL OPER/
AUTONOMOUS"
7659         GOTO Set_red_helos
7662     ELSE
7665     IF Helo>Bah1/1.667 THEN Helo=Bah1/1.667          ! USE 3:5 MIX FOR SCT:
7668     Bscct=Helo
7671     END IF
7674     ELSE      !SCOUTS WILL FIRE ON ITS OWN
7677     IF B_helo(1,1)>0 THEN                            !SCOUTS ARE LASING, BUT NOT THIS 30 MIN PERIO
7680         Bscct=0
7683         GOTO Set_red_helos
7686     END IF
7689     IF Helo<1 AND B_helo(3,3)>1 THEN
7692         B_helo(3,3)=B_helo(3,3)-1      !DECREASE # OF CELLS BY 1
7695         GOTO Set_bsct_cell
7698     ELSE
7701     IF Helo<1 AND B_helo(3,3)=1 THEN
7704         Bscct=0
7707         GOTO Set_red_helos
7710     END IF
7713     END IF
7716     ! SCHEDULE THE ARRIVAL TIME OF THE CELL
7719     SELECT B_helo(3,3)
7722     CASE =1
7725     IF Last_bsct_seg=0 OR Time_seg-Last_bsct_seg=4 THEN
7728     Bscct=Helo

```

Table 6-14. Ground combat code (continued).

```

7731     Last_bsct_seg=Time_seg
7734     ELSE
7737     Bsct=0
7740     END IF
7743     CASE =2
7746     IF Last_bsct_seg=0 OR Time_seg-Last_bsct_seg=2 THEN
7749     Bsct=Helo
7752     Last_bsct_seg=Time_seg
7755     ELSE
7758     Bsct=0
7761     END IF
7764     CASE =3
7767     IF Last_bsct_seg=0 THEN
7770     Bsct=Helo
7773     Last_bsct_seg=Time_seg
7776     Bsct_seg=1
7779     GOTO Set_red_helos
7782     END IF
7785     IF Bsct_seg<3 THEN
7788     Bsct=Helo
7791     Bsct_seg=Bsct_seg+1
7794     Last_bsct_seg=Time_seg
7797     ELSE
7800     Bsct=0
7803     Bsct_seg=0
7806     END IF
7809     CASE =4
7812     Bsct=Helo
7815     Last_bsct_seg=Time_seg
7818     END SELECT
7821     END IF
7824     Set_red_helos:  ! SCHEDULE RED ATTACK HELICOPTERS
7827     !
7830     ! CHECK DELAY FACTORS
7833     Earliest_time=0
7836     IF R_helo_delay>0 THEN
7839     Delay_time=R_helo_delay
7842     GOSUB Chk_delay_time
7845     END IF
7848     !
7851     ! IF DELAYS ARE IN EFFECT NO ATK HELOS ARRIVE
7854     IF Btl_time<=Earliest_time OR (Btl_rg>R_helo_rg_delay AND R_helo_rg_delay
0) OR Vis=4 THEN
7857     Rah1=0
7860     GOTO End_helo_arrive
7863     END IF
7866     !
7869     Set_red_ah1:  ! SCHEDULE RED #1 ATK HELOS
7872     !
7875     Helo_alive=R_helo(1,1)-R_helo(1,2)
7878     IF Helo_alive<=0 THEN GOTO Set_red_ah2
7881     Set_rah1_cell:Helo=Helo_alive*1/R_helo(1,3)      ! OA RATE=0.75

```

Table 6-14. Ground combat code (continued).

```

7884 IF Helo<1 AND R_helo(1,3)>1 THEN
7887   R_helo(1,3)=R_helo(1,3)-1
7890   GOTO Set_rah1_cell
7893 ELSE
7896   IF Helo<1 AND R_helo(1,3)=1 THEN
7899     Rah1=0
7902     GOTO End_helo_arrive
7905   END IF
7908 END IF
7911 !
7914 ! SCHEDULE THE ARRIVAL TIME OF THE CELL
7917 SELECT R_helo(1,3)
7920 CASE =1
7923   IF Last_rah1_seg=0 OR Time_seg-Last_rah1_seg=4 THEN
7926     Rah1=Helo
7929     Last_rah1_seg=Time_seg
7932   ELSE
7935     Rah1=0
7938   END IF
7941 CASE =2
7944   IF Last_rah1_seg=0 OR Time_seg-Last_rah1_seg=2 THEN
7947     Rah1=Helo
7950     Last_rah1_seg=Time_seg
7953   ELSE
7956     Rah1=0
7959   END IF
7962 CASE =3
7965   IF Last_rah1_seg=0 THEN
7968     Rah1=Helo
7971     Last_rah1_seg=Time_seg
7974     Rah1_seg=1
7977     GOTO Set_red_ah2
7980   END IF
7983   IF Rah1_seg<3 THEN
7986     Rah1=Helo
7989     Rah1_seg=Rah1_seg+1
7992     Last_rah1_seg=Time_seg
7995   ELSE
7998     Rah1=0
8001     Rah1_seg=0
8004   END IF
8007 CASE =4
8010   Rah1=Helo
8013   Last_rah1_seg=Time_seg
8016 END SELECT
8019 !
8022 Set_red_ah2: ! SCHEDULE RED #2 ATK HELOS   ROE
8025 !
8028 Helo_alive=R_helo(2,1)-R_helo(2,2)
8031 IF Helo_alive<=0 THEN Set_red_sct
8034 Set_rah2_cell:Helo=Helo_alive*1/R_helo(2,3)
8037 IF Helo<1 AND R_helo(2,3)>1 THEN

```

Table 6-14. Ground combat code (continued).

```

8040 R_helo(2,3)=R_helo(2,3)-1
8043 GOTO Set_rah2_cell
8046 ELSE
8049 IF Helo<1 AND R_helo(2,3)=1 THEN
8052 Rah2=0
8055 GOTO Set_red_sct
8058 END IF
8061 END IF
8064 SELECT R_helo(2,3)
8067 CASE =1
8070 IF Last_rah2_seg=0 OR Time_seg-Last_rah2_seg=4 THEN
8073 Rah2=Helo
8076 Last_rah2_seg=Time_seg
8079 ELSE
8082 Rah2=0
8085 END IF
8088 CASE =2
8091 IF Last_rah2_seg=0 OR Time_seg-Last_rah2_seg=2 THEN
8094 Rah2=Helo
8097 Last_rah2_seg=Time_seg
8100 ELSE
8103 Rah2=0
8106 END IF
8109 CASE =3
8112 IF Last_rah2_seg=0 THEN
8115 Rah2=Helo
8118 Last_rah2_seg=Time_seg
8121 Rah2_seg=1
8124 GOTO Set_red_sct
8127 END IF
8130 IF Rah2_seg<3 THEN
8133 Rah2=Helo
8136 Rah2_seg=Rah2_seg+1
8139 Last_rah2_seg=Time_seg
8142 ELSE
8145 Rah2=0
8148 Rah2_seg=0
8151 END IF
8154 CASE =4
8157 Rah2=Helo
8160 Last_rah2_seg=Time_seg
8163 END SELECT
8166!
8169 Set_red_sct: ! SCHEDULE RED SCOUT HELOS NEW CODE 12/11/86 DWS
8172 Helo_alive=R_helo(3,1)-R_helo(3,2)
8175 IF Helo_alive=0 THEN End_helo_arrive
8178 Set_rsct_cell:Helo=Helo_alive*1/R_helo(3,3) ! DA RATE=0.83
8181 IF Rah1>0 THEN !SCOUTS LASING FOR AH1
8184 IF Helo<1 OR Helo<.4*Rah1 THEN
8187 Rsct=0
8190 PRINT
8193 PRINT " INSUFFICIENT SCOUTS TO CONTINUE, REMAINING RED AH1S WILL

```

Table 6-14. Ground combat code (continued).

```

RATE AUTONOMOUS"
8196     GOTO End_helo_arrive
8199     ELSE
8202     IF Helo=Rah1/1.667 THEN Helo=Rah1/1.667      ' USE 3:5 MIX FOR SCT
8205     Rsct=Helo
8208     END IF
8211     ELSE      !SCOUTS WILL FIRE ON ITS OWN
8214     IF Helo<1 AND R_helo(3,3)>1 THEN
8217     R_helo(3,3)=R_helo(3,3)-1      !DECREASE # OF CELLS BY 1
8220     GOTO Set_rsct_cell
8223     ELSE
8226     IF Helo<1 AND R_helo(3,3)=1 THEN
8229     Rsct=0
8232     GOTO End_helo_arrive
8235     END IF
8238     END IF
8241     ! SCHEDULE THE ARRIVAL TIME OF THE CELL
8244     SELECT R_helo(3,3)
8247     CASE =1
8250     IF Last_rsct_seg=0 OR Time_seg-Last_rsct_seg=4 THEN
8253     Rsct=Helo
8256     Last_rsct_seg=Time_seg
8259     ELSE
8262     Rsct=0
8265     END IF
8268     CASE =2
8271     IF Last_rsct_seg=0 OR Time_seg-Last_rsct_seg=2 THEN
8274     Rsct=Helo
8277     Last_rsct_seg=Time_seg
8280     ELSE
8283     Rsct=0
8286     END IF
8289     CASE =3
8292     IF Last_rsct_seg=0 THEN
8295     Rsct=Helo
8298     Last_rsct_seg=Time_seg
8301     Rsct_seg=1
8304     GOTO End_helo_arrive
8307     END IF
8310     IF Rsct_seg<3 THEN
8313     Rsct=Helo
8316     Rsct_seg=Rsct_seg+1
8319     Last_rsct_seg=Time_seg
8322     ELSE
8325     Rsct=0
8328     Rsct_seg=0
8331     END IF
8334     CASE =4
8337     Rsct=Helo
8340     Last_rsct_seg=Time_seg
8343     END SELECT
8346     END IF
'END OF NEW CODE 12/11/86 DWS

```

Table 6-14. Ground combat code (continued).

```

8349 End_helo_arrive: ! UPDATE SORTIE NUMBERS
8352 R_helo(1,6)=R_helo(1,6)+Bah1
8355 R_helo(2,6)=R_helo(2,6)+Bah2
8358 R_helo(3,6)=R_helo(3,6)+Bsct
8361 R_helo(1,6)=R_helo(1,6)+Rah1
8364 R_helo(2,6)=R_helo(2,6)+Rah2
8367 R_helo(2,6)=R_helo(2,6)+Rsct
8370 !
8373 RETURN
8376 !
8379 ! -----
8382 !
8385 Chk_delay_time: ! THIS SBR CALCULATES DELAY TIMES
8388 !
8391 Int_time=INT(St_time/100)*100
8394 Int_delay=INT(Delay_time/100)*100
8397 Minute=(St_time MOD 100)+(Delay_time MOD 100)
8400 SELECT Minute
8403 CASE =0
8406 Delay_minute=0
8409 CASE =30
8412 Delay_minute=30
8415 CASE =60
8418 Delay_minute=100
8421 END SELECT
8424 !
8427 ! SET EARLIEST ARRIVAL TIME
8430 Earliest_time=Int_time+Int_delay+Delay_minute
8433 !
8436 RETURN
8439 !
8442 ! -----
8445 !
8448 Ammo_breakdown: ! THIS SBR APPORTIONS AMMO FOR USE BY WEAPONS SYSTEMS
8451 !
8454 FOR Ikp=1 TO 15
8457 Sys_ammo(Ikp)=0
8460 NEXT Ikp
8463 If_ammo_divisor=0
8466 ! APPORTION IF AMMO AMONG ARTY, MORTARS, AND MLRS
8469 FOR J1=1 TO 15
8472 Sys_ammo(J1)=N(J1+20)*Arty_30min_wt(Side,J1)
8475 If_ammo_divisor=If_ammo_divisor+Sys_ammo(J1)
8478 NEXT J1
8481 FOR J1=1 TO 15
8484 IF If_ammo_divisor=0 THEN
8487 If_ammo(J1)=0
8490 ELSE
8493 If_ammo(J1)=N(132)*Sys_ammo(J1)/If_ammo_divisor
8496 END IF
8499 NEXT J1
8502 !

```

Table 6-14. Ground combat code (continued).

```

8505 RETURN
8508 !
8511 ! -----
8514 !
8517 Arty_arrive: ! THIS SBR CALCULATES THE AMOUNT OF INCOMING ARTILLERY F:
8520 !
8523 !SET VISIBILITY FOR 100%-- WILL BE DEGRADED IF SMOKE IS FIRED
8526 FOR I=1 TO 3
8529 R_vis(I)=1
8532 B_vis(I)=1
8535 NEXT I
8538 !SET CAP FOR ARTY
8541 FOR I=1 TO 5
8544 FOR J=1 TO 7
8547 B_arty_cap(J,I)=Sys_tot(2,J+20)*Arty_30min_wt(1,J)*Bif_msn(I)/100
8550 R_arty_cap(J,I)=Sys_tot(4,J+20)*Arty_30min_wt(2,J)*Rif_msn(I)/100
8553 NEXT J
8556 !SET CAP FOR MLRS
8559 IF I=2 THEN Mort_cap
8562 FOR J=1 TO 4
8565 IF Bif_msn(2)>=100 THEN
8568 B_mlrs_cap(J,I)=0
8571 ELSE
8574 B_mlrs_cap(J,I)=Sys_tot(2,J+31)*Arty_30min_wt(1,J+1)*Bif_msn(I)/(
-Bif_msn(2))
8577 END IF
8580 IF Rif_msn(2)>=100 THEN
8583 R_mlrs_cap(J,I)=0
8586 ELSE
8589 R_mlrs_cap(J,I)=Sys_tot(4,J+31)*Arty_30min_wt(2,J+1)*Rif_msn(I)/(
-Rif_msn(2))
8592 END IF
8595 NEXT J
8598 Mort_cap: !
8601 FOR J=1 TO 4
8604 B_mort_cap(J,I)=0
8607 R_mort_cap(J,I)=0
8610 NEXT J
8613 IF I=4 OR I=5 THEN Next_cap
8616 IF Int_bmort=0 THEN Next_mort_cr
8619 FOR J=1 TO 4
8622 B_mort_cap(J,I)=Sys_tot(2,J+27)*Arty_30min_wt(1,J+7)*Bif_msn(I)/Int_b
rt
8625 NEXT J
8628 Next_mort_cr: !
8631 IF Int_rmort=0 THEN Next_cap
8634 FOR J=1 TO 4
8637 R_mort_cap(J,I)=Sys_tot(4,J+27)*Arty_30min_wt(2,J+7)*Rif_msn(I)/Int_r
rt
8640 NEXT J
8643 Next_cap:NEXT I
8646 FOR I=1 TO 15

```

Table 6-14. Ground combat code (continued).

```

8649 Tot_arty(1,I)=0          SUB-TOTAL OF AMT DELIVERED PER 30 MI
8652 Tot_arty(2,I)=0
8655 FOR J=1 TO 5
8658     Bif_fired(I,J)=0
8661     Rif_fired(I,J)=0
8664 NEXT J
8667 NEXT I
8670 !
8673 Clgp_msns=0
8676 Gamp_msns=0
8679 SELECT Clgp_rpv
8682 CASE 0 ! NO RPV
8685     FOR I=1 TO 7
8688         IF Sys_tot(2,2)+Sys_tot(2,3)<=0 OR Clgp_avail=0 THEN !SET CLGP TO
8691             B_clgp_cap(I)=0
8694         ELSE
8697             B_clgp_cap(I)=Sys_tot(2,I+20)*Arty_30min_wt(1,I)*Perc_clgp*(Sys_tot
,2)+Sys_tot(2,3))/((Sys_tot(1,2)+Sys_tot(1,3))*100) !?? STILL 2 & 3
8700         END IF
8703     NEXT I
8706 CASE 1 ! RPV AVAILABLE
8709     FOR I=1 TO 7
8712         IF Clgp_avail=0 THEN
8715             B_clgp_cap(I)=0
8718         ELSE
8721             B_clgp_cap(I)=Svs_tot(2,I+20)*Arty_30min_wt(1,I)*Perc_clgp/100
8724         END IF
8727     NEXT I
8730 END SELECT
8733 FOR I=1 TO 4
8736     B_gamp_cap(I)=Sys_tot(2,I+31)*Arty_30min_wt(1,I+11)*Perc_gamp/100
8739 NEXT I
8742 !
8745 IF Cloud_ht*3.28<=1500 THEN No_clgp_gamp
8748 IF Vis=4 THEN No_clgp
8751 IF Btl_rg>Ds_start(B_terr) THEN No_clgp_gamp
8754 IF Btl_rg-150<=Ds_start(B_terr) AND Btl_rg>Ds_start(B_terr)-500 AND Clgp
v=0 THEN No_clgp
8757 GOTO Allocate_smoke
8760 No_clgp_gamp: !
8763 FOR I=1 TO 4
8766     B_mort_cap(I,2)=B_mort_cap(I,2)+B_gamp_cap(I)
8769     B_gamp_cap(I)=0
8772 NEXT I
8775 No_clgp: !
8778 FOR I=1 TO 7
8781     B_arty_cap(I,2)=B_arty_cap(I,2)+B_clgp_cap(I)
8784     B_clgp_cap(I)=0
8787 NEXT I
8790 !
8793 Allocate_smoke: !
8796 IF Btl_phases<3 OR Btl_rg>3200 THEN Allocate_prep

```


Table 6-14. Ground combat code (continued).

```

8799 Fire_smoke: !
8802 IF Break_point=1 THEN
8805 ! BLUE BREAKS...HENCE IT WILL SMOKE
8808 FOR I=1 TO 7
8811     B_smk_cap(I)=B_arty_cap(I,2)*Bif_msn(6)/100
8814     IF B_smk_cap(I)>Bif_msn_tons(I,2) THEN
8817         B_smok_tons(I)=Bif_msn_tons(I,2)
8820     ELSE
8823         B_smok_tons(I)=B_smk_cap(I)
8826     END IF
8829 NEXT I
8832 FOR I=8 TO 11
8835     B_smk_cap(I)=B_mort_cap(I-7,2)*Bif_msn(6)/100
8838     IF B_smk_cap(I)>Bif_msn_tons(I,2) THEN
8841         B_smok_tons(I)=Bif_msn_tons(I,2)
8844     ELSE
8847         B_smok_tons(I)=B_smk_cap(I)
8850     END IF
8853 NEXT I
8856 A_ammo_ton=0
8859 M_ammo_ton=0
8862 FOR I=1 TO 7             !TOTAL ARTY AMMO TONNAGE
8865     A_ammo_ton=B_smok_tons(I)+A_ammo_ton
8868 NEXT I
8871 FOR I=8 TO 11         !TOTAL MORT AMMO TONNAGE
8874     M_ammo_ton=B_smok_tons(I)+M_ammo_ton
8877 NEXT I
8880 IF A_ammo_ton<.1 AND M_ammo_ton<.1 THEN Allocate_prep
8883 GOSUB W_smoke
8886 ! UPDATE ARTILLERY CAPACITY FOR TONNAGE NOT USED
8889 FOR I=1 TO 7
8892     B_arty_cap(I,2)=B_arty_cap(I,2)-B_asmk_used(I)
8895     Bif_msn_tons(I,2)=Bif_msn_tons(I,2)-B_asmk_used(I)
8898 NEXT I
8901 FOR I=1 TO 4
8904     B_mort_cap(I,2)=B_mort_cap(I,2)-B_msmk_used(I)
8907     Bif_msn_tons(I+7,2)=Bif_msn_tons(I+7,2)-B_msmk_used(I)
8910 NEXT I
8913 Smoke_used=0
8916 FOR I=1 TO 4
8919     Smoke_used=Smoke_used+B_msmk_used(I)
8922 NEXT I
8925 IF Smoke_used>0 THEN
8928     PRINT
8931     PRINT USING Fmt_m_smk;"    TONS OF SMOKE FIRED BY BLUE MORTAR DURING
HDRAWAL",Smoke_used
8934     END IF
8937 Fmt_m_smk:IMAGE 55A,4D.1D
8940 Smoke_used=0
8943 FOR I=1 TO 7
8946     Smoke_used=Smoke_used+B_asmk_used(I)
8949 NEXT I

```

Table 6-14. Ground combat code (continued).

```

8952 IF Smoke_used>0 THEN
8955 PRINT
8958 PRINT USING Fmt_a_smk;" TONS OF SMOKE FIRED BY BLUE ARTILLERY DURI
WITHDRAWAL",Smoke_used
8961 END IF
8964 ELSE
8967 ! RED FIRING SMOKE
8970 FOR I=1 TO 7
8973 R_smk_cap(I)=R_arty_cap(I,2)*Rif_msn(6)/100
8976 IF R_smk_cap(I)>Rif_msn_tons(I,2) THEN
8979 R_smok_tons(I)=Rif_msn_tons(I,2)
8982 ELSE
8985 R_smok_tons(I)=R_smk_cap(I)
8988 END IF
8991 NEXT I
8994 FOR I=8 TO 11
8997 R_smk_cap(I)=R_mort_cap(I-7,2)*Rif_msn(6)/100
9000 IF R_smk_cap(I)>Rif_msn_tons(I,2) THEN
9003 R_smok_tons(I)=Rif_msn_tons(I,2)
9006 ELSE
9009 R_smok_tons(I)=R_smk_cap(I)
9012 END IF
9015 NEXT I
9018 A_ammo_ton=0
9021 M_ammo_ton=0
9024 FOR I=1 TO 7 !TOTAL ARTY AMMO TONNAGE
9027 A_ammo_ton=R_smok_tons(I)+A_ammo_ton
9030 NEXT I
9033 FOR I=8 TO 11 !TOTAL MORT AMMO TONNAGE
9036 M_ammo_ton=R_smok_tons(I)+M_ammo_ton
9039 NEXT I
9042 IF A_ammo_ton<.1 AND M_ammo_ton<.1 THEN Allocate_prep
9045 GOSUB W_smoke
9048 ! UPDATE ARTILLERY CAPABILITY FOR AMMO NOT USED
9051 FOR I=1 TO 7
9054 R_arty_cap(I,2)=R_arty_cap(I,2)-R_asmk_used(I)
9057 Rif_msn_tons(I,2)=Rif_msn_tons(I,2)-R_asmk_used(I)
9060 NEXT I
9063 FOR I=1 TO 4
9066 R_mort_cap(I,2)=R_mort_cap(I,2)-R_msmk_used(I)
9069 Rif_msn_tons(I+7,2)=Rif_msn_tons(I+7,2)-R_msmk_used(I)
9072 NEXT I
9075 Smoke_used=0
9078 FOR I=1 TO 4
9081 Smoke_used=Smoke_used+R_msmk_used(I)
9084 NEXT I
9087 IF Smoke_used>0 THEN
9090 PRINT
9093 PRINT USING Fmt_m_smk;" TONS OF SMOKE FIRED BY RED MORTARS DURING
HDRAWAL",Smoke_used
9096 Fmt_a_smk:IMAGE 58A,4D.1D
9099 END IF

```

Table 6-14. Ground combat code (continued).

```

9102  Smoke_used=0
9105  FOR I=1 TO 7
9108    Smoke_used=Smoke_used+R_asmk_used(I)
9111  NEXT I
9114  IF Smoke_used>0 THEN
9117    PRINT
9120    PRINT USING Fmt_a_smk;"  TONS OF SMOKE FIRED BY RED  ARTILLERY DUR:
WITHDRAWAL",Smoke_used
9123  END IF
9126  END IF
9129  Allocate_prep: ! SCHEDULE INCOMING PREP FIRES
9132  ! CHANGED TO ALLOW INDEPENDENT SCHEDULING OF FIRES ROB
9135  !IF Atk_def=0 THEN
9138  !Prep_time=R_prep_time
9141  !ELSE
9144  !Prep_time=B_prep_time
9147  !END IF
9150  !IF Btl_time<=Prep_fire_time THEN
9153  !FOR I=1 TO 15
9156  !Bif_fired(I,1)=0
9159  !Rif_fired(I,1)=0
9162  !NEXT I
9165  !GOTO Allocate_clgp
9168  !END IF
9171  !
9174  ! ALLOCATE MORTAR FIRES FOR PREP
9177  IF Btl_rg>5700 THEN
9180  FOR I=8 TO 11
9183  Bif_fired(I,1)=0
9186  Rif_fired(I,1)=0
9189  NEXT I
9192  GOTO Arty_prep
9195  END IF
9198  IF Btl_time<B_prep_time THEN 9294
9201  IF Btl_rg<B_dsmort_start THEN
9204  Tons_avail=0
9207  FOR I=8 TO 11
9210  IF Bif_msn_tons(I,1)>0 THEN
9213  Bif_msn_tons(I,2)=Bif_msn_tons(I,1)+Bif_msn_tons(I,2)
9216  B_dsmort_avail(I-7)=B_dsmort_avail(I-7)+Bif_msn_tons(I,1)
9219  Tons_avail=Tons_avail+Bif_msn_tons(I,1)
9222  Bif_msn_tons(I,1)=0
9225  END IF
9228  B_mort_cap(I-7,2)=B_mort_cap(I-7,2)+B_mort_cap(I-7,1)
9231  Bif_fired(I,1)=0
9234  NEXT I
9237  IF Tons_avail>0 THEN
9240  PRINT
9243  PRINT "  RED  WITHIN BLUE MORT CS RANGE ; REMAINING BLUE PREP AMMO
ILABLE FOR CS"
9246  END IF
9249  GOTO Red_mort_prep

```

Table 6-14. Ground combat code (continued).

```

9252 END IF
9255 Blue_mort_prep: !
9258 FOR I=8 TO 11
9261   IF Bif_msn_tons(I,1)<B_mort_cap(I-7,1) THEN
9264     Bif_fired(I,1)=Bif_msn_tons(I,1)
9267     Bif_msn_tons(I,1)=0
9270     Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,1)
9273   ELSE
9276     Bif_fired(I,1)=B_mort_cap(I-7,1)
9279     Bif_msn_tons(I,1)=Bif_msn_tons(I,1)-B_mort_cap(I-7,1)
9282     Tot_arty(1,I)=Tot_arty(1,I)+B_mort_cap(I-7,1)
9285   END IF
9288 NEXT I
9291   !
9294 Red_mort_prep: !
9297 IF Btl_time<R_prep_time THEN 9390
9300 IF Btl_rg<R_dsmort_start THEN
9303   Tons_avail=0
9306   FOR I=8 TO 11
9309     IF Rif_msn_tons(I,1)>0 THEN
9312       Rif_msn_tons(I,2)=Rif_msn_tons(I,1)+Rif_msn_tons(I,2)
9315       R_dsmort_avail(I-7)=R_dsmort_avail(I-7)+Rif_msn_tons(I,1)
9318       Tons_avail=Tons_avail+Rif_msn_tons(I,1)
9321       Rif_msn_tons(I,1)=0
9324     END IF
9327     R_mort_cap(I-7,2)=R_mort_cap(I-7,2)+Rif_fired(I,1)
9330     Rif_fired(I,1)=0
9333   NEXT I
9336   IF Tons_avail>0 THEN
9339     PRINT
9342     PRINT "   BLUE WITHIN RED MORT CS RANGE ; REMAINING RED PREP AMMO
ILABLE FOR CS"
9345   END IF
9348   GOTO Arty_prep
9351 END IF
9354 FOR I=8 TO 11
9357   IF Rif_msn_tons(I,1)<R_mort_cap(I-7,1) THEN
9360     Rif_fired(I,1)=Rif_msn_tons(I,1)
9363     Rif_msn_tons(I,1)=0
9366     Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,1)
9369   ELSE
9372     Rif_fired(I,1)=R_mort_cap(I-7,1)
9375     Rif_msn_tons(I,1)=Rif_msn_tons(I,1)-R_mort_cap(I-7,1)
9378     Tot_arty(2,I)=Tot_arty(2,I)+R_mort_cap(I-7,1)
9381   END IF
9384 NEXT I
9387   !
9390 Arty_prep: ! ALLOCATE PREP FIRES FOR ARTILLERY PIECES
9393   !
9396 Blue_arty_prep: IF Btl_rg>12000 OR Btl_time<B_prep_time THEN
9399   FOR I=1 TO 7
9402     Bif_fired(I,1)=0

```

Table 6-14. Ground combat code (continued).

```

9405 NEXT I
9408 GOTO Red_arty_prep
9411 END IF
9414 IF Btl_rg<B_dsarty_start THEN
9417 Tons_avail=0
9420 FOR I=1 TO 7
9423 IF Bif_msn_tons(I,1)>0 THEN
9426 Bif_msn_tons(I,2)=Bif_msn_tons(I,1)+Bif_msn_tons(I,2)
9429 B_dsarty_avail(I)=B_dsarty_avail(I)+Bif_msn_tons(I,1)
9432 Tons_avail=Tons_avail+Bif_msn_tons(I,1)
9435 Bif_msn_tons(I,1)=0
9438 END IF
9441 B_arty_cap(I,2)=B_arty_cap(I,2)+B_arty_cap(I,1)
9444 Bif_fired(I,1)=0
9447 NEXT I
9450 IF Tons_avail>0 THEN
9453 PRINT
9456 PRINT " RED WITHIN BLUE ARTY CS RANGE ; REMAINING BLUE PREP AMMO
ILABLE FOR CS"
9459 END IF
9462 GOTO Red_arty_prep
9465 END IF
9468 !
9471 FOR I=1 TO 7
9474 IF Bif_msn_tons(I,1)<B_arty_cap(I,1) THEN
9477 Bif_fired(I,1)=Bif_msn_tons(I,1)
9480 Bif_msn_tons(I,1)=0
9483 Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,1)
9486 ELSE
9489 Bif_fired(I,1)=B_arty_cap(I,1)
9492 Bif_msn_tons(I,1)=Bif_msn_tons(I,1)-B_arty_cap(I,1)
9495 Tot_arty(1,I)=Tot_arty(1,I)+B_arty_cap(I,1)
9498 END IF
9501 NEXT I
9504 !
9507 Red_arty_prep: !
9510 IF Btl_rg>14000 OR Btl_time<R_prep_time THEN
9513 FOR I=1 TO 7
9516 Rif_fired(I,1)=0
9519 NEXT I
9522 GOTO Mlrs_prep
9525 END IF
9528 IF Btl_rg<R_dsarty_start THEN
9531 Tons_avail=0
9534 FOR I=1 TO 7
9537 IF Rif_msn_tons(I,1)>0 THEN
9540 Rif_msn_tons(I,2)=Rif_msn_tons(I,1)+Rif_msn_tons(I,2)
9543 R_dsarty_avail(I)=R_dsarty_avail(I)+Rif_msn_tons(I,1)
9546 Tons_avail=Tons_avail+Rif_msn_tons(I,1)
9549 Rif_msn_tons(I,1)=0
9552 END IF
9555 R_arty_cap(I,2)=R_arty_cap(I,2)+R_arty_cap(I,1)

```

Table 6-14. Ground combat code (continued).

```

9558 NEXT I
9561 IF Tons_avail>0 THEN
9564 PRINT
9567 PRINT " BLUE WITHIN RED ARTY CS RANGE : REMAINING RED PREP AMMO
ILABLE FOR CS"
9570 END IF
9573 GOTO Mlrs_prep
9576 END IF
9579 !
9582 FOR I=1 TO 7
9585 IF Rif_msn_tons(I,1)<R_arty_cap(I,1) THEN
9588 Rif_fired(I,1)=Rif_msn_tons(I,1)
9591 Rif_msn_tons(I,1)=0
9594 Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,1)
9597 ELSE
9600 Rif_fired(I,1)=R_arty_cap(I,1)
9603 Rif_msn_tons(I,1)=Rif_msn_tons(I,1)-R_arty_cap(I,1)
9606 Tot_arty(2,I)=Tot_arty(2,I)+R_arty_cap(I,1)
9609 END IF
9612 NEXT I
9615 !
9618 Mlrs_prep: ! ALLOCATE PREP FIRES FOR MLRS SYSTEMS
9621 !
9624 FOR I=12 TO 15
9627 Bif_fired(I,1)=0
9630 Rif_fired(I,1)=0
9633 NEXT I
9636 IF Btl_rg>25000 THEN Red_mlrs_prep
9639 IF Btl_time<B_prep_time THEN Red_mlrs_prep
9642 IF Btl_rg<B_dsarty_start THEN Red_mlrs_prep
9645 !
9648 Blue_mlrs_prep: !
9651 FOR I=12 TO 15
9654 IF Bif_msn_tons(I,1)<B_mlrs_cap(I-11,1) THEN
9657 Bif_fired(I,1)=Bif_msn_tons(I,1)
9660 Bif_msn_tons(I,1)=0
9663 Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,1)
9666 ELSE
9669 Bif_fired(I,1)=B_mlrs_cap(I-11,1)
9672 Bif_msn_tons(I,1)=Bif_msn_tons(I,1)-B_mlrs_cap(I-11,1)
9675 Tot_arty(1,I)=Tot_arty(1,I)+B_mlrs_cap(I-11,1)
9678 END IF
9681 NEXT I
9684 !
9687 Red_mlrs_prep: !
9690 IF Btl_time<R_prep_time OR Btl_rg>15500 THEN Allocate_clgp
9693 IF Btl_rg<R_dsarty_start THEN Allocate_clgp
9696 FOR I=12 TO 15
9699 IF Rif_msn_tons(I,1)<R_mlrs_cap(I-11,1) THEN
9702 Rif_fired(I,1)=Rif_msn_tons(I,1)
9705 Rif_msn_tons(I,1)=0
9708 Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,1)

```

Table 6-14. Ground combat code (continued).

```

9711 ELSE
9714   Rif_fired(I,1)=R_mlr_cap(I-11,1)
9717   Rif_msn_tons(I,1)=Rif_msn_tons(I,1)-R_mlr_cap(I-11,1)
9720   Tot_arty(2,1)=Tot_arty(2,1)+R_mlr_cap(I-11,1)
9723 END IF
9726 NEXT I
9729 !
9732 !
9735 Allocate_clgp: ! ALLOCATE CLGP MISSIONS FOR THIS 30 MIN PD
9738 !
9741 IF Btl_rg>12000 OR Btl_time<B_prep_time THEN
9744   Clgp_msns=0
9747   Gamp_msns=0
9750   GOTO Allocate_ds
9753 END IF
9756 !
9759 IF Clgp_avail<=0 THEN
9762   FOR I=1 TO 7
9765     B_arty_cap(I,2)=B_arty_cap(I,2)+B_clgp_cap(I)
9768   NEXT I
9771   Clgp_msns=0
9774   GOTO Allocate_gamp
9777 END IF
9780 Tot_clgp=0
9783 FOR I=1 TO 7
9786   Tot_clgp=Tot_clgp+B_clgp_cap(I)
9789 NEXT I
9792 IF Tot_clgp>Clgp_avail THEN
9795   Clgp_msns=Clgp_avail
9798   Clgp_avail=0
9801 ELSE
9804   Clgp_msns=Tot_clgp
9807   Clgp_avail=Clgp_avail-Tot_clgp
9810 END IF
9813 !
9816 !
9819 Allocate_gamp: ! ALLOCATE GAMP MISSIONS FOR THIS 30 MIN PERIOD
9822 !
9825 IF Btl_rg>5700 THEN
9828   Gamp_msns=0
9831   GOTO Allocate_ds
9834 END IF
9837 !
9840 IF Gamp_avail<=0 THEN
9843   FOR I=1 TO 4
9846     B_mort_cap(I,2)=B_mort_cap(I,2)+B_gamp_cap(I)
9849   NEXT I
9852   Gamp_msns=0
9855   GOTO Allocate_ds
9858 END IF
9861 Tot_gamp=0
9864 FOR I=1 TO 4

```

Table 6-14. Ground combat code (continued).

```

9867 Tot_gamp=Tot_gamp+B_gamp_cap(I)
9870 NEXT I
9873 IF Tot_gamp>Gamp_avail THEN
9876 Gamp_msns=Gamp_avail
9879 Gamp_avail=0
9882 ELSE
9885 Gamp_msns=Tot_gamp
9888 Gamp_avail=Gamp_avail-Tot_gamp
9891 END IF
9894 !
9897 Allocate_ds: ! SCHEDULE INCOMING DIRECT SUPPORT FIRES
9900 !
9903 TRACE OFF
9906 ! MLRS DOES NOT FIRE IN DIRECT SUPPORT
9909 FOR I=12 TO 15
9912 Bif_msn_tons(I,2)=0
9915 Rif_msn_tons(I,2)=0
9918 NEXT I
9921 !
9924 Set_blue_ds: !
9927 Tot_ds_avail=0
9930 FOR I=1 TO 7
9933 Tot_ds_avail=Tot_ds_avail+B_dsarty_avail(I)
9936 NEXT I
9939 IF Btl_rg>B_dsarty_start OR Tot_ds_avail=0 OR Btl_time<B_prep_time THEN
9942 FOR I=1 TO 11
9945 Bif_fired(I,2)=0
9948 NEXT I
9951 GOTO Set_b_dsmort
9954 END IF
9957 !
9960 Set_b_dsarty:IF Btl_rg<B_dsarty_start AND Btl_rg>=B_ds_conc_pt THEN
9963 X=B_dsarty_start-B_ds_conc_pt
9966 Y=B_ds_conc_level
9969 FOR I=1 TO 7
9972 IF B_dsarty_avail(I)>0 THEN
9975 Frac_arty(I)=(Y/X*(B_dsarty_start-Btl_rg))-(B_dsarty_fire(I)/B_dsart
_
avail(I))
9978 ELSE
9981 Frac_arty(I)=0
9984 END IF
9987 NEXT I
9990 B_p30_artvrg=Btl_rg
9993 GOTO Set_b_dsarty_rd
9996 END IF
9999 !
10002 IF Btl_rg<B_ds_conc_pt AND B_p30_artvrg>=B_ds_conc_pt AND B_ds_shift=0 TH
N
10005 FOR I=3 TO 5
10008 FOR J=1 TO 7
10011 Bif_msn_tons(J,2)=Bif_msn_tons(J,2)+Rif_msn_tons(J,I)
10014 B_dsarty_avail(J)=B_dsarty_avail(J)+Bif_msn_tons(J,I)

```


Table 6-14. Ground combat code (continued).

```

10017     Bif_msn_tons(J,I)=0
10020     NEXT J
10023     NEXT I
10026     B_ds_shift=1
10029     END IF
10032     !
10035     IF B_ds_shift=1 THEN
10038     FOR I=3 TO 5
10041     FOR J=1 TO 7
10044         B_arty_cap(J,2)=B_arty_cap(J,2)+B_arty_cap(J,I)
10047         B_arty_cap(J,I)=0
10050     NEXT J
10053     NEXT I
10056     X=B_p30_artyrg-B_dsarty_brkrng
10059     IF X<=0 THEN
10062         X=500
10065         B_p30_artyrg=Btl_rg+500
10068     END IF
10071     FOR I=1 TO 7
10074         IF B_dsarty_avail(I)>0 THEN
10077             Y=1-(B_dsarty_fire(I)/B_dsarty_avail(I))
10080             Frac_arty(I)=(Y/X*(B_p30_artyrg-Btl_rg))
10083         ELSE
10086             Frac_arty(I)=0
10089         END IF
10092     NEXT I
10095     B_p30_artyrg=Btl_rg
10098     END IF
10101     !
10104     Set_b_dsarty_rd:IF B_ds_shift=0 THEN
10107     Arty_bound=B_ds_conc_level
10110     ELSE
10113     Arty_bound=1.0
10116     END IF
10119     !
10122     FOR I=1 TO 7
10125     IF Frac_arty(I)<.083 THEN Frac_arty(I)=.083
10128     IF Mine_hit<>0 AND Frac_arty(I)<.20 THEN Frac_arty(I)=.20
10131     IF B_dsarty_avail(I)>0 THEN
10134         IF Frac_arty(I)>Arty_bound-(B_dsarty_fire(I)/B_dsarty_avail(I)) THEN
10137             Frac_arty(I)=Arty_bound-(B_dsarty_fire(I)/B_dsarty_avail(I))
10140         END IF
10143     END IF
10146     !
10149     Ds_attempted(I)=Frac_arty(I)*B_dsarty_avail(I)
10152     IF Ds_attempted(I)>Bif_msn_tons(I,2) THEN Ds_attempted(I)=Bif_msn_tons(
2)
10155     IF Ds_attempted(I)<B_arty_cap(I,2) THEN
10158         Bif_fired(I,2)=Ds_attempted(I)
10161         Bif_msn_tons(I,2)=Bif_msn_tons(I,2)-Ds_attempted(I)
10164         Tot_arty(I,I)=Tot_arty(I,I)+Ds_attempted(I)
10167         B_dsarty_fire(I)=B_dsarty_fire(I)+Ds_attempted(I)

```

Table 6-14. Ground combat code (continued).

```

10170 ELSE
10173   Ds_attempted(I)=B_arty_cap(I,2)
10176   Bif_fired(I,2)=Ds_attempted(I)
10179   Bif_msn_tons(I,2)=Bif_msn_tons(I,2)-Ds_attempted(I)
10182   Tot_arty(1,I)=Tot_arty(1,I)+Ds_attempted(I)
10185   B_dsarty_fire(I)=B_dsarty_fire(I)+Ds_attempted(I)
10188 END IF
10191 NEXT I
10194 !
10197 !
10200 Set_b_dsmort: ! ALLOCATE BLUE MORTAR DS FIRES
10203 Tot_ds_avail=0
10206 FOR I=1 TO 4
10209   Tot_ds_avail=Tot_ds_avail+B_dsmort_avail(I)
10212 NEXT I
10215 IF Btl_rg>B_dsmort_start OR Tot_ds_avail=0 OR Btl_time<B_prep_time THEN
10218   FOR I=8 TO 11
10221     Bif_fired(I,2)=0
10224   NEXT I
10227   GOTO Set_red_ds
10230 END IF
10233 !
10236 IF Btl_rg<B_dsmort_start AND Btl_rg>=B_mo_conc_pt THEN
10239   X=B_dsmort_start-B_mo_conc_pt
10242   Y=B_mo_conc_level
10245   FOR I=1 TO 4
10248     IF B_dsmort_avail(I)>0 THEN
10251       Frac_mort(I)=(Y/X*(B_dsmort_start-Btl_rg))-(B_dsmort_fire(I)/B_dsmor
_avail(I))
10254     ELSE
10257       Frac_mort(I)=0
10260     END IF
10263   NEXT I
10266   B_p30_mortrg=Btl_rg
10269   GOTO Set_b_dsmort_rd
10272 END IF
10275 !
10278 IF Btl_rg<B_mo_conc_pt AND B_p30_mortrg>=B_mo_conc_pt AND B_mo_shift=0 TH
N
10281   B_mo_shift=1
10284 END IF
10287 !
10290 IF B_mo_shift=1 THEN
10293   X=B_p30_mortrg-B_dsmort_brkrq
10296   IF X<=0 THEN
10299     X=500
10302   B_p30_mortrg=Btl_rg+500
10305 END IF
10308 FOR I=1 TO 4
10311   IF B_dsmort_avail(I)>0 THEN
10314     Y=1-(B_dsmort_fire(I)/B_dsmort_avail(I))
10317     Frac_mort(I)=(Y/X*(B_p30_mortrg-Btl_rg))

```

Table 6-14. Ground combat code (continued).

```

10320     ELSE
10323         Frac_mort(I)=0
10326     END IF
10329     NEXT I
10332     B_p30_mortrg=Btl_rg
10335 END IF
10338     !
10341 Set_b_dsmort_rd:IF B_mo_shift=0 THEN
10344     Mort_bound=B_mo_conc_level
10347 ELSE
10350     Mort_bound=1.0
10353 END IF
10356     !
10359     FOR I=1 TO 4
10362         IF Frac_mort(I)<.083 THEN Frac_mort(I)=.083
10365         IF Mine_hit<>0 AND Frac_mort(I)<.20 THEN Frac_mort(I)=.20
10368         IF B_dsmort_avail(I)>0 THEN
10371             IF Frac_mort(I)>Mort_bound-(B_dsmort_fire(I)/B_dsmort_avail(I)) THEN
10374                 Frac_mort(I)=Mort_bound-(B_dsmort_fire(I)/B_dsmort_avail(I))
10377             END IF
10380         END IF
10383         !
10386         Mo_attempted(I)=Frac_mort(I)*B_dsmort_avail(I)
10389         IF Mo_attempted(I)>Bif_msn_tons(I+7,2) THEN Mo_attempted(I)=Bif_msn_ton
I+7,2)
10392         IF Mo_attempted(I)<B_mort_cap(I,2) THEN
10395             Bif_fired(I+7,2)=Mo_attempted(I)
10398             Bif_msn_tons(I+7,2)=Bif_msn_tons(I+7,2)-Mo_attempted(I)
10401             B_dsmort_fire(I)=B_dsmort_fire(I)+Mo_attempted(I)
10404             Tot_arty(1,I+7)=Tot_arty(1,I+7)+Mo_attempted(I)
10407         ELSE
10410             Mo_attempted(I)=B_mort_cap(I,2)
10413             Bif_fired(I+7,2)=Mo_attempted(I)
10416             Bif_msn_tons(I+7,2)=Bif_msn_tons(I+7,2)-Mo_attempted(I)
10419             B_dsmort_fire(I)=B_dsmort_fire(I)+Mo_attempted(I)
10422             Tot_arty(1,I+7)=Tot_arty(1,I+7)+Mo_attempted(I)
10425         END IF
10428     NEXT I
10431     !
10434 Set_red_ds: !
10437     Tot_ds_avail=0
10440     FOR I=1 TO 7
10443         Tot_ds_avail=Tot_ds_avail+R_dsarty_avail(I)
10446     NEXT I
10449     IF Btl_rg>R_dsarty_start OR Tot_ds_avail=0 OR Btl_time<R_prep_time THEN
10452         FOR I=1 TO 11
10455             Rif_fired(I,2)=0
10458         NEXT I
10461         GOTO Set_r_dsmort
10464     END IF
10467     !
10470     Set_r_dsarty:IF Btl_rg<R_dsarty_start AND Btl_rg>=R_ds_conc_pt THEN

```

Table 6-14. Ground combat code (continued).

```

10473 X=R_dsarty_start-R_ds_conc_pt
10476 Y=R_ds_conc_level
10479 FOR I=1 TO 7
10482     IF R_dsarty_avail(I)>0 THEN
10485         Frac_arty(I)=(Y/X*(R_dsarty_start-Btl_rg))-(R_dsarty_fire(I)/R_dsar
_
_avail(I))
10488     ELSE
10491         Frac_arty(I)=0
10494     END IF
10497 NEXT I
10500 R_p30_artyrng=Btl_rg
10503 GOTO Set_r_dsarty_rd
10506 END IF
10509 !
10512 IF Btl_rg<R_ds_conc_pt AND R_p30_artyrng>=R_ds_conc_pt AND R_ds_shift=0 TI
N
10515 FOR I=3 TO 5
10518     FOR J=1 TO 7
10521         Rif_msn_tons(J,2)=Rif_msn_tons(J,2)+Rif_msn_tons(J,I)
10524         R_dsarty_avail(J)=R_dsarty_avail(J)+Rif_msn_tons(J,I)
10527         Rif_msn_tons(J,I)=0
10530     NEXT J
10533 NEXT I
10536 R_ds_shift=1
10539 END IF
10542 !
10545 IF R_ds_shift=1 THEN
10548     FOR I=3 TO 5
10551         FOR J=1 TO 7
10554             R_arty_cap(J,2)=R_arty_cap(J,2)+R_arty_cap(J,I)
10557             R_arty_cap(J,I)=0
10560         NEXT J
10563     NEXT I
10566 X=R_p30_artyrng-R_dsarty_brkng
10569 IF X<=0 THEN
10572     X=500
10575     R_p30_artyrng=Btl_rg+500
10578 END IF
10581 FOR I=1 TO 7
10584     IF R_dsarty_avail(I)>0 THEN
10587         Y=1-(R_dsarty_fire(I)/R_dsarty_avail(I))
10590         Frac_arty(I)=(Y/X*(R_p30_artyrng-Btl_rg))
10593     ELSE
10596         Frac_arty(I)=0
10599     END IF
10602 NEXT I
10605 R_p30_artyrng=Btl_rg
10608 END IF
10611 !
10614 Set_r_dsarty_rd:IF R_ds_shift=0 THEN
10617     Arty_bound=R_ds_conc_level
10620 ELSE

```

Table 6-14. Ground combat code (continued).

```

10623 Arty_bound=1.0
10626 END IF
10629 !
10632 FOR I=1 TO 7
10635 IF Frac_arty(I)<.083 THEN Frac_arty(I)=.083
10638 IF Mine_hit<>0 AND Frac_arty(I)<.20 THEN Frac_arty(I)=.20
10641 IF R_dsarty_avail(I)>0 THEN
10644 IF Frac_arty(I)>Arty_bound-(R_dsarty_fire(I)/R_dsarty_avail(I)) THEN
10647 Frac_arty(I)=Arty_bound-(R_dsarty_fire(I)/R_dsarty_avail(I))
10650 END IF
10653 END IF
10656 !
10659 Ds_attempted(I)=Frac_arty(I)*R_dsarty_avail(I)
10662 IF Ds_attempted(I)>Rif_msn_tons(I,2) THEN Ds_attempted(I)=Rif_msn_tons(
2)
10665 IF Ds_attempted(I)<R_arty_cap(I,2) THEN
10668 Rif_fired(I,2)=Ds_attempted(I)
10671 Rif_msn_tons(I,2)=Rif_msn_tons(I,2)-Ds_attempted(I)
10674 Tot_arty(2,I)=Tot_arty(2,I)+Ds_attempted(I)
10677 R_dsarty_fire(I)=R_dsarty_fire(I)+Ds_attempted(I)
10680 ELSE
10683 Ds_attempted(I)=R_arty_cap(I,2)
10686 Rif_fired(I,2)=Ds_attempted(I)
10689 Rif_msn_tons(I,2)=Rif_msn_tons(I,2)-Ds_attempted(I)
10692 Tot_arty(2,I)=Tot_arty(2,I)+Ds_attempted(I)
10695 R_dsarty_fire(I)=R_dsarty_fire(I)+Ds_attempted(I)
10698 END IF
10701 NEXT I
10704 !
10707 !
10710 Set_r_dsmort: ! ALLOCATE RED MORTAR DS FIRES
10713 Tot_ds_avail=0
10716 FOR I=1 TO 4
10719 Tot_ds_avail=Tot_ds_avail+R_dsmort_avail(I)
10722 NEXT I
10725 IF Btl_rg>R_dsmort_start OR Tot_ds_avail=0 OR Btl_time<R_prep_time THEN
10728 FOR I=8 TO 11
10731 Rif_fired(I,2)=0
10734 NEXT I
10737 GOTO 10944
10740 END IF
10743 !
10746 IF Btl_rg<R_dsmort_start AND Btl_rg>=R_mo_conc_pt THEN
10749 X=R_dsmort_start-R_mo_conc_pt
10752 Y=R_mo_conc_level
10755 FOR I=1 TO 4
10758 IF R_dsmort_avail(I)>0 THEN
10761 Frac_mort(I)=(Y/X*(R_dsmort_start-Btl_rg))-(R_dsmort_fire(I)/R_dsmo
_
avail(I))
10764 ELSE
10767 Frac_mort(I)=0
10770 END IF

```

Table 6-14. Ground combat code (continued).

```

10773 NEXT I
10776 R_p30_mortrg=Btl_rg
10779 GOTO Set_r_dsmort_rd
10782 END IF
10785 !
10788 IF Btl_rg<R_mo_conc_pt AND R_p30_mortrg>=R_mo_conc_pt AND R_mo_shift=0 TI
N
10791 R_mo_shift=1
10794 END IF
10797 !
10800 IF R_mo_shift=1 THEN
10803 X=R_p30_mortrg-R_dsmort_brkrq
10806 IF X<=0 THEN
10809 X=500
10812 R_p30_mortrg=Btl_rg+500
10815 END IF
10818 FOR I=1 TO 4
10821 IF R_dsmort_avail(I)>0 THEN
10824 Y=1-(R_dsmort_fire(I)/R_dsmort_avail(I))
10827 Frac_mort(I)=(Y/X*(R_p30_mortrg-Btl_rg))
10830 ELSE
10833 Frac_mort(I)=0
10836 END IF
10839 NEXT I
10842 END IF
10845 !
10848 Set_r_dsmort_rd:IF R_mo_shift=0 THEN
10851 Mort_bound=R_mo_conc_level
10854 ELSE
10857 Mort_bound=1.0
10860 END IF
10863 !
10866 FOR I=1 TO 4
10869 IF Frac_mort(I)<.083 THEN Frac_mort(I)=.083
10872 IF Mine_hit<>0 AND Frac_mort(I)<.20 THEN Frac_mort(I)=.20
10875 IF R_dsmort_avail(I)>0 THEN
10878 IF Frac_mort(I)>Mort_bound-(R_dsmort_fire(I)/R_dsmort_avail(I)) THEN
10881 Frac_mort(I)=Mort_bound-(R_dsmort_fire(I)/R_dsmort_avail(I))
10884 END IF
10887 END IF
10890 !
10893 Mo_attempted(I)=Frac_mort(I)*R_dsmort_avail(I)
10896 IF Mo_attempted(I)>Rif_msn_tons(I+7,2) THEN Mo_attempted(I)=Rif_msn_tons
I+7,2)
10899 IF Mo_attempted(I)<R_mort_cap(I,2) THEN
10902 Rif_fired(I+7,2)=Mo_attempted(I)
10905 Rif_msn_tons(I+7,2)=Rif_msn_tons(I+7,2)-Mo_attempted(I)
10908 R_dsmort_fire(I)=R_dsmort_fire(I)+Mo_attempted(I)
10911 Tot_arty(2,I+7)=Tot_arty(2,I+7)+Mo_attempted(I)
10914 ELSE
10917 Mo_attempted(I)=R_mort_cap(I,2)
10920 Rif_fired(I+7,2)=Mo_attempted(I)

```

Table 6-14. Ground combat code (continued).

```

10923   Rif_msn_tons(I+7,2)=Rif_msn_tons(I+7,2)-Mo_attempted(I)
10926   R_dsmort_fire(I)=R_dsmort_fire(I)+Mo_attempted(I)
10929   Tot_arty(2,I+7)=Tot_arty(2,I+7)+Mo_attempted(I)
10932   END IF
10935   NEXT I
10938   !
10941   !
10944   !Allocate_sead !SCHEDULE INCOMING SEAD MISSIONS ! ROE
10947   !
10950   ! MORTARS DO NOT FIRE SEAD
10953   FOR I=8 TO 11
10956     Bif_msn_tons(I,3)=0
10959     Rif_msn_tons(I,3)=0
10962   NEXT I
10965   !
10968   IF Btl_rg>12000 OR Btl_time<B_prep_time THEN
10971     FOR I=1 TO 7
10974       Bif_fired(I,3)=0
10977     NEXT I
10980     GOTO Red_arty_sead
10983   END IF
10986   Blue_arty_sead: !
10989   FOR I=1 TO 7
10992     IF Bif_msn_tons(I,3)<B_arty_cap(I,3) THEN
10995       Bif_fired(I,3)=Bif_msn_tons(I,3)
10998       Bif_msn_tons(I,3)=0
11001       Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,3)
11004     ELSE
11007       Bif_fired(I,3)=B_arty_cap(I,3)
11010       Bif_msn_tons(I,3)=Bif_msn_tons(I,3)-(B_arty_cap(I,3))
11013       Tot_arty(1,I)=Tot_arty(1,I)+(B_arty_cap(I,3))
11016     END IF
11019   NEXT I
11022   !
11025   Red_arty_sead: !
11028   IF Btl_rg>14000 OR Btl_time<R_prep_time THEN
11031     FOR I=1 TO 7
11034       Rif_fired(I,3)=0
11037     NEXT I
11040     GOTO Blue_mlrs_sead
11043   END IF
11046   FOR I=1 TO 7
11049     IF Rif_msn_tons(I,3)<R_arty_cap(I,3) THEN
11052       Rif_fired(I,3)=Rif_msn_tons(I,3)
11055       Rif_msn_tons(I,3)=0
11058       Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,3)
11061     ELSE
11064       Rif_fired(I,3)=R_arty_cap(I,3)
11067       Rif_msn_tons(I,3)=Rif_msn_tons(I,3)-(R_arty_cap(I,3))
11070       Tot_arty(2,I)=Tot_arty(2,I)+(R_arty_cap(I,3))
11073     END IF
11076   NEXT I

```

Table 6-14. Ground combat code (continued).

```

11079 !
11082 Blue_mlrs_sead: IF Btl_rg>25000 OR Btl_time<B_prep_time THEN
11085   FOR I=12 TO 15
11088     Bif_fired(I,3)=0
11091   NEXT I
11094   GOTO Red_mlrs_sead
11097 END IF
11100 !
11103 FOR I=12 TO 15
11106   IF Bif_msn_tons(I,3)<B_mlrs_cap(I-11,3) THEN
11109     Bif_fired(I,3)=Bif_msn_tons(I,3)
11112     Bif_msn_tons(I,3)=0
11115     Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,3)
11118   ELSE
11121     Bif_fired(I,3)=B_mlrs_cap(I-11,3)
11124     Bif_msn_tons(I,3)=Bif_msn_tons(I,3)-(B_mlrs_cap(I-11,3))
11127     Tot_arty(1,I)=Tot_arty(1,I)+(B_mlrs_cap(I-11,3))
11130   END IF
11133 NEXT I
11136 !
11139 Red_mlrs_sead: !
11142 IF Btl_rg>15500 OR Btl_time<R_prep_time THEN
11145   FOR I=12 TO 15
11148     Rif_fired(I,3)=0
11151   NEXT I
11154   GOTO Allocate_cfire
11157 END IF
11160 FOR I=12 TO 15
11163   IF Rif_msn_tons(I,3)<R_mlrs_cap(I-11,3) THEN
11166     Rif_fired(I,3)=Rif_msn_tons(I,3)
11169     Rif_msn_tons(I,3)=0
11172     Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,3)
11175   ELSE
11178     Rif_fired(I,3)=R_mlrs_cap(I-11,3)
11181     Rif_msn_tons(I,3)=Rif_msn_tons(I,3)-(R_mlrs_cap(I-11,3))
11184     Tot_arty(2,I)=Tot_arty(2,I)+(R_mlrs_cap(I-11,3))
11187   END IF
11190 NEXT I
11193 !
11196 !
11199 Allocate_cfire: ! SCHEDULE INCOMING COUNTERFIRE MISSIONS
11202 !
11205 ! MORTARS DO NOT FIRE COUNTERFIRE
11208 FOR I=8 TO 11
11211   Bif_msn_tons(I,4)=0
11214   Rif_msn_tons(I,4)=0
11217 NEXT I
11220 !
11223 IF Btl_rg>12000 OR Btl_time<B_prep_time THEN
11226   FOR I=1 TO 7
11229     Bif_fired(I,4)=0
11232   NEXT I

```


Table 6-14. Ground combat code (continued).

```

11235 GOTO Red_arty_cfire
11238 END IF
11241 Blue_arty_cfire: !
11244 FOR I=1 TO 7
11247 IF Bif_msn_tons(I,4)<B_arty_cap(I,4) THEN
11250 Bif_fired(I,4)=Bif_msn_tons(I,4)
11253 Bif_msn_tons(I,4)=0
11256 Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,4)
11259 ELSE
11262 Bif_fired(I,4)=B_arty_cap(I,4)
11265 Bif_msn_tons(I,4)=Bif_msn_tons(I,4)-(B_arty_cap(I,4))
11268 Tot_arty(1,I)=Tot_arty(1,I)+(B_arty_cap(I,4))
11271 END IF
11274 NEXT I
11277 !
11280 Red_arty_cfire: !
11283 IF Btl_rg>14000 OR Btl_time<R_prep_time THEN
11286 FOR I=1 TO 7
11289 Rif_fired(I,4)=0
11292 NEXT I
11295 GOTO Blue_mlrs_cfire
11298 END IF
11301 FOR I=1 TO 7
11304 IF Rif_msn_tons(I,4)<R_arty_cap(I,4) THEN
11307 Rif_fired(I,4)=Rif_msn_tons(I,4)
11310 Rif_msn_tons(I,4)=0
11313 Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,4)
11316 ELSE
11319 Rif_fired(I,4)=R_arty_cap(I,4)
11322 Rif_msn_tons(I,4)=Rif_msn_tons(I,4)-(R_arty_cap(I,4))
11325 Tot_arty(2,I)=Tot_arty(2,I)+(R_arty_cap(I,4))
11328 END IF
11331 NEXT I
11334 !
11337 Blue_mlrs_cfire: IF Btl_rg>25000 OR Btl_time<B_prep_time THEN
11340 FOR I=12 TO 15
11343 Bif_fired(I,4)=0
11346 NEXT I
11349 GOTO Red_mlrs_cfire
11352 END IF
11355 !
11358 FOR I=12 TO 15
11361 IF Bif_msn_tons(I,4)<B_mlrs_cap(I-11,4) THEN
11364 Bif_fired(I,4)=Bif_msn_tons(I,4)
11367 Bif_msn_tons(I,4)=0
11370 Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,4)
11373 ELSE
11376 Bif_fired(I,4)=B_mlrs_cap(I-11,4)
11379 Bif_msn_tons(I,4)=Bif_msn_tons(I,4)-(B_mlrs_cap(I-11,4))
11382 Tot_arty(1,I)=Tot_arty(1,I)+(B_mlrs_cap(I-11,4))
11385 END IF
11388 NEXT I

```

Table 6-14. Ground combat code (continued).

```

11391 !
11394 Red_mlrs_cfir: ! CALCULATE PFD MRL COUNTERFIRE
11397 !
11400 IF Btl_rg>15500 OR Btl_time<R_prep_time THEN
11403 FOR I=12 TO 15
11406   Rif_fired(I,4)=0
11409 NEXT I
11412 GOTO Allocate_intd
11415 END IF
11418 FOR I=12 TO 15
11421   IF Rif_msn_tons(I,4)<R_mlrs_cap(I-11,4) THEN
11424     Rif_fired(I,4)=Rif_msn_tons(I,4)
11427     Rif_msn_tons(I,4)=0
11430     Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,4)
11433   ELSE
11436     Rif_fired(I,4)=R_mlrs_cap(I-11,4)
11439     Rif_msn_tons(I,4)=Rif_msn_tons(I,4)-(R_mlrs_cap(I-11,4))
11442     Tot_arty(2,I)=Tot_arty(2,I)+(R_mlrs_cap(I-11,4))
11445   END IF
11448 NEXT I
11451 !
11454 !
11457 Allocate_intd: ! SCHEDULE INCOMING INTERDICTION MISSIONS
11460 !
11463 ! MORTARS DO NOT FIRE INTERDICTION
11466 FOR I=8 TO 11
11469   Bif_msn_tons(I,5)=0
11472   Rif_msn_tons(I,5)=0
11475 NEXT I
11478 !
11481 IF Btl_rg>12000 OR Btl_time<B_prep_time THEN
11484 FOR I=1 TO 7
11487   Bif_fired(I,5)=0
11490 NEXT I
11493 GOTO Red_arty_intd
11496 END IF
11499 Blue_arty_intd: !
11502 !
11505 FOR I=1 TO 7
11508   IF Bif_msn_tons(I,5)<B_arty_cap(I,5) THEN
11511     Bif_fired(I,5)=Bif_msn_tons(I,5)
11514     Bif_msn_tons(I,5)=0
11517     Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,5)
11520   ELSE
11523     Bif_fired(I,5)=B_arty_cap(I,5)
11526     Bif_msn_tons(I,5)=Bif_msn_tons(I,5)-(B_arty_cap(I,5))
11529     Tot_arty(1,I)=Tot_arty(1,I)+(B_arty_cap(I,5))
11532   END IF
11535 NEXT I
11538 !
11541 Red_arty_intd: !
11544 IF Btl_rg>14000 OR Btl_time<R_prep_time THEN

```

Table 6-14. Ground combat code (continued).

```

11547 FOR I=1 TO 7
11550   Rif_fired(I,5)=0
11553 NEXT I
11556 GOTO Blue_mlrs_intd
11559 END IF
11562 !
11565 FOR I=1 TO 7
11568   IF Rif_msn_tons(I,5)<R_arty_cap(I,5) THEN
11571     Rif_fired(I,5)=Rif_msn_tons(I,5)
11574     Rif_msn_tons(I,5)=0
11577     Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,5)
11580   ELSE
11583     Rif_fired(I,5)=R_arty_cap(I,5)
11586     Rif_msn_tons(I,5)=Rif_msn_tons(I,5)-(R_arty_cap(I,5))
11589     Tot_arty(2,I)=Tot_arty(2,I)+(R_arty_cap(I,5))
11592   END IF
11595 NEXT I
11598 !
11601 Blue_mlrs_intd: IF Btl_rg>25000 OR Btl_time<B_prep_time THEN
11604   FOR I=12 TO 15
11607     Bif_fired(I,5)=0
11610   NEXT I
11613   GOTO Red_mlrs_intd
11616 END IF
11619 !
11622 FOR I=12 TO 15
11625   IF Bif_msn_tons(I,5)<B_mlrs_cap(I-11,5) THEN
11628     Bif_fired(I,5)=Bif_msn_tons(I,5)
11631     Bif_msn_tons(I,5)=0
11634     Tot_arty(1,I)=Tot_arty(1,I)+Bif_fired(I,5)
11637   ELSE
11640     Bif_fired(I,5)=B_mlrs_cap(I-11,5)
11643     Bif_msn_tons(I,5)=Bif_msn_tons(I,5)-(B_mlrs_cap(I-11,5))
11646     Tot_arty(1,I)=Tot_arty(1,I)+(B_mlrs_cap(I-11,5))
11649   END IF
11652 NEXT I
11655 !
11658 Red_mlrs_intd: ! CALCULATE RED MRL INTERDICTION
11661 !
11664 IF Btl_rg>15500 OR Btl_time<R_prep_time THEN
11667   FOR I=12 TO 15
11670     Rif_fired(I,5)=0
11673   NEXT I
11676   GOTO End_arty_arrive
11679 END IF
11682 FOR I=12 TO 15
11685   IF Rif_msn_tons(I,5)<R_mlrs_cap(I-11,5) THEN
11688     Rif_fired(I,5)=Rif_msn_tons(I,5)
11691     Rif_msn_tons(I,5)=0
11694     Tot_arty(2,I)=Tot_arty(2,I)+Rif_fired(I,5)
11697   ELSE
11700     Rif_fired(I,5)=R_mlrs_cap(I-11,5)

```

Table 6-14. Ground combat code (continued).

```

11703   Rif_msn_tons(I,5)=Rif_msn_tons(I,5)-(R_mlrs_cap(I-11,5))
11706   Tot_arty(2,I)=Tot_arty(2,I)+(R_mlrs_cap(I-11,5))
11709   END IF
11712   NEXT I
11715   !
11718   !
11721   End_arty_arrive:RETURN
11724   !
11727   !-----
11730   !
11733   Calc_movement:  ! THIS SBR CALCULATES ATTACKER MOVEMENT DISTANCES DURING
11736   !                 THE DESIGNATED 30 MINUTE PERIOD
11739   !
11742   Prev30_btl_rg=Btl_rg
11745   !
11748   ! SET NUMBER OF MINUTES ADVANCED
11751   IF Mine_delay<30 THEN
11754   Move_minutes=30-Mine_delay
11757   ELSE
11760   Move_minutes=0
11763   Mine_delay=Mine_delay-30
11766   END IF
11769   !
11772   ! SET UNSUPPRESSED ADVANCE RATE PER MINUTE
11775   IF Atk_def=0 THEN
11778   Mission=R_msn(1)
11781   ELSE
11784   Mission=B_msn(1)
11787   END IF
11790   !
11793   IF Btl_phase=1 THEN
11796   Phase=1
11799   ELSE
11802   Phase=3
11805   END IF
11808   !
11811   M_per_minute=Advance_rate(Phase+Ride,Mission)
11814   Unsupp_advance=M_per_minute*Move_minutes
11817   !
11820   ! CALCULATE SUPPRESSION FROM CASUALTIES (UP TO 40%)
11823   !       6% CASUALTIES IN THE PREVIOUS GAME TURN WILL CAUSE MAX
11826   !       MOVEMENT SUPPRESSION
11829   !
11832   IF Atk_def=0 THEN
11835   Casualty_level=(Prev30_r_eff/Init_r_eff)-Curr_r_eff
11838   ELSE
11841   Casualty_level=(Prev30_b_eff/Init_b_eff)-Curr_b_eff
11844   END IF
11847   IF Casualty_level>.06 THEN Casualty_level=.06
11850   Cas_suppr=.40*Casualty_level/.06
11853   !
11856   ! CALCULATE SUPPRESSION FROM ARTILLERY (UP TO 30%)

```

Table 6-14. Ground combat code (continued).

```

11859 !      DS AND COUNTERPREP SUPPRESS ATTACKER MOVEMENT
11862 !      A SINGLE 155mm EQUIV MISSION SUPPRESSES A CO-
11865 !      SIZED ELEMENT FOR 5 MINUTES
11868 !
11871 IF Atk_def=0 THEN
11874   Side=4
11877 ELSE
11880   Side=2
11883 END IF
11886 !
11889 ! TALLY SYSTEMS TO BE SUPPRESSED
11892 Tot_systems=0
11895 FOR I=1 TO 20   ! TALLY DIRECT FIRE PLATFORMS
11898   Tot_systems=Tot_systems+Sys_tot(Side,I)
11901 NEXT I
11904 FOR I=36 TO 47   ! TALLY SMALL ARMS (INFANTRY)
11907   Tot_systems=Tot_systems+Sys_tot(Side,I)/8
11910 NEXT I
11913 !
11916 ! TALLY AMOUNT OF INCOMING FIRE
11919 IF Atk_def=0 THEN
11922   FOR I=1 TO 7
11925     Incoming_arty(I)=Bif_fired(I,1)+Bif_fired(I,2)
11928   NEXT I
11931   FOR I=1 TO 4
11934     Incoming_mlr(I)=Bif_fired(I+11,1)
11937   NEXT I
11940   FOR I=1 TO 4
11943     Incoming_mort(I)=Bif_fired(I+7,1)+Bif_fired(I+7,2)
11946   NEXT I
11949 ELSE
11952   FOR I=1 TO 7
11955     Incoming_arty(I)=Rif_fired(I,1)+Rif_fired(I,2)
11958   NEXT I
11961   FOR I=1 TO 4
11964     Incoming_mlr(I)=Rif_fired(I+11,1)
11967   NEXT I
11970   FOR I=1 TO 4
11973     Incoming_mort(I)=Rif_fired(I+7,1)+Rif_fired(I+7,2)
11976   NEXT I
11979 END IF
11982 !
11985 ! TALLY 155mm MISSION EQUIVALENTS
11988 Arty_equiv=0
11991 Mort_equiv=0
11994 Mlr_equiv=0
11997 FOR I=1 TO 7   !NEED TO CHANGE NO. OF TONS W/IN TYPES??
12000   Arty_equiv=Arty_equiv+Incoming_arty(I)/1.8   ! 1.8=TONS IN 1 FA 155mm M
12003 NEXT I
12006 FOR I=1 TO 4
12009   Mort_equiv=Mort_equiv+Incoming_mort(I)/1.2 ! 1.2=TONS IN A MORTAR->155r
EQUIV

```

Table 6-14. Ground combat code (continued).

```

12012 NEXT I
12015 FOR I=1 TO 4
12018 Mlrs_equiv=Mlrs_equiv+Incoming_mlr(I)/1.8
12021 NEXT I
12024 Tot_incom_msn=Arty_equiv+Mort_equiv+Mlrs_equiv
12027 !
12030 ! TALLY NUMBER OF COMPANY EQUIVALENTS
12033 Arty_level=0
12036 IF Tot_incom_msn=0 THEN GOTO Helo_suppress
12039 Company_equiv=Tot_systems/28
12042 Arty_level=Tot_incom_msn/Company_equiv
12045 !
12048 ! COMPUTE ARTY LEVEL
12051 IF Arty_level>6 THEN Arty_level=6
12054 !
12057 ! COMPUTE ARTILLERY SUPPRESSION
12060 IF Atk_def=0 THEN
12063 Arty_suppr=Arty_level*.30/6
12066 ELSE
12069 Arty_suppr=Arty_level*.40/6
12072 END IF
12075 !
12078 ! CALCULATE SUPPRESSION FROM ATK HELICOPTERS (UP TO 20%)
12081 !     ONE ATTACK HELICOPTER WILL SUPPRESS THE MOVEMENT
12084 !     OF 12 VEHICLES
12087 Helo_suppress: !
12090 Tot_vehicles=0
12093 IF Atk_def=0 THEN
12096 Side=4
12099 ELSE
12102 Side=2
12105 END IF
12108 FOR I=1 TO 20
12111 Tot_vehicles=Tot_vehicles+Sys_tot(Side,I)
12114 NEXT I
12117 Tot_vehicles=Tot_vehicles+.5*Sys_tot(Side,48)+.20*Sys_tot(Side,10)
12120 IF Atk_def=0 THEN
12123 Atk_helos=Bah1+Bah2
12126 ELSE
12129 Atk_helos=Rah1+Rah2
12132 END IF
12135 Atk_helo_level=0
12138 IF Tot_vehicles=0 THEN GOTO Atkhelo_s
12141 Atk_helo_level=12*Atk_helos/Tot_vehicles
12144 IF Atk_helo_level>1 THEN Atk_helo_level=1
12147 Atkhelo_s: !
12150 Atkhelo_suppr=Atk_helo_level*.30
12153 !
12156 Tot_move_suppr=Cas_suppr+Arty_suppr+Atkhelo_suppr
12159 !
12162 ! CALCULATE AMOUNT OF ADVANCE
12165 !

```

Table 6-14. Ground combat code (continued).

```

12168 Amt_of_advance=Unsupp_advance*(1-Tot_move_suppr)
12171 !
12174 RETURN
12177 !
12180 ! -----
12183 !
12186 Mine_encounter: ! THIS SBR CHECKS FOR MINEFIELD ACTIVATION
12189 !
12192 Mine_hit=0
12195 IF No_minefields=0 THEN End_mine_encoun
12198 FOR I=1 TO No_minefields
12201 IF Btl_rg-Amt_of_advance<Minefield(I,1) AND Minefield(I,6)=0 THEN
12204 ! MINEFIELD ENCOUNTERED WHICH HAS NOT BEEN ASSESSED BEFORE
12207 Mine_hit=I
12210 !
12213 ! CALCULATE MINE DELAY AND SET MINE TACTIC
12216 SELECT Atk_def
12219 CASE 0 ! RED IS ENTERING MINEFIELD
12222 Mine_vic$="RED"
12225 ! CHECK FOR OVER KILL BY MINES
12228 IF (Curr_r_eff-R_cas_break)<.05 THEN
12231 IF Minefield(I,1)>Df_rg THEN
12234 Mine_delay=30
12237 ELSE
12240 Mine_delay=45
12243 END IF
12246 Bul_bch=0
12249 GOTO Mine_clear
12252 END IF
12255 CASE 1 ! BLUE IS ENTERING MINEFIELD
12258 Mine_vic$="BLUE"
12261 ! CHECK FOR OVERKILL BY MINES
12264 IF (Curr_b_eff-B_cas_break)<.05 THEN
12267 SELECT Btl_phase
12270 CASE 1
12273 Mine_delay=30
12276 CASE 2,3
12279 Mine_delay=45
12282 END SELECT
12285 Bul_bch=0
12288 GOTO Mine_clear
12291 END IF
12294 END SELECT
12297 GOTO Bull_or_breach
12300 Mine_clear: !
12303 PRINT
12306 PRINT " ";Mine_vic$;" ENCOUNTERS MINEFIELD WITH CASUALTIES NEAR BR
POINT"
12309 PRINT
12312 PRINT " ";Mine_vic$;" STOPS TO CLEAR MINEFIELD"
12315 GOTO End_delay
12318 Bull_or_breach: !

```

Table 6-14. Ground combat code (continued).

```

12321 IF Minefield(I,1)>Df_rg THEN
12324   Max_delay=30
12327   Bul_bch=2
12330   Mine_tac$="BREACH"
12333 ELSE
12336   Max_delay=10
12339   Bul_bch=1
12342   Mine_tac$="BULL THROUGH"
12345 END IF
12348 Mine_delay=Max_delay*Minefield(Mine_hit,2)/Minefield(Mine_hit,3)*Mine
eld(Mine_hit,4)/100
12351 PRINT
12354 PRINT "   ";Mine_vic$;" ENCOUNTERS MINEFIELD"
12357 PRINT
12360 PRINT "   ";Mine_vic$;" ELECTS TO ";Mine_tac$;" MINEFIELD"
12363 End_delay: !
12366   Prnt_mn_dlay=Mine_delay
12369   GOTO End_mine_encoun
12372 END IF
12375 NEXT I
12378 End_mine_encoun: !
12381 RETURN
12384 !
12387 ! -----
12390 !
12393 Phase1_btl: ! THIS SBR CONDUCTS THE ATTRITION ASSESSMENTS FOR THE
12396 !   PHASE 1 (PRE-CLOSURE FIRE) BATTLE
12399 !
12402 Phase_ct(1)=Phase_ct(1)+1 !COUNTS NUMBER OF 30MIN. INTERVALS OF THIS PHA
12405 Del_blue=0
12408 Del_red=0
12411 GOSUB Phase_int
12414 ! ** MINEFILD PORTION OF PHASE I **
12417 ! CHECK FOR MINEFIELD ASSESSMENTS
12420 IF Mine_hit=0 THEN GOTO Run_arty
12423 IF Minefield(Mine_hit,6)=1 THEN GOTO Run_arty
12426 !
12429 GOSUB Run_mine
12432 !
12435 !
12438 Run_arty: !** ARTILLERY ATTRITION OF PHASE I **
12441 !
12444 !CHECK ON INDIRECT FIRE USED THIS PHASE
12447 Blue_aty=0 !BLUE FIRE FLAG
12450 Red_aty=0 !RED FIRE FLAG
12453 FOR I=1 TO 15
12456   FOR J=1 TO 5
12459     IF Bif_fired(I,J)>0 THEN Blue_atv=1
12462     IF Rif_fired(I,J)>0 THEN Red_atv=1
12465   NEXT J
12468 NEXT I
12471 !

```


Table 6-14. Ground combat code (continued).

```

12474 !SET PARAMETERS FOR ARTY.
12477 IF Blue_aty=0 AND Red_aty=0 THEN GOTO Direct_fire
12480 !
12483 GOSUB Arty_sub
12486 !
12489 Direct_fire: ! ** DIRECT FIRE PORTION OF PHASE I **
12492 IF Atk_def=0 THEN
12495 A_pct_fwd=R_pct_fwd !RED ATTACKER SET ATTACKER FORWARD
12498 D_pct_fwd=B_pct_fwd !BLUE IS DEFENDER
12501 ELSE
12504 A_pct_fwd=B_pct_fwd !BLUE ATTACKER
12507 D_pct_fwd=R_pct_fwd !RED DEFENDER
12510 END IF
12513 FOR I=1 TO 2
12516 FOR J=1 TO 3
12519 Cell(I,2,J)=0 !ZERO OUT RED & BLUE HELD'S CELLS
12522 NEXT J
12525 NEXT I
12528 Cell(1,1,1)=Bah1 !LOAD UP CELLS
12531 Cell(1,1,2)=Bah2
12534 Cell(1,1,3)=Bsct
12537 Cell(2,1,1)=Rah1
12540 Cell(2,1,2)=Rah2
12543 Cell(2,1,3)=Rsct
12546 CALL Helo_range(Cell(*),Helo_mis(*),Stnd_off_rg(*)) !CALCULATE RANGES
12549 !
12552 !IF DEFENDER HAS NO FORCES FORWARD THEN THERE WILL BE NO DIRECT FIRE
12555 !BATTLE IN PHASE I.
12558 IF D_pct_fwd=0 THEN GOTO Helo_atrit
12561 !
12564 !DEFENDER IS FORWARD. DETERMINE IF DEFENDER PULLED BACK FOR ATTRITIO
12567 IF Atk_def=0 THEN !RED IS DEFENDER
12570 !CALCULATE FP SCORE
12573 CALL Fwdfp(Sys_tot(*),Bf_mask(*),Atk_def,D_pct_fwd,D_fp,Sys_eff(*))
12576 ELSE !BLUE IS DEFENDER
12579 !CALCULATE FP SCORE
12582 CALL Fwdfp(Sys_tot(*),Rf_mask(*),Atk_def,D_pct_fwd,D_fp,Sys_eff(*))
12585 END IF
12588 !
12591 !
12594 IF D_fp>.25 THEN GOTO Start_direct
12597 PRINT
12600 PRINT " FORWARD FORCES ATTRITED TO ";D_fp
12603 PRINT
12606 PRINT " NO DIRECT FIRE PHASE I BATTLE IN STEP ";Phase_ct(1)
12609 GOTO Helo_atrit
12612 !
12615 Start_direct: !
12618 IF A_pct_fwd<>0 THEN GOTO Attack_fwd
12621 !
12624 !ATTACKING MAIN BODY ; SET UP ARRAY
12627 IF Atk_def=0 THEN GOTO Red_attck

```

Table 6-14. Ground combat code (continued).

```

12630 FOR I=1 TO 70      !SET UP BLUE MAIN BODY
12633 Sys(1,I)=Sys_tot(2,I)*Bdf_mask(1,I)*B_df_t(B_ms,I)
12636 Sys(5,I)=Sys_tot(2,I)*Bdf_mask(1,I)*B_f(B_ms,I)
12639 NEXT I            !***** ANTI-ARMOR
12642 FOR I=1 TO 70    !SET UP RED ELEMENTS
12645 Sys(3,I)=Sys_tot(4,I)*Rf_mask(I)*D_pct_fwd
12648 Sys(6,I)=Sys(3,I)
12651 NEXT I
12654 !SET UP VULNERABILITY--ASSUME MAIN BODY WILL HAVE GIVEN VULNERABILITY
12657 FOR I=1 TO 70
12660 Blue_vul(I)=B_v(B_ms,I)
12663 Red_vul(I)=.25          !RED DEFENDERS FORWARD
12666 NEXT I
12669 GOTO Call_df_cbt
12672 Red_attck: ! RED ATTACKING WITH NO FORCES FORWARD
12675 FOR I=1 TO 70      !SET UP RED MAIN BODY
12678 Sys(3,I)=Sys_tot(4,I)*Rdf_mask(1,I)*R_df_t(R_ms,I)
12681 Sys(6,I)=Sys_tot(4,I)*Rdf_mask(1,I)*R_df_t(R_ms,I)
12684 NEXT I
12687 FOR I=1 TO 70    !SET UP BLUE ELEMENTS
12690 Sys(1,I)=Sys_tot(2,I)*Bf_mask(I)*D_pct_fwd
12693 Sys(5,I)=Sys(1,I)
12696 NEXT I
12699 Sys(1,5)=0 !TEMPORARY CODE FOR HTLE/ADEA ONLY
12702 FOR I=1 TO 70
12705 Red_vul(I)=R_v(R_ms,I)
12708 Blue_vul(I)=.25
12711 NEXT I
12714 GOTO Call_df_cbt
12717 Attack_fwd: ! BOTH ATTACKER AND DEFENDER HAVE FORCES FORWARD
12720 FOR I=1 TO 70
12723 Sys(1,I)=Sys_tot(2,I)*Bf_mask(I)*B_pct_fwd
12726 Sys(5,I)=Sys(1,I)
12729 Sys(3,I)=Sys_tot(4,I)*Rf_mask(I)*R_pct_fwd
12732 Sys(6,I)=Sys(3,I)
12735 NEXT I
12738 Sys(1,5)=0 !TEMPORARY CODE FOR HTLD/ADEA ONLY
12741 FOR I=1 TO 70
12744 Red_vul(I)=.25          !ASSUME BOTH RED AND BLUE
12747 Blue_vul(I)=.25        !ELEMENTS FORWARD HAVE ONLY 25% EXPOSED
12750 NEXT I
12753 !
12756 !NOW CAL GROUND ATTRITION ; NOTE-ONLY HANDLING 1 RANGE BAND AT 2000M
12759 Call_df_cbt: !
12762 Btl_phase=1 !BATTLE PHASE 1
12765 !SET RANGE BAND
12768 SELECT Vis
12771 CASE 1 TO 2
12774 Rng_band=4 !ENGAGEMENTS AT 2000m
12777 CASE 3
12780 Rng_band=3 !ENGAGEMENTS AT 1500m
12783 CASE 4

```

Table 6-14. Ground combat code (continued).

```

12786 Rng_band=1      !ENGAGEMENTS AT 0 TO 500m FOR 1km DAY
12789 END SELECT
12792 Terrain=R_terr  !FIGHT ON DEFENDERS TERRAIN
12795 IF Atk_def=1 THEN Terrain=R_terr
12798 Num_bands=.5    !ONLY HALF A RANGE BAND
12801 GOSUB Df_cbt
12804 !
12807 Helo_atrit: ! ** HELICOPTER ATTRITION FOR PHASE I **
12810 IF Bah1+Bah2+Bsc<=0 AND Rah1+Rah2+Rsct<=0 THEN GOTO No_helo1
12813 !LOAD CELL SIZES
12816 Arty(1)=2        !ARTILLERY NOT SHOOTING
12819 Arty(2)=2
12822 Veh_ada(1)=Bveh_sup !SUPPRESSION OF VEHICULAR & HAND-HELD ADA
12825 Veh_ada(2)=Rveh_sup
12828 Hnd_ada(1)=Bhnd_sup
12831 Hnd_ada(2)=Rhnd_sup
12834 Time_step=15
12837 !SET VULNERABILITY OF RED TARGETS
12840 IF L_blue_helos=Phase_ct(1)-1 THEN
12843 Del_red=Del_red+1
12846 ELSE
12849 Del_red=0
12852 END IF
12855 L_blue_helos=Phase_ct(1)
12858 FOR I=1 TO 70
12861 P_def(2,I)=R_v(R_ms,I)+Del_red*R_dv(R_ms,I)
12864 IF P_def(2,I)<.1 THEN P_def(2,I)=.1
12867 IF P_def(2,I)>.9 THEN P_def(2,I)=.9
12870 NEXT I
12873 !SET VULNERABILITY OF BLUE TARGETS
12876 IF L_red_helos=Phase_ct(1)-1 THEN
12879 Del_blue=Del_blue+1
12882 ELSE
12885 Del_blue=0
12888 END IF
12891 L_red_helos=Phase_ct(1)
12894 FOR I=1 TO 70
12897 P_def(1,I)=B_v(B_ms,I)+Del_blue*B_dv(B_ms,I)
12900 IF P_def(1,I)<.1 THEN P_def(1,I)=.1
12903 IF P_def(1,I)>.9 THEN P_def(1,I)=.9
12906 NEXT I
12909 ! ---PREPARE FORCES
12912 FOR I=1 TO 70 !RED GROUND TARGETS
12915 Target(1,I)=Sys_tot(4,I)*R_df_t(R_ms,I)
12918 Target(2,I)=0
12921 Helo_tgt(2,1,I)=Target(1,I) !PASSED TO HELO_KILLS (INITIAL NO.)
12924 Helo_tgt(2,2,I)=0 !REMAINING NO OF TGTS
12927 NEXT I
12930 !
12933 !APPORTION RED AD AMMO BASED ON RED TARGET ELEMENTS
12936 ! RED AD SYSTEMS
12939 Adside=2

```

Table 6-14. Ground combat code (continued).

```

12942 Ad_ammo=R_ad_ammo
12945 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(2),Basic_ld(*
Ammo_wt(*))
12948 Ad_sv(2)=Ad_helo(2)
12951 Sided=2
12954 FOR I=1 TO 70
12957   H_targ(3,I)=Target(1,I)
12960 NEXT I
12963 CALL Dismount(H_targ(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mount,R_dmout
12966 CALL Apport_inf(Target(*),1,R_dmout)
12969   !RED HELOS--PREPARE BLUE FORCES
12972 FOR I=1 TO 70
12975   Target(1,I)=Sys_tot(2,I)*B_df_t(B_ms,I)
12978   Target(2,I)=0
12981   Helo_tgt(1,1,I)=Target(1,I)      !PASSED TO HELO_KILLS (INITIAL NO.)
12984   Helo_tgt(1,2,I)=0              !REMAINING NO OF TGTS
12987 NEXT I
12990   'APPORTION BLUE AD AMMO
12993   ! BLUE AD SYSTEMS
12996 Adside=1
12999 Ad_ammo=B_ad_ammo
13002 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(1),Basic_ld(*
Ammo_wt(*))
13005 Ad_sv(1)=Ad_helo(1)
13008 Df_ammo(1)=B_df_ammo
13011 Df_ammo(2)=R_df_ammo
13014 Sided=1
13017 FOR I=1 TO 70
13020   H_targ(1,I)=Target(1,I)
13023 NEXT I
13026 CALL Dismount(H_targ(*),B_ld_fact,B_msn(1),Sided,Btl_rg,B_mount,B_dmout
13029 CALL Apport_inf(Target(*),1,B_dmout)
13032!
13035 CALL Helo_kills(Cell(*),Helo_tgt(*),Ad_helo(*),Terr,Atk_prof(*),Helo_mis
),Day_nite,Time_step,P_def(*),Arty(*),Veh_ada(*),Hnd_ada(*),Std_off_rg(*),Vis
13038!
13041 R_ad_ammo=R_ad_ammo-(Ad_sv(2)-Ad_helo(2))
13044 B_ad_ammo=B_ad_ammo-(Ad_sv(1)-Ad_helo(1))
13047 B_df_ammo=Df_ammo(1)
13050 R_df_ammo=Df_ammo(2)
13053   !
13056   !STORE KILLS AND SUBTRACT BLUE HELICOPTERS
13059 FOR Side=1 TO 2
13062   FOR I=1 TO 70
13065     Sys_helo(Side,I)=Helo_tgt(Side,1,I)-Helo_tgt(Side,2,I)
13068   NEXT I
13071   IF Side=1 THEN CALL Inf_survive(H_targ(*),1,Sys_helo(*),1,B_ld_fact,Inf
urv(*))
13074   IF Side=2 THEN CALL Inf_survive(H_targ(*),3,Sys_helo(*),2,R_ld_fact,Inf
urv(*))
13077   FOR I=36 TO 40
13080     Sys_helo(Side,I)=Sys_helo(Side,I)+Inf_surv(I-35)

```

Table 6-14. Ground combat code (continued).

```

13083 NEXT I
13086 NEXT Side
13089 !REMOVE HELOS (ATTACKING AND DEFENDING)
13092 FOR I=1 TO 3
13095 B_helo(I,2)=B_helo(I,2)+Cell(1,1,I)-Cell(1,2,I)
13098 R_helo(I,2)=R_helo(I,2)+Cell(2,1,I)-Cell(2,2,I)
13101 NEXT I
13104 !SUBTRACT SYSTEM LOSSES
13107 FOR I=1 TO 70
13110 Sys_tot(2,I)=Sys_tot(2,I)-Sys_helo(1,I)
13113 Sys_tot(4,I)=Sys_tot(4,I)-Sys_helo(2,I)
13116 NEXT I
13119 No_helol: !
13122 !
13125 ! ** PGM PORTION OF PHASE I **
13128 !SET UP CLGP AND GAMP ARRAY FACTORS
13131 FOR I=1 TO 70
13134 Gamp_fact(I)=R_df_t(R_ms,I)
13137 Clgp_fact(I)=2*R_pct_fwd
13140 IF R_pct_fwd=0 THEN Clgp_fact(I)=R_df_t(R_ms,I)*2
13143 IF Clgp_fact(I)>1 OR Clgp_rpv=1 THEN Clgp_fact(I)=1
13146 NEXT I
13149 GOSUB Clgp_gamp_atrit
13152 !
13155 GOSUB Updatek_v
13158 !
13161 End_phase1_btl:RETURN ! ** END BATTLE PHASE I **
13164 !
13167 !-----
13170 !
13173 Phase2_btl: ! THIS SBR ASSESSES ATTRITION IN THE PHASE 2 (DIRECT FIRE)
13176 !
13179 Phase_ct(2)=Phase_ct(2)+1 !COUNT NUMBER OF 30 MIN INTERVALS IN PHASE
13182 Btl_phase=2
13185 GOSUB Phase_int !ZERO ALL KILL ARRAYS FOR THIS 30 MINUTES
13188 !
13191 ! ** MINEFIELD PORTION OF PHASE II **
13194 IF Mine_hit=0 THEN GOTO Arty_phase2
13197 IF Minefield(Mine_hit,6)=1 THEN GOTO Arty_phase2
13200 GOSUB Run_mine
13203 Arty_phase2: ! ** ARTILLERY PORTION OF PHASE II **
13206 !
13209 !CHECK ON INDIRECT FIRE USED IN THIS PHASE
13212 Blue_aty=0 !BLUE FIRE FLAG
13215 Red_aty=0 !RED FIRE FLAG
13218 FOR I=1 TO 15
13221 FOR J=1 TO 5
13224 IF Bif_fired(I,J)>0 THEN Blue_aty=1
13227 IF Rif_fired(I,J)>0 THEN Red_aty=1
13230 NEXT J
13233 NEXT I
13236 IF Blue_aty=0 AND Red_aty=0 THEN GOTO Dir_fir2

```

Table 6-14. Ground combat code (continued).

```

13239 GOSUB Arty_sub
13242 Dir_fir2: ! ** DIRECT FIRE PORTION OF PHASE II **
13245 !SET UP FORCES FOR TARGETS IN DIRECT FIRE
13248 Del_30=Phase_ct(2)-1
13251 GOSUB Collect_trucks !TEMPORARY CODE FOR HTLE/ADEA ONLY
13254 FOR I=1 TO 70
13257 Red_fct=R_f(R_ms,I)+Del_30*R_df(R_ms,I)
13260 Blue_fct=B_f(B_ms,I)+Del_30*B_df(B_ms,I)
13263 IF Red_fct>.95 THEN Red_fct=.95
13266 IF Blue_fct>.95 THEN Blue_fct=.95 !ADJUST FIRERS FOR THIS 30 MIN
13269 IF Blue_fct<.05 THEN Blue_fct=.05
13272 IF Red_fct<.05 THEN Red_fct=.05
13275 Sys(5,I)=Sys_tot(2,I)*Bdf_mask(Balb,I)*Blue_fct !SET # BLUE FIRE
13278 Sys(6,I)=Sys_tot(4,I)*Rdf_mask(Ralb,I)*Red_fct !SET # RED FIRE
13281 !CALCULATE # OF SYSTEMS WHICH ARE TARGETS
13284 Red_f_t(I)=R_df_t(R_ms,I)+Del_30*R_df_dt(R_ms,I)
13287 Blue_f_t(I)=B_df_t(B_ms,I)+Del_30*B_df_dt(B_ms,I)
13290 IF Red_f_t(I)>1 THEN Red_f_t(I)=1
13293 IF Blue_f_t(I)>1 THEN Blue_f_t(I)=1
13296 IF Red_f_t(I)<.05 THEN Red_f_t(I)=.05
13299 IF Blue_f_t(I)<.05 THEN Blue_f_t(I)=.05
13302 Sys(1,I)=Sys_tot(2,I)*Blue_f_t(I)*Bdf_mask(Balb,I)
13305 Sys(3,I)=Sys_tot(4,I)*Red_f_t(I)*Rdf_mask(Ralb,I)
13308 !CALCULATE SYSTEM VULNERABILITIES
13311 Red_fct=R_v(R_ms,I)+R_dv(R_ms,I)*Del_30
13314 Blue_fct=B_v(B_ms,I)+B_dv(B_ms,I)*Del_30
13317 IF Red_fct>1 THEN Red_fct=1
13320 IF Blue_fct>1 THEN Blue_fct=1
13323 IF Red_fct<.05 THEN Red_fct=.05
13326 IF Blue_fct<.05 THEN Blue_fct=.05
13329 Red_vul(I)=Red_fct
13332 Blue_vul(I)=Blue_fct
13335 NEXT I
13338 !
13341 Sys(1,5)=0 !TEMPORARY CODE FOR HTLE/ADEA ONLY
13344 !SET UP GROUND ATRITION PARAMETERS
13347 Btl_phase=2
13350 !DETERMINE PROPER RANGE BAND
13353 Rng_band=Cur_bnd
13356 Num_bands=Df_500_bds
13359 IF Cur_bnd-Num_bands<0 THEN Num_bands=1
13362 IF Amt_of_advance=0 AND Cur_bnd<>0 THEN
13365 Cur_bnd=Cur_bnd !NO ADVANCE
13368 ELSE
13371 Cur_bnd=Cur_bnd-Num_bands !SET UP CURRENT BAND FOR NEXT CALL
13374 END IF
13377 IF Cur_bnd<0 THEN Rng_band=1 !DON'T ALLOW FORCES TOGET BEHIND EACH OTH
13380 Terrain=B_terr !FIGHT ON DEFENDERS TERRAIN
13383 IF Atk_def=1 THEN Terrain=R_terr
13386 !
13389 FOR I=1 TO 2
13392 FOR J=1 TO 3

```

Table 6-14. Ground combat code (continued).

```

13395 Cell(1,2,J)=0 !ZERO OUT RED & BLUE HELO'S CELLS
13398 NEXT J
13401 NEXT I
13404 Cell(1,1,1)=Bah1 !LOAD UP CELLS
13407 Cell(1,1,2)=Bah2
13410 Cell(1,1,3)=Bsct
13413 Cell(2,1,1)=Rah1
13416 Cell(2,1,2)=Rah2
13419 Cell(2,1,3)=Rsct
13422 CALL Helo_range(Cell(*),Helo_mis(*),Stnd_off_rg(*)) !CALCULATE RANGES
!FOR HELICOPTERS

13425 GOSUB Df_cbt !PERFORM DIRECT FIRE COMBAT
13428 !
13431 ! ** HELICOPTER ATTRITION OF PHASE II **
13434 IF Bah1+Bah2+Bsct<=0 AND Rah1+Rah2+Rsct<=0 THEN GOTO No_helo2
13437 !
13440 Arty(1)=2
13443 Arty(2)=2
13446 Veh_ada(1)=Bveh_sup !SUPPRESSION OF VEHICULAR & HAND-HELD ADA
13449 Veh_ada(2)=Rveh_sup
13452 Hnd_ada(1)=Bhnd_sup
13455 Hnd_ada(2)=Rhnd_sup
13458 Time_step=15
13461 !BLUE HELOS ---- PREPARE RED FORCES
13464 FOR I=1 TO 70
13467 Target(1,I)=Sys_tot(4,I)*Red_f_t(I)*Rdf_mask(Ralb,I)
13470 Target(2,I)=0
13473 P_def(2,I)=Red_vul(I) !SET VULNERABILITY
13476 Helo_tgt(2,1,I)=Target(1,I) !PASSED TO HELO_KILLS (INITIAL NO OF TGTS
13479 Helo_tgt(2,2,I)=0 !REMAINING NO. OF TARGETS
13482 NEXT I
13485 !
13488 !APPORTION RED AD AMMO BASED ON RED TARGETS
13491 ! RED AD SYSTEMS
13494 Adside=2
13497 Ad_ammo=R_ad_ammo
13500 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(2),Basic_ld(
Ammo_wt(*))
13503 Ad_sv(2)=Ad_helo(2)
13506 Sided=2
13509 FOR I=1 TO 70
13512 H_targ(3,I)=Target(1,I)
13515 NEXT I
13518 CALL Dismount(H_targ(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mount,R_dmoun
13521 CALL Apport_inf(Target(*),1,R_dmoun)
13524 !
13527 !RED HELOS -- PREPARE FORCES
13530 FOR I=1 TO 70
13533 Target(1,I)=Sys_tot(2,I)*Blue_f_t(I)*Bdf_mask(Balb,I)
13536 Target(2,I)=0
13539 P_def(1,I)=Blue_vul(I) !SET VULNERABILITY
13542 Helo_tgt(1,1,I)=Target(1,I) !PASSED TO HELO_KILLS (INITIAL NO.)

```

Table 6-14. Ground combat code (continued).

```

13545 Helo_tgt(1,2,I)=0          'SET REMAINING NO. OF TGTS TO 0
13548 NEXT I
13551 !APPORTION AD_AMMO TO BLUE AD SYSTEMS
13554 Adside=1
13557 Ad_ammo=B_ad_ammo
13560 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(1),Basic_ld(*
Ammo_wt(*))
13563 Ad_sv(1)=Ad_helo(1)
13566 Df_ammo(1)=B_df_ammo
13569 Df_ammo(2)=R_df_ammo
13572 Sided=1
13575 FOR I=1 TO 70
13578 H_targ(1,I)=Target(1,I)
13581 NEXT I
13584 CALL Dismount(H_targ(*),B_ld_fact,B_msn(1),Sided,Btl_rg,B_mount,B_dmount
13587 CALL Apport_inf(Target(*),1,B_dmount)
13590 !
13593 CALL Helo_kills(Cell(*),Helo_tgt(*),Ad_helo(*),Terr,Atk_prof(*),Helo_mis
),Day_nite,Time_step,P_def(*),Arty(*),Veh_ada(*),Hnd_ada(*),Std_off_rg(*),Vis
13596 !
13599 R_ad_ammo=R_ad_ammo-(Ad_sv(2)-Ad_helo(2))
13602 B_ad_ammo=B_ad_ammo-(Ad_sv(1)-Ad_helo(1))
13605 B_df_ammo=Df_ammo(1)
13608 R_df_ammo=Df_ammo(2)
13611 !STORE KILLS AND SUBTRACT BLUE HELICOPTERS
13614 FOR Side=1 TO 2
13617 FOR I=1 TO 70
13620 Sys_helo(Side,I)=Helo_tgt(Side,1,I)-Helo_tgt(Side,2,I)
13623 NEXT I
13626 IF Side=1 THEN CALL Inf_survive(H_targ(*),1,Sys_helo(*),1,B_ld_fact,Inf
urv(*))
13629 IF Side=2 THEN CALL Inf_survive(H_targ(*),3,Sys_helo(*),2,R_ld_fact,Inf
urv(*))
13632 FOR I=36 TO 40
13635 Sys_helo(Side,I)=Sys_helo(Side,I)+Inf_surv(I-35)
13638 NEXT I
13641 NEXT Side
13644 !REMOVE HELOS
13647 FOR I=1 TO 3
13650 B_helo(I,2)=B_helo(I,2)+Cell(1,1,I)-Cell(1,2,I)
13653 R_helo(I,2)=R_helo(I,2)+Cell(2,1,I)-Cell(2,2,I)
13656 NEXT I
13659 !
13662 !ADJUST BLUE AD AMMO AND DELETE SYSTEMS
13665 !SUBTRACT SYSTEM LOSSES FOR HELOS
13668 FOR I=1 TO 70
13671 Sys_tot(2,I)=Sys_tot(2,I)-Sys_helo(1,I)
13674 Sys_tot(4,I)=Sys_tot(4,I)-Sys_helo(2,I)
13677 NEXT I
13680 No_helo2: !
13683 !
13686 ! ** PGM PORTION OF PHASE II **

```


Table 6-14. Ground combat code (continued).

```

13689 !SET UP CLGP AND GAMP ARRAY FACTORS
13692 FOR I=1 TO 70
13695   Gamp_fact(I)=Red_f_t(I)
13698   Clgp_fact(I)=Red_f_t(I)*2
13701   IF Clgp_fact(I)>1 OR Clgp_rpv=1 THEN Clgp_fact(I)=1
13704 NEXT I
13707 GOSUB Clgp_gamp_atrit
13710 !
13713 ! ** INFANTRY PORTION OF PHASE II **
13716 ! NOTE: RNG_BAND HOLDS THE BAND IN WHICH THE FIGHT HAS BEGUN
13719 !       IF RNG_BAND<=2 THEN, AT LESS THAN 1000M , INFANTRY WILL DISMOUNT
13722 IF Rng_band>=2 THEN GOTO Finish2
13725 !
13728 T_conflict=.5 !INFANTRY CONFLICT TIME IN HOURS
13731 GOSUB Infantry_cbt
13734 !
13737 Finish2: !
13740 GOSUB Updatek_v
13743 End_phase2_bt1:RETURN ! ** END BATTLE PHASE II **
13746 !
13749 !-----
13752 !
13755 Phase3_bt1: ! THIS SUBROUTINE CONDUCTS ATTRITION ASSESSMENTS FOR
13758 !           ! PHASE III (WITHDRAWAL)
13761 !
13764 !
13767 Phase_ct(3)=Phase_ct(3)+1 !COUNT # OF 30 MINUTE SEGMENTS IN PHASE III:
13770 !           ! (SHOULD ONLY BE ONE)
13773 Bt1_phase=3
13776 GOSUB Phase_int !ZERO ALL KILL ARRAYS FOR THIS 30 MIN.
13779 !
13782 ! ** NO MINES IN PHASE III **
13785 !
13788 ! MINES ADDED TO PHASE III ! ROB
13791 IF Mine_hit=0 THEN GOTO 13803
13794 IF Minefield(Mine_hit,6)=1 THEN GOTO 13803
13797 GOSUB Run_mine
13800 ! ** ARTILLERY PORTION OF PHASE III **
13803 ! CHECK ON INDIRECT FIRE USED IN THIS PHASE
13806 Blue_aty=0 !BLUE FIRE FLAG
13809 Red_aty=0 !RED FIRE FLAG
13812 FOR I=1 TO 15
13815   FOR J=1 TO 5
13818     IF Bif_fired(I,J)>0 THEN Blue_aty=1
13821     IF Rif_fired(I,J)>0 THEN Red_aty=1
13824   NEXT J
13827 NEXT I
13830 IF Blue_aty=0 AND Red_aty=0 THEN GOTO Direct_3
13833 GOSUB Arty_sub
13836 !
13839 Direct_3: ! ** DIRECT FIRE PORTION OF PHASE III **
13842 FOR I=1 TO 2

```

Table 6-14. Ground combat code (continued).

```

13845 FOR J=1 TO 3
13848   Cell(I,2,J)=0           !ZERO OUT RED & BLUE HELO'S CELLS
13851 NEXT J
13854 NEXT I
13857 Cell(1,1,1)=Bah1       !LOAD UP CELLS
13860 Cell(1,1,2)=Bah2
13863 Cell(1,1,3)=Bsct
13866 Cell(2,1,1)=Rah1
13869 Cell(2,1,2)=Rah2
13872 Cell(2,1,3)=Rsct
13875 CALL Helo_range(Cell(*),Helo_mis(*),Std_off_rg(*)) !CALCULATE RANGES
13878   !TEST FOR ENTERING PHASE II
13881 IF Phase_ct(2)=0 THEN GOTO Helos3 !NO PHASE II, NO DIRECT FIRE PULLC
13884   !
13887 GOSUB Collect_trucks   !TEMPORARY CODE FOR HTLD/ADEA ONLY
13890 FOR I=1 TO 70
13893   SELECT Break_point
13896   CASE 1 !BLUE BREAK
13899     Blue_fct=B_f(B_ms,I)*.9 !SET BLUE FIRERS TO 90%
13902     Red_fct=R_f(R_ms,I)+Phase_ct(2)*R_df(R_ms,I)
13905     IF Red_fct<.05 THEN Red_fct=.05
13908   CASE 2 !RED BREAK
13911     Blue_fct=B_f(B_ms,I)+Phase_ct(2)*B_df(B_ms,I)
13914     Red_fct=R_f(R_ms,I)*.9 !SET RED FIRERS TO 90%
13917     IF Blue_fct<.05 THEN Blue_fct=.05
13920   END SELECT
13923   IF Red_fct>1 THEN Red_fct=1
13926   IF Blue_fct>1 THEN Blue_fct=1
13929   Sys(5,I)=Sys_tot(2,I)*Bdf_mask(Balb,I)*Blue_fct !SET BLUE FIRERS
13932   Sys(6,I)=Sys_tot(4,I)*Rdf_mask(Ralb,I)*Red_fct !SET RED FIRERS
13935   !
13938   !CALCULATE SYSTEMS WHICH ARE TARGETS
13941   SELECT Break_point
13944   CASE 1 !BLUE BREAK
13947     Blue_f_t(I)=B_df_t(B_ms,I)*.9
13950     Red_f_t(I)=R_df_t(R_ms,I)+Phase_ct(2)*R_df_dt(R_ms,I)
13953   CASE 2 !RED BREAK
13956     Blue_f_t(I)=B_df_t(B_ms,I)+Phase_ct(2)*B_df_dt(B_ms,I)
13959     Red_f_t(I)=R_df_t(R_ms,I)*.9
13962   END SELECT
13965   IF Red_f_t(I)>1 THEN Red_f_t(I)=1
13968   IF Blue_f_t(I)>1 THEN Blue_f_t(I)=1
13971   IF Red_f_t(I)<.05 THEN Red_f_t(I)=.05
13974   IF Blue_f_t(I)<.05 THEN Blue_f_t(I)=.05
13977   Sys(1,I)=Sys_tot(2,I)*Blue_f_t(I)*Bdf_mask(Balb,I)
13980   Sys(3,I)=Sys_tot(4,I)*Red_f_t(I)*Rdf_mask(Ralb,I)
13983   !CALCULATE SYSTEM VULNERABILITIES
13986   SELECT Break_point
13989   CASE 1 !BLUE BREAK
13992     Red_fct=R_v(R_ms,I)+R_dv(R_ms,I)*Phase_ct(2)
13995     Blue_fct=B_v(B_ms,I)*.9
13998   CASE 2 !RED BREAK

```

Table 6-14. Ground combat code (continued).

```

14001 Red_fct=R_v(R_ms,I)*.9
14004 Blue_fct=B_v(B_ms,I)+B_dv(B_ms,I)*Phase_ct(2)
14007 END SELECT
14010 IF Red_fct>1 THEN Red_fct=1
14013 IF Blue_fct>1 THEN Blue_fct=1
14016 IF Red_fct<.05 THEN Red_fct=.05
14019 IF Blue_fct<.05 THEN Blue_fct=.05
14022 Red_vul(I)=Red_fct
14025 Blue_vul(I)=Blue_fct
14028 NEXT I
14031 IF Break_point<>1 THEN Sys(1,5)=0 !TEMPORARY CODE FOR HTLD/ADEA ONLY
14034 !SET UP GROUND ATTRITION PARAMETERS
14037 Btl_phase=3
14040 Rng_band=Cur_bnd
14043 SELECT Break_point !SET BREAK TIME
14046 CASE 1 !BLUE BREAK
14049 Num_bands=B_break_t(B_ms)/30
14052 CASE 2 !RED BREAK
14055 Num_bands=R_break_t(R_ms)/30
14058 END SELECT
14061 IF Cur_bnd<=0 THEN Rng_band=1
14064 Terrain=B_terr !FIGHT ON DEFENDERS TERRAIN
14067 IF Atk_def=1 THEN Terrain=R_terr
14070 GOSUB Df_cbt !PERFORM DIRECT FIRE COMBAT
14073 !
14076 Helos3: ! ** HELICOPTER ATTRITION FOR PHASE III **
14079 IF Bah1+Bah2+Bsc<=0 AND Rah1+Rah2+Rsc<=0 THEN GOTO No_helo3
14082 Arty(1)=2
14085 Arty(2)=2
14088 Veh_ada(1)=Bveh_sup !SUPPRESSION OF VEHICULAR & HAND-HELD ADA
14091 Veh_ada(2)=Rveh_sup
14094 Hnd_ada(1)=Bhnd_sup
14097 Hnd_ada(2)=Rhnd_sup
14100 Time_step=15
14103 !BLUE HELOS -- PREPARE FORCES
14106 FOR I=1 TO 70
14109 IF Phase_ct(2)>0 THEN
14112 Target(1,I)=Sys_tot(4,I)*Red_f_t(I)*Rdf_mask(Ralb,I)
14115 P_def(2,I)=Red_vul(I)
14118 ELSE
14121 Target(1,I)=Sys_tot(4,I)*R_df_t(R_ms,I)
14124 SELECT Break_point
14127 CASE 1 !BLUE BREAK; RED VULNERABILITY NOT AFFECTED
14130 P_def(2,I)=R_v(R_ms,I)+Del_red*R_dv(R_ms,I)
14133 IF P_def(2,I)>1 THEN P_def(2,I)=1
14136 IF P_def(2,I)<.05 THEN P_def(2,I)=.05
14139 CASE 2 !RED BREAK
14142 P_def(2,I)=R_v(R_ms,I)*.9
14145 IF P_def(2,I)>1 THEN P_def(2,I)=1
14148 IF P_def(2,I)<.05 THEN P_def(2,I)=.05
14151 END SELECT
14154 END IF

```

Table 6-14. Ground combat code (continued).

```

14157 Target(2,I)=0
14160 Helo_tgt(2,1,I)=Target(1,I) !THIS ARRAY IS PASSED TO HELO_KILLS
14163 Helo_tgt(2,2,I)=0
14166 NEXT I
14169 !APPORTION RED AD AMMO BASED ON RED TARGETS
14172 ! RED AD SYSTEMS
14175 Adside=2
14178 Ad_ammo=R_ad_ammo
14181 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(2),Basic_ld(*
Ammo_wt(*))
14184 Ad_sv(1)=Ad_helo(2)
14187 Sided=2
14190 FOR I=1 TO 70
14193 H_targ(3,I)=Target(1,I)
14196 NEXT I
14199 CALL Dismount(H_targ(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mount,R_dmount
14202 CALL Apport_inf(Target(*),1,R_dmount)
14205 !---PREPARE BLUE FORCES
14208 FOR I=1 TO 70
14211 IF Phase_ct(2)>0 THEN
14214 Target(1,I)=Sys_tot(2,I)*Blue_f_t(I)*Bdf_mask(Balb,I)
14217 P_def(1,I)=Blue_vul(I)
14220 ELSE
14223 Target(1,I)=Sys_tot(2,I)*B_df_t(B_ms,I)
14226 SELECT Break_point
14229 CASE 1 !BLUE BREAK; BLUE VULNERABILITY AFFECTED
14232 P_def(1,I)=B_v(B_ms,I)*.9
14235 IF P_def(1,I)>1 THEN P_def(1,I)=1
14238 IF P_def(1,I)<.05 THEN P_def(1,I)=.05
14241 CASE 2 !RED BREAK; BLUE NOT AFFECTED
14244 P_def(1,I)=B_v(B_ms,I)+Del_blue*B_dv(B_ms,I)
14247 IF P_def(1,I)>1 THEN P_def(1,I)=1
14250 IF P_def(1,I)<.05 THEN P_def(1,I)=.05
14253 END SELECT
14256 END IF
14259 Target(2,I)=0
14262 Helo_tgt(1,1,I)=Target(1,I) !THIS ARRAY IS PASSED TO HELO_KILLS
14265 Helo_tgt(1,2,I)=0
14268 NEXT I
14271 !APPORTION AD_AMMO TO BLUE AD SYSTEMS
14274 Adside=1
14277 Ad_ammo=B_ad_ammo
14280 CALL Helo_ammo(Sys_tot(*),Target(*),Adside,Ad_ammo,Ad_helo(1),Basic_ld(*
Ammo_wt(*))
14283 Ad_sv(1)=Ad_helo(1)
14286 Df_ammo(1)=B_df_ammo
14289 Df_ammo(2)=R_df_ammo
14292 Sided=1
14295 FOR I=1 TO 70
14298 H_targ(1,I)=Target(1,I)
14301 NEXT I
14304 CALL Dismount(H_targ(*),B_ld_fact,B_msn(1),Sided,Rt1_rg,B_mount,B_dmount

```

Table 6-14. Ground combat code (continued).

```

14307 CALL Apport_inf(Target(*),1,B_dmount)
14310 !
14313 CALL Helo_kills(Cell(*),Helo_tgt(*),Ad_helo(*),Terr,Atk_prof(*),Helo_mis
),Day_nite,Time_step,P_def(*),Arty(*),Veh_ada(*),Hnd_ada(*),Std_off_rg(*),Vis
14316 !
14319 B_ad_ammo=B_ad_ammo-(Ad_sv(1)-Ad_helo(1))
14322 R_ad_ammo=R_ad_ammo-(Ad_sv(2)-Ad_helo(2))
14325 B_df_ammo=Df_ammo(1)
14328 R_df_ammo=Df_ammo(2)
14331 !STORE KILLS AND SUBTRACT BLUE HELICOPTERS
14334 FOR Side=1 TO 2
14337 FOR I=1 TO 70
14340 Sys_helo(2,I)=Helo_tgt(Side,1,I)-Helo_tgt(Side,2,I)
14343 NEXT I
14346 IF Side=1 THEN CALL Inf_survive(H_targ(*),1,Sys_helo(*),1,B_ld_fact,Inf
urv(*))
14349 IF Side=2 THEN CALL Inf_survive(H_targ(*),3,Sys_helo(*),2,R_ld_fact,Inf
urv(*))
14352 FOR I=36 TO 40
14355 Sys_helo(Side,I)=Sys_helo(Side,I)+Inf_surv(I-35)
14358 NEXT I
14361 NEXT Side
14364 !REMOVE HELOS
14367 FOR I=1 TO 3
14370 B_helo(I,2)=B_helo(I,2)+Cell(1,1,I)-Cell(1,2,I)
14373 R_helo(I,2)=R_helo(I,2)+Cell(2,1,I)-Cell(2,2,I)
14376 NEXT I
14379 !
14382 !ADJUST BLUE AD AMMO AND DELETE SYSTEMS
14385 !SUBTRACT SYSTEM LOSSES FOR HELOS
14388 FOR I=1 TO 70
14391 Sys_tot(2,I)=Sys_tot(2,I)-Sys_helo(1,I)
14394 Sys_tot(4,I)=Sys_tot(4,I)-Sys_helo(2,I)
14397 NEXT I
14400 No_helo3: !
14403 ! ** PGM PORTION OF PHASE III **
14406 ! IF BLUE IS BREAKING THEN ONLY GAMP
14409 FOR I=1 TO 70
14412 Gamp_fact(I)=Red_f_t(I)
14415 Clgp_fact(I)=Red_f_t(I)
14418 IF Break_point=1 AND Clgp_rpv=0 THEN Clgp_fact(I)=0 !BLUE BREAKS W.
14421 ! NO RPV'S
14424 NEXT I
14427 GOSUB Clgp_gamp_atrit
14430 ! ** INFANTRY PORTION OF PHASE III **
14433 IF Phase_ct(2)=0 THEN GOTO Finish3
14436 !If RNG_BAND<2 then infantry will play
14439 IF Rng_band>=2 THEN GOTO Finish3
14442 T_conflict=Time_step/60 !SET TIME IN HOUR UNITS
14445 GOSUB Infantry_cbt
14448 !
14451 Finish3: !

```

Table 6-14. Ground combat code (continued).

```

14454 GOSUB Updatek_v
14457 End_phase3_bt1:RETURN ! ** END BATTLE PHASE III **
14460 !
14463 !-----
14466 !
14469 Phase_int: !
14472 FOR I=1 TO 2
14475   FOR K=1 TO 70
14478     Sys_direct(I,K)=0           !ZERO DIRECT FIRE KILLS
14481   NEXT K
14484 NEXT I
14487 FOR J=1 TO 70
14490   FOR I=1 TO 2
14493     Sys_helo(I,J)=0
14496     Sys_pgm(I,J)=0
14499     Sys_inf(I,J)=0
14502   NEXT I
14505   FOR I=1 TO 4
14508     Sys_mine(I,J)=0
14511     Sys_arty(I,J)=0
14514   NEXT I
14517   FOR I=1 TO 6
14520     Sys(I,J)=0
14523   NEXT I
14526 NEXT J
14529 RETURN
14532 !
14535 !-----
14538 !
14541 Updatek_v: ! UPDATES THE KV
14544 Hh=Hh+1
14547 FOR J=1 TO 70
14550   Kv_b(1,J)=Kv_b(1,J)+Sys_direct(1,J)
14553   Kv_r(1,J)=Kv_r(1,J)+Sys_direct(2,J)
14556   Kv_b(2,J)=Kv_b(2,J)+Sys_arty(2,J)
14559   Kv_r(2,J)=Kv_r(2,J)+Sys_arty(4,J)
14562   Kv_b(3,J)=Kv_b(3,J)+Sys_pgm(1,J)
14565   Kv_r(3,J)=Kv_r(3,J)+Sys_pgm(2,J)
14568   Kv_b(4,J)=Kv_b(4,J)+Sys_helo(1,J)
14571   Kv_r(4,J)=Kv_r(4,J)+Sys_helo(2,J)
14574   Kv_b(5,J)=Kv_b(5,J)+Sys_inf(1,J)
14577   Kv_r(5,J)=Kv_r(5,J)+Sys_inf(2,J)
14580   Kv_b(6,J)=Kv_b(6,J)+Sys_mine(2,J)
14583   Kv_r(6,J)=Kv_r(6,J)+Sys_mine(4,J)
14586 NEXT J
14589 !
14592 RETURN
14595 !
14598 !-----
14601 !
14604 Run_mine: !
14607 !CALCULATE THE % OF FORCE IN MINEFIELD

```

Table 6-14. Ground combat code (continued).

```

14610 SELECT Atk_def+1
14613 CASE 1 !RED FORCES IN THE MINEFIELD
14616 FOR I=1 TO 70
14619 Sys_mine(3,I)=Sys_tot(4,I)*R_df_t(R_ms,I)*Rf_mask(I)
14622 NEXT I
14625 FOR I=36 TO 40 !SAVE INFANTRY COUNT FOR SUB INF_SURVIVE
14628 R_inf(1,I-35)=Sys_mine(3,I)
14631 NEXT I
14634 Sided=2
14637 CALL Dismount(Sys_mine(*),R_ld_fact,R_msn(1),Sided,Btl_rg.Mounted,Dism
ted)
14640 CALL Apport_inf(Sys_mine(*),3,Dismounted)
14643 CALL Mines(Sys_mine(*),Minefield(*),Mine_hit,Atk_def,Bul_bch,Btl_phase
14646 !
14649 !ELEMENTS LOST DUE TO MINES ARE IN SYS_MINE(4,I)
14652 FOR I=1 TO 70
14655 Sys_tot(4,I)=Sys_tot(4,I)-Sys_mine(4,I)
14658 NEXT I
14661 IF Mounted<>0 THEN
14664 CALL Inf_survive(R_inf(*),0,Sys_mine(*),4,R_ld_fact,Inf_surv(*))
14667 FOR I=36 TO 40
14670 Sys_tot(4,I)=Sys_tot(4,I)-Inf_surv(I-35)
14673 Sys_mine(4,I)=Sys_mine(4,I)+Inf_surv(I-35)
14676 NEXT I
14679 END IF
14682 PRINT
14685 PRINT " RED FORCES IN MINEFIELD AT RANGE ";Minefield(Mine_hit,1).":
LAY ";Frnt_mn_dlay;" MINUTES"
14688 CASE 2 !BLUE FORCES IN THE MINEFIELD
14691 FOR I=1 TO 70
14694 Sys_mine(1,I)=Sys_tot(2,I)*B_df_t(B_ms,I)*Bf_mask(I)
14697 NEXT I
14700 FOR I=36 TO 40 !SAVE INFANTRY COUNT BEFORE MOUNTING
14703 B_inf(1,I-35)=Sys_mine(1,I)
14706 NEXT I
14709 Sided=1
14712 CALL Dismount(Sys_mine(*),B_ld_fact,B_msn(1),Sided,Btl_rg.Mounted,Dism
ted)
14715 CALL Apport_inf(Sys_mine(*),1,Dismounted)
14718 CALL Mines(Sys_mine(*),Minefield(*),Mine_hit,Atk_def,Bul_bch,Btl_phase
14721 !
14724 FOR I=1 TO 70
14727 Sys_tot(2,I)=Sys_tot(2,I)-Sys_mine(2,I)
14730 NEXT I
14733 IF Mounted<>0 THEN
14736 CALL Inf_survive(B_inf(*),0,Sys_mine(*),2,B_ld_fact,Inf_surv(*))
14739 FOR I=36 TO 40
14742 Sys_tot(2,I)=Sys_tot(2,I)-Inf_surv(I-35)
14745 Sys_mine(2,I)=Sys_mine(2,I)+Inf_surv(I-35)
14748 NEXT I
14751 END IF
14754 PRINT

```

Table 6-14. Ground combat code (continued).

```

14757 PRINT " BLUE FORCES IN MINEFIELD AT RANGE ":Minefield(Mine_hit,1),"
LAY ";Prnt_mn_dlay;" MINUTES"
14760 END SELECT
14763 !
14766 RETURN
14769 !
14772 !-----
14775 !
14778 Arty_sub: !
14781 IF Red_aty=0 THEN GOTO Bluearty
14784 Redarty: !
14787 Rarty_fire=Rarty_fire+1 !INCREASE RED ARTY COUNTER
14790 FOR I=1 TO 70
14793 Blue_fct=B_if_t(B_ms,I)+B_if_dt(B_ms,I)*Rarty_fire
14796 IF Blue_fct>1 THEN Blue_fct=1
14799 Sys_arty(1,I)=Sys_tot(2,I)*Blue_fct
14802 NEXT I
14805 !
14808 !CALCULATE RED SYSTEMS TARGETABLE
14811 Bluearty: !
14814 IF Blue_aty=0 THEN Barty_fire=Barty_fire+1 !INCREASE BLUE ARTY COUNT
14817 FOR I=1 TO 70
14820 Red_fct=R_if_t(R_ms,I)+R_if_dt(R_ms,I)*Barty_fire
14823 IF Red_fct>1 THEN Red_fct=1
14826 Sys_arty(3,I)=Sys_tot(4,I)*Red_fct
14829 NEXT I
14832 FOR I=36 TO 40 !SAVE THE INFANTRY COUNT BEFORE MOUNTING
14835 B_inf(1,I-35)=Sys_arty(1,I)
14838 R_inf(1,I-35)=Sys_arty(3,I)
14841 NEXT I
14844 !
14847 !CALCULATE ARTILLERY LOSSES
14850 B_phase=Btl_phase
14853 R=Ride
14856 Sided=2
14859 CALL Dismount(Sys_arty(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mounted,R_d
ounted)
14862 CALL Apport_inf(Sys_arty(*),R,R_dismounted)
14865 Sided=1
14868 CALL Dismount(Sys_arty(*),B_ld_fact,B_msn(1),Sided,Btl_rg,B_mounted,B_d
ounted)
14871 CALL Apport_inf(Sys_arty(*),1,B_dismounted)
14874 CALL Arty_atrit(Sys_arty(*),B_msn(B_ms),R_msn(R_ms),Bif_fired(*),Rif_fir
(*),T_length(*),T_width(*),Barty_fire,Rarty_fire,B_phase,Atk_def,Sys_tot(*),R)
14877 FOR I=1 TO 70
14880 Sys_tot(2,I)=Sys_tot(2,I)-Sys_arty(2,I) !SUBTRACT BLUE KILLED
14883 Sys_tot(4,I)=Sys_tot(4,I)-Sys_arty(4,I) !SUBTRACT RED KILLED
14886 NEXT I
14889 IF R_mounted<>0 THEN
14892 CALL Inf_survive(R_inf(*),0,Sys_arty(*),4,R_ld_fact,Inf_surv(*))
14895 FOR I=36 TO 40
14898 Sys_arty(4,I)=Sys_arty(4,I)+Inf_surv(I-35)

```


Table 6-14. Ground combat code(continued).

```

14901   Sys_tot(4,I)=Sys_tot(4,I)-Inf_surv(I-35)
14904   NEXT I
14907   END IF
14910   IF B_mounted<>0 THEN
14913   CALL Inf_survive(B_inf(*),0,Sys_arty(*),2,B_ld_fact,Inf_surv(*))
14916   FOR I=36 TO 40
14919     Sys_arty(2,I)=Sys_arty(2,I)+Inf_surv(I-35)
14922     Sys_tot(2,I)=Sys_tot(2,I)-Inf_surv(I-35)
14925   NEXT I
14928   END IF
14931   !
14934   RETURN
14937   !
14940   !-----
14943   !
14946   Collect_trucks: ! TEMPORARY CODE FOR HTLD/ADEA ONLY
14949   IF Balb<>1 THEN
14952     Sys_tot(2,6)=Sys_tot(2,55)+Sys_tot(2,58)
14955     Pct_fuel_truck=Sys_tot(2,55)/Sys_tot(2,6)
14958   END IF
14961   RETURN           !ENDS TEMPORARY CODE FOR HTLD/ADEA
14964   !
14967   !-----
14970   !
14973   Df_cbt: !
14976   PRINT
14979   SELECT Btl_phase
14982   CASE 1
14985     PRINT " FORWARD FORCES IN CONTACT FOR 15 MINUTE PERIOD"
14988   CASE 2
14991     SELECT Atk_def
14994     CASE 0
14997       B_r_attack$="RED "
15000     CASE 1
15003       B_r_attack$="BLUE"
15006     END SELECT
15009     IF Cur_bnd=Rng_band THEN
15012       PRINT USING "30A,6D": " STATIONERY FORCES AT RANGE ";Btl_rg
15015     ELSE
15018       PRINT " BOTH FORCES IN CONTACT FOR 30 MINUTE PERIOD "
15021     END IF
15024   CASE 3
15027     Prnt_rg=B_rg_break
15030     IF Break_point=2 THEN Prnt_rg=R_rg_break
15033     !PRINT USING "54A,6D": " FORCES DISENGAGING ; DIRECT FIRE OR
RING AT RANGE ";Btl_rg
15036   END SELECT
15039   FOR I=1 TO 20
15042     B_fire_sv(I)=Sys(5,I)
15045     R_fire_sv(I)=Sys(6,I)
15048   NEXT I
15051   CALL Df_ammo(Sys_tot(*),B_ammo(*),R_ammo(*),B_df_ammo,R_df_ammo,B_engage

```

Table 6-14. Ground combat code (continued).

```

nts(*),R_engagements(*)
15054 FOR I=1 TO 5
15057   R_inf_save(I)=Sys(3,I+35)
15060   B_inf_save(I)=Sys(1,I+35)
15063 NEXT I
15066 Sided=2
15069 CALL Dismount(Sys(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mounted,R_dismoun
d)
15072 CALL Apport_inf(Sys(*),3,R_dismounted)
15075 Sided=1
15078 CALL Dismount(Sys(*),B_ld_fact,B_msn(1),Sided,Btl_rg,B_mounted,B_dismoun
d)
15081 CALL Apport_inf(Sys(*),1,B_dismounted)
15084 T=Turn
15087 Sec=Sector
15090 Bu=No_b_unit
15093 Ru=No_r_unit
15096 St=St_time
15099 CALL Df_attrition(Blue_vul(*),Red_vul(*),Terrain,Day_nite,Vis,Num_bands,
g_band,Atk_def,Sys(*),B_amm(*),R_amm(*),B_vis(*),R_vis(*),T,Sec,Bu,Ru,St,De)
15102   !
15105 Aportion_trucks:   ! TEMPORARY CODE FOR HTLD/ADEA ONLY
15108 IF Balb<>1 AND Btl_phase<>1 THEN
15111   Sys(2,55)=Sys(2,6)*Pct_fuel_truck
15114   Sys(2,58)=Sys(2,6)-Sys(2,55)
15117   Sys(2,6)=0
15120   Sys_tot(2,6)=0
15123 END IF
15126   ! ENDS TEMPORARY CODE FOR HTLD/ADEA
15129   !CALCULATE LOSSES AND STORE IN SYS_DIRECT
15132 R_amm_1st=0       !RED AMMO USED
15135 B_amm_1st=0       !BLUE AMMO USED
15138 FOR I=1 TO 70
15141   Sys_direct(1,I)=Sys(2,I) !UPDATE BLUE LOSSES
15144   Sys_direct(2,I)=Sys(4,I) !UPDATE RED LOSSES
15147   Sys_tot(2,I)=Sys_tot(2,I)-Sys(2,I)
15150   Sys_tot(4,I)=Sys_tot(4,I)-Sys(4,I)
15153 NEXT I
15156 FOR I=1 TO 5
15159   Sys(3,I+35)=R_inf_save(I)
15162   Sys(1,I+35)=B_inf_save(I)
15165 NEXT I
15168 IF B_mounted<>0 THEN
15171   CALL Inf_survive(Sys(*),1,Sys(*),2,B_ld_fact,Inf_surv(*))
15174   FOR I=36 TO 40
15177     Sys_tot(2,I)=Sys_tot(2,I)-Inf_surv(I-35)
15180     Sys_direct(1,I)=Sys_direct(1,I)+Inf_surv(I-35)
15183   NEXT I
15186 END IF
15189 IF R_mounted<>0 THEN
15192   CALL Inf_survive(Sys(*),3,Sys(*),4,R_ld_fact,Inf_surv(*))
15195   FOR I=36 TO 40

```

Table 6-14. Ground combat code (continued).

```

15198   Sys_tot(4,I)=Sys_tot(4,I)-Inf_surv(I-35)
15201   Sys_direct(2,I)=Sys_direct(2,I)+Inf_surv(I-35)
15204   NEXT I
15207   END IF
15210   !
15213   FOR I=1 TO 20
15216   B_ammo_load=Ammo_wt(1,I)*B_engagements(I)
15219   IF B_ammo_load>B_ammo(1,I) THEN B_ammo_load=B_ammo(1,I)
15222   B_ammo_lst=B_ammo_lst+Sys_direct(1,I)*B_ammo_load
15225   IF Sys_direct(1,I)<B_fire_sv(I) THEN
15228     B_ammo_lst=B_ammo_lst+(B_fire_sv(I)-Sys_direct(1,I))*B_ammo(2,I)
15231   END IF
15234   R_ammo_load=Ammo_wt(2,I)*R_engagements(I)
15237   IF R_ammo_load>R_ammo(1,I) THEN R_ammo_load=R_ammo(1,I)
15240   R_ammo_lst=R_ammo_lst+Sys_direct(2,I)*R_ammo_load
15243   IF Sys_direct(2,I)<R_fire_sv(I) THEN
15246     R_ammo_lst=R_ammo_lst+(R_fire_sv(I)-Sys_direct(2,I))*R_ammo(2,I)
15249   END IF
15252   !
15255   NEXT I
15258   !
15261   !UPDATE AMMO, BOTH RED AND BLUE
15264   B_df_ammo=B_df_ammo-B_ammo_lst
15267   R_df_ammo=R_df_ammo-R_ammo_lst
15270   !
15273   IF B_df_ammo<0 THEN B_df_ammo=0
15276   IF R_df_ammo<0 THEN R_df_ammo=0
15279   !
15282   RETURN
15285   !
15288   !-----
15291   W_smoke: !
15294   ! THIS ROUTINE WILL ESTABLISH DIMINISHES FOR SMOKE SCREEN AND THEN CAL
15297   ! SMOKE EMPLACE(SMKEMP) ROUTINE... THE SMKEMP ROUTINE RETURNS THE
15300   ! VISIBILITY THROUGH THE SCREEN AND THE AMOUNT OF AMMO USED TO EMPLACE
15303   ! THE SCREEN
15306   ! BLUE SMOKE
15309   Iunt=1   !***CHANGES ACCORDING TO HTLD(=1) OR C-SERIES(=2)????????????
15312   Ielem=1
15315   S_time=B_break_t(1)*1.1
15318   IF S_time>30 THEN S_time=30
15321   FOR Vkp=1 TO 3
15324     B_vis(Vkp)=1
15327   NEXT Vkp
15330   CALL Smkemp(Iunt,Ielem,B_smok_tons(*),T_width(1),S_time,Vis,Btl_rg,B_ms
used(*),B_asmk_used(*),B_vis(1),B_vis(2),B_vis(3),Irh)
15333   FOR I=1 TO 4
15336     B_msmk_used(I)=B_smok_tons(I+7)-B_msmk_left(I)
15339   NEXT I
15342   FOR I=1 TO 7
15345     B_asmk_used(I)=B_smok_tons(I)-B_asmk_left(I)
15348   NEXT I

```

Table 6-14. Ground combat code (continued).

```

15351 !
15354 ! RED SMOKE
15357 Iunt=3 !***3 REPRESENTS THE RED FORCE
15360 Ielem=1
15363 S_time=R_break_t(1)*1.1
15366 IF S_time>30 THEN S_time=30
15369 FOR Vkp=1 TO 3
15372 R_vis(Vkp)=1
15375 NEXT Vkp
15378 CALL Smkemp(Iunt,Ielem,R_smok_tons(*),T_width(2),S_time,Vis,Btl_rg,R_msmk
used(*),R_asmk_used(*),R_vis(1),R_vis(2),R_vis(3),Irh)
15381 FOR I=1 TO 4
15384 R_msmk_used(I)=R_smok_tons(I+7)-R_msmk_left(I)
15387 NEXT I
15390 FOR I=1 TO 7
15393 R_asmk_used(I)=R_smok_tons(I)-R_asmk_left(I)
15396 NEXT I
15399 !
15402 FOR Vkp=1 TO 3
15405 Viss=R_vis(Vkp)
15408 IF Viss>B_vis(Vkp) THEN Viss=B_vis(Vkp)
15411 B_vis(Vkp)=Viss
15414 R_vis(Vkp)=Viss
15417 NEXT Vkp
15420 RETURN
15423 !
15426 !-----
15429 Infantry_cbt: !
15432 Force=1 !***CHANGES ACCORDING TO HTLD(=1) OR C-SERIES(=2)????????????????
15435 Bstat(1)=B_msn(B_ms) !SET BLUE MISSION
15438 Bstat(2)=R_msn(R_ms) !SET RED MISSION
15441 Attacker=2-Atk_def !SET ATTACKER; 1 FOR BLUE, 2 FOR RED
15444 PRINT
15447 SELECT Attacker
15450 CASE 1
15453 B_r_attack$="BLUE"
15456 CASE 2
15459 B_r_attack$="RED"
15462 END SELECT
15465 PRINT " :B_r_attack$;" ATTACKER DISMOUNTS AND CONTINUES ATTACK"
15468 Lossblue=0
15471 Lossred=0
15474 Sided=2
15477 CALL Dismount(Sys(*),R_ld_fact,R_msn(1),Sided,Btl_rg,R_mounted,R_dismoun
d)
15480 CALL Apport_inf(Sys(*),3,R_dismounted)
15483 Sided=1
15486 CALL Dismount(Sys(*),B_ld_fact,B_msn(1),Sided,Btl_rg,B_mounted,B_dismour
d)
15489 CALL Apport_inf(Sys(*),1,B_dismounted)
15492 CALL Infantry(Sys(*),Force,Bstat(*),Attacker,T_conflict,Lossblue,Lossred)
15495 !APPORTION OUT LOSSES OVER SMALL ARMS ELEMENTS

```

Table 6-14. Ground combat code (continued).

```

15498 Sum_inf_b=0
15501 Sum_inf_r=0
15504 FOR I=36 TO 47 !SUM UP NO. OF SMALL ARMS
15507 Sum_inf_b=Sum_inf_b+Sys(1,I)
15510 Sum_inf_r=Sum_inf_r+Sys(3,I)
15513 NEXT I
15516 FOR I=36 TO 47 !APPORTION OUT LOSSES IN SMALL ARMS
15519 IF Sum_inf_b>0 THEN Sys_inf(1,I)=(Sys(1,I)/Sum_inf_b)*Lossblue
15522 IF Sum_inf_b<=0 THEN Sys_inf(1,I)=0
15525 IF Sum_inf_r>0 THEN Sys_inf(2,I)=(Sys(3,I)/Sum_inf_r)*Lossred
15528 IF Sum_inf_r<=0 THEN Sys_inf(2,I)=0
15531 Sys_tot(2,I)=Sys_tot(2,I)-Sys_inf(1,I)
15534 Sys_tot(4,I)=Sys_tot(4,I)-Sys_inf(2,I)
15537 NEXT I
15540 !
15543 RETURN
15546 !
15549 !-----
15552 !
15555 Clgp_gamp_atrit: !
15558 !
15561 IF Clgp_msns<=0 AND Gamp_msns<=0 THEN End_clgp
15564 FOR I=1 TO 2
15567 N_rnds(I)=0
15570 Sens_typ(I)=0
15573 Fir_typ(I)=0
15576 NEXT I
15579 S_clgp: !
15582 IF Clgp_msns<=0 THEN S_gamp
15585 Fir_typ(1)=1
15588 Sens_typ(1)=Clgp_rpv+1 ! SET RPV 1=no 2=yes
15591 N_rnds(1)=Clgp_msns/.11 ! CONVERT TONS TO ROUNDS
15594 S_gamp: !
15597 IF Gamp_msns<=0 THEN Set_pgm_tgt
15600 Fir_typ(2)=1
15603 Sens_typ(2)=0 ! SENSORS ASSUMED IN GAMP DATA
15606 N_rnds(2)=Gamp_msns/.11
15609 Set_pgm_tgt: !
15612 !
15615 FOR I=1 TO 70
15618 C_targ(1,I)=Sys_tot(4,I)*Clgp_fact(I)
15621 C_targ(2,I)=0
15624 C_t(3,I)=C_targ(1,I)
15627 C_t(4,I)=0
15630 NEXT I
15633 !
15636 !CALL DISMOUNT TO DETERMINE NUMBER OF INFANTRY IN CARRIERS
15639 Sided=2
15642 CALL Dismount(C_t(*),R_ld_fact,R_msn(1),Sided,Rt1_rq,R_mount,F_dmount)
15645 CALL Apport_inf(C_targ(*),1,R_dmount)
15648 Dust=1 !DUST FACTOR : NO DUST
15651 CALL Fgm_atrit(Fir_typ(*),N_rnds(*),Vis,R_terr,Sens_typ(*),Cloud_ht,Dust

```

Table 6-14. Ground combat code (continued).

```

_targ(*)
15654 !STORE CLGP KILLS AND SUBTRACT LOSSES
15657 FOR I=1 TO 70
15660 IF I<36 OR I>40 THEN
15663   Sys_pgm(2,I)=Sys_pgm(2,I)+C_targ(2,I)
15666   Sys_tot(4,I)=Sys_tot(4,I)-C_targ(2,I)
15669 END IF
15672 NEXT I
15675 IF R_mount<>0 THEN
15678 CALL Inf_survive(C_t(*),3,C_targ(*),2,R_ld_fact,Inf_surv(*))
15681 FOR I=36 TO 40
15684   Sys_pgm(2,I)=Sys_pgm(2,I)+Inf_surv(I-35)
15687   Sys_tot(4,I)=Sys_tot(4,I)-Inf_surv(I-35)
15690 NEXT I
15693 END IF
15696 !
15699 End_clgp: !
15702 RETURN
15705 !
15708 !-----
15711 !
15714 Dump_input: !
15717 IF End_time<2400 THEN
15720 PRINT "LINE 1 : ".Turn.Sector.No_b_unit.No_r_unit.St_time.End_time
15723 ELSE
15726 PRINT "LINE 1 : ".Turn.Sector.No_b_unit.No_r_unit.St_time.End_time-2400
15729 END IF
15732 PRINT USING "/.11A,29X.10A": "BLUE UNITS:", "RED UNITS:"
15735 FOR I=0 TO 9 STEP 3
15738 FOR J=1 TO 3
15741 PRINT USING Fmtd: B_unit_no(I+J), B_unit_pct(I+J)
15744 NEXT J
15747 Fmtd: IMAGE 3D, 1X, 3D, 3X, #
15750 PRINT USING "7X, #"
15753 FOR J=1 TO 3
15756 PRINT USING Fmtu: R_unit_no(I+J), R_unit_pct(I+J)
15759 NEXT J
15762 Fmtu: IMAGE 3X, 3D, 1X, 3D, #
15765 PRINT USING "/"
15768 NEXT I
15771 PRINT
15774 PRINT
15777 PRINT "          ": "ATTACKER", "INIT RG", "DF RG", "# MINFLDS", "MTD/DSMT", "
MT INF?"
15780 PRINT "LINE 4 : ": Atk_def, Init_rg, Df_rg, No_minefields, Ride, Dis_inf
15783 PRINT
15786 PRINT "LINE 5 : VISIBILITY, CLOUD HT. AND HUMIDITY: ": Vis, Cloud_ht, Irh
15789 PRINT
15792 PRINT "LINE 6 : DEEP ATTACK #": Ialb
15795 PRINT
15798 PRINT
15801 PRINT "BATTLE PARAMETERS:"

```

Table 6-14. Ground combat code (continued).

```

15804 PRINT
15807 PRINT "LINE 7 : ";B_msn(1)-1,B_terr,B_rg_break,B_pct_fwd,B_mopp,T_lenqt
1) / 1000,T_width(1) / 1000,B_break_t(1),B_cas_break
15810 PRINT
15813 PRINT "LINE 8 : ";R_msn(1)-1,R_terr,R_rq_break,R_pct_fwd,R_mopp,T_lenqt
2) / 1000,T_width(2) / 1000,R_break_t(1),R_cas_break
15816 PRINT
15819 PRINT
15822 PRINT "HELICOPTER DATA:"
15825 PRINT
15828 PRINT "LINE 9 : ";B_helo(1,1),B_helo(2,1),B_helo(3,1),B_helo(1,3),B_hel
2,3),B_helo_atkprof(*),B_helo_delay,B_helo_rq_delay,B_helo_msn(*),B_atk_rg(*)
15831 PRINT
15834 PRINT "LINE 10: ";R_helo(1,1),R_helo(2,1),R_helo(3,1),R_helo(1,3),R_helo
,3),R_helo_atkprof(*),R_helo_delay,R_helo_rq_delay,R_helo_msn(*),R_atk_rg(*)
15837 PRINT
15840 PRINT
15843 PRINT "ARTILLERY DATA:"
15846 PRINT
15849 PRINT "LINE 11: ";Bif_msn(*),B_prep_time-30,No_gamp,Perc_gamp,No_clgp,Pe
_clgp,Clgp_rpv
15852 PRINT
15855 PRINT "LINE 12: ";Rif_msn(*),R_prep_time-30
15858 PRINT
15861 PRINT
15864 PRINT "MINEFIELD DATA:"
15867 PRINT
15870 FOR I=13 TO 15
15873 PRINT "LINE ";I:" ";Minefield(I-12,1),Minefield(I-12,2),Minefield(I-12
),Minefield(I-12,4)
15876 NEXT I
15879 RETURN
15882 !
15885 !-----
15888 !
15891 Close_files: !
15894 ASSIGN @Unitpath TO *
15897 ASSIGN @Kvpath TO *
15900 ASSIGN @Helopath TO *
15903 ASSIGN @Ammopath TO *
15906 ASSIGN @Advanpath TO *
15909 RETURN
15912 !
15915 !-----
15918 !
15921 !
15924 Halt: !
15927 END
15930 !
15933 !
15936 !
15939 !*****

```

Table 6-14. Ground combat code (continued).

```

*****
15942 !
15945 SUB Fwdfp(Sys_tot(*),F_mask(*),At_df,D_pct_fwd,D_fp,Sys_eff(*))
15948 OPTION BASE 1
15951 !
15954 !SET POINTERS FOR EFFECTIVENESS
15957 !
15960 IF At_df=0 THEN
15963     Spt=1 !BLUE DEFENDER
15966     Sef=1
15969 ELSE
15972     Spt=3 !RED DEFENDER
15975     Sef=2
15978 END IF
15981 !
15984 !CALCULATE INITIAL EFFECTIVENESS
15987 !
15990 Init_eff=0
15993 Cur_eff=0
15996 !
15999 FOR I=1 TO 10
16002     A=F_mask(I)*D_pct_fwd*Sys_eff(Sef,I)
16005     Init_eff=Init_eff+A*Sys_tot(Spt,I)
16008     Cur_eff=Cur_eff+A*Sys_tot(Spt+1,I)
16011 NEXT I
16014 !
16017 D_fp=0
16020 IF Init_eff=0 THEN GOTO Ret
16023 D_fp=Cur_eff/Init_eff
16026 Ret:
16029 SUBEND
16032 !
16035 !*****
16038 !
16041 SUB Df_ammo(Sys_tot(*),B_ammo(*),R_ammo(*),B_df_ammo,R_df_ammo,B_engag
ts(*),R_engagements(*))
16044 !
16047 OPTION BASE 1
16050 !
16053 DIM B_ammo_wt(20),R_ammo_wt(20)
16056 !
16059 !
16062 Run$="BH_"
16065 DIM Disk3$(50)
16068 Disk3$=":9134,704.0"
16071 !
16074 !READ WEIGHT & ENGAGEMENT FILE
16077 ASSIGN @P1 TO Run$&"DFAMO"&Disk3$
16080 !
16083 Red$="RD_"
16086 ASSIGN @P2 TO Red$&"DFAMO"&Disk3$
16089 ENTER @P1,1:B_ammo_wt(*)

```


Table 6-14. Ground combat code (continued).

```

16092 ENTER @P1,2;B_engagements(*)
16095 ENTER @P2,1;R_ammo_wt(*)
16098 ENTER @P2,2;R_engagements(*)
16101 ASSIGN @P1 TO *
16104 ASSIGN @P2 TO *
16107 !
16110 !TOTAL CAPACITY
16113 B_capacity=0
16116 R_capacity=0
16119 FOR I=1 TO 20
16122 B_capacity=B_capacity+Sys_tot(2,I)*B_ammo_wt(I)*B_engagements(I)
16125 R_capacity=R_capacity+Sys_tot(4,I)*R_ammo_wt(I)*R_engagements(I)
16128 NEXT I
16131 !
16134 !RND$ FOR EACH WEAPON IN POUNDS
16137 FOR I=1 TO 20
16140 IF B_capacity<>0 THEN B_ammo(1,I)=B_engagements(I)*B_df_ammo*2000/B_c
acity
16143 IF R_capacity<>0 THEN R_ammo(1,I)=R_engagements(I)*R_df_ammo*2000/R_c
acity
16146 NEXT I
16149 FOR I=1 TO 20
16152 B_ammo(1,I)=B_ammo(1,I)*Sys_tot(2,I)
16155 R_ammo(1,I)=R_ammo(1,I)*Sys_tot(4,I)
16158 NEXT I
16161 FOR I=1 TO 20
16164 IF Sys_tot(2,I)<>0 THEN B_ammo(1,I)=B_ammo(1,I)/Sys_tot(2,I)
16167 IF Sys_tot(4,I)<>0 THEN R_ammo(1,I)=R_ammo(1,I)/Sys_tot(4,I)
16170 NEXT I
16173 !
16176 !WEIGHT IN TONS PER WEAPON
16179 FOR I=1 TO 20
16182 B_ammo(1,I)=B_ammo(1,I)*B_ammo_wt(I)/2000
16185 R_ammo(1,I)=R_ammo(1,I)*R_amm0_wt(I)/2000
16188 NEXT I
16191 !
16194 SUBEND
16197 !
16200 !*****
16203 !
16206 SUB Ammo(Rndse(*),Wrndse(*),Ad_ammo,Ad_ele(*),Ad_eng(*))
16209 !!!--THIS SUBROUTINE CALCULATES THE NUMBER OF ENGAGEMENTS AVAILABLE FOR
EACH AD ELEMENT BASED ON ITS SHARE OF THE AMMO.
16212 OPTION BASE 1
16215 DIM Wt_ad(7)
16218 ! CALCULATE THE PERCENTAGE OF AMMO DUE TO EACH ELEMENT TYPE
16221 Total=0
16224 FOR I=1 TO 7
16227 Wt_ad(I)=(Ad_ele(I)*(Ad_eng(I,1)+Ad_eng(I,2))*Wrndse(I))/2000
16230 Total=Wt_ad(I)+Total
16233 NEXT I
16236 IF Total<=Ad_ammo THEN 16269

```

Table 6-14. Ground combat code (continued).

```

16239 !COMPUTE SCALE FACTOR
16242   Scle=Ad_ammo/Total
16245 !RESCALE ALL
16248   FOR I=1 TO 7
16251     Wt_ad(I)=Scle*Wt_ad(I)
16254     Ad_eng(I,1)=Ad_eng(I,1)*Scle
16257     Ad_eng(I,2)=Ad_eng(I,2)*Scle
16260   NEXT I
16263   Total=Total*Scle
16266 !NOW SUBTRACT AMMO USED FROM AMOUNT AVAILABLE
16269   Ad_ammo=Ad_ammo-Total
16272 SUBEND
16275 !
16278 !*****
16281 !
16284 SUB Ad_pri(Expos(*),N_systems(*),Ad_prior(*))
16287 !!! - THIS SUBROUTINE DISTRIBUTES THE AD FIRERS
16290   OPTION BASE 1
16293   Total=0.
16296   FOR I=1 TO 2
16299     Ad_prior(I)=0
16302     Total=Expos(I)*N_systems(I)+Total
16305   NEXT I
16308   IF Total=0 THEN End_sub
16311   FOR I=1 TO 2
16314     Ad_prior(I)=Expos(I)*N_systems(I)/Total
16317   NEXT I
16320 End_sub:
16323 SUBEND
16326 !
16329 !*****
16332 !
16335 SUB Firedst(P_pref(*),Target(*),Mtgprf(*),P_pep,P_veh,T_targets,Pkmse(*)
16338 !!! - THIS SUBROUTINE CALCULATES THE DISTRIBUTION OF FIRE UNDER THE CUF
T TARGET CONFIGURATION. ADJUST THE TARGET ENTRY TO REPRESENT INFANTRY SQUADS
16341   OPTION BASE 1
16344   FOR I=36 TO 47
16347     Target(1,I)=Target(1,I)/8.
16350     Target(2,I)=Target(2,I)/8.
16353   NEXT I
16356 !!! - CALCULATE THE WEIGHTED TARGET SUM AND TARGET SUM
16359   W_sum=0
16362   T_targets=0.
16365   FOR I=1 TO 70
16368     Tgt=Target(2,I)
16371     W_sum=Mtgprf(I)*Tgt*Pkmse(I)+W_sum
16374     T_targets=T_targets+Tgt
16377   NEXT I
16380 !!! - CALCULATE THE WEIGHTS
16383   IF W_sum=0 THEN GOTO S_end
16386   FOR I=1 TO 70
16389     Tgt=Target(2,I)

```

Table 6-14. Ground combat code (continued).

```

16392     P_pref(I)=Mtgprf(I)*Tgt*Pkmse(I)/W_sum
16395 NEXT I
16398 IF T_targets=0 THEN
16401     P_pep=0
16404 ELSE
16407     Tot_init=0
16410     Tot_rem=0
16413     FOR I=36 TO 47
16416         Tot_init=Tot_init+Target(1,I)
16419         Tot_rem=Tot_rem+Target(2,I)
16422     NEXT I
16425     P_pep=(Tot_init-Tot_rem)/T_targets
16428 END IF
16431 P_veh=1.-P_pep
16434 FOR I=36 TO 47
16437     Target(1,I)=Target(1,I)*8. ! RESTORE TARGET
16440     Target(2,I)=Target(2,I)*8.
16443 NEXT I
16446 S_end: !
16449 SUBEND
16452 !
16455 !*****
16458 !
16461 SUB Helo_ammo(Sys_tot(*),Target(*),Side,Ad_ammo,Ad_helo,Basic_ld(*),Ammo
t(*))
16464 OPTION BASE 1
16467 DIM Adc(7)
16470 !
16473 Total=0 !SET TOTAL WEIGHT
16476!CALCULATE POINTER TO TOTAL
16479 Adpt=Side*2 !SET POINTER TO AD SIDE
16482 FOR I=1 TO 7
16485     Adc(I)=Sys_tot(Adpt,I+47)*Basic_ld(Side,I+47)*Ammo_wt(Side,I+47)
16488     Total=Total+Adc(I)
16491 NEXT I
16494 Ad_helo=0
16497 FOR I=1 TO 7
16500     IF Sys_tot(Adpt,I+47)<>0 AND Total<>0 THEN
16503         Ad_helo=Ad_helo+(Adc(I)/Total)*Ad_ammo/Sys_tot(Adpt,I+47)*Target(1.
47)
16506     END IF
16509 NEXT I
16512 SUBEND
16515 !
16518 !*****
16521 !
16524 SUB Mines(Sys_mine(*),Minefield(*),Mine_hit,Atk_def,Bul_bch,Phase)
16527 !
16530 OPTION BASE 1
16533 !
16536 COM /Mines/ Mine_frct(4,70)
16539 !

```

Table 6-14. Ground combat code (continued).

```

16542 ! INITIALIZE
16545 FOR I=1 TO 70
16548   Sys_mine(2,I)=0
16551   Sys_mine(4,I)=0
16554 NEXT I
16557 !
16560 ! CHECKS FOR:
16563 ! SECTOR WIDTH=0, MINEFIELD WIDTH=0, FORCE ENTERING=0, OR PREVIOUS ASSESSME.
16566 IF Minefield(Mine_hit,2)=0 OR Minefield(Mine_hit,3)=0 OR Minefield(Mine
it,4)=0 OR Minefield(Mine_hit,6)=1 OR Bul_bch=0 THEN GOTO Rtn
16569 ! SET FOR ATTACK POSITION
16572 SELECT Atk_def
16575 CASE 0 ! RED IS ENTERING MINEFIELD
16578   Entering=3
16581   Killed=4
16584   Ias=3
16587   IF Bul_bch=2 THEN Ias=4
16590 CASE 1
16593   Entering=1
16596   Killed=2
16599   Ias=1
16602   IF Bul_bch=2 THEN Ias=2
16605 END SELECT
16608 !
16611 ! MINEFIELD COVERAGE FRACTION
16614 Mcf=(Minefield(Mine_hit,2)/Minefield(Mine_hit,3))
16617 !
16620 Tot_veh=0
16623 FOR I=1 TO 70
16626   Tot_veh=Tot_veh+Sys_mine(Entering,I)
16629 NEXT I
16632 IF Tot_veh<3 THEN Rtn
16635 !
16638 SELECT Phase
16641 CASE 0,1 ! PHASE 1
16644   Col_no=3
16647 CASE ELSE ! PHASE 2 OR 3
16650   Col_no=6
16653 END SELECT
16656 !
16659 Columns=Tot_veh/Col_no
16662 !
16665 ! CALCULATE LOSSES
16668 FOR I=1 TO 70
16671   Sys_mine(killed,I)=(Mcf*Sys_mine(Entering,I)/Tot_veh)*Columns*Mine_fr
(Ias,I)
16674 NEXT I
16677 !
16680 ! SET ASSESSED FLAG
16683 Rtn: !
16686 Minefield(Mine_hit,6)=1
16689 !

```

Table 6-14. Ground combat code (continued).

```

16692 SUBEND
16695 !
16696 !*****
16701 !
16704 SUB Infantry(Sys(*),Force,Cstat(*),Attacker,Hr_conflict,Lossblue,Lossred)
16707 OPTION BASE 1
16710 DIM Brate(2),Loss(2),Pers(2),Bstat(2)
16713 DIM Fratio(2),What(2)
16716 !
16719 COM /Infantry/ Convertd(10),Converta(10,10),Fpsb(70,2,2),Fpsr(70,2,2)
16722 !
16725 Bstat(1)=Cstat(1)
16728 Bstat(2)=Cstat(2)
16731 Frac_comtd=1.
16734 IF Attacker=1 THEN
16737     Defender=2
16740 ELSE
16743     Defender=1
16746 END IF
16749 !
16752 Pers(1)=0
16755 Pers(2)=0
16758 FOR I=36 TO 47
16761     Pers(1)=Pers(1)+Sys(1,I)
16764     Pers(2)=Pers(2)+Sys(3,I)
16767 NEXT I
16770 !PERFORM CONVERSION TO SUB MISSION VALUES FOR RATE SUB USAGE
16773 What(Attacker)=Converta(Bstat(Attacker),Bstat(Defender))
16776 Defender=(Attacker MOD 2)+1
16779 What(Defender)=Convertd(Bstat(Defender))
16782 !
16785 Fratio(1)=0
16788 Fratio(2)=0
16791 !COMPUTE BLUE (1) AND RED (2) UNADJUSTED FIREPOWER SCORES
16794 FOR I=1 TO 70
16797     Fratio(1)=Fratio(1)+(Sys(1,I)*Fpsb(I,Force,Attacker))
16800     Fratio(2)=Fratio(2)+(Sys(3,I)*Fpsr(I,Force,Attacker))
16803 NEXT I
16806 !DETERMINE WHO IS ATTACKER/DEFENDER;GET APPROPRIATE FORCE MULTIPLIER
16809 !BASED ON MISSIONS OF EACH
16812 IF Attacker=1 THEN
16815     Top=Fratio(1)
16818     Bottom=Fratio(2)
16821 ELSE
16824     Top=Fratio(2)
16827     Bottom=Fratio(1)
16830 END IF
16833 SELECT What(Defender)
16836 CASE 21
16839     Dmultiply=1.0
16842 CASE 22
16845     Dmultiply=1.0

```

Table 6-14. Ground combat code (continued).

```

16848 CASE 23
16851   Dmultiply=.5
16854 CASE 24
16857   Dmultiply=2.0
16860 CASE 25
16863   Dmultiply=1.5
16866 CASE 26
16869   Dmultiply=1.2
16872 CASE 27
16875   Dmultiply=4.5
16878 END SELECT
16881 SELECT Bstat(Attacker)
16884 CASE 2
16887   Amultiply=1.5
16890 CASE 4
16893   SELECT Bstat(Defender)
16896     CASE 2
16899       Amultiply=1.5
16902     CASE 6
16905       Amultiply=1.5
16908     CASE 9
16911       Amultiply=2.
16914     CASE ELSE
16917       Amultiply=1
16920     END SELECT
16923 CASE 5
16926   SELECT Bstat(Defender)
16929     CASE 2
16932       Amultiply=1.5
16935     CASE 6
16938       Amultiply=1.5
16941     CASE 7
16944       Amultiply=1.5
16947     CASE 8
16950       Amultiply=1.3
16953     CASE 9
16956       Amultiply=2.0
16959     CASE ELSE
16962       Amultiply=1.
16965     END SELECT
16968 CASE 7
16971   PRINTER IS 1
16974   PRINT "ATTACKER HAS BEEN GIVEN DEFENSIVE MISSION."
16977   PRINT "INFANTRY ROUTINE WILL NOT ACCEPT THIS CASE."
16980   Subend$="SUBEND"
16983 CASE 8
16986   PRINTER IS 1
16989   PRINT "ATTACKER HAS BEEN GIVEN DEFENSIVE MISSION."
16992   PRINT "INFANTRY ROUTINE WILL NOT ACCEPT THIS CASE."
16995   Subend$="SUBEND"
16998 CASE 10
17001   Amultiply=4.5

```

Table 6-14. Ground combat code (continued).

```

17004 CASE ELSE
17007     Amultiply=1.
17010 END SELECT
17013 IF Subend$="SUBEND" THEN GOTO Subend
17016     ! COMPUTE FIREPOWER RATIO
17019 IF Amultiply=0 OR Dmultiply=0 THEN
17022     PRINTER IS 1
17025     PRINT "ERROR IN INFANTRY SUBROUTINE: FORCE MULTIPLIER IS 0"
17028 END IF
17031 Top=Top*Amultiply
17034 Bottom=Bottom*Dmultiply
17037 IF Bstat(Defender)=10 THEN
17040     X=Top
17043     Top=Bottom
17046     Bottom=X
17049 END IF
17052 Fpr=Top/Bottom
17055 GOSUB Losses
17058 Lossblue=Loss(1)
17061 Lossred=Loss(2)
17064 GOTO Subend
17067 !
17070 !-----
17073 !
17076 Losses: !
17079 FOR I=1 TO 2
17082     GOSUB Rate
17085     X=Pers(I)*Frac_comtd*Brate(I)*Hr_conflict
17088     Loss(I)=X
17091 NEXT I
17094 RETURN
17097 !
17100 !-----
17103 !
17106 Rate: !
17109 SELECT What(I)
17112 CASE 11
17115     Brate(I)=.0384*(Fpr^(-.2383))
17118 CASE 12
17121     Brate(I)=.0384*(Fpr^(-.2383))
17124 CASE 13
17127     Brate(I)=.0384*(Fpr^(-.2383))
17130 CASE 14
17133     Brate(I)=.0483*(Fpr^(-.251))
17136 CASE 15
17139     Brate(I)=.0483*(Fpr^(-.251))
17142 CASE 16
17145     Brate(I)=.0401*(Fpr^(-.237))
17148 CASE 21
17151     Brate(I)=.0125714+(Fpr*.0005)+(.001143*(Fpr*Fpr))
17154 CASE 22
17157     Brate(I)=.003286+(.0034286*Fpr)

```

Table 6-14. Ground combat code (continued).

```

17160 CASE 23
17163   Brate(I)=.003286+(.0034286*Fpr)
17166 CASE 24
17169   Brate(I)=.00919+(.004085*Fpr)+(.000097*(Fpr*Fpr))
17172 CASE 25
17175   Brate(I)=.00919+(.004085*Fpr)+(.000097*(Fpr*Fpr))
17178 CASE 26
17181   Brate(I)=.012714+(.0005*Fpr)+(.001*(Fpr*Fpr))
17184 CASE 27
17187   Brate(I)=.0384*(Fpr^(-.2383))
17190 CASE ELSE
17193   PRINTER IS 1
17196   PRINT "BAD What VALUE IN SUBROUTINE Rate"
17199   STOP
17202 END SELECT
17205 RETURN
17208 Subend:SUBEND
17211 !
17214 !*****
17217 !
17220 SUB Dismount(Sys(*),Load_factor,Mission,Side,Range,Mounted,Dismounted)
17223 ! PURPOSE TO CALCULATE THE NUMBER OF ELEMENTS MOUNTED AND DISMOUNTED
17226 OPTION BASE 1
17229 Side_pt=2*Side-1
17232 Sum_inf=0
17235 FOR I=36 TO 40
17238   Sum_inf=Sum_inf+Sys(Side_pt,I) !TOTAL INFANTRY FOR DF
17241 NEXT I
17244 IF (Mission=4 AND Range<600) OR (Mission>=6 AND Mission<=10) THEN
17247   Mounted=0
17250   Dismounted=Sum_inf
17253 ELSE
17256   Sum_df=Sys(Side_pt,16)+Sys(Side_pt,17)+Sys(Side_pt,18)+Sys(Side_pt,19)
17259   Sys(Side_pt,20)
17259   CALL Load_infantry(Sys(*),Mission,Side_pt,Sum_inf,Sum_df,Load_factor)
17262   Mounted=Sum_df*Load_factor
17265   Dismounted=Sum_inf-Mounted
17268 END IF
17271 SUBEND
17274 !
17277 !*****
17280 !
17283 SUB Load_infantry(Sys(*),Mission,Side_pt,Sum_inf,Sum_df,Load_factor)
17286 !
17289 OPTION BASE 1
17292 SELECT Mission
17295 CASE 1 TO 6
17298   IF Sum_df=0 THEN
17301     Load_factor=0
17304     GOTO End_rtn
17307   END IF
17310   Load_factor=Sum_inf/Sum_df

```


Table 6-14. Ground combat code (continued).

```

17313     IF Load_factor>8 THEN Load_factor=8
17316     GOTO End_rtn
17319     CASE 7 TO 10
17322     Load_factor=0
17325     End_rtn: !
17328     END SELECT
17331     SUBEND
17334     !
17337     !*****
17340     SUB Apport_inf(Target(*),Position,Dismount)
17343     Tot_targ=0
17346     FOR I=36 TO 40 !TOTAL UP INFANTRY FOR DF CARRIER
17349     Tot_targ=Tot_targ+Target(Position,I)
17352     NEXT I
17355     FOR I=36 TO 40 !APPORTION INFANTRY
17358     IF Tot_targ=0 THEN
17361     Target(Position,I)=0
17364     ELSE
17367     Target(Position,I)=(Target(Position,I)/Tot_targ)*Dismount
17370     END IF
17373     NEXT I
17376     SUBEND
17379     !*****
17382     SUB Inf_survive(Sys(*),Pos_init,Sys_rem(*),Pos_rem,Load_factor,Inf_surv
)
17385     !
17388     Sum_df=0
17391     FOR I=16 TO 20 !SUM INFANTRY CARRIERS THAT SURVIVED
17394     Sum_df=Sum_df+Sys_rem(Pos_rem,I)
17397     NEXT I
17400     Mount_inf=Load_factor*Sum_df !NO. OF MOUNTED INFANTRY THAT SURVIVED
17403     !
17406     Sum_inf=0
17409     FOR I=1 TO 5 !SUM INITIAL NO. OF INFANTRY
17412     IF Pos_init>0 THEN Sum_inf=Sum_inf+Sys(Pos_init,I+35)
17415     IF Pos_init=0 THEN Sum_inf=Sum_inf+Sys(1,I)
17418     NEXT I
17421     !
17424     FOR I=1 TO 5 !APPORTION MOUNTED INFANTRY THAT SURVIVED
17427     IF Sum_inf=0 THEN
17430     Inf_surv(I)=0
17433     ELSE
17436     IF Pos_init>0 THEN Inf_surv(I)=(Sys(Pos_init,I+35)/Sum_inf)*Mount_
17439     IF Pos_init=0 THEN Inf_surv(I)=(Sys(1,I)/Sum_inf)*Mount_inf
17442     END IF
17445     NEXT I
17448     SUBEND
17451     !*****
17454     !
17457     SUB Arty_atrit(Sys_art(*),B_msn,R_msn,Bif_fired(*),Rif_fired(*),T_leng
*),T_width(*),B_afire,R_afire,B_phase,Atk_def,Sys_tot(*),R)
17460     OPTION BASE 1

```

Table 6-14. Ground combat code (continued).

```

17463!
17466 DIM A1(15,72),F_d(5,72),Ps(72),Del_par(15,10)
17469 DIM Area(5),Length(5),Width(5),Disk3$(50)
17472 DIM Vollies(15,5)
17475!
17478 COM /Arty/ B_area_band(5),R_area_band(5),B_disprsn_mask(3,10),R_disprsn
ask(3,10),B_tgt_mask(5,72),R_tgt_mask(5,72),B_rd_wt(15),R_rd_wt(15)
17481 COM /Arty/ B_psnl_posture(2,2),R_psnl_posture(2,2),Tle(5)
17484!
17487 Barty_fire=B_afire
17490 Rarty_fire=R_afire
17493 IF Barty_fire>4 THEN Barty_fire=4
17496 IF Rarty_fire>4 THEN Rarty_fire=4
17499!
17502! BLUE firing on RED
17505 FOR Task=1 TO 5
17508     Increase_radius=0
17511     Calc tgt area
17514     ! this reduces total area to only that area task is targeted against
17517     Area(Task)=T_length(2)*T_width(2)*R_area_band(Task)
17520     ! now handle dispersion
17523     IF Barty_fire>1 THEN
17526     ! IF THE TARGET IS RECEIVING FIRE, IT CAN DISPERSE DEPENDING ON MSN%PHAS
17529     IF R_disprsn_mask(B_phase,R_msn)=1 THEN
17532     Increase_radius=200*(Barty_fire-1)     ! 200 DISMT MOVE/30 MIN
17535     IF R=0 AND Atk_def=0 THEN
17538     Increase_radius=1000*(Barty_fire-1)   ! 1000 MOUNT MOVE/30 MIN
17541     END IF
17544     Radius=SQR(Area(Task)/PI)
17547     Area(Task)=PI*(Radius+Increase_radius)^2
17550     END IF
17553     END IF
17556 Calc_len_r: !
17559     Length(Task)=SQR(Area(Task))
17562     Width(Task)=Length(Task)
17565 NEXT Task
17568 !
17571 ! LOAD LETHAL AREAS
17574 ! CHANGE BARTLA$ AND DISK3$ TO READ NEW FILENAMES AND WINCHESTER
17577 Bartla$="BH_R_LA"
17580 Disk3$=":9134,704,0"
17583 ASSIGN @Areafile TO Bartla$&&Disk3$
17586 ENTER @Areafile;A1(*)
17589 ! CONVERT TONS OF AMMO TO VOLLIES TO FIRE
17592 FOR Type=1 TO 15
17595     FOR Task=1 TO 5
17598     IF Type>=12 AND Type<=15 THEN     !MLRS
17601     Tubes_per_vol=1
17604     ELSE
17607     Tubes_per_vol=6
17610     END IF
17613     Throw_wt=Tubes_per_vol*B_rd_wt(Type)

```

Table 6-14. Ground combat code (continued).

```

17616     IF Sys_tot(2,Type+20)>0 THEN
17619         VOLLIES(Type,Task)=Bif_fired(Type,Task)/Throw_wt
17622     ELSE
17625         VOLLIES(Type,Task)=0      ! number of Btry/plt vollies or lchr loac
17628     END IF
17631     NEXT Task
17634     NEXT Type
17637 !
17640     Bfd$="FIDEL_H"
17643     Disk3$=":9134,704,0"
17646     ASSIGN @Readblue TO Bfd$&&Disk3$
17649     ENTER @Readblue;Del_par(*)
17652 !
17655 ! calculate fd & total if losses
17658 !
17661 ! THIS CHANGE TO DEL_PAR(1,3) REFLECTS TWO CANNON ARTILLERY SYSTEM BEIN
17664 ! PLAYED FOR BLUE(155MM AND 8") ONLY ONE USED IN HTLD STUDY
17667 !
17670     FOR Element=1 TO 35
17673         Ps(Element)=1
17676         GOSUB Compute
17679 ! this computes total losses due to indirect fire
17682         Sys_arty(4,Element)=(1-Ps(Element))*Sys_arty(3,Element)
17685     NEXT Element
17688 ! this allows 2 postures for infantry
17691     Element=71      ! standing
17694     Ps(71)=1
17697     GOSUB Compute
17700 !
17703     Element=72      ! CROUCH
17706     Ps(72)=1
17709     GOSUB Compute
17712 !
17715     Attacker=Atk_def+1
17718     IF Barty_fire>1 THEN
17721         Posture=B_psnl_posture(Attacker,2)
17724     ELSE
17727         Posture=B_psnl_posture(Attacker,1)
17730     END IF
17733 !
17736     Ps_inf=(1-Posture)*Ps(71)+Posture*Ps(72)
17739     FOR Element=36 TO 47
17742         Ps(Element)=Ps_inf
17745         Sys_arty(4,Element)=(1-Ps(Element))*Sys_arty(3,Element)
17748     NEXT Element
17751     FOR Element=48 TO 70
17754         Ps(Element)=1
17757         GOSUB Compute
17760         Sys_arty(4,Element)=(1-Ps(Element))*Sys_arty(3,Element)
17763     NEXT Element
17766 !
17769 !-----

```

Table 6-14. Ground combat code (continued).

```

17772!
17775! RED firing on BLUE
17778 FOR Task=1 TO 5
17781   Increase_radius=0
17784 ! Calc tgt area
17787 ! this reduces total area to only that area task is targeted against
17790 !
17793   Area(Task)=T_length(1)*T_width(1)*B_area_band(Task)
17796 ! now handle dispersion
17799   IF Rarty_fire>1 THEN
17802 ! IF THE TARGET IS RECEIVING FIRE, IT CAN DISPERSE DEPENDING ON MSN&PHAS
17805   IF B_disprsn_mask(B_phase,B_msn)=1 THEN
17808     Increase_radius=200*(Rarty_fire-1)
17811     IF R=0 AND Atk_def=1 THEN
17814       Increase_radius=1200*(Rarty_fire-1)
17817     END IF
17820     Radius=SQR(Area(Task)/PI)
17823     Area(Task)=PI*(Radius+Increase_radius)^2
17826   END IF
17829 END IF
17832 Calc_len_b: !
17835   Length(Task)=SQR(Area(Task))
17838   Width(Task)=Length(Task)
17841 NEXT Task
17844 ! LOAD LETHAL AREAS
17847 Rartla$="R_H_LA"
17850 Disk3$=":9134,704,0"
17853 ASSIGN @Areafile TO Rartla$&&Disk3$
17856 !
17859 ENTER @Areafile;A1(*)
17862 ! CONVERT TONS OF AMMO TO VOLLIES TO FIRE
17865 !
17868 FOR Type=1 TO 15
17871   FOR Task=1 TO 5
17874     IF Type>=12 AND Type<=15 THEN !MLRS
17877       Tubes_per_vol=1
17880     ELSE
17883       Tubes_per_vol=6
17886     END IF
17889     Throw_wt=Tubes_per_vol*R_rd_wt(Type)
17892     IF Sys_tot(4,Type+20)>0 THEN
17895       Vollies(Type,Task)=Rif_fired(Type,Task)/Throw_wt
17898     ELSE
17901       Vollies(Type,Task)=0 ! number of Btry/plt vollies or lchr loads
17904     END IF
17907   NEXT Task
17910 NEXT Type
17913 !
17916 Rfd$="FIDEL_R"
17919 Disk3$=":9134,704,0"
17922 ASSIGN @Readred TO Rfd$&&Disk3$
17925 ENTER @Readred;Del_par(*)

```

Table 6-14. Ground combat code (continued).

```

17928 !
17931 ! calculate fd & total if losses
17934 FOR Element=1 TO 35
17937     Ps(Element)=1
17940     GOSUB Compute_red
17943 !   this computes total losses due to indirect fire
17946     Sys_arty(2,Element)=(1-Ps(Element))*Sys_arty(1,Element)
17949     IF Element=1 THEN
17952         END IF
17955     NEXT Element
17958 ! this allows 2 postures for infantry
17961     Element=71 ! standing
17964     Ps(71)=1
17967     GOSUB Compute_red
17970 !
17973     Element=72 ! CROUCH
17976     Ps(72)=1
17979     GOSUB Compute_red
17982 !
17985     Attacker=Atk_def+1
17988     IF Rarty_fire>1 THEN
17991         Posture=R_psnl_posture(Attacker,2)
17994     ELSE
17997         Posture=R_psnl_posture(Attacker,1)
18000     END IF
18003 !
18006     Ps_inf=(1-Posture)*Ps(71)+Posture*Ps(72)
18009     FOR Element=36 TO 47
18012         Ps(Element)=Ps_inf
18015         Sys_arty(2,Element)=(1-Ps(Element))*Sys_arty(1,Element)
18018     NEXT Element
18021 !
18024     FOR Element=48 TO 70
18027         Ps(Element)=1
18030         GOSUB Compute_red
18033         Sys_arty(2,Element)=(1-Ps(Element))*Sys_arty(1,Element)
18036     NEXT Element
18039                                     ! FOR Element=1 TO 70
18042                                     ! NEXT Element
18045!
18048     GOTO Sub_end
18051!
18054!-----
18057!
18060 Compute: !
18063     FOR Task=1 TO 5
18066         F_d(Task,Element)=0
18069     NEXT Task
18072     !
18075     FOR Task=1 TO 5
18078         IF R_tgt_mask(Task,Element)=0 THEN End_loop
18081     ! Type=1 ! arty firing DP-ICM @ 10 K

```

Table 6-14. Ground combat code (continued).

```

18084     FOR Type=1 TO 7
18087         IF Vollies(Type,Task)>0 THEN
18090             GOSUB Re_read
18093             W_dp=L_dp
18096             P_dp=1-EXP(P_dp_f*A1(Type,Element))
18099             A_el=L_dp*W_dp*P_dp
18102             L_v=L_v_fac*(Sys_tot(2,Type+20)/6)
18105             W_v=W_v_fac*(Sys_tot(2,Type+20)/6)
18108             N_r=6
18111             GOSUB Calculate_fd
18114         END IF
18117     NEXT Type
18120 !
18123 Tpe2: !
18126 !
18129 !     Type=2 ! MLRS firing DP-ICM @ 25 Km
18132     FOR Type=12 TO 15
18135         IF Vollies(Type,Task)>0 THEN
18138             GOSUB Re_read
18141             W_dp=L_dp
18144             P_dp=1-EXP(P_dp_f*A1(Type,Element))
18147             A_el=L_dp*W_dp*P_dp
18150             L_v=L_v_fac*(Sys_tot(2,Type+20))
18153             W_v=W_v_fac*(Sys_tot(2,Type+20))
18156             N_r=12
18159             GOSUB Calculate_fd
18162         END IF
18165     NEXT Type
18168 !
18171 Tpe3: !
18174 !
18177 !     Type=3 ! MORTAR FIRING HE @ 3 Km
18180     FOR Type=8 TO 11
18183         IF Vollies(Type,Task)>0 THEN
18186             GOSUB Re_read
18189             L_dp=L_dp_f*SQR(A1(Type,Element))
18192             W_dp=L_dp/.564288772
18195             A_el=A1(Type,Element)
18198             L_v=L_v_fac*(Sys_tot(2,Type+20)/6)
18201             W_v=W_v_fac*(Sys_tot(2,Type+20)/6)
18204             N_r=6
18207             GOSUB Calculate_fd
18210         END IF
18213     NEXT Type
18216 !
18219 !
18222 End_loop: !
18225     NEXT Task
18228     RETURN
18231 !
18234 -----
18237 !

```

Table 6-14. Ground combat code (continued).

```

18240 Compute_red: !
18243   FOR Task=1 TO 5
18246     F_d(Task,Element)=0
18249   NEXT Task
18252   FOR Task=1 TO 5
18255     IF B_tgt_mask(Task,Element)=0 THEN Skip
18258 !   Type=1 ! Arty firing DP-ICM @ 11.5 Km
18261     FOR Type=1 TO 7
18264       IF Vollies(Type,Task)>0 THEN
18267         GOSUB Re_read
18270         L_dp=L_dp_f*SQR(A1(Type,Element))
18273         W_dp=L_dp/.564288772
18276 !   Note: A1 is equivalent rd A1, not submunition
18279         A_el=A1(Type,Element)
18282         L_v=L_v_fac*(Sys_tot(4,Type+20)/6)
18285         W_v=W_v_fac*(Sys_tot(4,Type+20)/6)
18288         N_r=6
18291         GOSUB Calculate_fd
18294       END IF
18297     NEXT Type
18300 Rtpe2: !
18303 !
18306 !   Type=2 ! mrl firing HE @ 13.7 Km
18309   FOR Type=12 TO 15
18312     IF Vollies(Type,Task)>0 THEN
18315       GOSUB Re_read
18318       L_dp=L_dp_f*SQR(A1(Type,Element))
18321       W_dp=L_dp/.564288772
18324       A_el=A1(Type,Element)
18327       L_v=L_v_fac*(Sys_tot(4,Type+20))
18330       W_v=W_v_fac*(Sys_tot(4,Type+20))
18333       N_r=40
18336       GOSUB Calculate_fd
18339     END IF
18342   NEXT Type
18345 !
18348 Rtpe3: !
18351 !
18354 !   Type=3 ! mortar firing HE @ 3.8 Km
18357   FOR Type=8 TO 11
18360     IF Vollies(Type,Task)>0 THEN
18363       GOSUB Re_read
18366       L_dp=L_dp_f*SQR(A1(Type,Element))
18369       W_dp=L_dp/.564288772
18372       A_el=A1(Type,Element)
18375       L_v=L_v_fac*(Sys_tot(4,Type+20)/6)
18378       W_v=W_v_fac*(Sys_tot(4,Type+20)/6)
18381       N_r=6
18384       GOSUB Calculate_fd
18387     END IF
18390   NEXT Type
18393 Skip: !

```

Table 6-14. Ground combat code (continued).

```

18396 NEXT Task
18399 RETURN
18402!
18405!-----
18408!
18411 Calculate_fd: !
18414 L_ap=L_dp+Krep_p      ! Single Round Adj
18417 W_ap=W_dp+Kdep_p    ! Damage Pattern
18420 L_vp=L_ap+L_v
18423 W_vp=W_ap+W_v
18426 A_vp=L_vp*W_vp      ! Volley Damage Pat.
18429 A_ap=L_ap*W_ap
18432 Of=N_r*A_ap/A_vp    ! Overlap Factor
18435 IF Of<1 THEN Of=1
18438 !P_nv=1-(1-(A_el*N_r*R_r)/(A_vp*Of))^(Vollies(Type,Task)*Of) ! P(damage)
18441 P_nv1=(A_el*N_r*R_r)/(A_vp*Of)
18444 IF P_nv1>1 THEN P_nv1=1
18447 P_nv=1-(1-P_nv1)^(Vollies(Type,Task)*Of)
18450 !
18453 Rep_tm=SQR((Rep_m^2)+(.5731*T1e(Task))^2)
18456 Dep_tm=SQR((Dep_m^2)+(.5731*T1e(Task))^2)
18459 A_1=(L_vp+Length(Task))/(2.96*Rep_tm)
18462 A_2=(ABS(L_vp-Length(Task)))/(2.96*Rep_tm)
18465 IF A_1>33.532 THEN A_1=33.532 ! trunk if area too large
18468 IF A_2>33.532 THEN A_2=33.532 ! " "
18471 F_1a=.5*A_1*SQR(1-EXP(-.63*A_1^2))+EXP(-.5*A_1^2)/SQR(2*PI)
18474 F_1b=.5*A_2*SQR(1-EXP(-.63*A_2^2))+EXP(-.5*A_2^2)/SQR(2*PI)
18477 F_1=F_1a-F_1b
18480 Ec_r=2.96*Rep_tm*F_1/Length(Task) ! expected frac coverage in range
18483 B_1=(W_vp+Width(Task))/(2.96*Dep_tm)
18486 B_2=ABS(W_vp-Width(Task))/(2.96*Dep_tm)
18489 IF B_1>33.532 THEN B_1=33.532 ! trunk if area too large
18492 IF B_2>33.532 THEN B_2=33.532 ! " "
18495 F_wa=.5*B_1*SQR(1-EXP(-.63*B_1^2))+EXP(-.5*B_1^2)/SQR(2*PI)
18498 F_wb=.5*B_2*SQR(1-EXP(-.63*B_2^2))+EXP(-.5*B_2^2)/SQR(2*PI)
18501 F_w=F_wa-F_wb
18504 Ec_d=2.96*Dep_tm*F_w/Width(Task) ! expected frac coverage in df
18507 F_d(Task,Element)=Ec_r*Ec_d*P_nv ! " " damage
18510 ! accumulate the prob of surv(Ps) since it is joint prob for all killer
18513 Ps(Element)=Ps(Element)*(1-F_d(Task,Element))
18516 RETURN
18519!
18522!-----
18525!
18528 Re_read: !
18531 L_dp=Del_par(Type,1)
18534 L_dp_f=Del_par(Type,2)
18537 P_dp_f=Del_par(Type,3)
18540 Krep_p=Del_par(Type,4)
18543 Kdep_p=Del_par(Type,5)
18546 L_v_fac=Del_par(Type,6)
18549 W_v_fac=Del_par(Type,7)

```


Table 6-14. Ground combat code (continued).

```

18552 R_r=Del_par(Type,8)
18555 Dep_m=Del_par(Type,9)
18558 Rep_m=Del_par(Type,10)
18561 RETURN
18564 !
18567 -----
18570 !
18573 Sub_end: !
18576 ASSIGN @Readred TO *
18579 ASSIGN @Readblue TO *
18582 ASSIGN @Areafile TO *
18585 SUBEND
18588 !
18591 !*****
18594 !
18597 SUB Ck_var(Var_name$,T$,Variable,Min_value,Max_value)
18600 PRINTER IS 1
18603 SELECT T$
18606 CASE "THRU"
18609     WHILE Variable<Min_value OR Variable>Max_value
18612         GOSUB Print_error
18615     END WHILE
18618 CASE "OR"
18621     GOTO Case_to
18624 CASE "TO"
18627 Case_to:FOR M=Min_value TO Max_value
18630     IF Variable=M THEN GOTO End_select
18633     NEXT M
18636     GOSUB Print_error
18639     GOTO Case_to
18642 End_select: !
18645 END SELECT
18648 GOTO Rtrn
18651 Print_error: !
18654 PRINT
18657 PRINT "** ERROR: ";Variable;" IS INVALID FOR ";Var_name$
18660 PRINT "INPUT: ";Min_value;" ";T$;" ";Max_value;" ONLY"
18663 INPUT Variable
18666 RETURN
18669 Rtrn: !
18672 SUBEND
18675 !
18678 !*****
18681 !
18684 SUB Smoke(Iunit, Ielem, Amowt (*), Fwidt, Mtime, Ikm, Range, Sleng (*), Tot_sleng.
n (*), Pseopt (*), Pseecs (*), Pseethm (*), Irh)
18687 OPTION BASE 1
18690 DIM Smkdat(3,2,4,7), Snrd(7), Disk3$(50)
18693 DIM Elem$(1), Type$(4), Side$(1)
18696 CDM /Smoke/ Amwtp(3,11), Irof(3,11)
18699 !
18702 Disk3$=":9134,704,0"

```

Table 6-14. Ground combat code (continued).

```

18705 IF Ikm=1 THEN Ikm=4
18708 IF Ikm=2 THEN Ikm=3
18711 IF Ikm=3 THEN Ikm=2
18714 IF Ikm=4 THEN Ikm=1
18717 IF Range<=500 THEN Irg=1
18720 IF Range<=1000 AND Range>500 THEN Irg=2
18723 IF Range<=1500 AND Range>1000 THEN Irg=3
18726 IF Range<=2000 AND Range>1500 THEN Irg=4
18729 IF Range<=2500 AND Range>2000 THEN Irg=5
18732 IF Range<=3000 AND Range>2500 THEN Irg=6
18735 IF Range>3000 THEN Irg=7
18738 !
18741 Istart=1
18744 IF Ielem=1 THEN !READ ARTILLERY DATA
18747 Iend=7
18750 Type$="ARTY"
18753 ELSE !READ MORTAR DATA
18756 Iend=4
18759 Type$="MORT"
18762 END IF
18765 IF Iunit=1 OR Iunit=2 THEN Side$="B"
18768 IF Iunit=3 THEN Side$="R"
18771 FOR I=Istart TO Iend
18774 J=I+Ielem-1
18777 Elem$=VAL$(I)
18780 ASSIGN @P TO "SMK_"&Type$&Side$&Elem$&Disk3$
18783 ENTER @P,1;Smkdat(*)
18786 ASSIGN @P TO *
18789 LET Pseeopt(I)=Smkdat(1,Irh,Ikm,Irg)
18792 LET Pseecs(I)=Smkdat(2,Irh,Ikm,Irg)
18795 LET Pseethm(I)=Smkdat(3,Irh,Ikm,Irg)
18798 !
18801 IF Amowt(J)>0 THEN
18804 LET Amwtp=Amowt(J)*2000
18807 LET Nrd=INT(Amwtp/Amwtp(Iunit,J))
18810 LET Snrd(I)=Nrd !SAVE NUMBER OF ROUNDS FIRED
18813 !
18816 ! THIS PORTION OF THE PROGRAM CALCULATES THE LENGTH(LENG) OF THE
18819 ! SCREEN, WHERE LENGTH IS EQUAL TO (NRD/(MTIME*IROF))*200
18822 LET Sleng(I)=(Nrd/(Mtime*Irof(Iunit,J)))*200
18825 Tot_sleng=Tot_sleng+Sleng(I) ! TOTAL LENGTH OF SCREEN
18828 ELSE
18831 Snrd(I)=0
18834 Sleng(I)=0
18837 END IF
18840 NEXT I
18843 !
18846 ! THIS PORTION OF THE PROGRAM DETERMINES IF THE SCREEN LENGTH(SLENG)
18849 ! IS GREATER THAN FRONTAGE WIDTH(FWIDT)...IF SO THEN SLENG BECOMES
18852 ! FWIDT AND EXTRA AMMO IS RETURNED TO DRIVER ROUTINE
18855 IF Tot_sleng>Fwidt THEN
18858 Perc_used=1-(Tot_sleng-Fwidt)/Tot_sleng

```

Table 6-14. Ground combat code (continued).

```

18861     Tot_sleng=Fwidt
18864     ELSE
18867       Perc_used=1.0
18870     END IF
18873     ! DETERMINE ANY UNUSED AMMO AND RETURN IN VARIABLE--TON
18876     FOR I=Istart TO Iend
18879       J=I+Ielem-1
18882       Sleng(I)=Sleng(I)*Perc_used
18885       IF Sleng(I)>0 THEN Nrd=INT(Sleng(I)/200*(Mtime*Irof(Iunit,J))+.5)
18888       IF Sleng(I)<=0 THEN Nrd=0
18891       IF Snrd(I)>Nrd THEN
18894         Nrd1=Snrd(I)-Nrd
18897         LET Amwtp1=Amwtp(Iunit,J)*Nrd1
18900         LET Ton(I)=Amwtp1/2000
18903       END IF
18906     NEXT I
18909     !DETERMINE THE % OF FRONTAGE COVERED BY THE SCREEN, WHERE THE % OF
18912     !FRONTAGE SMOKED(Psmoked) = LENGTH OF SCREEN DIVIDED BY THE TOTAL
18915     !FRONTAGE BETWEEN UNITS(FWIDT)
18918     Psmoked=Tot_sleng/Fwidt
18921     !
18924     !% FRONTAGE NOT COVERED BY SCREEN
18927     Pnotsmk=1-Psmoked
18930     !
18933     SUREND
18936     !
18939     !*****
18942     !
18945     SUB Smkemp(Iunt, Ielem, Amowt(*), Fwidt, Mxtime, Ik, Range, Mton(*), Aton(*), Pvc
, Pvc, Pvth, Irh)
18948     ! THIS ROUTINE CALLS FOR SMOKE. 1) MORTARS EMPLACE SMOKE... IF MORTARS
18951     ! ARE UNABLE TO COVER ENTIRE FRONTAGE, THEN 2) ARTILLERY EMPLACE SMOKE,
18954     ! BASED ON THE UNSMOKED FRONTAGE..
18957     !
18960     OPTION BASE 1
18963     DIM Mpseeopt(4), Mpseecs(4), Mpseeth(4), Apseeopt(7), Apseecs(7), Apseeth(7)
18966     DIM Mleng(4), Aleng(7)
18969     !
18972     Iunit=Iunt
18975     Ik=Ik
18978     Amwt=0
18981     FOR I=1 TO 4       ! TOTAL WT. OF MORT AMMO AVAILABLE TO FIRE FOR SMOKE
18984       Amwt=Amwt+Amowt(I+7)
18987     NEXT I
18990     IF Amwt>0 THEN
18993       Ielem=8
18996       CALL Smoke(Iunit, Ielem, Amowt(*), Fwidt, Mxtime, Ik, Range, Mleng(*), Tot_m
ng, Mton(*), Mpseeopt(*), Mpseecs(*), Mpseeth(*), Irh)
18999     END IF
19002     ! DETERMINE IF FRONTAGE IS COMPLETELY COVERED... IF NOT CALL EMPLACE ARTI
ERY SMOKE
19005     Amwt=0

```

Table 6-14. Ground combat code (continued).

```

19008 FOR I=1 TO 7      ! TOTAL WT. OF ARTY AMMO AVAILABLE TO FIRE FOR SMOKE
19011   Amwt=Amwt+Amwt(I)
19014 NEXT I
19017 IF Amwt>0 THEN
19020   IF Fwidt>Tot_mleng THEN
19023     Flwidt=Fwidt-Tot_mleng
19026     Ielem=1
19029     CALL Smoke(Iunit, Ielem, Amwt(*), Flwidt, Mxtime, Ikm, Range, Aleng(*),
aleng, Aton(*), Apseeopt(*), Apseecs(*), Apseeth(*), Irh)
19032   ELSE
19035     FOR I=1 TO 7
19038       Aton(I)=Amwt(I)
19041     NEXT I
19044   END IF
19047 END IF
19050 ! CALCULATE THE PERCENT VISIBLE ACROSS ENTIRE FRONTAGE FOR MAX TIME, AS
19053 ! A FUNCTION OF OPTICS SENSORS
19056 !
19059 LET Pnotsmok=((Fwidt-(Tot_mleng+Tot_aleng))/Fwidt)*1
19062 Pmorto=0
19065 FOR I=1 TO 4
19068   LET Pmorto=Pmorto+((Mleng(I)/Fwidt)*Mpseeopt(I))
19071 NEXT I
19074 Partyo=0
19077 FOR I=1 TO 7
19080   LET Partyo=Partyo+((Aleng(I)/Fwidt)*Apseeopt(I))
19083 NEXT I
19086 LET Pvopt=Pmorto+Partyo+Pnotsmok
19089 ! CALCULATE THE PERCENT VISIBLE ACROSS ENTIRE FRONTAGE FOR MAX TIME
19092 ! AS A FUNCTION OF CREW SERVED SENSORS
19095 !
19098 Pmortc=0
19101 FOR I=1 TO 4
19104   LET Pmortc=Pmortc+((Mleng(I)/Fwidt)*Mpseecs(I))
19107 NEXT I
19110 Partyc=0
19113 FOR I=1 TO 7
19116   LET Partyc=Partyc+((Aleng(I)/Fwidt)*Apseecs(I))
19119 NEXT I
19122 LET Pvcs=Pmortc+Partyc+Pnotsmok
19125 ! CALCULATE THE PERCENT VISIBLE ACROSS ENTIRE FRONTAGE FOR MAX TIME
19128 ! AS A FUNCTION OF THERMAL SENSORS
19131 !
19134 Pmortt=0
19137 FOR I=1 TO 4
19140   LET Pmortt=Pmortt+((Mleng(I)/Fwidt)*Mpseeth(I))
19143 NEXT I
19146 Partyt=0
19149 FOR I=1 TO 7
19152   LET Partyt=Partyt+((Aleng(I)/Fwidt)*Apseeth(I))
19155 NEXT I
19158 LET Pvth=Pmortt+Partyt+Pnotsmok

```

Table 6-14. Ground combat code (continued).

```

19161 SUBEND
19164 !
19167 !*****
19170 !
19173 SUB Df_attrition(B_vua(*),R_vua(*),Terrain,Day_nite,Vis.Num_bands,Rng_ba
,Atk_def,Sys(*),B_tons(*),R_tons(*),B_vis(*),R_vis(*),T,S,Bu,Ru,St,DC)
19176 !
19179 OPTION BASE 1
19182 !
19185 DIM Init_b_targets(70),Init_r_targets(70)
19188 DIM B_ammo(20),R_ammo(20)
19191 DIM B_ecf(20),R_ecf(20),B_ecf_vis(20,4),R_ecf_vis(20,4)
19194 DIM B_fire_d(20,20),R_fire_d(20,20)
19197 DIM B_pk_fe(20,20),R_pk_fe(20,20)
19200 DIM B_pk_hd(20,20),R_pk_hd(20,20)
19203 DIM B_targ(20),R_targ(20)
19206 DIM B_rnds_wep(20),R_rnds_wep(20)
19209 DIM B_sum(20),R_sum(20)
19212 DIM B_fdf(20,20),R_fdf(20,20)
19215 DIM Tot_b_rnds(20),Tot_r_rnds(20)
19218 DIM B_rnds_cat(20,17),R_rnds_cat(20,17)
19221 DIM Loss_b_cat(17),Loss_r_cat(17)
19224 DIM Loss_blue(70),Loss_red(70)
19227 DIM B_psuv(17),R_psuv(17)
19230 DIM B_targ_vis(17),R_targ_vis(17)
19233 DIM B_ex_r(20,17),R_ex_r(20,17)
19236 DIM B_ps(20,17),R_ps(20,17)
19239 DIM Lo_b_cats(17),Lo_r_cats(17)
19242 DIM Lo_b_cat(20,17),Lo_r_cat(20,17)
19245 DIM B_vul(17),R_vul(17),B_vul_t(17),R_vul_t(17)
19248 DIM B_sen(70),R_sen(70),B_look(17),R_look(17)
19251 DIM Df_pk_fe(20,20),Df_pk_hd(20,20)
19254 INTEGER I,J
19257 !
19260 COM /Direct_fire/ B_cat(70),R_cat(70),B_sen_d(70),B_sen_n(70),R_sen_d(7
,R_sen_n(70),B_ammo_wt(20),R_ammo_wt(20)
19263 !
19266 COM /Helo_info/ Btl_rg,Rg_avg(2,3,20),Rg_avg_pd(2,3,5),Df_ammo(2),Df_fir
dist(2,20,3),Df_pk_helo(2,20,3,2),INTEGER Df_sen_ptr(2,20),Df_muni_ptr(2,20)
19269 !
19272 COM /No_helos/ Cell(2,2,3)
19275 !
19278 Main:
19281 GOSUB Set_call
19284 GOSUB Init_reads
19287 !BEGIN RANGE BAND LOOP
19290 FOR Band_loop=1 TO Loops
19293 GOSUB Read_files
19296 GOSUB Categorize
19299 GOSUB Smokes
19302 GOSUB Calc_fdf
19305 GOSUB Ammo_available

```

Table 6-14. Ground combat code (continued).

```

19308 GOSUB Calc_rnd
19311 GOSUB Update_ammo
19314 GOSUB Calc_loss
19317 GOSUB Decat_losses
19320 GOSUB Set_next_loop
19323 IF Abort$="YES" THEN GOTO Out_loop
19326 NEXT Band_loop
19329 Out_loop:
19332 GOTO Set_return
19335 !
19338 !-----
19341 !
19344 Set_cal::
19347 Abort$="NO"
19350 Rng_band_save=Rng_band
19353 !INITIALIZE AMMO USED TO ZERO AND ELEMENTS KILLED TO ZERO
19356 FOR I=1 TO 70
19359 !SAVE INITIAL TARGETS
19362 Init_b_targets(I)=Sys(1,I)
19365 Init_r_targets(I)=Sys(3,I)
19368 NEXT I
19371 !INITIALIZE FOR LOOPS
19374 Loops=Num_bands
19377 Partial=1
19380 IF Num_bands<1 THEN
19383 Loops=1
19386 Partial=Num_bands
19389 END IF
19392 RETURN
19395 !
19398 !-----
19401 !
19404 Init_reads:
19407 IF Day_nite=0 THEN !DAY
19410 FOR I=1 TO 70
19413 B_sen(I)=B_sen_d(I)
19416 R_sen(I)=R_sen_d(I)
19419 NEXT I
19422 ELSE !NIGHT
19425 FOR I=1 TO 70
19428 B_sen(I)=B_sen_n(I)
19431 R_sen(I)=R_sen_n(I)
19434 NEXT I
19437 END IF
19440 !
19443 Disk3$=":9134,704,0"
19446 R$="RD"
19449 B$="BH"
19452 Rr$="RH"
19455 !SELECT ECF FILES
19458 SELECT Atk_def
19461 CASE 0

```

Table 6-14. Ground combat code (continued).

```

19464 Rad$="A"
19467 Bad$="D"
19470 CASE 1
19473 Rad$="D"
19476 Bad$="A"
19479 END SELECT
19482 !
19485 SELECT Day_nite
19488 CASE 0
19491 Dn$="D"
19494 CASE 1
19497 Dn$="N"
19500 END SELECT
19503 !
19506 SELECT Terrain
19509 CASE 1
19512 T$="D"
19515 CASE 2
19518 T$="R"
19521 CASE 3
19524 T$="H"
19527 CASE 4
19530 T$="M"
19533 END SELECT
19536 !
19539 !ENTER FIRE DISTRIBUTIONS
19542 ASSIGN @Path1 TO B$&"_FIRE_"&Bad$&":9134,704,0" !Disk3$
19545 ASSIGN @Path2 TO R$&"_FIRE_"&Rad$&":9134,704,0" !Disk3$
19548 ENTER @Path1,1;B_fire_d(*)
19551 ENTER @Path2,1;R_fire_d(*)
19554 ASSIGN @Path1 TO *
19557 ASSIGN @Path2 TO *
19560 !
19563 ! OPEN FILES THAT ARE READ WITHIN RANGE BAND LOOP
19566 ASSIGN @Path1 TO B$&Dn$&Bad$&"_ECF_"&T$&Disk3$
19569 ASSIGN @Path2 TO R$&Dn$&Rad$&"_ECF_"&T$&Disk3$
19572 ASSIGN @Path_b_fe TO B$&"_PKFE"&":9134,704,0" !Disk3$
19575 ASSIGN @Path_b_hd TO B$&"_PKHD"&":9134,704,0" !Disk3$
19578 ASSIGN @Path_r_fe TO R$&"_PKFE"&":9134,704,0" !Disk3$
19581 ASSIGN @Path_r_hd TO R$&"_PKHD"&":9134,704,0" !Disk3$
19584 FOR Side=1 TO 2 !READ IN & SAVE THE PK'S FOR HELOS BY DF
19587 Side_def=(Side MOD 2)+1
19590 FOR I=1 TO 3 !LOOP ON HELOS
19593 Helo_bnd=INT(Rg_avg(Side_def,I,1)/500+.5) !CALC HELO FK RANGE BAN
19596 IF Helo_bnd<=0 THEN Helo_bnd=1
19599 IF Helo_bnd<=6 THEN
19602 IF Side=1 THEN !BLUE
19605 ENTER @Path_b_fe,Helo_bnd;Df_pk_fe(*)
19608 ENTER @Path_b_hd,Helo_bnd;Df_pk_hd(*)
19611 ELSE !RED
19614 ENTER @Path_r_fe,Helo_bnd;Df_pk_fe(*)
19617 ENTER @Path_r_hd,Helo_bnd;Df_pk_hd(*)

```

Table 6-14. Ground combat code (continued).

```

19620         END IF
19623         FOR J=1 TO 20    !LOOP ON DF
19626             Df_pk_helo(Side,J,I,1)=Df_pk_fe(J,I+17) !NON MAST MOUNTED
19629             Df_pk_helo(Side,J,I,2)=Df_pk_hd(J,I+17) !MAST MOUNTED
19632         NEXT J
19635         ELSE    !OUTSIDE OF DF RANGE
19638             FOR J=1 TO 20
19641                 Df_pk_helo(Side,J,I,1)=0
19644                 Df_pk_helo(Side,J,I,2)=0
19647             NEXT J
19650         END IF
19653     NEXT I
19656 NEXT Side
19659 !
19662 RETURN
19665 !
19668 -----
19671 !
19674 Read_files: !
19677 !
19680 ENTER @Path1,Rng_band;B_ecf_vis(*)
19683 ENTER @Path2,Rng_band;R_ecf_vis(*)
19686 !
19689 FOR I=1 TO 20
19692     B_ecf(I)=B_ecf_vis(I,Vis)
19695     R_ecf(I)=R_ecf_vis(I,Vis)
19698 NEXT I
19701 !
19704 !DIVIDE ECF'S FOR PART OF RANGE BAND
19707 FOR I=1 TO 20
19710     B_ecf(I)=B_ecf(I)*Partia)
19713     R_ecf(I)=R_ecf(I)*Partia!
19716 NEXT I
19719 !
19722 !ENTER PK FILES
19725 ENTER @Path_b_fe,Rng_band;B_pk_fe(*)
19728 ENTER @Path_b_hd,Rng_band;B_pk_hd(*)
19731 ENTER @Path_r_fe,Rng_band;R_pk_fe(*)
19734 ENTER @Path_r_hd,Rng_band;R_pk_hd(*)
19737 FOR I=1 TO 20
19740     FOR J=1 TO 3
19743         B_pk_fe(I,J+17)=Df_pk_helo(1,I,J,1)    !SET HELO'S PK IN ARRAY
19746         R_pk_fe(I,J+17)=Df_pk_helo(2,I,J,1)
19749     NEXT J
19752 NEXT I
19755 RETURN
19758 !
19761 -----
19764 !
19767 Categorize: !   ROB
19770 Dc=Dc+1
19773 !           Roy_files$="R_"&VAL$(T)&"_"&VAL$(S)&"_"&VAL$(Dc)

```


Table 6-14. Ground combat code (continued).

```

19776 ! CREATE BDAT Roy_file%&":HF9121,700,1",10,1550
19779 ! ASSIGN @Proy TO Roy_file%&":HF9121,700,1"
19782 ! OUTPUT @Proy,1;T,S,Bu,Ru,St
19785 ! OUTPUT @Proy,2;Sys(*)
19788 ! INITIALIZE CATEGORIES
19791 FOR I=1 TO 17
19794 B_vul(I)=0
19797 R_vul(I)=0
19800 B_vul_t(I)=0
19803 R_vul_t(I)=0
19806 NEXT I
19809 FOR I=1 TO 20
19812 B_targ(I)=0
19815 R_targ(I)=0
19818 NEXT I
19821 ! ADD ELEMENTS TO CATEGORIES
19824 FOR I=1 TO 70
19827 IF B_cat(I)>0 AND B_cat(I)<=17 THEN
19830 B_targ(B_cat(I))=B_targ(B_cat(I))+Sys(1,I)
19833 B_vul_t(B_cat(I))=B_vul_t(B_cat(I))+Sys(1,I)*B_vua(I)
19836 END IF
19839 IF R_cat(I)>0 AND R_cat(I)<=17 THEN
19842 R_targ(R_cat(I))=R_targ(R_cat(I))+Sys(3,I)
19845 R_vul_t(R_cat(I))=R_vul_t(R_cat(I))+Sys(3,I)*R_vua(I)
19848 END IF
19851 NEXT I
19854 FOR I=18 TO 20 ! ADD HELD ELEMENTS TO TGT CATEGORIES
19857 B_targ(I)=Cell(1,1,I-17)
19860 R_targ(I)=Cell(2,1,I-17)
19863 NEXT I
19866 FOR I=1 TO 17
19869 IF B_targ(I)>0 THEN B_vul(I)=B_vul_t(I)/B_targ(I)
19872 IF R_targ(I)>0 THEN R_vul(I)=R_vul_t(I)/R_targ(I)
19875 NEXT I
19878 ! OUTPUT @Proy,3;B_targ(*),R_targ(*)
19881 RETURN
19884 !
19887 ! -----
19890 !
19893 Smokes: !
19896 ! CALCULATE TARGETS VISIBLE THROUGH SMOKE
19899 FOR I=1 TO 17
19902 B_targ_vis(I)=0
19905 R_targ_vis(I)=0
19908 B_look(I)=0
19911 R_look(I)=0
19914 NEXT I
19917 ! ADD VISIBLE ELEMENTS TO EACH CATEGORY
19920 FOR I=1 TO 17 ! GROUND TGT CATEG
19923 FOR J=1 TO 20 ! DIRECT FIRERS
19926 B_targ_vis(I)=B_targ_vis(I)+Sys(6,J)*R_vis(R_sen(J))
19929 R_targ_vis(I)=R_targ_vis(I)+Sys(5,J)*B_vis(B_sen(J))

```

Table 6-14. Ground combat code (continued).

```

19932     R_look(I)=R_look(I)+Sys(6,J)
19935     B_look(I)=B_look(I)+Sys(5,J)
19938     NEXT J
19941     IF R_look(I)>0 THEN
19944         B_targ_vis(I)=B_targ_vis(I)/R_look(I)
19947     ELSE
19950         B_targ_vis(I)=0
19953     END IF
19956     IF B_look(I)>0 THEN
19959         R_targ_vis(I)=R_targ_vis(I)/B_look(I)
19962     ELSE
19965         R_targ_vis(I)=0
19968     END IF
19971     NEXT I
19974     RETURN
19977!
19980!-----
19983!
19986 Calc_fdf: ! FIRE DISTRIBUTION FACTOR
19989     FOR I=1 TO 20
19992         B_sum(I)=0
19995         R_sum(I)=0
19998     NEXT I
20001     !SUM
20004     FOR I=1 TO 20
20007         FOR J=1 TO 20
20010             B_sum(I)=B_sum(I)+R_targ(J)*B_fire_d(I,J)*B_pk_fe(I,J)
20013             R_sum(I)=R_sum(I)+B_targ(J)*R_fire_d(I,J)*R_pk_fe(I,J)
20016         NEXT J
20019     NEXT I
20022     !
20025     !CALC FDF
20028     FOR I=1 TO 20
20031         FOR J=1 TO 20
20034             R_fdf(I,J)=0
20037             B_fdf(I,J)=0
20040             IF B_sum(I)<>0 THEN
20043                 B_fdf(I,J)=R_targ(J)*B_fire_d(I,J)*B_pk_fe(I,J)/B_sum(I)
20046             END IF
20049             IF R_sum(I)<>0 THEN
20052                 R_fdf(I,J)=B_targ(J)*R_fire_d(I,J)*R_pk_fe(I,J)/R_sum(I)
20055             END IF
20058         NEXT J
20061         FOR J=1 TO 3     !STORE FIRE DISTRIBUTION OF HELO TGTS FOR USE IN
                           !HELO_KILLS SUBROUTINE
20064             Df_fire_dist(1,I,J)=B_fdf(I,J+17)
20067             Df_fire_dist(2,I,J)=R_fdf(I,J+17)
20070         NEXT J
20073     NEXT I
20076     RETURN
20079!
20082!-----

```

Table 6-14. Ground combat code (continued).

```

20085!
20088 Ammo_available:!
20091 !CHANGE TONS PER SINGLE WEAPON TO RND5 PER TYPE IN POUNDS
20094 FOR I=1 TO 20
20097   B_ammo(I)=0
20100   IF B_ammo_wt(I)<>0 THEN
20103     B_ammo(I)=B_tons(1,I)/B_ammo_wt(I)*2000
20106   END IF
20109   R_ammo(I)=0
20112   IF R_ammo_wt(I)<>0 THEN
20115     R_ammo(I)=R_tons(1,I)/R_ammo_wt(I)*2000
20118   END IF
20121 NEXT I
20124 RETURN
20127 !
20130 !-----
20133 !
20136 Calc_rnd:! TOTAL ROUNDS FIRED
20139 FOR I=1 TO 20
20142   !ROUNDS FIRED
20145   IF B_ammo(I)>B_ecf(I) THEN
20148     B_rnds_wep(I)=B_ecf(I)
20151   ELSE
20154     B_rnds_wep(I)=B_ammo(I)
20157   END IF
20160   !
20163   IF R_ammo(I)>R_ecf(I) THEN
20166     R_rnds_wep(I)=R_ecf(I)
20169   ELSE
20172     R_rnds_wep(I)=R_ammo(I)
20175   END IF
20178   !
20181 NEXT I
20184 !
20187 !CALC. ROUNDS FIRED BY ALL CATEGORIES
20190 FOR I=1 TO 20
20193   Tot_b_rnds(I)=Sys(5,I)*B_rnds_wep(I)
20196   Tot_r_rnds(I)=Sys(6,I)*R_rnds_wep(I)
20199 NEXT I
20202 !
20205 !TEMPORARY CODE FOR HTLD/ADEA ONLY
20208   ! DET MAX # GLLD DESIGNATORS
20211   GlDs=Sys(5,4)/5      !CALCS GLLDS AVAIL FOR GLH
20214   Glh=MIN(GlDs,Sys(5,5))
20217   Tot_b_rnds(5)=Glh*B_rnds_wep(5)
20220   ! ENDS TEMP CODE
20223   !
20226   !ROUNDS PER CATEGORY
20229   FOR I=1 TO 20
20232     FOR J=1 TO 17
20235       B_rnds_cat(I,J)=B_fdf(I,J)*Tot_b_rnds(I)
20238       R_rnds_cat(I,J)=R_fdf(I,J)*Tot_r_rnds(I)

```

Table 6-14. Ground combat code (continued).

```

20241     NEXT J
20244     NEXT I
20247     !     OUTPUT @Proy,4:Tot_b_rnds(*),Tot_r_rnds(*),B_rnds_cat(*),R_rnd
cat(*)
20250     RETURN
20253 !
20256 !-----
20259 !
20262 Update_ammo: !
20265     !CALC. TONS USED; TAKE RND$ USED AND CHANGE TO TONS PER SINGLE WEAPON
20268     FOR I=1 TO 20
20271         IF Sys(5,I)<>0 THEN B_tons(2,I)=Tot_b_rnds(I)*B_ammo_wt(I)/2000/Svs(5
)+B_tons(2,I)
20274         IF Sys(6,I)<>0 THEN R_tons(2,I)=Tot_r_rnds(I)*R_ammo_wt(I)/2000/Sys(6
)+R_tons(2,I)
20277     NEXT I
20280     RETURN
20283 !
20286 !-----
20289 !
20292 Calc_loss: !
20295     ! INITIALIZE
20298     Nslices=15
20301     FOR J=1 TO 17
20304         B_psuv(J)=1
20307         R_psuv(J)=1
20310         Loss_r_cat(J)=0
20313         Loss_b_cat(J)=0
20316         Lo_r_cats(J)=0
20319         Lo_b_cats(J)=0
20322         FOR I=1 TO 20
20325             Lo_r_cat(I,J)=0
20328             Lo_b_cat(I,J)=0
20331             B_ex_r(I,J)=0
20334             R_ex_r(I,J)=0
20337         NEXT I
20340     NEXT J
20343     !
20346     ! CALCULATE THE AVERAGE NUMBER OF ROUNDS FIRED PER SLICE
20349     FOR I=1 TO 20     !FIRERS
20352         FOR J=1 TO 17 !TARGET CATEGORIES
20355             IF Sys(5,I)=0 THEN Rnd_red
20358                 B_ex_r(I,J)=B_rnds_cat(I,J)/Sys(5,I)/Nslices
20361 Rnd_red: !
20364             IF Sys(6,I)=0 THEN Rnd_end
20367                 R_ex_r(I,J)=R_rnds_cat(I,J)/Sys(6,I)/Nslices
20370 Rnd_end: !
20373         NEXT J
20376     NEXT I
20379     !
20382     !
20385     ! CALCULATE LOSSES

```

Table 6-14. Ground combat code (continued).

```

20388 FOR Slice=1 TO Nslices
20391   FOR I=1 TO 20 !FIRERS
20394     IF B_cat(I)>0 AND B_cat(I)<=17 THEN
20397       B_firers=B_psuv(B_cat(I))*Sys(5,I)
20400       ! TEMP CODE FOR HTLD/ADEA
20403       IF I=5 THEN
20406         Glds=B_psuv(B_cat(4))*Sys(5,4)/5
20409         IF Sys(1,5)>0 THEN           !STAY VULNERABLE
20412           IF Glds>B_firers THEN Glds=B_firers
20415         ELSE
20418           IF Glds>Sys(5,5) THEN Glds=Sys(5,5)
20421         END IF
20424         B_firers=Glds
20427       END IF
20430       !ENDS TEMP CODE
20433     END IF
20436     IF R_cat(I)>0 AND R_cat(I)<=17 THEN
20439       R_firers=R_psuv(R_cat(I))*Sys(6,I)
20442     END IF
20445     FOR J=1 TO 17
20448       !
20451       R_ps(I,J)=1
20454       B_ps(I,J)=1
20457       !
20460       Red_target=1
20463       IF R_targ(J)*R_targ_vis(J)>=1 THEN Red_target=R_targ(J)*R_targ_v
20466       Blue_target=1
20469       IF B_targ(J)*B_targ_vis(J)>=1 THEN Blue_target=B_targ(J)*B_targ_v
20472       !
20475       IF R_targ(J)>0 THEN
20478         Ps_r_ps=R_vul(J)*B_pk_fe(I,J)+(1-R_vul(J))*B_pk_hd(I,J)
20481         R_ps(I,J)=(1-Ps_r_ps/Red_target)^(B_firers*B_ex_r(I,J))
20484         Lossr=R_targ(J)*R_targ_vis(J)*R_psuv(J)*(1-R_ps(I,J))
20487         Lo_r_cat(I,J)=Lo_r_cat(I,J)+Lossr
20490         Lo_r_cats(J)=Lo_r_cats(J)+Lossr
20493       !
20496     END IF
20499     !
20502     IF B_targ(J)>0 THEN
20505       Ps_b_ps=B_vul(J)*R_pk_fe(I,J)+(1-B_vul(J))*R_pk_hd(I,J)
20508       B_ps(I,J)=(1-Ps_b_ps/Blue_target)^(R_firers*R_ex_r(I,J))
20511       Lossb=B_targ(J)*B_targ_vis(J)*B_psuv(J)*(1-B_ps(I,J))
20514       Lo_b_cat(I,J)=Lo_b_cat(I,J)+Lossb
20517       Lo_b_cats(J)=Lo_b_cats(J)+Lossb
20520     END IF
20523     !
20526   NEXT J
20529 NEXT I
20532 !
20535 FOR I=1 TO 20

```

Table 6-14. Ground combat code (continued).

```

20538     FOR J=1 TO 17
20541         B_psuv(J)=B_psuv(J)*B_ps(I,J)
20544         R_psuv(J)=R_psuv(J)*R_ps(I,J)
20547     !
20550     NEXT J
20553     NEXT I
20556     NEXT Slice
20559     !
20562     !
20565     FOR J=1 TO 17
20568         Loss_b_cat(J)=B_targ(J)*B_targ_vis(J)*(1-B_psuv(J))
20571         Loss_r_cat(J)=R_targ(J)*R_targ_vis(J)*(1-R_psuv(J))
20574     !
20577     NEXT J
20580     GOSUB Roy_dumps
20583     RETURN
20586     !
20589     !-----
20592     !
20595 Roy_dumps: !
20598     ! OUTPUT @Proy,5;Loss_b_cat(*)
20601     ! OUTPUT @Proy,6;Lo_b_cats(*)
20604     ! OUTPUT @Proy,7;Loss_r_cat(*)
20607     ! OUTPUT @Proy,8;Lo_r_cats(*)
20610     !NORMALIZE EACH GROUND TGT CATEGORY
20613     FOR J=1 TO 17
20616         IF Lo_b_cats(J)=0 THEN
20619             Loss_b_cat(J)=0
20622             Blossfac=0
20625         ELSE
20628             Blossfac=Loss_b_cat(J)/Lo_b_cats(J)
20631         END IF
20634         IF Lo_r_cats(J)=0 THEN
20637             Loss_r_cat(J)=0
20640             Rlossfac=0
20643         ELSE
20646             Rlossfac=Loss_r_cat(J)/Lo_r_cats(J)
20649         END IF
20652         FOR I=1 TO 20
20655             Lo_r_cat(I,J)=Lo_r_cat(I,J)*Rlossfac
20658             Lo_b_cat(I,J)=Lo_b_cat(I,J)*Blossfac
20661         NEXT I
20664     NEXT J
20667     ! OUTPUT @Proy,9;Lo_b_cat(*)
20670     ! OUTPUT @Proy,10;Lo_r_cat(*)
20673     RETURN
20676     !
20679     !-----
20682     !
20685 Decat_losses: !
20688     !APPORTION LOSSES TO EACH ELEMENT
20691     FOR I=1 TO 70

```

Table 6-14. Ground combat code (continued).

```

20694 IF B_cat(I)>0 AND B_cat(I)<=17 THEN
20697   IF B_targ(B_cat(I))<>0 THEN
20700     Loss_blue(I)=Sys(1,I)*Loss_b_cat(B_cat(I))/R_targ(B_cat(I))
20703   ELSE
20706     Loss_blue(I)=0
20709   END IF
20712 END IF
20715 !
20718 IF R_cat(I)>0 AND R_cat(I)<=17 THEN
20721   IF R_targ(R_cat(I))<>0 THEN
20724     Loss_red(I)=Sys(3,I)*Loss_r_cat(R_cat(I))/R_targ(R_cat(I))
20727   ELSE
20730     Loss_red(I)=0
20733   END IF
20736 END IF
20739 !
20742 NEXT I
20745 RETURN
20748 !
20751 -----
20754 !
20757 Set_next_loop: ! SET DATA BEFORE CONTINUING BAND_LOOP
20760 !UPDATE SYS
20763 FOR I=1 TO 70
20766   IF Sys(1,I)<>0 THEN Sys(5,I)=Sys(5,I)-(Sys(5,I)/Sys(1,I))*Loss_blue
20769   IF Sys(3,I)<>0 THEN Sys(6,I)=Sys(6,I)-(Sys(6,I)/Sys(3,I))*Loss_red(
20772     !SYS(2,I)&SYS(4,I) ARE FILLED WITH LOSSES
20775   Sys(2,I)=Sys(2,I)+Loss_blue(I)
20778   Sys(4,I)=Sys(4,I)+Loss_red(I)
20781   !
20784   Sys(1,I)=Sys(1,I)-Loss_blue(I)
20787   Sys(3,I)=Sys(3,I)-Loss_red(I)
20790 NEXT I
20793 !UPDATE RANGE_BAND
20796 Rng_band=Rng_band-1
20799 IF Rng_band=0 AND Band_loop<Num_bands THEN
20802   PRINT
20805   PRINT "** ERROR: # OF RANGE BANDS DO NOT CORRESPOND WITH PRESENT PO
20808   Abort$="YES"
20811 END IF
20814 RETURN
20817 !
20820 -----
20823 !
20826 Set_return: ! RESET DATA BEFORE EXITING
20829 Rng_band=Rng_band_save
20832 !RESTORE SYS(1,I)&SYS(3,I)
20835 FOR I=1 TO 70
20838   Sys(1,I)=Init_b_targets(I)
20841   Sys(3,I)=Init_r_targets(I)
20844 NEXT I

```

Table 6-14. Ground combat code (continued).

```

20847 !
20850 ASSIGN @Path1 TO *      !CLOSE ALL FILES
20853 ASSIGN @Path2 TO *
20856 ASSIGN @Path_b_fe TO *
20859 ASSIGN @Path_b_hd TO *
20862 ASSIGN @Path_r_fe TO *
20865 ASSIGN @Path_r_hd TO *
20868 SUBEND
20871 !
20874 !*****
20877 !
20880 SUB Pgm_atrit(Fir_typ(*),N_rnds(*),Vis_rng,Terr_typ,Sens_typ(*),Cloud_ht
ust_index,Targets(*))
20883 OPTION BASE 1
20886 DIM Prob_dsg(6,4),Sskp_clgp(70),Clgp_mask(70),Sskp(2,70)
20889 DIM P_surv(70),N_rnds_fired(2),Psurv_tf(2,70)
20892 DIM Tgts_avail(70),Tgt_mask(2,70),W_sum(2)
20895 !
20898 COM /Pgm/ Tgt_value(2,70),Tgt_mask1(2,70),Terr_factor(4),Prob_dustabort
,4),Clgp_msk_ns(70),Clgp_msk_gl(70),Clgp_msk_rp(70)
20901 COM /Pgm/ Prob_dsg_ns(6,4),Prob_dsg_gl(6,4),Prob_dsg_rp(6,4),Sskp_ns(70
Sskp_gl(70),Sskp_rp(70)
20904 !
20907 ! NOTE -- CLGP IS NOT LOADED BUT WILL LATER BE REPLACED WITH ALL 1'S.
20910 !
20913 Dcdisk$=":9134,704,0"
20916 ASSIGN @Psskp TO "SSKP"&Dcdisk$
20919 ENTER @Psskp,1;Sskp(*)
20922 ASSIGN @Psskp TO *
20925 !
20928 ! SET THE CLOUD INDEX
20931 !
20934 Cloud=Cloud_ht*3.28
20937 SELECT Cloud
20940 CASE <1500
20943     Cld_ndx=1
20946 CASE 1500 TO 2000
20949     Cld_ndx=2
20952 CASE 2000 TO 2500
20955     Cld_ndx=3
20958 CASE 2500 TO 3000
20961     Cld_ndx=4
20964 CASE 3000 TO 4500
20967     Cld_ndx=5
20970 CASE >4500
20973     Cld_ndx=6
20976 END SELECT
20979 !
20982 !     SET VISIBILITY INDEX
20985 !
20988 Vis_ndx=Vis_rng
20991 Nslices=15

```


Table 6-14. Ground combat code (continued).

```

20994 Nfirers=2 ! USING CLGP AND GAMF
20997 Ntargets=70
21000 !
21003 !Set probability of survival for all targets at 1 to start
21006 FOR Target=1 TO Ntargets
21009     P_surv(Target)=1
21012     FOR Firer=1 TO Nfirers
21015         Psurv_tf(Firer,Target)=1
21018     NEXT Firer
21021 NEXT Target
21024 !
21027 N_tot=0
21030 FOR Init=1 TO 2
21033     N_rnds_fired(Init)=0
21036 NEXT Init
21039 !
21042 !Attrition calculations.
21045 !SET ARRAYS FOR PGM'S
21048 !
21051 IF Fir_typ(1)=0 THEN Set_new_pgm
21054 !
21057 IF THIS IS CLGP THEN LOAD APPROPRIATE PK'S
21060 IF Sens_typ(1)<0 OR Sens_typ(1)>2 THEN Set_new_pgm
21063 !
21066 SELECT Sens_typ(1)
21069 CASE 0 !NO SENSOR AVAILABLE
21072     FOR I=1 TO 70
21075         Clgp_mask(I)=Clgp_msk_ns(I)
21078         Sskp_clgp(I)=Sskp_ns(I)
21081     NEXT I
21084     FOR I=1 TO 6
21087         FOR J=1 TO 4
21090             Prob_desg(I,J)=Prob_dsg_ns(I,J)
21093         NEXT J
21096     NEXT I
21099 CASE 1 !GLLD
21102     FOR I=1 TO 70
21105         Clgp_mask(I)=Clgp_msk_gl(I)
21108         Sskp_clgp(I)=Sskp_gl(I)
21111     NEXT I
21114     FOR I=1 TO 6
21117         FOR J=1 TO 4
21120             Prob_desg(I,J)=Prob_dsg_gl(I,J)
21123         NEXT J
21126     NEXT I
21129 CASE 2,3 !RPV
21132     FOR I=1 TO 70
21135         Clgp_mask(I)=Clgp_msk_rp(I)
21138         Sskp_clgp(I)=Sskp_rp(I)
21141     NEXT I
21144     FOR I=1 TO 6
21147         FOR J=1 TO 4

```

Table 6-14. Ground combat code (continued).

```

21150     Prob_desg(I,J)=Prob_dsg_rp(I,J)
21153     NEXT J
21156     NEXT I
21159     END SELECT
21162     !
21165     Set_new_pgm: !
21168     FOR Pgm=1 TO 2
21171         IF Fir_typ(Pgm)=0 THEN N_pgm
21174         FOR Target=1 TO Ntargets
21177             !SET SENSOR MASK
21180             IF Pgm=1 THEN
21183                 S_mask=C1gp_mask(Target)
21186             ELSE
21189                 S_mask=1           !ALL SENSOR MASKS=1 FOR AMSAA PGM'S
21192             END IF
21195             !SET TARGET MASK WITH MISSION VALUE
21198             Tgt_mask(Pgm,Target)=Tgt_mask1(Pgm,Target)*S_mask
21201             !SET SSKP
21204             IF Pgm=1 THEN Sskp(1,Target)=Sskp_c1gp(Target)
21207         NEXT Target
21210     N_pgm:NEXT Pgm
21213     !SET PK'S
21216     FOR Target=1 TO Ntargets
21219         P_surv(Target)=1
21222     NEXT Target
21225     !
21228     !CALCULATE THE WEIGHT SUM FOR EACH FIRER
21231     FOR Slice=1 TO Nslices
21234         FOR Target=1 TO Ntargets
21237             FOR Firer=1 TO Nfirers
21240                 Psurv_tf(Firer,Target)=1
21243             NEXT Firer
21246         NEXT Target
21249         FOR Pgm=1 TO 2
21252             W_sum(Pgm)=0
21255             IF Fir_typ(Pgm)=0 THEN End_wt
21258             FOR Target=1 TO Ntargets
21261                 Des=1
21264                 IF Pgm=1 THEN Des=Sskp(1,Target)
21267                 W_sum(Pgm)=W_sum(Pgm)+Tgt_value(Pgm,Target)*P_surv(Target)*Target
21270             !
21273             N_targ:NEXT Target
21276         End_wt:NEXT Pgm
21279     !
21282     !
21285     !NEW BEGIN THE FIRER LOOP FOR THIS SLICE
21288     FOR Firer=1 TO Nfirers
21291         IF Fir_typ(Firer)=0 THEN N_firer
21294         ! SET LOCAL PARAMETERS FOR THIS FIRER
21297         IF Firer>1 THEN New_pgm
21300         Lase_reliab=.8

```

Table 6-14. Ground combat code (continued).

```

21303 P_desg=Prob_desg(Cld_ndx,Vis_ndx)
21306 P_dustabort=Prob_dustabort(Dust_index,Vis_ndx)
21309 Terr_degrd=Terr_factor(Terr_tvp)
21312 GOTO Ct_kills
21315 ! SET PARAMETERS FOR GAMF. ALL SET TO NO EFFECT BECAUSE
21318 ! OF AMSAA DATA.
21321 New_pgm:Lase_reliab=1
21324 P_desg=1
21327 P_dustabort=0
21330 Terr_degrd=1
21333 Ct_kills:FOR Target=1 TO Ntargets
21336 N_tgts=Targets(1,Target)*P_surv(Target)
21339 IF Tgt_mask(Firer,Target)*N_tgts>0 THEN
21342 Pk=Sskp(Firer,Target)
21345 ! SET SWITCH FOR SMART DESIGNATOR DISCRIMINATING
21348 ! BETWEEN HIGH PK AND LOW PK TARGETS
21351 Des=1
21354 IF Firer=1 THEN Des=Sskp(Firer,Target)
21357 IF W_sum(Firer)<=0 THEN N_firer
21360 Nrnds=((N_tgts*Tgt_value(Firer,Target)*Des)/W_sum(Firer))*(N_rn
(Firer)/Nslices)
21363 N_rnds_fired(Firer)=N_rnds_fired(Firer)+Nrnds
21366 Nrnds=Nrnds*Terr_degrd*(1-P_dustabort)*P_desg
21369 Smk=1
21372 IF (N_tgts*Smk)<1 THEN
21375 Div=1
21378 ELSE
21381 Div=N_tgts*Smk
21384 END IF
21387 Psurv_tf(Firer,Target)=(1-Pk*Lase_reliab/Div)^Nrnds
21390 END IF
21393 NEXT Target
21396 N_firer:NEXT Firer
21399 ! UPDATE OVERALL PROBABILITY OF SURVIVAL FOR EACH TARGET
21402 FOR Target=1 TO Ntargets
21405 FOR Firer=1 TO Nfirers
21408 P_surv(Target)=P_surv(Target)*Psurv_tf(Firer,Target)
21411 NEXT Firer
21414 NEXT Target
21417 NEXT Slice
21420 !
21423 ! Talley the kills
21426 !
21429 FOR Target=1 TO Ntargets
21432 Targets(2,Target)=(1-P_surv(Target))*Targets(1,Target)
21435 NEXT Target
21438 End_pgm:SUBEND
21441 !
21444 !*****
21447 SUB Missn_tmpls(Side,I,T,K,Unit_no(*),Hfile(*),Listop)
21450 OPTION BASE 1
21453 DIM Unitname$(16),Cdesc$(28)

```

Table 6-14. Ground combat code (continued).

```

21456 INTEGER J,X
21459 ! ADDED TO PREVENT 2ND 3 HRS FROM APPEARING
21462 ! REMOVE FOLLOWING "IF" STATEMENT WHEN NO LONGER REQUIRED
21465 IF I=2 THEN
21468   FOR L=1 TO 8
21471     Hfile(2,K,L)=Hfile(1,K,L)
21474   NEXT L
21477   GOTO End_missn
21480 END IF
21483 FOR X=1 TO 2
21486   FOR J=1 TO 12
21489     IF Hfile(X,J,9)=Side AND Hfile(X,J,10)=T THEN
21492       FOR L=1 TO 8
21495         Hfile(I,K,L)=Hfile(X,J,L)
21498       NEXT L
21501       PRINTER IS 1
21504       GOSUB Prt_missn_tmpls
21507       IF Listop=2 THEN
21510         PRINTER IS 702
21513         GOSUB Prt_missn_tmpls
21516       ELSE
21519         PRINTER IS 702
21522       END IF
21525       GOTO End_missn
21528     END IF
21531   NEXT J
21534 NEXT X
21537 Start_missn: !
21540 PRINTER IS 1
21543 GOSUB Prt_missn_tmpls
21546 Chg_values: !
21549 INPUT "FIELD #,NEW VALUE TO CHANGE (9,9 TO END)",Fieldn,Nvalue
21552 Sel_field: !
21555 SELECT Fieldn
21558 CASE 1 TO 8
21561   Hfile(I,K,Fieldn)=Nvalue
21564 CASE 9
21567   IF Listop=2 THEN
21570     PRINTER IS 702
21573     GOSUB Prt_missn_tmpls
21576   ELSE
21579     PRINTER IS 702
21582   END IF
21585   DISP "CHANGE ALL ";
21588   IF Side=1 THEN
21591     Cdesc$="BLUE "&Cdesc$
21594   ELSE
21597     Cdesc$="RED "&Cdesc$
21600   END IF
21603   DISP Cdesc$;
21606   DISP "S TO THE SAME VALUES (Y/N)";
21609   INPUT Ans$

```

Table 6-14. Ground combat code (continued).

```

21612 IF Ans$="Y" THEN
21615   Hfile(I,K,9)=Side
21618   Hfile(I,K,10)=T
21621 END IF
21624 GOTO End_missn
21627 CASE ELSE
21630   GOTO Chg_values
21633 END SELECT
21636 GOTO Start_missn
21639 Prt_missn_tmpls: !
21642 ASSIGN @Name TO "NAMEFILE:9134,704,0"
21645 ENTER @Name,Unit_no(K);Unitname$
21648 ASSIGN @Name TO *
21651 PRINT USING "/,6A,3D,3A,16A,#";"UNIT #",Unit_no(K)," - ",Unitname$
21654 SELECT T
21657 CASE 1,11
21660   Cdesc$="COMBAT "
21663 CASE 2,12
21666   Cdesc$="ARTILLERY "
21669 CASE 3,13
21672   Cdesc$="AIR DEFENSE "
21675 CASE 4,14
21678   Cdesc$="FARRP "
21681 CASE 5,15
21684   Cdesc$="COMMAND POST "
21687 CASE 6,16
21690   Cdesc$="ENGINEER "
21693 CASE 7,17
21696   Cdesc$="SUPPLY "
21699 CASE 8,18
21702   Cdesc$="MAINTENANCE "
21705 CASE 9,19
21708   Cdesc$="BRIDGE "
21711 CASE 10,20
21714   Cdesc$="COMMO/EW SITE "
21717 END SELECT
21720 SELECT Side
21723 CASE 1
21726   SELECT T
21729   CASE 1 TO 10
21732     Cdesc$=Cdesc$&"BATTALION"
21735   CASE 11 TO 20
21738     Cdesc$=Cdesc$&"COMPANY"
21741   END SELECT
21744 CASE 2
21747   SELECT T
21750   CASE 1 TO 10
21753     Cdesc$=Cdesc$&"REGIMENT"
21756   CASE 11 TO 20
21759     Cdesc$=Cdesc$&"BATTALION"
21762   END SELECT
21765 END SELECT

```

Table 6-14. Ground combat code (continued).

```

21768 PRINT Cdesc%$, " ";
21771 SELECT I
21774 CASE 1
21777 PRINT "1ST 3 HOURS"
21780 CASE 2
21783 PRINT "2ND 3 HOURS"
21786 END SELECT
21789 PRINT USING "/,8(2X,7A)";" (1) ", " (2) ", " (3) ", " (4) ", " (5)
", " (6) ", " (7) ", " (8) "
21792 PRINT USING "8(2X,7A)";" MIFT ", " MDFT ", " MIFDT ", " MDFDT ", " MFIRE
" MDFIRE ", " MVUL ", " MDVUL "
21795 PRINT USING "8(2X,7A)";"-----", "-----", "-----", "-----", "-----
"-----", "-----", "-----"
21798 PRINT USING "8(3X,1D.4D)";Hfile(I,K,1),Hfile(I,K,2),Hfile(I,K,3),Hfile(I,
K,4),Hfile(I,K,5),Hfile(I,K,6),Hfile(I,K,7),Hfile(I,K,8)
21801 RETURN
21804 End_missn: !
21807 SUBEND
21810 !*****
21813 SUB Helo_range(Cell(*),Helo_mis(*),Std_off_rg(*))
21816 OPTION BASE 1
21819!-----
21822! CALCULATE THE RANGES FROM HELO TO GROUND & HELO TO HELO
21825!-----
21828 INTEGER Side,Side_def
21831 !
21834 COM /Helo_info/ Btl_rg,Rg_avg(2,3,20),Rg_avg_pd(2,3,5),Df_ammo(2),Df_fir
dist(2,20,3),Df_pk_helo(2,20,3,2),INTEGER Df_sen_ptr(2,20),Df_muni_ptr(2,20)
21837 !
21840 FOR Side=1 TO 2
21843 Side_def=(Side MOD 2)+1 'CALCULATE DEFENDING SIDE
21846 FOR I=1 TO 3 ' COMPUTE HELICOPTER TO HELICOPTER RANGES
21849 IF Cell(Side,I)<=0 THEN GOTO No_rg
21852 FOR J=1 TO 3
21855 SELECT Helo_mis(Side,I)
21858 CASE =1
21861 SELECT Helo_mis(Side_def,J)
21864 CASE =0 ! NO ENEMY HELOS FLYING FOR THIS BATTLE
21867 Rg_avg(Side,I,J+17)=0
21870 CASE =1 ! DIRECT SUPPORT<>DIRECT SUPPORT
21873 Rg_avg(Side,I,J+17)=ABS(Std_off_rg(Side,I)+Std_off_rg(Side_
f,J)-Btl_rg)
21876 CASE =2 ! DIRECT SUPPORT<>HELO TO HELO
21879 Rg_avg(Side,I,J+17)=Std_off_rg(Side_def,J)
21882 CASE =3 ! DIRECT SUPPORT<>SEAD
21885 Rg_avg(Side,I,J+17)=SQR((Std_off_rg(Side,I)-Btl_rg)^2+(Std_
f_rg(Side_def,J))^2)
21888 END SELECT
21891 CASE =2
21894 SELECT Helo_mis(Side_def,J)
21897 CASE =0 ! NO ENEMY HELOS
21900 Rg_avg(Side,I,J+17)=0

```

Table 6-14. Ground combat code (continued).

```

21903      CASE =1      ! HELO TO HELO<>DIRECT SUPPORT
21906      Rg_avg(Side,I,J+17)=Stnd_off_rg(Side,I)
21909      CASE =2      ! HELO TO HELO<>HELO TO HELO
21912      Rg_avg(Side,I,J+17)=(Stnd_off_rg(Side,I)+Stnd_off_rg(Side_def
)))/2
21915      CASE =3      ! HELO TO HELO<>SEAD
21918      Rg_avg(Side,I,J+17)=Stnd_off_rg(Side,I)
21921      END SELECT
21924      CASE =3
21927      SELECT Helo_mis(Side_def,J)
21930      CASE =0      ! NO ENEMY HELOS FLYING
21933      Rg_avg(Side,I,J+17)=0
21936      CASE =1      ! SEAD<>DIRECT SUPPORT
21939      Rg_avg(Side,I,J+17)=SQR((Stnd_off_rg(Side_def,J)-Btl_rg)^2+(S
d_off_rg(Side,I))^2)
21942      CASE =2      ! SEAD<>HELO TO HELO
21945      Rg_avg(Side,I,J+17)=Stnd_off_rg(Side_def,J)
21948      CASE =3      ! SEAD<>SEAD
21951      Rg_avg(Side,I,J+17)=(Btl_rg/2)+(SQR(Btl_rg*Btl_rg+(Stnd_off_r
Side,I)+Stnd_off_rg(Side_def,J))^2))/2
21954      END SELECT
21957      CASE ELSE      ! NO ATTACKING HELOS OF THIS TYPE
21960      Rg_avg(Side,I,J+17)=0
21963      END SELECT
21966      NEXT J
21969      No_rg:NEXT I
21972! COMPUTE RANGE BETWEEN GROUND AND HELICOPTER
21975      Tot_en_helos=Cell(Side_def,1,1)+Cell(Side_def,1,2)+Cell(Side_def,1,3)
!TOTAL NO. OF ENEMY HELOS
21978      FOR I=1 TO 3
21981      IF Helo_mis(Side,I)<=0 OR Cell(Side,1,I)<=0 THEN !NO ATTACKING
21984      FOR K=1 TO 17                                     !HELOS OF TYPE I
21987      Rg_avg(Side,I,K)=0
21990      NEXT K
21993      GOTO Grd_hlo
21996      END IF
21999      SELECT Helo_mis(Side,I)
22002      CASE =1      ! DIRECT SUPPORT
22005      FOR K=1 TO 17
22008      Rg_avg(Side,I,K)=Stnd_off_rg(Side,I)
22011      NEXT K
22014      CASE =2      ! HELO TO HELO
22017      Rg_avg(Side,I,1)=0
22020      IF Tot_en_helos<=0 THEN GOTO H_h_rg
22023      FOR J=1 TO 3      ! COMPUTE WEIGHTED AVERAGE DEPENDING UPON
22026      ! PERCENTAGE OF ENEMY HELICOPTERS ON A
22029      ! PARTICULAR MISSION
22032      SELECT Helo_mis(Side_def,J)
22035      CASE 1
22038      Rg_avg(Side,I,1)=Rg_avg(Side,I,1)+(SQR((Stnd_off_rg(Side_def,
-Btl_rg)^2+(Stnd_off_rg(Side,I))^2)))*(Cell(Side_def,1,J)/Tot_en_helos)
22041      CASE 2

```

Table 6-14. Ground combat code (continued).

```

22044      Rg_avg(Side,I,1)=Rg_avg(Side,I,1)+(Btl_rg/2+((Stnd_off_rg(Sid
I)+Std_off_rg(Side_def,J))/4))*(Cell(Side_def,1,J)/Tot_en_helos)
22047      CASE 3
22050      Rg_avg(Side,I,1)=Rg_avg(Side,I,1)+(Btl_rg+SQR(ABS(Std_off_rg
ide,I)^2-Std_off_rg(Side_def,J)^2)))*(Cell(Side_def,1,J)/Tot_en_helos)
22053      END SELECT
22056      NEXT J
22059 H_h_rg:FOR K=2 TO 17
22062      Rg_avg(Side,I,K)=Rg_avg(Side,I,1)
22065      NEXT K
22068      CASE =3      ! SEAD
22071      FOR K=1 TO 17
22074      Rg_avg(Side,I,K)=Std_off_rg(Side,I)
22077      NEXT K
22080      END SELECT
22083 Grd_hlo:NEXT I
22086      FOR I=1 TO 3
22089      FOR J=1 TO 4!STORE THE RANGES FOR THE PROB OF DETECTION CATEGORIES
22092      Rg_avg_pd(Side,I,J)=Rg_avg(Side,I,1)
22095      NEXT J
22098      Rg_avg_pd(Side,I,5)=0
22101      IF Tot_en_helos>0 THEN
22104      FOR J=18 TO 20 !LOOP ON HELD TGT CATEGORIES
22107      Rg_avg_pd(Side,I,5)=Rg_avg_pd(Side,I,5)+Rg_avg(Side,I,J)*(Cell(
de_def,1,J-17)/Tot_en_helos)
22110      NEXT J
22113      END IF
22116      NEXT I
22119      NEXT Side
22122      SUBEND
22125!*****
22128 SUB Helo_kills(Cell(*),Target(*),Ad_ammo(*),Terr,Atk_prof(*),Helo_mis(*),
ay_nite,Time_step,P_def_ray(*),Arty(*),Veh_ada(*),Hnd_ada(*),Std_off_rg(*),V1
22131!*****
22134!SUBROUTINE HELO_KILLS CALCULATES KILLS BY HELICOPTERS AGAINST GROUND *
22137!ELEMENTS AND ENEMY HELICOPTERS, AND HELICOPTER LOSSES BY AD WEAPONS *
22140!*****
22143!
22146      OPTION BASE 1
22149      DIM Red_blue$(4),No_targets(2,20),Cell_save(2,3),Helo_loss(2,3)
22152      DIM Target_loss(2,20),Helo_pd_targ(3,20),Helo_pd_tgt(5),Ut(3),Plos(2,3)
22155      DIM Ad_pd_helo(7,3),Ad_avg_fired(7,3),Ad_pk_helo(2,7,3)
22158      DIM Helo_avg_fired(3,20),Helo_fire_dist(3,20),Helo_act_fired(3,20)
22161      DIM Helo_pk_targ(3,20),Ad_fire_dist(7,3),Ad_act_fired(7,3)
22164      DIM Pop_tstep(3),No_pd_tgt(5),Adust(2),Ad_ele(7),Te_firer(3)
22167      DIM Air_rnds_avl(2,3),Helo_rnds_avl(2,3),Target_psrv(2,20),Helo_psrv(2,
22170      DIM Pct_force_fe(2),Pct_force_hd(2),Pct_mm(2),Pct_non_mm(2)
22173      DIM Df_pd_helo(20,3),Df_avg_fired(20,3),Df_act_fired(20,3),Dfinf(2,3)
22176      DIM Dftbar(2,3)
22179      INTEGER I,J,K,L,M,Atmos,Side_def,H_lase(2),Lase,Tim_step,Ctg,Muni(3),En
uni(3)
22182 !

```


Table 6-14. Ground combat code (continued).

```

22185 COM /Helo_attrite/ Helo_load(2,3,3),Pd_fe_inf_a(2,3,5),Pd_fe_inf_b(2,3,
.Pd_fe_inf_c(2,3,5),Pd_hd_inf_a(2,3,5),Pd_hd_inf_b(2,3,5)
22188 COM /Helo_attrite/ Pd_hd_inf_c(2,3,5),Pd_fe_tbar_a(2,3,5),Pd_fe_tbar_b
3,5),Pd_fe_tbar_c(2,3,5),Pd_hd_tbar_a(2,3,5),Pd_hd_tbar_b(2,3,5)
22191 COM /Helo_attrite/ Pd_hd_tbar_c(2,3,5),Pd_rmin(2,3,8),Pd_rmax(2,3,8),P
e_a(2,3,3,20),Pk_fe_b(2,3,3,20),Pk_fe_c(2,3,3,20),Pk_hd_a(2,3,3,20)
22194 COM /Helo_attrite/ Pk_hd_b(2,3,3,20),Pk_hd_c(2,3,3,20),Pk_rmin(2,3,3),F
rmax(2,3,3),Np(2,3,3),Fm(2,3,3),Tm(2,3,3),Te(2,3,3)
22197 COM /Helo_attrite/ Plos_alpha(2,3),Plos_beta(2,3),Pd_inf_ad_a(2,7,2),P
nf_ad_b(2,7,2),Pd_inf_ad_c(2,7,2),Pd_tbar_ad_a(2,7,2),Pd_tbar_ad_b(2,7,2)
22200 COM /Helo_attrite/ Pd_tbar_ad_c(2,7,2),Pd_ad_rmin(2,7,8),Pd_ad_rmax(2,7
),Pk_ad_a(2,7,2),Pk_ad_b(2,7,2),Pk_ad_c(2,7,2),Pk_ad_rmin(2,7),Pk_ad_rmax(2,7)
22203 COM /Helo_attrite/ Rnd_wt(2,7),Rnds(2,7),Fad(2,7),Pd_inf_df_a(2,2,2),Pc
nf_df_b(2,2,2),Pd_inf_df_c(2,2,2),Pd_tbar_df_a(2,2,2),Pd_tbar_df_b(2,2,2)
22206 COM /Helo_attrite/ Pd_tbar_df_c(2,2,2),Pd_df_rmin(2,2,8),Pd_df_rmax(2,2
),Df_rnds_eng(2,2),F_df(2,2)
22209 COM /Helo_attrite/ INTEGER Mast_mnt(2,3),Tgt_pref(2,3,20),Ad_pref(2,7,3
Pd_cat(2,20)
22212!
22215 COM /Direct_fire/ B_cat(70),R_cat(70),B_sen_d(70),B_sen_n(70),R_sen_d(7
,R_sen_n(70),B_ammo_wt(20),R_ammo_wt(20)
22218!
22221 COM /Helo_info/ Btl_rng_avg(2,3,20),Rg_avg_pd(2,3,5),Df_ammo(2),Df_fi
_dist(2,20,3),Df_pk_helo(2,20,3,2),INTEGER Df_sen_ptr(2,20),Df_muni_ptr(2,20)
22224!
22227 Atmos=Day_nite*4+Vis !COMPUTE ATMOSPHERIC CONDITIONS
22230 Adust(1)=.5
22233 Adust(2)=1.0
22236 Time_step=Time_step*60 !CHANGE TO SECONDS
22239 PRINT
22242 PRINT USING "22X,11A,19X,4A"; " BLUE ";" RED"
22245 PRINT USING "17X,52A"; "HELO 1 HELO 2 HELO 3 HELO 1 HELO 2 HELO
22248 PRINT USING "17X,52A"; "-----"
22251 PRINT USING Fmt1; "STANDOFF RANGE:"; Stnd_off_rg(1,1); Stnd_off_rg(1,2); St
_off_rg(1,3); Stnd_off_rg(2,1); Stnd_off_rg(2,2); Stnd_off_rg(2,3)
22254 PRINT USING Fmt1; "HELO MSN: "; Helo_mis(1,1); Helo_mis(1,2); Helo_mis
,3); Helo_mis(2,1); Helo_mis(2,2); Helo_mis(2,3)
22257 PRINT USING Fmt1; "ATK_PROF: "; Atk_prof(1,1); Atk_prof(1,2); Atk_prof
.3); Atk_prof(2,1); Atk_prof(2,2); Atk_prof(2,3)
22260 PRINT USING Fmt2; "# HELOS: "; Cell(1,1,1), Cell(1,1,2), Cell(1,1,3),
11(2,1,1), Cell(2,1,2), Cell(2,1,3)
22263 Fmt1: IMAGE 15A,3(2X,6D),3X,3(2X,6D)
22266 Fmt2: IMAGE 15A,3(2X,3D.2D),3X,3(2X,3D.2D)
22269 PRINT
22272!
22275 FOR Side=1 TO 2 !1=BLUE 2=RED
22278 Ad_wt_avl(Side)=Ad_ammo(Side)*2000 !CHANGE AD AMMO AVAIL-TONS TO LBS
22281 Df_wt_avl(Side)=Df_ammo(Side)*2000 !CHANGE DF AMMO AVAIL-TONS TO LBS
22284 FOR I=1 TO 70 !PLACE 70 TARGETS INTO 20 CATEGORIES
22287 IF Side=1 THEN Ctg=B_cat(I)
22290 IF Side=2 THEN Ctg=R_cat(I)
22293 Target(Side,2,I)=Target(Side,1,I)

```

Table 6-14. Ground combat code (continued).

```

22296     IF Ctg>0 AND Ctg<=17 THEN No_targets(Side,Ctg)=No_targets(Side,Ctg)
target(Side,1,I)
22299     NEXT I
-----
22302!
22305     FOR I=1 TO 3           !PLACE HELO TARGETS INTO LAST 3 CATEG (18,19,20)
22308     No_targets(Side,I+17)=Cell(Side,1,I) !MAP IN ONE-TO-ONE
22311     IF No_targets(Side,I+17)<.1 THEN No_targets(Side,I+17)=0
22314     Cell(Side,2,I)=No_targets(Side,I+17) !INIT REMAINING # OF TGT HEL
22317     NEXT I
22320     NEXT Side
-----
22323!
22326     FOR Side=1 TO 2
22329     Side_def=(Side MOD 2)+1 !DEFENDING SIDE
22332     PRINT !COMMENT THESE PRINT STATEMENTS OUT, BUT LEAVE IN CODE!
22335     IF Side=1 THEN PRINT " *** BLUE HELO RANGES ***"
22338     IF Side=2 THEN PRINT " *** RED HELO RANGES ***"
22341     FOR I=1 TO 3
22344     PRINT "Helo ";I;"HELO TO GRND RG:";Rg_avg(Side,I,1)
22347     PRINT TAB(9);"HELO TO HELO RG:";Rg_avg(Side,I,18);Rg_avg(Side,I,1
;Rg_avg(Side,I,20)
22350     PRINT TAB(9);"AVG RG TO HELOS FOR PROB OF DET:";Rg_avg_pd(Side,I
22353     PRINT
22356     NEXT I
-----
22359!
22362     Ful_exp:Totnum=0 !CALCULATE % OF FORCE FULLY EXPOSED & HULL DEFILADE
22365     Totden=0 !FOR BOTH SIDES
22368     FOR I=1 TO 70
22371     Totnum=Totnum+Target(Side,2,I)*P_def_ray(Side,I)
22374     Totden=Totden+Target(Side,2,I)
22377     NEXT I
22380     Pct_force_fe(Side)=Totnum/Totden
22383     Pct_force_hd(Side)=1.0-Pct_force_fe(Side)
22386     ! CALCULATE % OF TGT HELOS MAST MOUNTED & NON-MAST-MNT
22389     Totden=Cell(Side,1,1)+Cell(Side,1,2)+Cell(Side,1,3)
22392     IF Totden>0 THEN
22395     Totnum=0
22398     FOR I=1 TO 3 !CALCULATE NO. OF HELOS NON MAST MOUNTED
22401     Totnum=Totnum+Cell(Side,1,I)*Mast_mnt(Side,I)
22404     NEXT I
22407     Pct_mm(Side)=Totnum/Totden !PERCENT MAST MOUNTED
22410     Pct_non_mm(Side)=1.0-Pct_mm(Side) !PERCENT NON MAST MOUNTED
22413     ELSE !NO TARGET HELOS
22416     Pct_mm(Side)=0
22419     Pct_non_mm(Side)=0
22422     END IF
-----
22425!
22428     FOR I=1 TO 3           !LOOP ON HELO
22431     Air_rnds_avl(Side,I)=0
22434     Helo_rnds_avl(Side,I)=0
22437     SELECT Atk_prof(Side,I) !CALCULATE NO. OF ROUNDS AVAILABLE
22440     CASE 1 !MSL LOAD
22443     Helo_rnds_avl(Side,I)=Helo_load(Side,I,1)*Cell(Side,1,I)

```

Table 6-14. Ground combat code (continued).

```

22446 CASE 2 !MSL/GUN (MSL LOAD FIRST)
22449 Helo_rnds_avl(Side,I)=Helo_load(Side,I,1)*.5*Cell(Side,1,I)
22452 CASE 3 !GUN
22455 Helo_rnds_avl(Side,I)=Helo_load(Side,I,2)*Cell(Side,1,I)
22458 CASE 4 !AIR-TO-AIR
22461 Air_rnds_avl(Side,I)=Helo_load(Side,I,3)*Cell(Side,1,I)
22464 CASE 5 !AIR/MSL
22467 Air_rnds_avl(Side,I)=Helo_load(Side,I,3)*Cell(Side,1,I)
22470 Helo_rnds_avl(Side,I)=Helo_load(Side,I,1)*Cell(Side,1,I)
22473 CASE 6 !AIR/MSL/GUN
22476 Air_rnds_avl(Side,I)=Helo_load(Side,I,3)*Cell(Side,1,I)
22479 Helo_rnds_avl(Side,I)=Helo_load(Side,I,1)*.5*Cell(Side,1,I)
22482 CASE 7 !AIR/GUN
22485 Air_rnds_avl(Side,I)=Helo_load(Side,I,3)*Cell(Side,1,I)
22488 Helo_rnds_avl(Side,I)=Helo_load(Side,I,2)*Cell(Side,1,I)
22491 END SELECT
22494 NEXT I
22497 GOSUB Line_of_sight !CALC PROB OF LINE OF SIGHT BETWEEN GRND & HELO
22500 GOSUB Ad_pk_helo !CALCULATE PROB. OF KILL BY AD WEAPONS
22503 NEXT Side
22506!
22509!-----
22512 FOR Tim_step=1 TO 2 !LOOP ON 15 MINUTE TIME STEP
22515 FOR Side=1 TO 2
22518 FOR J=1 TO 20 !INITIALIZE TARGETS' PROB OF SURVIVAL ARRAY
22521 Target_psrv(Side,J)=1.0
22524 NEXT J
22527 FOR J=1 TO 3 !INITIALIZE HELOS' PROB OF SURVIVAL ARRAY
22530 Helo_psrv(Side,J)=1.0
22533 NEXT J
22536 IF Side=1 THEN Red_blue$="BLUE"
22539 IF Side=2 THEN Red_blue$="RED"
22542 IF Tim_step=1 THEN GOTO Skp_chk !REST IS FOR 2ND TIMESTEP
22545 FOR I=1 TO 3
22548 IF Cell(Side,1,I)<=0 THEN Nxt_lup
22551 Cell_save(Side,I)=Cell(Side,2,I) !SAVE REMAINING NO. OF HELOS
22554 IF Cell(Side,2,I)<.8*Cell(Side,1,I) THEN
22557 IF I=3 AND Cell(Side,1,I)>0 THEN GOTO Nxt_lup !NO MSG IF SCTS LI
T
22560 Cell(Side,2,I)=0 !TEMPORARILY ZERO OUT HELOS SO AD & ENEMY HEL
S WON'T SHOOT AT IT
22563 No_targets(Side,I+17)=0
22566 PRINT
22569 PRINT " ";Red_blue$;" HELICOPTER MISSION ":I:"ABORTED DUE TO I
CESSIVE LOSSES."
22572 ELSE !CHECK FOR ENOUGH MUNITIONS FOR THIS TIMESTEP
22575 IF Cell(Side,1,I)=0 THEN GOTO Nxt_lup
22578 IF Helo_mis(Side,I)=1 OR Helo_mis(Side,I)=3 THEN
22581 IF Helo_rnds_avl(Side,I)<=0 THEN
22584 IF Atk_prof(Side,I)<>2 AND Atk_prof(Side,I)<>6 THEN
22587 PRINT
22590 PRINT " NO MORE ":

```

Table 6-14. Ground combat code (continued).

```

22593             IF Atk_prof(Side,I)=1 OR Atk_prof(Side,I)=5 THEN PRINT "C
UND MISSILES AVAILABLE FOR ";Red_blue$;" HELO ";I;". WILL RETURN TO BASE."
22596             IF Atk_prof(Side,I)=3 OR Atk_prof(Side,I)=7 THEN PRINT "C
ROUNDS AVAILABLE FOR ";Red_blue$;" HELO ";I;". WILL RETURN TO BASE."
22599             Cell(Side,2,I)=0
22602             No_targets(Side,I+17)=0
22605             END IF
22608             END IF
22611             ELSE !CHECK FOR ENOUGH AIR MISSILES FOR AIR MISSION
22614             IF Air_rnds_avl(Side,I)<=0 THEN
22617             PRINT
22620             PRINT " NO MORE AIR MISSILES AVAILABLE FOR ";Red_blue$;"
LO ";I;". WILL RETURN TO BASE."
22623             Cell(Side,2,I)=0
22626             No_targets(Side,I+17)=0
22629             END IF
22632             END IF
22635             END IF
22638 Nxt_lup:NEXT I
22641 ! IF PRIMARY MSN IS D.S. OR SEAD, MUNITIONS IS MISSILES AND SCT AND AH1 E
ST, THEN SCTS LASING
22644 Skp_chk:H_lase(Side)=1
22647             IF (Helo_mis(Side,1)<>2) AND (Atk_prof(Side,1)=1 OR Atk_prof(Side,1
5) AND Cell(Side,1,3)>0 AND Cell(Side,2,1)>0 THEN
22650             IF Cell(Side,2,3)<.8*Cell(Side,1,3) THEN !CHECK FOR ENUF SCTS
22653             PRINT
22656             PRINT " INSUFFICIENT ";Red_blue$;" SCOUTS TO CONTINUE LASING.
REMAINING AH1 WILL OPERATE AUTONOMOUS."
22659             Cell(Side,2,3)=0 !ZERO OUT SCOUTS
22662             No_targets(Side,20)=0
22665             ELSE
22668             H_lase(Side)=3 !SCOUTS WILL LASE FOR HELO 1
22671             END IF
22674             END IF
22677             NEXT Side
22680 !
22683             FOR Side=1 TO 2
22686             IF Cell(Side,2,1)+Cell(Side,2,2)+Cell(Side,2,3)<=0 THEN GOTO Nxt_si
22689             Side_def=(Side MOD 2)+1
22692             IF Side=1 THEN Red_blue$="BLUE"
22695             IF Side=2 THEN Red_blue$="RED"
22698             FOR J=1 TO 20 !WHEN # OF TGTS ARE CLOSE TO 0, SET IT TO 0
22701             IF No_targets(Side_def,J)<.1 THEN No_targets(Side_def,J)=0
22704             NEXT J
22707             Tot_en_helos=No_targets(Side_def,18)+No_targets(Side_def,19)+No_tar
ts(Side_def,20) !TOTAL NO. OF ENEMY HELOS
22710             FOR J=1 TO 3 !LOOP ON TARGET HELOS
22713             SELECT Atk_prof(Side_def,J) !SET ENEMY MUNI TYPE USED FOR PRIMARY
N
22716             CASE 1,5 !MSL
22719             En_muni(J)=1
22722             CASE 2,6 !MSL/GUN

```

Table 6-14. Ground combat code (continued).

```

22725         IF Tim_step=1 THEN En_muni(J)=1 !SET TO MISSILES FIRST
22728         IF Tim_step=2 THEN En_muni(J)=2 !SET TO GUNS SECOND
22731         CASE 3,7
22734             En_muni(J)=2
22737         CASE 4 !AIR-TO-AIR
22740             En_muni(J)=3
22743         CASE ELSE!NO ATTACK PROFILE
22746             En_muni(J)=0
22749         END SELECT
22752         IF Helo_mis(Side_def,J)=2 AND Atk_prof(Side_def,J)>4 THEN En_muni
) =3 !PRIMARY MSN IS ENEMY HELO KILLS, THEN SET MUNITION USED TO AIR MSL
22755         NEXT J
22758!
22761         FOR I=1 TO 3
22764             Muni(I)=0
22767             IF Atk_prof(Side,I)>=4 THEN Muni(I)=3!AIR MSLS ON BOARD
22770         NEXT I
22773         IF Muni(1)+Muni(2)+Muni(3)>0 THEN !AT LEAST 1 HELO HAS AIR MSL
22776             Beg_cat=18 !LOOP THRU AIR TGT PK W/ AIR MUNI
22779             End_cat=20
22782             GOSUB Helo_pk_targ !CALCULATE PROB. OF KILL OF TGT HELOS
22785         END IF
22788!
22791         FOR I=1 TO 3 !LOOP ON HELO
22794             SELECT Atk_prof(Side,I)!SET ARRAY TO MUNITION TYPE USED THIS TST
22797             CASE 1,5 !MSL
22800                 Muni(I)=1
22803             CASE 2,6 !MSL/GUN
22806                 IF Tim_step=1 THEN Muni(I)=1 !MISSILE
22809                 IF Tim_step=2 THEN Muni(I)=2 !GUN
22812             CASE 3,7 !GUN
22815                 Muni(I)=2
22818             CASE 4 !AIR-TO-AIR
22821                 Muni(I)=3
22824             CASE ELSE!NO ATTACK PROFILE
22827                 Muni(I)=0
22830             END SELECT
22833             Lase=I !SET Lase TO WHICH HELO IS LASING-ITSELF OR SCT
22836             IF I=1 THEN Lase=H_lase(Side)
22839             Pop_tstep(I)=0
22842             SELECT Helo_mis(Side,I) !CALCULATE POPUPS PER TIMESTEP
22845             CASE 1,3 !PRIMARY MSN IS GROUND KILLS, USE MSL OR GUN TE & TM
22848                 IF Tm(Side,Lase,Muni(I))+Te(Side,Lase,Muni(I))>0 THEN Pop_tstep
) =Time_step/(Tm(Side,Lase,Muni(I))+Te(Side,Lase,Muni(I)))
22851                 Te_firer(I)=Te(Side,Lase,Muni(I)) !STORE TIME EXPOSED OF FIRER
22854             CASE 2 !PRIMARY MSN IS HELO KILLS, USE AIR MSL TE & TM
22857                 IF Tm(Side,Lase,3)+Te(Side,Lase,3)>0 THEN Pop_tstep(I)=Time_st
(Tm(Side,Lase,3)+Te(Side,Lase,3))
22860                 Te_firer(I)=Te(Side,Lase,3)
22863             END SELECT
22866         NEXT I
22869         IF (Muni(1)>0 AND Muni(1)<3) OR (Muni(2)>0 AND Muni(2)<3) OR (Muni

```

Table 6-14. Ground combat code (continued).

```

30 AND Muni(3)<3) THEN !AT LEAST 1 HELO HAS GRND MUNI
22872     Beg_cat=1           !LOOP THRU GROUND TGT PK W/ GROUND MUNI
22875     End_cat=17
22878     GOSUB Helo_pk_targ  !CALCULATE PROB. OF KILL BY HELOS
22881     END IF
22884     GOSUB Helo_pd_targ  !CALCULATE PROB. OF DETECTION BY HELOS
22887     GOSUB Ad_pd_helo   !CALCULATE PROB. OF DETECTION BY AD WEAPONS
22890     GOSUB Ad_avg_fired !CALCULATE AVERAGE ROUNDS FIRED BY AD
22893     GOSUB Df_pd_helo   !CALCULATE PROB. OF DETECTION BY DIRECT FIRE
22896     GOSUB Df_avg_fired !CALCULATE AVERAGE ROUNDS FIRED BY DIRECT FIRE
22899!
22902     FOR I=1 TO 3       !LOOP ON HELO TYPE
22905         IF I=3 AND H_lase(Side)=3 THEN !SET SCOUT'S POPUPS SAME AS AH1
22908             Pop_tstep(3)=Pop_tstep(1)
22911             GOTO Next_loop
22914         END IF
22917         IF Cell(Side,2,I)<=0 THEN GOTO Next_loop !NO HELOS OF TYPE I
22920         IF Helo_mis(Side,I)=2 AND Tot_en_helos<=0 THEN
22923             Cell(Side,2,I)=0 !HELO ON AIR MSN BUT NO ENEMY HELOS THIS 30 M.
                BTL
22926             PRINT " ";Red_blue$;" HELICOPTER ";I;" ON AIR-TO-AIR MISSION I
                T NO ENEMY HELOS FLYING."
22929             PRINT " WILL RETURN TO BASE."
22932             GOTO Next_loop
22935         END IF
22938         Lase=I           !SET Lase TO WHICH HELO IS LASING-ITSELF OR SCT
22941         IF I=1 THEN Lase=H_lase(Side)
22944!
22947         ON Atk_prof(Side,I) GOSUB Missile_attrite,Msl_gun,Gun_attrite,Next
                air,Missile_attrite,Msl_gun,Gun_attrite
22950         IF Cell(Side,2,I)<=0 THEN GOTO Next_loop !MEANS NO MUNITIONS LEFT
22953 Next_air:IF Atk_prof(Side,I)>=4 THEN GOSUB Air_attrite !CALC AIR KILLS
22956 Next_loop:NEXT I
22959!
22962         IF Cell(Side,2,1)+Cell(Side,2,2)+Cell(Side,2,3)>0 THEN
22965             GOSUB Ad_fire_dist !CALCULATE AD FIRE DISTRIBUTION AGAINST HELI'S
22968             GOSUB Ad_act_fired !CALCULATE ACTUAL ROUNDS FIRED BY AD
22971             GOSUB Df_act_fired !CALCULATE ACTUAL ROUNDS FIRED BY DIRECT FIRE
22974             GOSUB Helo_psrvc !CALCULATE HELICOPTER PROB. OF SURVIVAL
22977         END IF
22980!
22983 Nxt_side:NEXT Side
22986!
22989     FOR Side=1 TO 2     !DO ALL THE LOSS CALCULATIONS
22992         FOR I=1 TO 3     !RESET CELLS IF NEEDED
22995             IF Cell(Side,2,I)=0 AND Cell_save(Side,I)>0 THEN
22998                 Cell(Side,2,I)=Cell_save(Side,I)
23001                 No_targets(Side,I+17)=Cell_save(Side,I)
23004             END IF
23007         NEXT I
23010!
23013     FOR J=1 TO 17       !CALCULATE GROUND TARGET LOSSES BY ATK HELO

```

Table 6-14. Ground combat code (continued).

```

23016      Target_loss(Side,J)=(1-Target_psrv(Side,J))*No_targets(Side,J)
23019      NEXT J
23022      FOR I=1 TO 3      !HELO PROB OF SURV AND LOSS BY AD. DF & ENEMY HELO
23025      Helo_psrv(Side,I)=Target_psrv(Side,I+17)*Helo_psrv(Side,I)
23028      Helo_loss(Side,I)=(1.0-Helo_psrv(Side,I))*Cell(Side,2,I)
23031      Target_loss(Side,I+17)=Helo_loss(Side,I)
23034      NEXT I
23037!
23040      FOR I=1 TO 70      !DECATEGORIZE LOSSES TO GROUND ELEMENTS
23043      IF Side=1 THEN Ctg=B_cat(I)
23046      IF Side=2 THEN Ctg=R_cat(I)
23049      IF Ctg>0 AND Ctg<=17 THEN
23052      IF Target(Side,1,I)>0 AND No_targets(Side,Ctg)>0 THEN
23055      Target(Side,2,I)=Target(Side,2,I)-Target(Side,2,I)*(Target_lo
(Side,Ctg)/No_targets(Side,Ctg))
23058      END IF
23061      END IF
23064      NEXT I
23067!
23070      FOR I=1 TO 20      !CALCULATE NO. OF TARGETS REMAINING
23073      No_targets(Side,I)=No_targets(Side,I)-Target_loss(Side,I)
23076      Target_loss(Side,I)=0
23079      NEXT I
23082!
23085      FOR I=1 TO 3      !SUBTRACT HELO LOSSES
23088      Cell(Side,2,I)=Cell(Side,2,I)-Helo_loss(Side,I)
23091      Helo_loss(Side,I)=0      !ZERO OUT AGAIN
23094      NEXT I
23097      NEXT Side
23100      NEXT Tim_step
23103!
23106      FOR Side=1 TO 2
23109      Ad_amm0(Side)=Ad_wt_avl(Side)/2000      !CHANGE BACK TO TONS
23112      Df_amm0(Side)=Df_wt_avl(Side)/2000
23115      NEXT Side
23118      GOTO Subrout_end
23121!-----
23124      Missile_attrite: !
23127      IF Helo_rnds_avl(Side,I)<=0 THEN
23130      PRINT "      NO MORE GROUND MISSILES AVAILABLE FOR ";Red_blue$;" HELO ":I
23133      FOR J=1 TO 17
23136      Helo_avg_fired(I,J)=0 !ZERO OUT AVG ROUNDS FIRED PER POPUP
23139      NEXT J
23142      RETURN
23145      END IF
23148      GOSUB Helo_avg_fired      !CALCULATE AVERAGE ROUNDS FIRED BY HELOS
23151      IF Atk_prof(Side,I)<=2 THEN      !NO AIR TO AIR KILLS - DO LOSSES
23154      GOSUB Helo_fire_dist      !CALCULATE FIRE DISTRIBUTION BY HELOS
23157      GOSUB Helo_act_fired      !CALCULATE ACTUAL ROUNDS FIRED BY HELOS
23160      GOSUB Target_psrv      !CALCULATE TGTS' PROB OF SURVIVAL
23163      END IF
23166      RETURN

```

Table 6-14. Ground combat code (continued).

```

23169!-----
23172 Gun attrite:      !
23175 IF Helo_rnds_avl(Side,I)<=0 THEN
23178 PRINT " NO MORE GUN ROUNDS AVAILABLE FOR ";Red_blue$;" HELO ";I
23181 FOR J=1 TO 17
23184 Helo_avg_fired(I,J)=0 !ZERO OUT AVG. ROUNDS FIRED PER POPUP
23187 NEXT J
23190 RETURN
23193 END IF
23196 GOSUB Helo_avg_fired      !CALCULATE AVERAGE ROUNDS FIRED BY HELOS
23199 IF Atk_prof(Side,I)=2 OR Atk_prof(Side,I)=3 THEN !NO AIR KILLS-DO LOS
23202 GOSUB Helo_fire_dist     !CALCULATE FIRE DISTRIBUTION BY HELOS
23205 GOSUB Helo_act_fired    !CALCULATE ACTUAL ROUNDS FIRED BY HELOS
23208 GOSUB Target_psrvc     !CALCULATE TGTS' PROB OF SURVIVAL
23211 END IF
23214 RETURN
23217!-----
23220 Air_attrite:     !
23223 IF Air_rnds_avl(Side,I)<=0 THEN
23226 PRINT " NO MORE AIR MISSILES AVAILABLE FOR ";Red_blue$;" HELO ";I
23229 FOR J=18 TO 20
23232 Helo_avg_fired(I,J)=0 !ZERO OUT AVG AIR MSLs FIRED PER POPUP
23235 NEXT J
23238 ELSE
23241 Muni(I)=3           !SET POINTER TO AIR MUNITIONS
23244 GOSUB Air_avg_fired !CALCULATE AVERAGE ROUNDS FIRED BY HELOS
23247 END IF
23250 GOSUB Helo_fire_dist !CALCULATE FIRE DISTRIBUTION BY HELOS
23253 GOSUB Air_act_fired  !CALCULATE ACTUAL ROUNDS FIRED BY HELOS
23256 GOSUB Target_psrvc  !CALCULATE TGTS' PROB OF SURVIVAL
23259 RETURN
23262!-----
23265 Msl_gun:         !
23268 IF Tim_step=1 THEN
23271 GOSUB Missile_attrite
23274 ELSE
23277 Helo_rnds_avl(Side,I)=Helo_load(Side,I,2)*.5*Cell(Side,2,I)
                                           !GUN BASIC LOAD
23280 GOSUB Gun_attrite
23283 END IF
23286 RETURN
23289!-----
23292 Line_of_sight:   ! Prob of Line of Sight bet. helo & grnd
23295 FOR I=1 TO 3
23298 IF Helo_mis(Side,I)>0 THEN
23301 Los_msn=Helo_mis(Side,I)
23304 IF Los_msn=2 THEN Los_msn=1!Use D.S. msn data to calc. plos if helo
s
on an air to air msn
23307 Plos(Side,I)=Plos_alpha(Side,Los_msn)*(EXP(-Plos_beta(Side,Los_msn)*
g_avg(Side,I,1)))
23310 END IF
23313 NEXT I

```


Table 6-14. Ground combat code (continued).

```

23316 RETURN
23319
23322 -----
23325 Helo_pk_targ: ! Calculate the Prob. of Killing Target
23328 FOR I=1 TO 3 ! Looping on Helicopter Type
23331 IF Cell(Side,1,I)<=0 OR Muni(I)<=0 THEN GOTO Next_i_2
23334 FOR J=Beg_cat TO End_cat ! Looping on Target Category
23337 IF Muni(I)=0 THEN
23340 Helo_pk_targ(I,J)=0
23343 GOTO Next_helo_pk_tg
23346 END IF
23349 ! Is this Target within Range?
23352 IF Rg_avg(Side,I,J)<Pk_rmin(Side,I,Muni(I)) OR Rg_avg(Side,I,J)>Pk_
ax(Side,I,Muni(I)) THEN
23355 Helo_pk_targ(I,J)=0 ! No-then Prob. of Killing is Zero
23358 GOTO Next_helo_pk_tg
23361 END IF
23364 ! Calculate Fully Exposed & Hull Defiladed Prob. of Killing
23367 ! Target using a Specified Munitions at a given Range
23370 Pkhd=(Pk_hd_a(Side,I,Muni(I),J)*(Rg_avg(Side,I,J)^2))+(Pk_hd_b(Side
,Muni(I),J)*Rg_avg(Side,I,J))+Pk_hd_c(Side,I,Muni(I),J)
23373 Pkfe=Pk_fe_a(Side,I,Muni(I),J)*Rg_avg(Side,I,J)^2+Pk_fe_b(Side,I,Mun
(I),J)*Rg_avg(Side,I,J)+Pk_fe_c(Side,I,Muni(I),J)
23376 ! Calculate the Prob. of Killing this Target Category
23379 IF J<=17 THEN Helo_pk_targ(I,J)=Pkhd*Pct_force_hd(Side)+Pkfe*Pct_for
e_fe(Side)
23382 IF J>=18 THEN Helo_pk_targ(I,J)=Pkhd*Pct_mm(Side)+Pkfe*Pct_non_mm(S:
e)
23385 IF Helo_pk_targ(I,J)<0 THEN ! If Prob. of Kill is Negative (bad
23388 Helo_pk_targ(I,J)=0 ! points) then Set it to Zero
23391 END IF
23394 Next_helo_pk_tg:
23397 NEXT J
23400 Next_i_2:NEXT I
23403 RETURN
23406 -----
23409 Helo_pd_targ: ! Helicopter Prob. of Detecting Target
23412 FOR I=1 TO 3 ! Looping on Helicopter Type
23415 IF Cell(Side,1,I)<=0 OR Muni(I)<=0 THEN GOTO Next_i_1
23418 FOR J5=1 TO 5 ! Looping on Collapsed Target Category
23421 ! Is this Target within Range?
23424 IF Rg_avg_pd(Side,I,J5)<Pd_rmin(Side,I,Atmos) OR Rg_avg_pd(Side,I,J5
)>Pd_rmax(Side,I,Atmos) THEN
23427 Helo_pd_tgt(J5)=0 ! No-then Prob. of Detecting is Zero
23430 GOTO Next_coltg_pd
23433 END IF
23436 ! Calculate Fully Exposed & Hull Defiladed Prob. of Detecting; Infinite
23439 ! Time & Average Time to Detect a Target at a Specified Range
23442 Hdinf=Pd_hd_inf_a(Side,I,J5)*Rg_avg_pd(Side,I,J5)^2+Pd_hd_inf_b(Side
I,J5)*Rg_avg_pd(Side,I,J5)+Pd_hd_inf_c(Side,I,J5)
23445 Feinf=Pd_fe_inf_a(Side,I,J5)*Rg_avg_pd(Side,I,J5)^2+Pd_fe_inf_b(Side
I,J5)*Rg_avg_pd(Side,I,J5)+Pd_fe_inf_c(Side,I,J5)

```

Table 6-14. Ground combat code (continued).

```

23448      Hdtbar=Fd_hd_tbar_a(Side,I,J5)*Rg_avg_pd(Side,I,J5)^2+Pd_hd_tbar_b
de,I,J5)*Rg_avg_pd(Side,I,J5)+Pd_hd_tbar_c(Side,I,J5)
23451      Fetbar=Fd_fe_tbar_a(Side,I,J5)*Rg_avg_pd(Side,I,J5)^2+Pd_fe_tbar_b
de,I,J5)*Rg_avg_pd(Side,I,J5)+Pd_fe_tbar_c(Side,I,J5)
23454 ! Calculate Search Time, then Prob. of Detection for
23457 ! Fully Exposed & Hu.1 Defiladed Collapsed Target Category
23460      Ut(I)=Te_firer(I)-(Rg_avg_pd(Side,I,J5)/Fm(Side,I,Muni(I)))
23463      IF Ut(I)<0 THEN Ut(I)=0
23466 ! Calculate Prob. of Helicopter Detecting this Collapsed Target
23469 ! Category
23472      Pdt_fe=Feinf*(1-EXP(-MIN(Ut(I)/Fetbar,708)))
23475      Pdt_hd=Hdinf*(1-EXP(-MIN(Ut(I)/Hdtbar,708)))
23478      Helo_pd_tgt(J5)=Pdt_fe*Pct_force_fe(Side)+Pdt_hd*Pct_force_hd(Side)
23481      IF J5=5 THEN ! AIR TARGETS
23484          Pdt_rate(I)=(Pdt_fe*Pct_non_mm(Side))+(Pdt_hd*Pct_mm(Side))
23487      END IF
23490      IF Helo_pd_tgt(J5)<0 THEN ! If Prob. of Detecting is Negative
23493          Helo_pd_tgt(J5)=0 ! (bad points) then Set it to Zero
23496      END IF
23499 Next_coltg_pd: !
23502      NEXT J5
23505 Next_helo_pd: !
23508 ! Expand the 5 Collapsed Target Categories to 20 Target Categories
23511      FOR J=1 TO 20
23514          IF Pd_cat(Side_def,J)>0 AND Pd_cat(Side_def,J)<=5 THEN Helo_pd_targ
,J)=Helo_pd_tgt(Pd_cat(Side_def,J))
23517      NEXT J
23520      IF H_lase(Side_def)=3 THEN Helo_pd_targ(I,18)=0 !NO PROB OF DET OF H
0 1 IF SCTS LASING
23523 Next_i_1:NEXT I
23526      RETURN
23529 !
23532 !-----
23535 Helo_avg_fired: ! Calculate Average Rounds Fired at Target
23538      FOR J=1 TO 17 ! Looping on Target Category
23541          Helo_avg_fired(I,J)=0
23544          IF No_targets(Side_def,J)>0 THEN
23547 ! Calculate Average Rounds Fired by Helicopter using Specified
23550 ! Munition Type
23553          Helo_avg_fired(I,J)=Helo_pd_targ(Lase,J)*Plos(Side,I)*Np(Side,I,Muni
I))
23556      END IF
23559      NEXT J
23562      RETURN
23565 !
23568 !-----
23571 Helo_fire_dist: ! Calculate Fire Distribution against Target
23574      Helo_tot_dist=0
23577      Helo_grd_dist=0
23580      FOR J=1 TO 20 ! Looping on Target Category
23583 ! Calculate the Total Distribution of Fire across all Targets
23586      Helo_tot_dist=Helo_tot_dist+(Helo_pd_targ(Lase,J)*(No_targets(Side_def

```

Table 6-14. Ground combat code (continued).

```

J)*Helo_pk_targ(I,J))*Tgt_pref(Side,Helo_mis(Side,I),J))
23589 NEXT J
23592 ! Calculate the Distribution of Fire for a Single Target
23595 FOR J=1 TO 20
23598 IF Helo_tot_dist<>0 THEN
23601 Helo_fire_dist(I,J)=(Helo_pd_targ(Lase,J))*(No_targets(Side_def,J)*+
o_pk_targ(I,J))*Tgt_pref(Side,Helo_mis(Side,I),J))/Helo_tot_dist
23604 IF J<=17 THEN Helo_grd_dist=Helo_grd_dist+Helo_fire_dist(I,J)
23607 ELSE
23610 Helo_fire_dist(I,J)=0
23613 END IF
23616 NEXT J
23619 RETURN
23622 !
23625 !-----
23628 Helo_act_fired: ! Calculate Actual Rounds Fired at Target
23631 Tot_rnds_fired=0
23634 Grd_act_pp(I)=0
23637 FOR J=1 TO 20 ! Looping on Target Category
23640 ! Calculate Actual Rounds Fired at Target per Timestep
23643 Helo_act_fired(I,J)=Helo_avg_fired(I,J)*Pop_tstep(I)*Helo_fire_dist(I
)*Cell(Side,2,I)
23646 IF Muni(I)=1 THEN Helo_act_fired(I,J)=Helo_act_fired(I,J)*.8*Adust(Ar
(Side)) !MUNITIONS IS MISSILE
23649 ! Calculate Total Rounds Fired per Timestep
23652 Tot_rnds_fired=Tot_rnds_fired+Helo_act_fired(I,J)
23655 NEXT J
23658 ! Are There Enough Rounds Available?
23661 IF Tot_rnds_fired>Helo_rnds_avl(Side,I) THEN
23664 Adj_tot_rnds=0
23667 FOR J=1 TO 20
23670 ! NO-then Adjust Each Category By an Equivalent Percentage of the Rounds
23673 ! Available for Firing
23676 Helo_act_fired(I,J)=(Helo_rnds_avl(Side,I)/Tot_rnds_fired)*Helo_act_
ired(I,J)
23679 NEXT J
23682 ! Also Adjust the Number of Poppups in a Timestep Downward by an
23685 ! Equivalent Percentage
23688 IF Tot_rnds_fired>0 THEN
23691 Pop_tstep(I)=(Helo_rnds_avl(Side,I)/Tot_rnds_fired)*Pop_tstep(I)
23694 END IF
23697 ! Adjust Total Rounds Fired (you've fired all you have)
23700 Tot_rnds_fired=Helo_rnds_avl(Side,I)
23703 END IF
23706 ! Reset the Rounds Available
23709 Helo_rnds_avl(Side,I)=Helo_rnds_avl(Side,I)-Tot_rnds_fired
23712 RETURN
23715 !
23718 !-----
23721 Air_avg_fired: ! CALCULATE AVERAGE ROUNDS FIRED AT OPPOSING HELICOPTERS
23724 FOR J=18 TO 20
23727 IF En_muni(J-17)=0 THEN

```

Table 6-14. Ground combat code (continued).

```

23730     Helo_avg_fired(I,J)=0
23733     GOTO E_air_avg_fired
23736     END IF
23739     Te_targ_recip=1/Te(Side_def,J-17,En_muni(J-17))
23742     Tm_targ_recip=1/Tm(Side_def,J-17,En_muni(J-17))
23745 ! CALCULATE RATE AT WHICH FIRING HELICOPTER "I" DETECTS TARGET
23748 ! HELICOPTER "J" WITH BOTH OF THEM "POPPING" IN & OUT OF THE LINE
23751 ! OF SIGHT
23754     Pdt_rate_los=(Pdt_rate(Lase)*Tm_targ_recip)/(Tm_targ_recip+Te_targ_recip)
23757     IF No_targets(Side_def,J)<=0 THEN
23760         Helo_avg_fired(I,J)=0
23763         GOTO E_air_avg_fired
23766     END IF
23769     Time_to_impact=Rg_avg(Side,I,J)/Fm(Side,I,Muni(I))
23772     Te_recip=1/Te_firer(I)
23775     Den_90=LOG(.1)/(-Te_recip)
23778     P_engage=0
23781 ! CALCULATE THE PROB. OF ENGAGEMENT
23784     FOR T=Time_to_impact TO Den_90
23787         Pdt_t1=(Pdt_rate_los/(Te_targ_recip-Pdt_rate_los))*(EXP(-MIN(Pdt_rate_los*(T-Time_to_impact),708))-EXP(-MIN(Te_targ_recip*(T-Time_to_impact),708)))
23790         Pdt_time=1-(1-Pdt_t1)^No_targets(Side_def,J)
23793         P_engage=P_engage+(Te_recip*EXP(-MIN(Te_recip*T,708))*Pdt_time)
23796     NEXT T
23799     Helo_avg_fired(I,J)=P_engage*Np(Side,I,Muni(I))
23802 E_air_avg_fired:
23805     NEXT J
23808     RETURN
23811 !
23814 -----
23817 Air_act_fired: ! CALCULATE ACTUAL ROUNDS FIRED AT OPPOSING HELICOPTERS
23820 ! AND GROUND TARGETS
23823     Tot_rnds_fired=0
23826     Grd_pp=0
23829     Air_pp=0
23832     Helo_actual=0
23835     Air_actual=0
23838     Helo_air_dist=1.0-Helo_grd_dist !TOTAL AIR DISTRIBUTION
23841     FOR J=1 TO 20 ! Looping on Target Category
23844         Helo_act_fired(I,J)=0
23847         IF J<=17 THEN
23850 ! CALCULATE ACTUAL ROUNDS FIRED PER POPUP AT ALL GROUND TARGETS
23853             IF Helo_grd_dist>0 THEN
23856                 Grd_pp=Grd_pp+Helo_avg_fired(I,J)*Helo_fire_dist(I,J)/Helo_grd_dist
23859 ! CALCULATE ACTUAL ROUNDS FIRED PER TIMESTEP AT ALL GROUND TARGETS
23862                 Helo_act_fired(I,J)=Helo_avg_fired(I,J)*Pop_tstep(I)*Helo_fire_dist(I,J)*Cell(Side,2,I)
23865                 IF Muni(I)=1 THEN Helo_act_fired(I,J)=Helo_act_fired(I,J)*.8*Adj_rty(Side) !MUNITIONS IS MISSILE
23868                 Helo_actual=Helo_actual+Helo_act_fired(I,J)
23871             END IF

```

Table 6-14. Ground combat code (continued).

```

23874 ELSE
23877! CALCULATE ACTUAL ROUNDS FIRED PER POPUP AT ALL OPPOSING HELICOPTERS
23880 IF Helo_air_dist>0 THEN
23883 Air_pp=Air_pp+Helo_avg_fired(I,J)*Helo_fire_dist(I,J)/Helo_air_di
23886! CALCULATE ACTUAL ROUNDS FIRED PER TIMESTEP AT ALL OPPOSING HELICOPTERS
23889 Helo_act_fired(I,J)=Helo_avg_fired(I,J)*Pop_tstep(I)*Helo_fire_di
(I,J)*Cell(Side,2,I)
23892 Air_actual=Air_actual+Helo_act_fired(I,J)
23895 END IF
23898 END IF
23901 NEXT J
23904! ARE THERE ENOUGH AIR & GROUND ROUNDS AVAILABLE TO SUPPORT CALCULATED
23907! FIRING. IF NOT CONVERT EXCESS AIR ROUNDS TO GROUND FIRING AND VICE VER
23910 Old_air_actual=Air_actual
23913 Old_helo_actual=Helo_actual
23916 IF Air_actual>Air_rnds_avl(Side,I) THEN
23919 Helo_actual=Helo_actual+(Air_actual-Air_rnds_avl(Side,I))*(Grd_pp/Air
p)
23922 Air_actual=Air_rnds_avl(Side,I)
23925 IF Helo_actual>Helo_rnds_avl(Side,I) OR Helo_actual=0 THEN
23928 IF Helo_actual>0 THEN Helo_actual=Helo_rnds_avl(Side,I)
23931 ! Also Adjust the Number of Popups in a Timestep Downward by an
23934 ! Equivalent Percentage
23937 IF Grd_pp>0 THEN A_g_ratio=Air_pp/Grd_pp !AIR/GROUND RATIO
23940 IF Grd_pp<=0 THEN A_g_ratio=0
23943 Pop_tstep(I)=(Helo_rnds_avl(Side,I)*A_g_ratio+Air_rnds_avl(Side,I))
Old_helo_actual*A_g_ratio+Old_air_actual)*Pop_tstep(I)
23946 END IF
23949 GOTO E_air_act_fired
23952 END IF
23955 IF Helo_actual>Helo_rnds_avl(Side,I) THEN
23958 Air_actual=Air_actual+((Helo_actual-Helo_rnds_avl(Side,I))*(Air_pp/Gr
pp))
23961 Helo_actual=Helo_rnds_avl(Side,I)
23964 IF Air_actual>Air_rnds_avl(Side,I) OR Air_actual<=0 THEN
23967 IF Air_actual>0 THEN Air_actual=Air_rnds_avl(Side,I)
23970 ! Also Adjust the Number of Popups in a Timestep Downward by an
23973 ! Equivalent Percentage
23976 IF Air_pp>0 THEN G_a_ratio=Grd_pp/Air_pp !GROUND/AIR TRADEOFF RATE
23979 IF Air_pp<=0 THEN G_a_ratio=0
23982 Pop_tstep(I)=(Helo_rnds_avl(Side,I)+Air_rnds_avl(Side,I)*G_a_ratio)
Old_helo_actual+Old_air_actual*G_a_ratio)*Pop_tstep(I)
23985 END IF
23988 END IF
23991 E_air_act_fired: !
23994 ! ARE THERE ENOUGH GROUND ROUNDS AVAILABLE?
23997 IF Old_helo_actual<>Helo_actual THEN
24000 FOR J=1 TO 17
24003 ! NO-THEN ADJUST EACH GROUND CATEGORY BY AN EQUIVALENT PERCENTAGE OF T
24006 ! ROUNDS AVAILABLE FOR FIRING
24009 Helo_act_fired(I,J)=(Helo_actual/Old_helo_actual)*Helo_act_fired(I,
24012 NEXT J

```

Table 6-14. Ground combat code (continued).

```

24015 END IF
24018! DECREMENT GROUND ROUNDS AVAILABLE
24021 Helo_rnds_avl(Side,I)=Helo_rnds_avl(Side,I)-Helo_actual
24024 ! ARE THERE ENOUGH AIR ROUNDS AVAILABLE?
24027 IF Old_air_actual<>Air_actual THEN
24030   FOR J=18 TO 20
24033   ! NO-THEN ADJUST EACH AIR CATEGORY BY AN EQUIVALENT PERCENTAGE OF THE
24036   ! ROUNDS AVAILABLE FOR FIRING
24039     Helo_act_fired(I,J)=(Air_actual/Old_air_actual)*Helo_act_fired(I,J)
24042   NEXT J
24045 END IF
24048! DECREMENT AIR ROUNDS AVAILABLE
24051 Air_rnds_avl(Side,I)=Air_rnds_avl(Side,I)-Air_actual
24054 RETURN
24057 !
24060 !-----
24063 Target_psrv:           ! Calculate Prob. of Target Survival
24066   FOR J=1 TO 20       ! Looping on Target Category
24069     Tgt=MAX(No_targets(Side_def,J),1.0) ! HAS TO BE 1.0 OR MORE
24072     Target_psrv(Side_def,J)=Target_psrv(Side_def,J)*((1-(Helo_pk_targ(I,J)
Tgt))^Helo_act_fired(I,J))
24075   NEXT J
24078 RETURN
24081 !
24084 !-----
24087 Ad_pk_helo:           ! AD Prob. of Killing Helicopter
24090   FOR I=1 TO 7       ! Looping on AD Type
24093     FOR J=1 TO 3     ! Looping on Helicopter Type
24096     IF Rg_avg(Side,J,1)<Pk_ad_rmin(Side_def,I) OR Rg_avg(Side,J,1)>Pk_ad
rmax(Side_def,I) THEN
24099       Ad_pk_helo(Side_def,I,J)=0 ! No-then Prob. of Killing is Zero
24102       GOTO Next_ad_pk_helo
24105     END IF
24108     ! Use Probabilities for the Appropriate Mast Type
24111     IF Mast_mnt(Side,J)=0 THEN
24114       Mt=2 !non mast-mounted
24117     ELSE
24120       Mt=1 !mast-mounted
24123     END IF
24126     ! Calculate the Prob. of Killing at a Specified Range
24129     Ad_pk_helo(Side_def,I,J)=Pk_ad_a(Side_def,I,Mt)*Rg_avg(Side,J,1)^2+P
_ad_b(Side_def,I,Mt)*Rg_avg(Side,J,1)+Pk_ad_c(Side_def,I,Mt)
24132   Next_ad_pk_helo: !
24135     NEXT J
24138   NEXT I
24141 RETURN
24144 !
24147 !-----
24150 Ad_pd_helo:           ! AD Prob. of Detecting Helicopter
24153   FOR I=1 TO 7       ! Looping on AD Type
24156     IF Fad(Side_def,I)<=0 THEN !NO AD TYPE I DATA AVAIL
24159     FOR J=1 TO 3

```

Table 6-14. Ground combat code (continued).

```

24162     Ad_pd_helo(I,J)=0
24165     NEXT J
24168     GOTO Next_ad_i
24171     END IF
24174     FOR J=1 TO 3           ! Looping on Helicopter Type
24177     Ad_pd_helo(I,J)=0
24180     IF J=1 AND H_lase(Side)=3 THEN GOTO Next_ad_pd_helo
24183     IF Cell(Side,1,J)<=0 OR Muni(J)<=0 THEN GOTO Next_ad_pd_helo
24186     IF Rg_avg(Side,J,1)<Pd_ad_rmin(Side_def,I,Atmos) OR Rg_avg(Side,J,1
Pd_ad_rmax(Side_def,I,Atmos) THEN           !Is it within range?
24189     GOTO Next_ad_pd_helo !no-Prob of detection is zero
24192     END IF
24195     ! Use Probabilities for the Appropriate Mast Type
24198     IF Mast_mnt(Side,J)=0 THEN
24201     Mt=2           !non mast-mounted
24204     ELSE
24207     Mt=1           !mast-mounted
24210     END IF
24213 ! Calculate the Prob. of Detecting; Infinite Time & Average Time
24216 ! to Detect at a Specified Range
24219     Adinf=Pd_inf_ad_a(Side_def,I,Mt)*Rg_avg(Side,J,1)^2+Pd_inf_ad_b(Sid
def,I,Mt)*Rg_avg(Side,J,1)+Pd_inf_ad_c(Side_def,I,Mt)
24222     Adtbar=Pd_tbar_ad_a(Side_def,I,Mt)*Rg_avg(Side,J,1)^2+Pd_tbar_ad_b(
de_def,I,Mt)*Rg_avg(Side,J,1)+Pd_tbar_ad_c(Side_def,I,Mt)
24225 ! Calculate the Time to Detect this Helicopter Assuming an
24228 ! Engagement will follow
24231     Adteng=Te_firer(J)-(Rg_avg(Side,J,1)/Fad(Side_def,I))
24234     IF Adteng<0 THEN Adteng=0
24237 ! Calculate Prob. of the AD Detecting this Helicopter
24240     IF Adtbar>0 THEN Ad_pd_helo(I,J)=Adinf*(1-EXP(-Adteng/Adtbar))
24243 Next_ad_pd_helo:NEXT J
24246 Next_ad_i:NEXT I
24249     RETURN
24252 !
24255 !-----
24258 Ad_avg_fired:           ! AD Average Rounds Fired at Helicopter
24261     FOR I=1 TO 7           ! Looping on AD Type
24264     FOR J=1 TO 3           ! Looping on Helicopter Type
24267     IF Cell(Side,1,J)<=0 OR Helo_mis(Side,J)<=0 THEN GOTO Next_j_1
24270 ! Calculate the Average Rounds Fired at the Helicopter
24273     Ad_avg_fired(I,J)=Ad_pd_helo(I,J)*Plos(Side,J)
24276 Next_j_1:NEXT J
24279     NEXT I
24282     RETURN
24285 !
24288 !-----
24291 Ad_fire_dist:           ! Calculate AD Distribution against Helo
24294     FOR I=1 TO 7           ! Looping on AD Type
24297     Ad_tot_dist=0
24300     FOR J=1 TO 3           ! Looping on Helicopter Type
24303 ! Calculate the Total Distribution of Fire across all Helicopters
24306     Ad_tot_dist=Ad_tot_dist+(Ad_pd_helo(I,J))*(Cell(Side,2,J)*Ad_pk_helo

```

Table 6-14. Ground combat code (continued).

```

ide_def,I,J))*Ad_pref(Side_def,I,J)
24309     NEXT J
24312 ! Calculate the Distribution of Fire for a Single Target
24315     FOR J=1 TO 3           ! Looping on Helicopter Type
24318         IF Ad_tot_dist<>0 THEN
24321             Ad_fire_dist(I,J)=(Ad_pd_helo(I,J)*(Cell(Side,2,J)*Ad_pk_helo(Sid
def,I,J))*Ad_pref(Side_def,I,J))/Ad_tot_dist
24324         ELSE
24327             Ad_fire_dist(I,J)=0
24330         END IF
24333     NEXT J
24336 NEXT I
24339 RETURN
24342 !
24345 !-----
24348 Ad_act_fired:           ! Calculate Actual Rounds Fired at Helo
24351     FOR I=1 TO 5           ! FIGURE OUT NO. OF AD ELEMENTS ABLE TO FIRE
24354         Ad_ele(I)=Target(Side_def,2,I+47)*(1-Veh_ada(Side_def))
24357     NEXT I
24360     Ad_ele(6)=Target(Side_def,2,53)*(1-Hnd_ada(Side_def))
24363     Ad_ele(7)=Target(Side_def,2,54)*(1-Hnd_ada(Side_def))
24366     Tot_rnds_fired=0
24369     Tot_wt_fired=0
24372     FOR I=1 TO 7           ! Looping on AD Type
24375         FOR J=1 TO 3       ! Looping on Helicopter Type
24378 ! If Scouts are Lasing for AH1's then they can't be Detected
24381             IF H_lase(Side)=3 AND J=1 THEN
24384                 Ad_act_fired(I,J)=0
24387             ELSE
24390                 Ad_act_fired(I,J)=Ad_avg_fired(I,J)*Pop_tstep(J)*Ad_fire_dist(I,J)
Ad_ele(I)
24393             END IF
24396 ! Calculate Total Rounds Fired per Timestep
24399             Tot_rnds_fired=Tot_rnds_fired+Ad_act_fired(I,J)
24402         NEXT J
24405             Tot_wt_fired=Tot_wt_fired+Tot_rnds_fired*Rnd_wt(Side_def,I) ! IN LBS
24408             Tot_rnds_fired=0
24411     NEXT I
24414 ! Are There Enough Rounds Available?
24417     IF Tot_wt_fired>Ad_wt_avl(Side_def) THEN
24420         Adj_tot_rnds=0
24423         FOR I=1 TO 7           ! Looping on AD Type
24426             FOR J=1 TO 3       ! Looping on Helicopter Type
24429 ! NO-then Adjust Each Category By an Equivalent Percentage of the Round
24432 ! Available for Firing
24435                 Ad_act_fired(I,J)=(Ad_wt_avl(Side_def)/Tot_wt_fired)*Ad_act_fired(
,J)
24438 ! Calculate NEW Total Rounds Fired
24441             NEXT J
24444         NEXT I
24447 ! Adjust Total weight Fired (you've fired all you have)
24450             Tot_wt_fired=Ad_wt_avl(Side_def)

```


Table 6-14. Ground combat code (continued).

```

24453 END IF
24456 ! Reset the ammo weight Available
24459 Ad_wt_avl(Side_def)=Ad_wt_avl(Side_def)-Tot_wt_fired
24462 RETURN
24465 !
24468 !-----
24471 Df_pd_helo: ! DF Prob. of Detecting Helicopter
24474 FOR I=1 TO 2 ! Looping on Sensor Type
24477 FOR J=1 TO 3 ! Looping on Helicopter Type
24480 Dfinf(I,J)=0
24483 Dftbar(I,J)=0
24486 IF J=1 AND H_lase(Side)=3 THEN GOTO Next_df_pd_helo
24489 IF Cell(Side,I,J)<=0 OR Muni(J)<=0 THEN GOTO Next_df_pd_helo
24492 IF Rg_avg(Side,J,1)<Pd_df_rmin(Side_def,I,Atmos) OR Rg_avg(Side,J,1)
d_df_rmax(Side_def,I,Atmos) THEN ! Is it within range?
24495 GOTO Next_df_pd_helo ! No-Prob of detection is zero
24498 END IF
24501 ! Use Probabilities for the Appropriate Mast Type
24504 IF Mast_mnt(Side,J)=0 THEN
24507 Mt=2 ! Non mast-mounted
24510 ELSE
24513 Mt=1 ! Mast-mounted
24516 END IF
24519 ! Calculate the Prob. of Detecting; Infinite Time & Average Time
24522 ! to Detect at a Specified Range
24525 Dfinf(I,J)=Pd_inf_df_a(Side_def,I,Mt)*Rg_avg(Side,J,1)^2+Pd_inf_df_b
ide_def,I,Mt)*Rg_avg(Side,J,1)+Pd_inf_df_c(Side_def,I,Mt)
24528 Dftbar(I,J)=Pd_tbar_df_a(Side_def,I,Mt)*Rg_avg(Side,J,1)^2+Pd_tbar_d
b(Side_def,I,Mt)*Rg_avg(Side,J,1)+Pd_tbar_df_c(Side_def,I,Mt)
24531 Next_df_pd_helo: !
24534 NEXT J
24537 NEXT I
24540 FOR I=1 TO 20 ! LOOPING ON DF TYPE
24543 IF Df_muni_ptr(Side_def,I)<=0 OR Df_sen_ptr(Side_def,I)<=0 THEN
! NO DF TYPE I DATA AVAIL
24546 FOR J=1 TO 3
24549 Df_pd_helo(I,J)=0
24552 NEXT J
24555 GOTO Next_df_i
24558 END IF
24561 FOR J=1 TO 3 ! LOOPING ON HELICOPTER TYPE
24564 ! Calculate the Time to Detect this Helicopter Assuming an
24567 ! Engagement will follow
24570 Dfteng=Te_firer(J)-(Rg_avg(Side,J,1)/F_df(Side_def,Df_muni_ptr(Side_c
f,I)))
24573 IF Dfteng<0 THEN Dfteng=0
24576 ! Calculate Prob. of the DF Detecting this Helicopter
24579 IF Dftbar(Df_sen_ptr(Side_def,I),J)>0 THEN
24582 Df_pd_helo(I,J)=Dfinf(Df_sen_ptr(Side_def,I),J)*(1-EXP(-Dfteng/Dftt
r(Df_sen_ptr(Side_def,I),J)))
24585 END IF
24588 NEXT J

```

Table 6-14. Ground combat code (continued).

```

24591 Next_df_1:
24594 NEXT I
24597 RETURN
24600 !
24603 !-----
24606 Df_avg_fired:                ! DF Average Rounds Fired at Helicopter
24609 FOR I=1 TO 20                ! Looping on DF Type
24612   IF Df_muni_ptr(Side_def,I)<=0 THEN
24615     FOR J=1 TO 3              ! ZERO OUT ROUNDS FIRED BY THIS DIRECT FIRER
24618       Df_avg_fired(I,J)=0
24621     NEXT J
24624     GOTO Nxt_i_1
24627   END IF
24630   FOR J=1 TO 3                ! Looping on Helicopter Type
24633     Df_avg_fired(I,J)=0
24636     IF Cell(Side,1,J)<=0 OR Helo_mis(Side,J)<=0 THEN GOTO Nxt_j_1
24639 ! Calculate the Average Rounds Fired at the Helicopter
24642     Df_avg_fired(I,J)=Df_pd_helo(I,J)*Plos(Side,J)*Df_rnds_eng(Side_def.I
_muni_ptr(Side_def,I))
24645     Nxt_j_1:NEXT J
24648     Nxt_i_1:NEXT I
24651 RETURN
24654 !
24657 !-----
24660 Df_act_fired:                ! Calculate Actual Rounds Fired at Helo
24663 Tot_rnds_fired=0
24666 Tot_wt_fired=0
24669 FOR I=1 TO 20                ! Looping on DF Type
24672   FOR J=1 TO 3                ! Looping on Helicopter Type
24675 ! If Scouts are Lasing for AH1's then they can't be Detected
24678   IF H_lase(Side)=3 AND J=1 THEN
24681     Df_act_fired(I,J)=0
24684   ELSE
24687     Df_act_fired(I,J)=Df_avg_fired(I,J)*Pop_tstep(J)*Df_fire_dist(Side
ef,I,J)*Target(Side_def,2,I)
24690   END IF
24693 ! Calculate Total Rounds Fired per Popup
24696   Tot_rnds_fired=Tot_rnds_fired+Df_act_fired(I,J)
24699   NEXT J
24702   IF Side_def=1 THEN Df_rnd_wt=B_ammo_wt(I)
24705   IF Side_def=2 THEN Df_rnd_wt=R_ammo_wt(I)
24708   Tot_wt_fired=Tot_wt_fired+Tot_rnds_fired*Df_rnd_wt          ! IN LBS
24711   Tot_rnds_fired=0
24714 NEXT I
24717 ! Are There Enough Rounds Available?
24720 IF Tot_wt_fired>Df_wt_avl(Side_def) THEN
24723   Dfj_tot_rnds=0
24726   FOR I=1 TO 20                ! Looping on DF Type
24729     FOR J=1 TO 3                ! Looping on Helicopter Type
24732 ! NO-then adjust Each Category By an Equivalent Percentage of the Rounds
24735 ! Available for Firing
24738     Df_act_fired(I,J)=(Df_wt_avl(Side_def)/Tot_wt_fired)*Df_act_fired(I

```

Table 6-14. Ground combat code (concluded).

```

J)
24741     NEXT J
24744     NEXT I
24747     ! Adjust Total weight Fired (you've fired all you have)
24750     Tot_wt_fired=Df_wt_avl(Side_def)
24753     END IF
24756     ! Reset the ammo weight Available
24759     Df_wt_avl(Side_def)=Df_wt_avl(Side_def)-Tot_wt_fired
24762     RETURN
24765     !
24768     !-----
24771     Helo_psrv:                                ! Calculate Prob. of Helicopter Survival
24774     FOR J=1 TO 3                               ! Looping on Helicopter Type
24777     Helo_psrv(Side,J)=1                       ! Set initial Prob. of Survival to 1.0
24780     IF Cell(Side,2,J)<=0 THEN GOTO No_psrv
24783     H_alv=MAX(Cell(Side,2,J),1.0)             ! HAS TO BE >=1.0
24786     FOR I=1 TO 7                               ! Looping on AD Type
24789     Helo_psrv(Side,J)=Helo_psrv(Side,J)*(((1-(Ad_pk_helo(Side_def,I,J)/H_
_v))Ad_act_fired(I,J))
24792     NEXT I
24795     IF Mast_mnt(Side,J)=0 THEN Mt=1 !NON MAST MT (FE)
24798     IF Mast_mnt(Side,J)=1 THEN Mt=2 !MAST MNT (HD)
24801     FOR I=1 TO 20                             ! Looping on DF Type
24804     Helo_psrv(Side,J)=Helo_psrv(Side,J)*(((1-(Df_pk_helo(Side_def,I,J,Mt)
_alv))Df_act_fired(I,J))
24807     NEXT I
24810     No_psrv:NEXT J
24813     RETURN
24816     !
24819     Subrout_end: !
24822     SUBEND
24825     !
24828     !*****
                *****

```

CHAPTER 7

CHEMICAL ATTRITION

1. PURPOSE.

The purpose of the chemical attrition program is to calculate attrition from chemical munitions based on agent type, firing unit, unit type, composition, and mission-oriented protective posture (MOPP) status.

2. GENERAL.

A. The chemical attrition program (P5) is a slightly modified version of the DAME chemical module discussed in CAORA/TR-5/83, Deep Attack Map Exercise (DAME) Game Rules and Operation Procedures. The attrition process remains the same.

B. Attrition of Red and Blue forces due to chemical warfare is played in DIME using the chemical program. However, it is important to realize that chemical attrition is not a separate process but must be integrated into the overall loss assessment process used in the game. The chemical munitions used in DIME are artillery or rocket delivered and are measured in battery (48-round) or battalion (144-round) missions. The program allows Red and Blue forces to deliver either persistent or non-persistent agents against enemy forces. The use of chemical munitions must be integrated into the artillery fire planning process, and use of chemical munitions must not exceed prescribed firing rates, range requirements, or basic loads. Chemical missions replace conventional missions in the overall firing profile of an artillery unit. An artillery unit may not exceed its conventional rate of fire or basic load.

3. DATA FLOW.

A. Input data. As with other programs, an input sheet has been developed to simplify the development of chemical attrition assessments. Figure 7-1 shows an example of the form. The following paragraphs describe the required inputs.

(1) Type of mission. Circle the type of mission desired. A separate input sheet is required for each individual mission type. For example, if the gamer desires to shoot Red battalion missions of persistent agent and Blue battery missions of non-persistent agent, two separate input sheets are required. Note that Red battalion mission denotes the Red attacker.

GAMER INPUT SHEET

A. Circle one of the following:

(1) Red Battery of Persistent

(2) Red Battery of Non-persistent

(3) Red Battalion of Persistent

(4) Red Battalion of Non-persistent

(5) Blue Battery of Persistent

(6) Blue Battery of Non-persistent

(7) Blue Battalion of Persistent

(8) Blue Battalion of Non-persistent

B. Enter number of units to assess as targets for the above mission (max 10). _____

C. Fill in the table with the following information for each target selected:

UNIT - A legitimate unit number from the unit file.

FRACTION - Fraction of unit affected by mission.

MISSIONS - Number of mission assessments against unit.

HOPP - HOPP status (1 = Not in HOPP, 2 = In HOPP)

TARGET	UNIT	FRACTION	MISSIONS	HOPP
1				
2				
3				
4				
5				
6				
7				
8				
9				
10				

Figure 7-1. Chemical attrition input sheet

(2) Number of targets. Enter the number of units which will be targeted by a particular type of mission. A target may only have one unit in it. A maximum of 10 targets may be designated for a mission type. If the gamer desires more than 10 targets, an additional input sheet must be used.

(3) Target data matrix. Information on each target is specified by entering:

(a) The unit number of the target (1-400).

(b) The fraction of the unit which is affected by the mission. For example, if only half a unit is in the target area, then .50 is entered.

(c) The number of missions which will be fired against the target.

(d) The MOPP status of the target unit (1 = not in MOPP, 2 = in MOPP). Units which are in MOPP do not sustain casualties from chemical attack.

B. Output data. Output consists of the total chemical kills for each side per mission and total chemical kills for each side per critical incident (CI).

C. Data flows are depicted in Figure 7-2.

4. FILE STRUCTURE.

Data files supporting the chemical program are held external to the program. These files consist of target radius files and target profile files.

A. A target radius file exists for both defenders, Blue and Red (BLTEMP and RDTEMP). This data is read into the Trgt_rds(I,J) array, where:

I = unit type (1-10)
J = major mission
1 = attack
2 = defend
3 = reserve
4 = movement.




Figure 7-2. Chemical data flow.

The appropriate value from this array, for the unit being attacked, is used to access the correct target profile array.

B. A target profile file containing casualty fractions exists for the combinations of the following:

- (1) Blue or Red defender.
- (2) Battery or Battalion.
- (3) Persistent or non-persistent chemical.
- (4) Major mission (defend, attack, reserve, move).

The appropriate one-record file is read into the Defend_file(*), Attack_file(*), Reserve_file(*), and Move_file(*) arrays. The casualty fraction for each element type within a unit is accessed by choosing the appropriate major mission file for the defending unit (Defend_file (I,J), Attack_file (I,J), Reserve_file (I,J), and Move_file (I,J)), where:

I = 1-70 element types.
J = 1-5, target radius value divided by 100.

C. It should be noted that no data currently exists for the chemical program. Therefore, volume III of this report does not contain information and data concerning the chemical program.

5. ALGORITHMS.


The primary algorithm/equation used to assess chemical attrition is:

$$\text{Kills} = \text{Csly_frct} * \text{N_elements} \quad (\text{Eq. 7-1})$$

This calculation is repeated for the number of missions using the new number of elements ($\text{N_elements} = \text{N_elements} - \text{Kills}$) for each repetition where:

Kills = number of victims.
Csly_frct = casualty fraction to be assessed, depends on target radius and profile.
N_elements = number of elements to assess.

The logic flow of the chemical program is depicted in Figure 7-3.



6. "UNITFILE" IMPACT.

This program changes several elements in the unit status file ("UNITFILE"). Elements 1-70 are suffer attrition if chemical losses are subtracted. Element 77 (MOPP status) is changed to a 2 which indicates that the unit is in MOPP. There is no interaction with any other programs. Control is returned to the DIME driver program.

7. CODE.

A. The chemical program code is discussed in the following paragraphs. The functional areas discussed are represented in Figure 7-4.

(1) Initialization of variables and selection from the menu shown in Figure 7-1 (gamer input sheet), part A, are the first occurrences within the program. Appropriate data files are then read.

(2) Following other inputs (see Figure 7-1), the MOPP value entered is assessed. If the MOPP status is 2, the unit is in MOPP and cannot be assessed. If the value 1 is entered for a unit, the assessment is continued. It should be noted that the MOPP value input for each unit from the menu should correspond accordingly with the unit's MOPP value held within the "UNITFILE".

(3) If assessment is to continue, another check must be made. An attacker may not inflict attrition on a friendly unit (on the same side). If the unit suffering attrition is unfriendly, the appropriate casualty fraction is multiplied by the number of elements to get the number of elements killed.

(4) MOPP status is changed to "in MOPP" for those units assessed. A summary of the inputs and total chemical kills for the current critical incident (CI) is printed if the choice was to update the kills to the units.

B. A subroutine variable listing appears in Table 7-1. Table 7-2 contains a listing of the chemical program code.




Figure 7-4. Chemical functional flow.

Table 7-1. Chemical subroutine table.

Functional area(s): <u>Chemical program</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Menu selection		Select appropriate menu options and set variables.	A. Menu_optn	Option 1-9 on menu 1 = Red battery of persistent 2 = Red battery of non-persistent 3 = Red battal'n of persistent 4 = Red battal'n of non-persistent 5 = Blue battery of persistent 6 = Blue battery of non-persistent 7 = Blue battal'n of persistent 8 = Blue battal'n of non-persistent 9 = Exit chemical module
	B. Name_p1\$			Mission for firer abbreviation
	C. Np1\$			Mission firer
	D. Name_p2\$			Chemical agent fired abbreviation
	E. Np2\$			Chemical agent fired
	F. Name_p3\$			Victim force abbreviation
	G. Attacker\$			Attacking force
	H. Victim\$			Victim force

Table 7-1. Chemical subroutine table.

<u>Functional area(s):</u> <u>Chemical program</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Read_files</u>	Opens needed files	A. Trgt_rds (*)	Target radii for Red and Blue forces.
		B. Defend_file(*)	Defend target profile data
		C. Attack_file(*)	Attack target profile data
		D. Reserve_file(*)	Reserve target profile data
		E. Move_file(*)	Movement target profile data
<u>Input_output</u>	Processes input and output data from keyboard.	A. Num_units	Number of units to assess.
		B. Unit_num(*)	Unit being assessed.
		C. Trgt_frct(*)	Fraction of area targeted
		D. Nm_missions(*)	Number of missions required/unit.
		E. Mopp_status(*)	1 = not in MOPP 2 = in MOPP.
		F. Targ_id	Target number.
<u>Attrition</u>	Assesses attrition losses.	A. Chem_losses(*)	Assessed chemical attrition losses.
<u>Assess</u>	Called by Attrition	A. Force_type	1 = Blue; 2 = Red
		B. Force\$	Force type from N(26) of unit file.

Table 7-1. Chemical subroutine table.

<u>Functional area(s):</u> <u>Chemical program</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
<u>Chem_kill</u>	Called by Assess; assesses chemical losses.	A. Unit_type B. Trgt_radius C. Calty_frct D. Sum_kill E. N_elements	Unit member to be chemically assessed. Target radius based on unit type and mission profile. Casualty fraction from a selected table. Element victim tabulator. Number of elements times fraction targeted.
<u>Print_losses</u>	Called by Assess; prints loss assessment.	A. Mission_tot(I)	Total chemical kills for an entire mission. (I = 1 - 70)
<u>Accumulate</u>	Totals kills	A. Bl_game_tot(I) B. Rd_game_tot(I)	Total Blue chemical kills for an entire CI. Total Red chemical kills for an entire CI.
<u>Sub_end</u>	Returns to DIME menu.		

Table 7-1. Chemical subroutine table.

<u>Functional area(s):</u> <u>Check variables</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Ck_var		Called by all routines with inputs. Checks inputs for correct values.	A. Min_value B. Max_value C. Variable	Minimum value of variable. Maximum value of variable. Variable to be checked.
Print_error		Prints error messages.		

Table 7-2. Chemical code.

```

10  !!! P5 - CHEMICAL ATTRITION
20  !           REWRITTEN FROM DAME CHEMICAL MODULE INTO HP BASIC
30  ! EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
40  OPTION BASE 1
50  DIM N(150),Trgt_rds(10,4)
60  DIM Chem_losses(70),Bl_game_tot(70),Rd_game_tot(70),Mission_tot(70)
70  DIM Defend_file(70,5),Attack_file(70,5),Reserve_file(70,5),Move_file(70,5)
80  DIM Unit_num(10),Trgt_frct(10),Nm_missions(10),Mopp_status(10)
90  !
100 !
110 Main_program: !
120 PRINT USING "@,@"
130 Disk$=":HP9134,701"
140 Menu$="REPEAT"
150 WHILE Menu$="REPEAT"
160     GOSUB Menu_selection
170     SELECT Option$
180     CASE "RUN"
190         GOSUB Read_files
200         GOSUB Input_output
210         GOSUB Attrition
220         GOSUB Accumulate
230     CASE "EXIT"
240         PRINT
250         PRINT
260         PRINT
270         PRINT "EXIT CHEMICAL MODULE"
280         Menu$="STOP"
290     END SELECT
300 END WHILE
310 !
320 GOTO Sub_end
330 !
340 Menu_selection: !
350 REPEAT
360     PRINT
370     PRINT "CHEMICAL MODULE MENU--INPUT FOLLOWING OPTION:"
380     PRINT "      (1)RED BATTERY OF PERSISTENT"
390     PRINT "      (2)RED BATTERY OF NON-PERSISTENT"
400     PRINT "      (3)RED BATTALION OF PERSISTENT"
410     PRINT "      (4)RED BATTALION OF NON-PERSISTENT"
420     PRINT "      (5)BLUE BATTERY OF PERSISTENT"
430     PRINT "      (6)BLUE BATTERY OF NON-PERSISTENT"
440     PRINT "      (7)BLUE BATTALION OF PERSISTENT"
450     PRINT "      (8)BLUE BATTALION OF NON-PERSISTENT"
460     PRINT "      (9)EXIT CHEMICAL MODULE"
470     INPUT Menu_optn
480     Option$="RUN"
490     SELECT Menu_optn
500     CASE 1
510         Name_p1$="BTY"
520         Np1$="BATTERY"

```


Table 7-2. Chemical code (continued).

```

530     Name_p2$="PS"
540     Np2$="PERSISTENT"
550     Name_p3$="BL"
560     Attacker$="RED"
570     Victim$="BLUE"
580     CASE 2
590     Name_p1$="BTY"
600     Np1$="BATTERY"
610     Name_p2$="NP"
620     Np2$="NON-PERSISTENT"
630     Name_p3$="BL"
640     Attacker$="RED"
650     Victim$="BLUE"
660     CASE 3
670     Name_p1$="BN"
680     Np1$="BATTALION"
690     Name_p2$="PS"
700     Np2$="PERSISTENT"
710     Name_p3$="BL"
720     Attacker$="RED"
730     Victim$="BLUE"
740     CASE 4
750     Name_p1$="BN"
760     Np1$="BATTALION"
770     Name_p2$="NP"
780     Np2$="NON-PERSISTENT"
790     Name_p3$="BL"
800     Attacker$="RED"
810     Victim$="BLUE"
820     CASE 5
830     Name_p1$="BTY"
840     Np1$="BATTERY"
850     Name_p2$="PS"
860     Np2$="PERSISTENT"
870     Name_p3$="RD"
880     Attacker$="BLUE"
890     Victim$="RED"
900     CASE 6
910     Name_p1$="BTY"
920     Np1$="BATTERY"
930     Name_p2$="NP"
940     Np2$="NON-PERSISTENT"
950     Name_p3$="RD"
960     Attacker$="BLUE"
970     Victim$="RED"
980     CASE 7
990     Name_p1$="BN"
1000    Np1$="BATTALION"
1010    Name_p2$="PS"
1020    Np2$="PERSISTENT"
1030    Name_p3$="RD"
1040    Attacker$="BLUE"

```

Table 7-2. Chemical code (continued).

```

1050     Victim$="RED"
1060     CASE 8
1070         Name_p1$="BN"
1080         Np1$="BATTALION"
1090         Name_p2$="NP"
1100         Np2$="NON-PERSISTENT"
1110         Name_p3$="RD"
1120         Attacker$="BLUE"
1130         Victim$="RED"
1140     CASE 9
1150         Option$="EXIT"
1160     CASE ELSE
1170         PRINT
1180         PRINT "## ERROR:  INVALID MENU SELECTION"
1190         WAIT 1
1200     END SELECT
1210     UNTIL Menu_optn>=1 AND Menu_optn<=9
1220     RETURN
1230!
1240 Read_files:!
1250     File$=Name_p3$&"TEMP"
1260     ASSIGN @Path TO File$&Disk$
1270     ENTER @Path,1;Trgt_rds(*)
1280     Name$=Name_p1$&Name_p2$&Name_p3$
1290     File$=Name$&"DFN"
1300     ASSIGN @Path TO File$&Disk$
1310     ENTER @Path,1;Defend_file(*)
1320     File$=Name$&"ATK"
1330     ASSIGN @Path TO File$&Disk$
1340     ENTER @Path,1;Attack_file(*)
1350     File$=Name$&"RS"
1360     ASSIGN @Path TO File$&Disk$
1370     ENTER @Path,1;Reserve_file(*)
1380     File$=Name$&"MV"
1390     ASSIGN @Path TO File$&Disk$
1400     ENTER @Path,1;Move_file(*)
1410     ASSIGN @Path TO *
1420     RETURN
1430!
1440 Input_output:!
1450     !
1460     INPUT "ENTER:  # OF UNITS TO ASSESS (MAX 10)",Num_units
1470     CALL Ck_var("# OF UNITS","TO",Num_units,1,10)
1480     PRINT
1490     PRINT "FOR EACH UNIT, ENTER:  UNIT #,  TGT FRACTION,  # MISSIONS,  MOFF #"
1500     FOR I=1 TO Num_units
1510         PRINT USING Fiol;" TGT # ",I
1520     Fiol:IMAGE 5A,2D,2X
1530     INPUT Unit_num(I),Trgt_frct(I),Nm_missions(I),Mopp_status(I)
1540     CALL Ck_var("UNIT #","TO",Unit_num(I),1,400)
1550     CALL Ck_var("TGT FRACTION","THROUGH",Trgt_frct(I),0,1)
1560     CALL Ck_var("# MISSIONS","TO",Nm_missions(I),0,10)

```

Table 7-2. Chemical code (continued).

```

1570 CALL Ck_var("MOPP #","OR",Mopp_status(I),1,2)
1580 NEXT I
1590 !
1600 Pt:Re_enter$="CONT"
1610 PRINT
1620 PRINT "THE FOLLOWING WERE CHOSEN: "
1630 GOSUB Prnt
1640 !
1650 REPEAT
1660 INPUT "DO YOU WISH TO CHANGE INPUTS? (Y/N)",Answ$
1670 UNTIL Answ$="Y" OR Answ$="N"
1680 !
1690 WHILE Re_enter$="CONT"
1700 SELECT Answ$
1710 CASE "Y"
1720 INPUT "ENTER TARGET #",Targ_id
1730 CALL Ck_var("TARGET #","TO",Targ_id,1,Num_units)
1740 INPUT "ENTER: UNIT #, TGT FRACTION, # MISSIONS, MOPP #",Unit_num(Targ
_id),Trgt_frct(Targ_id),Nm_missions(Targ_id),Mopp_status(Targ_id)
1750 CALL Ck_var("UNIT #","TO",Unit_num(Targ_id),1,400)
1760 CALL Ck_var("TGT FRACTION","THROUGH",Trgt_frct(Targ_id),0,1)
1770 CALL Ck_var("# MISSIONS","TO",Nm_missions(Targ_id),0,10)
1780 CALL Ck_var("MOPP #","OR",Mopp_status(Targ_id),1,2)
1790 !
1800 REPEAT
1810 INPUT "ARE CHANGES COMPLETE? (Y/N)",An$
1820 UNTIL An$="Y" OR An$="N"
1830 !
1840 SELECT An$
1850 CASE "Y"
1860 Re_enter$="STOP"
1870 CASE "N"
1880 Re_enter$="CONT"
1890 END SELECT
1900 !
1910 CASE "N"
1920 GOTO Ret
1930 END SELECT
1940 END WHILE
1950 GOTO Pt
1960 Ret: !
1970 RETURN
1980 !
1990 Attrition: !
2000 FOR I=1 TO Num_units
2010 ! INITIALIZE LOSSES
2020 FOR L=1 TO 70
2030 Chem_losses(L)=0
2040 NEXT L
2050 ! CHECK MOPP STATUS
2060 IF Mopp_status(I)=2 THEN
2070 PRINT

```

Table 7-2. Chemical code (continued).

```

2080     PRINT "UNIT ";Unit_num(I);" IN MOPP, CANNOT BE ASSESSED"
2090     ELSE
2100     GOSUB Assess
2110     END IF
2120     NEXT I
2130     RETURN
2140     !
2150 Assess: !
2160     ASSIGN @Path TO "UNITFILE:HP9134,701"
2170     ENTER @Path,Unit_num(I);N(*)
2180     !
2190     !CHECK COLOR OF UNIT
2200     Force_type=INT(N(78))
2210     SELECT Force_type
2220     CASE 1
2230     Force$="BLUE"
2240     CASE 2
2250     Force$="RED"
2260     END SELECT
2270     IF Force$=Attacker$ THEN
2280     PRINT
2290     PRINT "CANNOT ASSESS FRIENDLY UNIT ";Unit_num(I)
2300     ELSE
2310     GOSUB Chem_kill
2320     ! CHANGE MOPP STATUS IN UNITFILE
2330     N(77)=2
2340     GOSUB Prnt_losses
2350     END IF
2360     !
2370     !
2380     OUTPUT @Path,Unit_num(I);N(*)
2390     ASSIGN @Path TO *
2400     !
2410     !
2420     RETURN
2430     !
2440 Chem_kill: !
2450     !UNPACK TO GET UNIT TYPE
2460     Unit_type=(N(78)-Force_type)*10+1
2470     Trgt_radius=Trgt_rds(Unit_type,N(75))/100
2480     !
2490     FOR J=1 TO 70
2500     SELECT N(75)
2510     CASE 1
2520     Cslty_frct=Attack_file(J,Trgt_radius)
2530     CASE 2
2540     Cslty_frct=Defend_file(J,Trgt_radius)
2550     CASE 3
2560     Cslty_frct=Reserve_file(J,Trgt_radius)
2570     CASE 4
2580     Cslty_frct=Move_file(J,Trgt_radius)
2590     END SELECT

```

Table 7-2. Chemical code (continued).

```

2600      !
2610      Sum_kill=0
2620      N_elements=N(J)*Trgt_frct(I)
2630      FOR K=1 TO Nm_missions(I)
2640          Sum_kill=Sum_kill+Cslty_frct*N_elements
2650          N_elements=N_elements-Sum_kill
2660          IF N_elements<=0 THEN
2670              N_elements=0
2680          END IF
2690      NEXT K
2700      !
2710      Chem_losses(J)=Sum_kill
2720  NEXT J
2730  RETURN
2740  !
2750 Prnt: !
2760 PRINT
2770 PRINT "TGT #          UNIT #          TGT FRACTION          # MISSIONS          MOP
P #"
2780 FOR I=1 TO Num_units
2790     PRINT USING Fio2;I,Unit_num(I),Trgt_frct(I),Nm_missions(I),Mopp_status(I)
2800 Fio2: IMAGE 3X,2D,12X,3D,11X,D.2D,16X,2D,16X,D
2810 NEXT I
2820 RETURN
2830 !
2840 Prnt_losses: !
2850 PRINT
2860 PRINT "CHEMICAL LOSSES TO UNIT ";Unit_num(I)
2870 PRINT
2880 PRINT "          ELEMENT #          LOSSES"
2890 FOR M=1 TO 70
2900     PRINT USING Fp11;M,Chem_losses(M)
2910 NEXT M
2920 Fp11: IMAGE 15X,3D, 7X,4D.2D
2930 REPEAT
2940     INPUT "DO YOU WISH TO SUBTRACT LOSSES? (Y/N)",An$
2950 UNTIL An$="Y" OR An$="N"
2960 IF An$="Y" THEN
2970     FOR M=1 TO 70
2980         Mission_tot(M)=Mission_tot(M)+Chem_losses(M)
2990         N(M)=N(M)-Chem_losses(M)
3000     NEXT M
3010 END IF
3020 RETURN
3030 !
3040 Accumulate: !
3050 PRINTER IS 702
3060 PRINT
3070 PRINT
3080 PRINT "THE FOLLOWING PARAMETERS WERE CHOSEN FOR MISSION ":Attacker$:" ":Np
1$:" OF ":Np2$

```

Table 7-2. Chemical code (continued).

```

3090 GOSUB Prnt
3100 PRINT
3110 PRINT
3120 PRINT "          ";Victim#;" CHEMICAL VICTIMS FOR THIS MISSION"
3130 PRINT "          ELEMENT #          VICTIMS"
3140 FOR I=1 TO 70
3150   PRINT USING Fa1;I,Mission_tot(I)
3160 NEXT I
3170 Fa1:IMAGE 25X,3D,11X,4D.2D
3180 !
3190 ASSIGN @Blvctm TO "BLCHMVCTM"
3200 ASSIGN @Rdvctm TO "RDCHMVCTM"
3210 ENTER @Blvctm,1;Bl_game_tot(*)
3220 ENTER @Rdvctm,1;Rd_game_tot(*)
3230 !
3240 IF Name_p3#="BL" THEN
3250   FOR I=1 TO 70
3260     Bl_game_tot(I)=Bl_game_tot(I)+Mission_tot(I)
3270   NEXT I
3280 END IF
3290 IF Name_p3#="RD" THEN
3300   FOR I=1 TO 70
3310     Rd_game_tot(I)=Rd_game_tot(I)+Mission_tot(I)
3320   NEXT I
3330 END IF
3340 OUTPUT @Blvctm,1;Bl_game_tot(*)
3350 OUTPUT @Rdvctm,1;Rd_game_tot(*)
3360 !
3370 PRINT
3380 PRINT
3390 PRINT "TOTAL BLUE CHEMICAL VICTIMS          TOTAL RED CHEMICAL VI
TIMS"
3400 PRINT "  ELEMENT #          VICTIMS          ELEMENT #          VICTI
S"
3410 FOR I=1 TO 70
3420   PRINT USING Fa2;I,Bl_game_tot(I),I,Rd_game_tot(I)
3430 NEXT I
3440 Fa2:IMAGE 9X,2D, 5X,4D.2D,31X,2D, 4X,4D.2D
3450 PRINTER IS 1
3460 RETURN
3470 !
3480 Sub_end: !
3490 LOAD "DIME:HP9134,701"
3500 END
3510 !
3520 !*****
3530 !
3540 SUB Ck_var(Var_name$,T$,Variable,Min_value,Max_value)
3550   SELECT T$
3560   CASE "THROUGH"
3570     WHILE Variable<Min_value OR Variable>Max_value
3580       GOSUB Print_error

```

Table 7-2. Chemical code (concluded).

```
3590     END WHILE
3600     CASE "OR"
3610         GOTO Case_to
3620     CASE "TO"
3630 Case_to:FOR M=Min_value TO Max_value
3640         IF Variable=M THEN GOTO End_select
3650         NEXT M
3660         GOSUB Print_error
3670         GOTO Case_to
3680 End_select:!
3690     END SELECT
3700     GOTO Rtrn
3710 Print_error:    !
3720     PRINT
3730     PRINT "*** ERROR: ";Variable;" IS INVALID FOR ";Var_name$
3740     PRINT "INPUT: ";Min_value;" ";T$;" ";Max_value;" ONLY"
3750     INPUT Variable
3760     RETURN
3770 Rtrn:!
3780 SUBEND
```

CHAPTER 8

COMMAND AND CONTROL

1. PURPOSE.

The purpose of the DIME command and control program (PIO) is to calculate the reaction time for both the commander and staff to begin a new mission.

2. GENERAL.

The command and control program calculates the total reaction time needed to react to a change in mission.

A. The command and control program uses an interactive menu/response format to access the appropriate delay times stored in auxiliary data files.

B. Combining the responses from the gamer with the appropriate delay times, the program calculates the total reaction time for the change in mission.

C. This program develops the command and control table look-up procedure from the Deep Attack Map Exercise (DAME) model into a computerized process.

3. DATA FLOW.

A. The data flow consists of a menu/response format in which the user answers questions concerning:

(1) Side: 1 = Blue; 2 = Red.

(2) Mission: 1 = Defend
2 = Move
3 = Reserve
4 = Attack.

(3) Transmission of commands:

(a) Issuing echelon: 0 = Battalion/regiment
1 = Brigade/division
2 = Division (Blue only)
3 = Corps/army
4 = Army/front.

(b) Receiving echelon: 1 = Brigade/division
2 = Division (Blue only)
3 = Corps/army.

- (4) Weather conditions: 1 = Moderate
 2 = Severe
 3 = Good.
- (5) Combat condition: 1 = Conventional
 2 = Integrated (chemical/nuclear)
 3 = Conventional and integrated.
- (6) Day/night condition: 1 = Night (1800 to 0600 hours)
 2 = Day.

B. Using the responses input by the user, the program accesses the appropriate delay time array.

C. Figure 8-1 indicates the data flow with the appropriate inputs and outputs.

4. FILE STRUCTURE.

The command and control program data consists solely of eight auxiliary data files which contain the delay time in minutes under various combat and environmental conditions.

A. Combat related delay and effect arrays include: Conv_delay(*), Integ_delay(*), Attrite_eff(*), Inter_eff(*), and Deep_atk_eff(*) .

(1) Conv_delay(M). A 40-dimensional array containing the conventional delay time in minutes. This delay time is dependent upon the side, mission and issuing echelon. For means of simplicity, the array Conv_delay(M) is equivalent in structure to C_d (I,J,K) where:

- I = 1 to 2 sides
 - J = 1 to 4 missions
 - K = 1 to 5 issuing echelon.
- Note: K = 3 is vacant for Red.

(2) Integ_delay(M). A 40-dimensional array containing the integrated delay time in minutes. Indexes are same as above.

(3) Attrite_eff(N). An eight-dimensional array containing the attrition delay time in minutes. This delay time is dependent upon the side and the mission for a Blue battalion or a Red regiment. For means of simplicity, the array Attrite_eff(N) is equivalent in structure to A_e (I,J) where:

- I = 1 to 2 sides
- J = 1 to 4 missions for a Blue battalion or a regiment or a Red regiment.

MAIN DRIVER:

MISSION
ECHELON ISSUING ORDER
RECEIVING ECHELON
BATTLEFIELD MODE
WEATHER CONDITIONS
DAY/NIGHT
ATTRITION
INTERDICTION
DEEP ATTACK

ON-LINE DATA ARRAYS:

CONVENTIONAL DELAY
INTEGRATED DELAY
MODERATE WEATHER EFFECTS
SEVERE WEATHER EFFECTS
NIGHT EFFECTS
ATTRITION EFFECTS
INTERDICTION EFFECTS
DEEP ATTACK EFFECTS

RESULTS
OF HOURS REQUIRED
TO CHANGE TO
NEW MISSION.

CALCULATE TIME
DELAY FOR
COMMAND AND
CONTROL

Figure 8-1. Command and control data flow.

(4) Inter_eff(M). A 40-dimensional array containing the air interdiction delay effects in minutes. This delay is dependent upon the side, mission, and issuing echelon. Refer to (1) above for indices.

(5) Deep_atk_eff(P). A 10-dimensional array containing the deep attack effects (in minutes) for a unit with an attacking mission. For means of simplicity, the array Deep_atk_eff(P) is equivalent in structure to D_e(I,K) where:

I = 1 to 2 sides
K = 1 to 5 issuing echelon.
Note: K = 3 is vacant for Red.

B. Environmental effect arrays include: Mod_weather_eff(*), Sev_weather_eff(*) and Night_eff(*).

(1) Mod_weather_eff(M). A 40-dimensional array containing the delay time, in minutes, due to moderate weather conditions. Refer to A(1) for index descriptions.

(2) Sev_weather_eff(M). A 40-dimensional array containing the delay time, in minutes, due to severe weather conditions. Refer to A(1) for index descriptions.

(3) Night_eff(M). A 40-dimensional array containing the delay time, in minutes, due to nighttime decreases in visibility. Refer to A(1) for index descriptions.

5. ALGORITHMS.

A. The command and control program uses an interactive menu/response format to access the delay times associated with battle mode, weather effects, visibility, attrition, interdiction by air, and deep attack.

B. Once the appropriate delay times have been read into the data arrays, the program uses a simple formula to calculate the total reaction time needed to change from an existing mission to a new mission. Equation 8-1 shows this formula.

$$T = \left[\sum_{i=1}^{he} (B_i + W_i + V_i + D_i) + \sum_{j=1}^{ie} (I_j + A) \right] / 60 \quad (\text{Eq. 8-1})$$

where:

T = total time to react to mission change (hours).
he = number corresponding to the highest echelon involved.

le = number corresponding to the lowest echelon involved.
B_i = delay (minutes) due to battle mode for each echelon involved (i).
W_i = delay (minutes) due to weather conditions for each echelon involved (i).
V_i = delay (minutes) due to day/night for each echelon involved (i).
D_i = delay (minutes) if unit mission is deep attack for each echelon involved (i).
ie = number of interdicted echelons.
I_j = delay (minutes) due to air interdiction for the jth echelon.
A = delay (minutes) due to attrition suffered by the lowest echelon (Blue battalion/Red regiment).

C. Figure 8-2 contains a generalized flow of the command and control program.

6. "UNITFILE" IMPACT.

The command and control program is a stand-alone program, which does not impact directly with the DIME unit status file ("UNITFILE").

7. CODE.

A. The command and control program consists of 15 subroutines performing three major functions: game initialization, data entry, and calculation of total time required to react to a mission change.

(1) Game initialization. The game initialization routines (Start, Defend, Relocate, Reserve, and Attack) establish the initial pointers and data parameters needed to access the appropriate delay time arrays.

(2) Data entry. The data entry routines (Conven, Integ, Both, Moderate, Severe, Night, Attrite, Interdict, Deep_atk) use the pointers and parameters established by the game initialization routes to access the appropriate delay time arrays.

(3) Total time calculation. The total time is a cumulative value resulting from totaling all the delay times read into the program by the data entry routines. The calculation does not occur in any specific routine but is calculated throughout all the data entry routines.

B. Table 8-1 contains a description of the primary variables associated with the subroutines in the command and control program. Table 8-2 contains a listing of the command and control code.




Figure 8-2. Command and control logic flow

Table U-1. Command and control subroutine table.

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
A. Game Initialization.	Start	Establishes initial pointer and data parameters by using gamer inputs. Calls the appropriate data routines. Outputs the total time required to change mission.	a. Side b. Mission	An integer value of 1 or 2, which identifies the force: 1 = Blue 2 = Red An integer value of 1 to 4 which identifies the mission: 1 = Defend 2 = Move 3 = Reserve 4 = Attack
			c. Hi_echelon	An integer value of 0 to 4, which represents the echelon issuing the order: 0 = Battalion/Regiment 1 = Brigade/Division 2 = Division (Blue only) 3 = Corps/Army 4 = Army/Front
			d. Lo_echelon	An integer value of 1 to 3 which represents the echelon receiving the order: 1 = Brigade/Division 2 = Division (Blue only) 3 = Corps/Army
			e. Mode	An integer value of 1 to 3 which represents the battlefield mode: 1 = Conventional 2 = Integrated 3 = Both

Table U-1. Command and control subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
A. Game initialization (concluded)	Start (concluded)		f. Weather	An integer value of 1 to 3 which represents the weather condition: 1 = Moderate 2 = Severe 3 = Good
			g. Phase	An integer value of 1 or 2 which represents the visibility due to time of day: 1 = Night (1800 - 0600 hrs) 2 = Day
			h. Response\$	A character value of "Y" or "N" which indicates if the unit has suffered attrition
			i. Answer\$	A character value of "Y" or "N" which indicates if the unit has suffered air interdiction
			j. Anser\$	A character value of "Y" or "N" which indicates if the unit's mission is a deep attack
			k. Hours	A real value which contains the total reaction time in hours
			l. Respond\$	An integer value of "Y" or "N" which indicates if any other mission change times need to be calculated "Y" = Repeat program "N" = Return to DIME Menu

Table B-1. Command and control subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
B. Access data files; calculate total time required to change mission.	Conven; Integ; Both; Moderate; Severe; Night; Attrite; Interdict; Deep_atk	Reads in appropriate delay times from data arrays. Calculates delay times based on data and gamer inputs.	a. Conv_delay(*) b. Integ_delay(*)	A 1 x 40 array containing the delay time, in minutes, due to a conventional battle A 1 x 40 array containing the delay time, in minutes, due to an integrated battle
			c. Mod_weather_eff	A 1 x 40 array containing the delay time, in minutes, due to moderate weather effects
			d. Sev_weather_eff	A 1 x 40 array containing the delay time, in minutes, due to severe weather effects
			e. Night_eff(*)	A 1 x 40 array containing the delay time, in minutes, due to night conditions
			f. Attrite_eff(*)	A 1 x 8 array containing the delay time, in minutes, due to attrition suffered by a Battalion or Regiment
			g. Percent	A 2-digit, integer number which represents the percent of the unit suffering attrition
			h. Amount	A real value indicating the percent of a unit suffering attrition
			i. Inter_eff(*)	A 1 x 40 array containing the delay time, in minutes, due to air interdiction

Table B-1. Command and control subroutine table (concluded).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
B. Access data files; calculate total time required to change mission (concluded).	Conven; Integ; Both; Moderate; Severe; Night; Attrite; Interdict; Deep_atk (concluded)		j. Inter_ech	An Integer value of 0 to 4 which indicates the echelon suffering air interdiction
			k. Deep_atk_eff(*)	A 1 x 10 array containing the delay time, in minutes, due to a deep attack

Table 8-2. Command and control code.

```

110 REM-"P10" IS THE COMMAND & CONTROL DELAY TIME CALCULATOR PROGRAM FOR DIMI
;
20 !CODED BY MAJ A. RESNICK, FDAD, SAD, CADRA, AVN 552-5481/3595.
30 !THE PROGRAM WAS LAST CHANGED ON 23 MAY 1983.
40 !
50 !
60 !
70 OPTION BASE 1
80 DIM Conv_delay(40),Integ_delay(40),Mod_weather_eff(40),Sev_weather_eff(40
,Night_eff(40),Inter_eff(40),Deep_atk_eff(10),Dataline(18),Attrite_eff(8)
90 !
100 Datdrive$=":HP9121,700,0"
110 Start:PRINT USING "@,#"
120 PRINT "THIS PROGRAM CALCULATES THE STAFF & COMMANDER REACTION TIME"
130 INPUT "WHICH SIDE? (1=BLUE 2=RED)",Side
140 IF Side<>1 AND Side<>2 THEN Start
150 IF Side=1 THEN Start_point=1
160 IF Side=2 THEN Start_point=21
170 Delay=0
180 PRINT USING "@"
190 PRINT "WHAT IS THE ASSIGNED MISSION?"
200 PRINT " 1 = DEFEND"
210 PRINT " 2 = MOVE"
220 PRINT " 3 = RESERVE"
230 PRINT " 4 = ATTACK"
240 INPUT "ENTER ASSIGNED MISSION:",Mission
250 IF Mission<>1 AND Mission<>2 AND Mission<>3 AND Mission<>4 THEN 190
260 ON Mission GOTO Defend,Relocate,Reserve,Attack
270 Defend:Pointer=Start_point
280 GOTO 340
290 Relocate:Pointer=Start_point+5
300 GOTO 340
310 Reserve:Pointer=Start_point+10
320 GOTO 340
330 Attack:Pointer=Start_point+15
340 PRINT USING "@"
350 PRINT "WHAT IS HIGHEST ECHELON ISSUING ORDER?"
360 PRINT "0 = BATTALION/REGIMENT (BLUE/RED)"
370 PRINT "1 = BRIGADE/DIVISION"
380 PRINT "2 = DIVISION (BLUE ONLY)"
390 PRINT "3 = CORPS/ARMY"
400 PRINT "4 = ARMY/FRONT"
410 INPUT "ENTER HIGHEST ECHELON:",Hi_echelon
420 IF Hi_echelon<>0 AND Hi_echelon<>1 AND Hi_echelon<>2 AND Hi_echelon<>3 AND
Hi_echelon<>4 THEN 350
430 PRINT USING "@"
440 PRINT "IS THE RECEIVING ECHELON A BATTALION/REGIMENT?"
450 PRINT "Y = YES N = NO"
460 INPUT "ENTER RESPONSE:",Answer$
470 IF Answer$<>"Y" AND Answer$<>"N" THEN 440
480 IF Answer$="N" THEN
490 PRINT USING "@"

```

Table 8-2. Command and control code (continued).

```

500     PRINT "WHAT LEVEL IS RECEIVING THE ORDER?"
510     PRINT "1 = BRIGADE/DIVISION"
520     PRINT "2 = DIVISION (BLUE ONLY)"
530     PRINT "3 = CORPS/ARMY"
540     INPUT "ENTER RECEIVING ECHELON:",Lo_echelon
550     IF Lo_echelon<>1 AND Lo_echelon<>2 AND Lo_echelon<>3 THEN 500
560     ELSE
570         Lo_echelon=0
580     END IF
590 !
600     ASSIGN @Cc_file TO "CMD_CNTRL"&Datdrive$
610     ASSIGN @Cc_file2 TO "CC_EFF"&Datdrive$
620     ENTER @Cc_file2,1;Dataline(*)
630     ASSIGN @Cc_file2 TO *
640     FOR I=1 TO 8
650         Attrib_eff(I)=Dataline(I)
660     NEXT I
670     FOR I=1 TO 10
680         Deep_atk_eff(I)=Dataline(I+8)
690     NEXT I
700 !
710     PRINT USING "@"
720     PRINT "WHAT IS BATTLEFIELD MODE?"
730     PRINT "1=CONVENTIONAL  2=INTEGRATED  3=BOTH"
740     INPUT "ENTER MODE:",Mode
750     IF Mode<>1 AND Mode<>2 AND Mode<>3 THEN 720
760     ON Mode GOSUB Conven,Integ,Both
770     PRINT USING "@"
780     PRINT "WHAT ARE WEATHER CONDITIONS?"
790     PRINT "1=MODERATE  2=SEVERE  3=GOOD"
800     INPUT "ENTER WEATHER CONDITIONS:",Weather
810     IF Weather<>1 AND Weather<>2 AND Weather<>3 THEN 780
820     ON Weather GOSUB Moderate,Severe,Good
830     PRINT USING "@"
840     PRINT "IS IT DAY OR NIGHT?"
850     PRINT "1=NIGHT (2100 TO 0600 HRS)  2=DAY"
860     INPUT "PHASE OF DAY:",Phase
870     IF Phase<>1 AND Phase<>2 THEN 840
880     IF Phase=1 THEN GOSUB Night
890     PRINT USING "@"
900     PRINT "HAS THIS BATTALION/REGIMENT BEEN ATTRITED?"
910     PRINT "Y = YES  N = NO"
920     INPUT "ENTER RESPONSE:",Response$
930     IF Response$<>"Y" AND Response$<>"N" THEN 900
940     IF Response$="Y" THEN GOSUB Attrite
950     PRINT USING "@"
960     PRINT "HAS ANY ECHELON BEEN INTERDICTED BY AIR?"
970     PRINT "Y = YES  N = NO"
980     INPUT "ENTER ANSWER:",Answer$
990     IF Answer$<>"Y" AND Answer$<>"N" THEN 960
1000    IF Answer$="Y" THEN GOSUB Interdict
1010    PRINT USING "@"

```

Table 8-2. Command and control code (continued).

```

1020 PRINT "IS THIS A DEEP ATTACK?"
1030 PRINT "Y = YES          N = NO"
1040 INPUT "ENTER RESPONSE:",Anser$
1050 IF Anser$<>"Y" AND Anser$<>"N" THEN 1020
1060 IF Anser$="Y" THEN GOSUB Deep_atk
1070 Hours=Delay/60.
1080 PRINT USING "@"
1090 PRINT "TIME DELAY IMPOSED FOR COMMAND AND"
1100 PRINT "CONTROL PROCESSING IS ",Hours,"HOURS"
1110 PRINT USING "//////"
1120 PRINT "PRESS CONT TO PROCEED"
1130 PAUSE
1140 PRINT USING "@"
1150 PRINT "IS THERE ANY FURTHER PROCESSING REQUIRED?"
1160 PRINT "Y = YES          N = NO"
1170 INPUT "ENTER RESPONSE:",Respond$
1180 IF Respond$<>"Y" AND Respond$<>"N" THEN 1150
1190 IF Respond$="Y" THEN Start
1200 ! LOAD "DIME"
1210 GOTO Halt
1220 !
1230 !
1240 !
1250 Conven: !CONVENTIONAL MODE
1260 ENTER @Cc_file,1;Conv_delay(*)
1270 FOR I=Pointer+Lo_echelon TO Pointer+Hi_echelon
1280   Delay=Delay+Conv_delay(I)
1290 NEXT I
1300 RETURN
1310 !
1320 Integ: !INTEGRATED MODE
1330 ENTER @Cc_file,2;Integ_delay(*)
1340 FOR I=Pointer+Lo_echelon TO Pointer+Hi_echelon
1350   Delay=Delay+Integ_delay(I)
1360 NEXT I
1370 RETURN
1380 !
1390 Both: !COMBINED CONVENTIONAL & INTEGRATED
1400 PRINT USING "@"
1410 PRINT "FOR COMBINED CONVENTIONAL & INTEGRATED MODE:"
1420 PRINT "WHAT IS LOWEST INTEGRATED ECHELON?"
1430 PRINT "0 = BATTALION/REGIMENT"
1440 PRINT "1 = BRIGADE/DIVISION"
1450 PRINT "2 = DIVISION (BLUE ONLY)"
1460 PRINT "3 = CORPS/ARMY"
1470 PRINT "4 = ARMY/FRONT"
1480 INPUT "ENTER LOWEST INTEGRATED ECHELON:",Lo_integ_ech
1490 IF Lo_integ_ech<>0 AND Lo_integ_ech<>1 AND Lo_integ_ech<>2 AND Lo_integ_e
h<>3 AND Lo_integ_ech<>4 THEN 1420
1500 !COMPUTES DELAY TIME FOR CONVEN & INTEG SEPARATELY
1510 Hi_echelon_tem=Hi_echelon
1520 Hi_echelon=Lo_integ_ech-1

```

Table 8-2. Command and control code (continued).

```

1530 GOSUB Conven
1540 Hi_echelon=Hi_echelon_tem
1550 Lo_echelon_tem=Lo_echelon
1560 Lo_echelon=Lo_integ_ech
1570 GOSUB Integ
1580 Lo_echelon=Lo_echelon_tem
1590 RETURN
1600 !
1610 Moderate: !MODERATE WEATHER EFFECTS
1620 ENTER @Cc_file,3;Mod_weather_eff(*)
1630 FOR J=Pointer+Lo_echelon TO Pointer+Hi_echelon
1640   Delay=Delay+Mod_weather_eff(J)
1650 NEXT J
1660 RETURN
1670 !
1680 Severe: !SEVERE WEATHER EFFECTS
1690 ENTER @Cc_file,4;Sev_weather_eff(*)
1700 FOR J=Pointer+Lo_echelon TO Pointer+Hi_echelon
1710   Delay=Delay+Sev_weather_eff(J)
1720 NEXT J
1730 RETURN
1740 !
1750 Good: !THERE ARE NO EFFECTS FOR GOOD WEATHER
1760 RETURN
1770 !
1780 Night: !
1790 ENTER @Cc_file,5;Night_eff(*)
1800 FOR K=Pointer+Lo_echelon TO Pointer+Hi_echelon
1810   Delay=Delay+Night_eff(K)
1820 NEXT K
1830 RETURN
1840 !
1850 Attrite: !
1860 PRINT USING "@ "
1870 INPUT "ENTER PERCENT OF UNIT ATTRITED (AS 2-DIGIT NO.):",Percent
1880 Amount=Percent/10
1890 IF Side=2 THEN
1900   Factor=Mission+4
1910 ELSE
1920   Factor=Mission
1930 END IF
1940 IF Lo_echelon=0 THEN
1950   Attrition=Attrite_eff(Factor)*Amount
1960 ELSE
1970   Attrition=0
1980 END IF
1990 Delay=Delay+Attrition
2000 RETURN
2010 !
2020 Interdict: !ADDS TIME FOR INTERDICTED MODES
2030 ENTER @Cc_file,6;Inter_eff(*)
2040 PRINT USING "@ "

```

Table 8-2. Command and control code (concluded).

```
2050 Again:PRINT "WHICH ECHELON IS INTERDICTED?"
2060 PRINT "0 = BATTALION/REGIMENT"
2070 PRINT "1 = BRIGADE/DIVISION"
2080 PRINT "2 = DIVISION (BLUE ONLY)"
2090 PRINT "3 = CORPS/ARMY"
2100 PRINT "4 = ARMY/FRONT"
2110 INPUT "ENTER INTERDICTED ECHELON:",Inter_ech
2120 IF Inter_ech<>0 AND Inter_ech<>1 AND Inter_ech<>2 AND Inter_ech<>3 AND Int
er_ech<>4 THEN 2050
2130 Delay=Delay+Inter_eff(Pointer+Inter_ech)
2140 PRINT USING "@"
2150 INPUT "ARE THERE ANY OTHER ECHELONS INTERDICTED? (Y OR N)",Q$
2160 IF Q$<>"Y" AND Q$<>"N" THEN 2140
2170 IF Q$="Y" THEN GOTO Again
2180 RETURN
2190 !
2200 Deep_atk:~
2210 FOR K=Lo_echelon+1 TO Hi_echelon+1
2220   Delay=Delay+Deep_atk_eff(K)
2230 NEXT K
2240 RETURN
2250 !
2260 Halt:ASSIGN @Cc_file TO *
2270 LOAD "DIME:HF9134,701"
2280 END
2290 !FINIS CORONAT OFUM
```

CHAPTER 9

MOVEMENT GENERATOR¹

1. PURPOSE.

The purpose of the DIME movement generator (P9) is to provide a deterministic method for calculating troop and cargo movement capabilities and timelines.

2. GENERAL.

The DIME movement program portrays two movement phases: troop movement and cargo transport.

A. Troops move as either dismounted or mounted during the ground movement phase.

(1) The user decides whether troop movement is dismounted or mounted and the number of resting periods the unit shall receive.

(2) A movement rate value is used by the troop movement phase to determine the total time needed to complete a march along a predetermined route of specified length.

B. Cargo transport is modeled in phase two of the movement program. Cargo may be moved by two helicopters, the CH47D and the UH60A.

(1) The cargo transport phase loads the helicopters by a simplistic loading routine which gives first priority to transporting troops, second priority to loading helicopter slings, and third priority to loading the interior of the helicopter.

(2) The cargo transport module uses gamer inputs to access data on the transportability, rate of movement, and fuel use needed to transport cargo by the helicopters.

(3) Once the appropriate data has been accessed, the cargo transport phase calculates the amount of cargo and the time necessary to transport that cargo along the route(s) indicated by the gamer.

¹ This chapter describes the original DIME program before it was changed by ADEA in Ft. Lewis, WA. It has been retained to demonstrate the methodology and structure. The original code is listed in Table 9-3. The code developed by ADEA is listed in Table 9-3a.

C. In either phase, a summary report is generated following the reaching of a final destination by all movement types.

3. DATA FLOW.

The DIME movement program requires a separate data flow for the troop movement phase and the cargo transport phase.

A. The troop movement phase uses two auxiliary data files: mounted movement rates and dismounted movement rates.

(1) The movement rates are for ground forces moving under noncombat conditions. The rates are expressed in km/hr as a function of five geographic area and eight traveling conditions. For a detailed discussion of the troop movement data files, refer to paragraph 4 of this chapter.

(2) The user accesses the appropriate movement rates through a question/answer format. The following inputs must be entered to establish the parameters necessary to access the correct file.

(a) Force: 1 = Blue; 2 = Red.

(b) Pace: 1 = Normal day
2 = Forced day
3 = Normal night
4 = Forced night.

(c) March: MH = Hours to march
RH = Hours to rest.

(d) Start time: The time for start of movement.

(e) Column length: NP = Number of persons in longest column
NV = Number of vehicles in longest column.

(f) Tankers: The number of tankers available.

(g) Distance of leg: 1 = Flat road/trail
2 = Hilly road/trail
3 = Cross country flat
4 = Cross country hilly
5 = Cross country mountainous.

(3) The troop movement phase combines the movement rates with the methodology discussed in paragraph 5 to determine the total time needed to move a march column over a specified route. See Figure 9-1 for a generalized data flow of the troop movement phase.




Figure 9-1. Troop movement data flow.

B. The cargo transport phase accesses three sets of data files which provide information on the transportability, rate of movement, and fuel usage needed to transport cargo from one destination to another by the UH60A and the CH47D helicopters. The file structure for these three files will be discussed in paragraph 4 of this chapter.

(1) The cargo transport files, similar to the troop movement files, are accessed through gamer inputs. The following inputs must be supplied by the gamer.

(a) Force: 1 = Blue; 2 = Red.

(b) Start time: The time in hours and minutes for start of mission.

(c) Air temperature: 1 = -10° C
2 = 0° C
3 = 10° C
4 = 20° C
5 = 30° C
6 = 40° C.

(d) Pressure density altitude: 1 = sea level
2 = 2,000 ft
3 = 4,000 ft
4 = 6,000 ft
5 = 8,000 ft
6 = 10,000 ft.

(e) Number of troops to move, including hand-carried weapons and crew members.

(f) Helicopter data:

1. Number of helicopters available for both the CH47D and the UH60A.

2. Loading profile; whether interior and sling or interior only.

3. Refueling status; whether full tanks or one-hour fuel and reserves.

4. CH47D usage only (yes/no).

(g) Routes of travel. Distance in miles along designated routes. Figure 9-2 indicates the seven legs of the route the helicopters may travel.

- Leg 1 = Distance from CH47D origin point to load zone.
- Leg 2 = Distance from UH60A origin point to load zone.
- Leg 3 = Distance from load zone to drop zone.
- Leg 4 = Distance from load zone to refuel point.
- Leg 5 = Distance from drop zone to refuel point.
- Leg 6 = Distance from drop zone to CH47D destination.
- Leg 7 = Distance from drop zone to UH60A destination.

(h) Cargo data includes a cargo number identifier (element number) and the number of cargo elements to move.

(2) The cargo transport phase combines the transportability, rate of movement, and fuel use data files with the methodology discussed in paragraph 5 to determine the amount of cargo and the time needed to transport that cargo along the predetermined route(s). See Figure 9-3 for a generalized data flow of the cargo transport phase.

4. FILE STRUCTURE.

The movement program portrays two movement phases (ground and cargo) with each phase having unique data files.

A. Ground movement of troops uses mounted and dismounted movement rates.

(1) The mounted movement rates file structure consists of an 8x5 file with the following records and indexes:

(a) Record 1 contains the movement rates for the five geographic areas when a Blue force is traveling at a normal march pace during the day. This record is composed of the following five indexes:

1. Index 1 contains the movement rate for ground troops traveling on an open road or trail.

2. Index 2 contains the movement rate for ground troops traveling on a hilly road or trail.

3. Index 3 contains the movement rate for ground troops traveling in open cross country.




Figure 9-2. Conceptual map of routes to fly.




Figure 9-3. Cargo transport data flow.

4. Index 4 contains the movement rate for ground troops traveling in hilly cross country.

5. Index 5 contains the movement rate for ground troops traveling in mountainous cross country.

(b) Record 2 contains the movement rates for the five geographic areas when a Blue force is traveling at forced march pace during the day.

(c) Record 3 contains the movement rates for the five geographic areas when a Blue force is traveling at a normal march pace during the night.

(d) Record 4 contains the movement rates for the five geographic areas when a Blue force is traveling at a forced march pace during the night.

(e) Record 5 contains the movement rates for the five geographic areas when a Red force is traveling at normal march pace during the day.

(f) Record 6 contains the movement rates for the five geographic areas when a Red force is traveling at forced march pace during the day.

(g) Record 7 contains the movement rates for the five geographic areas when a Red force is traveling at normal march pace during the night.

(h) Record 8 contains the movement rates for the five geographic areas when a Red force is traveling at forced march pace during the night.

(2) The dismounted movement rate file is in the same format as the mounted movement rate file previously discussed.

B. The cargo transport module uses three auxiliary files: Copter(*), Cargo(*) and Fuelarray(*) .

(1) Copter(*). The Copter(I,J,K) array contains information about the two helicopters used within the cargo transport phase. The array is created interactively by the running of the cargo transport phase and is based on the helicopter's maximum lift weight, maximum fuel capacity, cruising and hovering speed, and time needed to refuel and load cargo. The copter array is dimensioned (2,10,10) and has indexes as follows:

(a) Index I identifies the helicopter being used this mission (1 = CH47D, 2 = UH60A). The cargo movement module allows the user to fly 10 helicopters of each type.

(b) Index J identifies which of the 10 helicopters of the type indicated by index I are being used during this mission. For example, if the third helicopter in the CH47D group were being employed, then the first and second subscripts of Copter(*) would have the values Copter(1,3,K).

(c) Index K contains the following:

<u>K</u>	<u>Description</u>
1	Vacant
2	Weight allowable for transporting of cargo.
3	Weight of crew + fuel reserve + fuel load.
4	Total allowable weight for the helicopter.
5	Vacant
6	Total cargo space, in inches, available on the helicopter: CH47D = 366 inches; UH60A = 151 inches.
7	Total cargo space, in inches, taken up within the helicopter.
8	Current amount of fuel on board the helicopter.
9	Vacant
10	Current weight of helicopter with crew + fuel reserve + fuel load + cargo + weight of the helicopter.

(2) Cargo(*). The Cargo (I,J) array contains information about the cargo being transported by the helicopters within the cargo transport phase and is dimensioned (71,9).

(a) Index I contains the type of cargo, identifiable by its location on the weapons list, which is to be moved by the helicopters. Items 1-70 are equivalent to those listed on the unit status file as the weapons list. Item 71 was added to provide the transporting of strictly personnel.

(b) Index J contains the description of indexes as follows:

<u>J</u>	<u>Description</u>
1	The total number of each item that is being carried by the helicopter.
2	An integer value of 1, 2, or 3 that indicates which helicopter is being used to transport cargo. 1 = CH47D; 2 = UH60A; 3 = Either.
3	Weight of cargo item.

- 4 Vacant
- 5 Either a 2 digit or 4 digit number that describes how an item may be carried by a given helicopter.

If item is only transportable by one helicopter (xy).

x = Helicopter used
y = How item may be transported.
1 = Sling only
2 = Sling or interior.
3 = Interior only.

If an item may be transported by both helicopters (wxyz).

w = helicopter one.
x = how item may be transported.
y = helicopter two.
z = how item may be transported

- 6-8 Vacant
- 9 Cargo space required for transporting of item by helicopter.

(3) Fuelarray(*). The fuel use file contains the fuel needed to transport cargo of a specified weight over a predetermined route. The fuel use file is a function of helicopter type I, altitude J, temperature K, flying speed L, and weight class M:

I = 1 = CH47D
2 = UH60A.

J = 1 = sea level
2 = 2,000 ft
3 = 4,000 ft
4 = 6,000 ft
5 = 8,000 ft
6 = 10,000 ft.

K = 1 = -10° C
2 = 0° C
3 = 10° C
4 = 20° C.
5 = 30° C.
6 = 40° C.

L = 1 = 40 knots
2 = 60 knots
3 = 80 knots
4 = 100 knots
5 = 120 knots

6 = 140 knots
7 = 160 knots.

M = Weight class for CH47D
1 = 22,000 to 26,000 lbs
2 = 26,000 to 30,000 lbs
3 = 30,000 to 34,000 lbs
4 = 34,000 to 38,000 lbs
5 = 38,000 to 42,000 lbs
6 = 42,000 to 46,000 lbs
7 = 46,000 to 50,000 lbs

Weight class for UH60A
1 = 10,000 to 12,000 lbs
2 = 12,000 to 14,000 lbs
3 = 14,000 to 16,000 lbs
4 = 16,000 to 18,000 lbs
5 = 18,000 to 20,500 lbs

5. ALGORITHMS.

The DIME movement program portrays two movement phases with each having unique algorithms. The two sections consist of ground troop movement and cargo transport by helicopters.

A. The troop movement section depicts dismounted and mounted troop movement.

(1) Mounted. The mounted troop movement routine requires the execution of six formulas in order to calculate the total time required to move mounted troops.

(a) Time required to refuel a column of tankers.

$$\text{Trf} = (\text{Pr} / \text{Tkrs} / 4) * 8 \quad (\text{Eq. 9-1})$$

where:

Pr = length of a march column.

Tkrs = number of tankers available.

Trf = time required to refuel a column of tankers in hours.

Constants = time required for one tanker to discharge fuel.

(b) Time spent resting (Tr).

$$\text{Tr} = \sum_{i=1}^{n1} \left(\left[\frac{\text{Dd}_i}{\text{Vdtr}} / \text{Mp} \right]_I + \left[\frac{\text{Dr}_i}{\text{Vntr}} / \text{Mp} \right]_I \right) * \text{Rp} \quad (\text{Eq. 9-2})$$

Tr = time spent resting, in hours.

n1 = number of legs.

Dd_i = distance of leg i that may be moved under daylight conditions.

Dn_i = distance of leg i that may be moved under night conditions.

Vdtr = velocity possible under day conditions through the current terrain type.
 Vntr = Velocity possible under night conditions through the current terrain type.
 Mp = march period; march cycle time in hours.
 Rp = rest period, in hours.

(c) Time for refueling the force.

$$\text{Trff} = \left[\frac{\sum_{i=1}^{n1} (Dd_i + Dn_i)}{\text{Drf}} \right] * \text{Trf} \quad (\text{Eq. 9-3})$$

where:

Trff = total time for refueling the force, in hours.
 Drf = distance between refueling points.
 Trf = total time required to refuel the column, in hours.

(d) Closure time for mounted troops (Mclose), in hours.

$$\text{Mclose} = \text{Pr}/180 \quad (\text{Eq. 9-4})$$

where:

Pr = length of a march column.
 180 = factor necessary for closure of mounted troops.

(e) Total time required for mounted troops to complete a march along a predetermined route (Tmtime).

$$\text{Tmtime} = \left[\sum_{i=1}^{n1} \left(\frac{Dd_i}{Vdtr} + \frac{Dn_i}{Vntr} \right) \right] + \text{Max} (\text{Tr}, \text{Trff}) + \text{Mclose} \quad (\text{Eq. 9-5})$$

(2) Dismounted. The dismounted troop movement routine uses equations 9-2 and 9-3 without any modifications. In addition, the dismounted routine requires that two other formulas be executed in order to

calculate the total time required to move dismantled troops over a predetermined route.

(a) Closure time for dismantled troops (D_{close}), in hours.

$$D_{close} = Pr/360 \quad (Eq. 9-6)$$

where:

Pr = length of a column.
360 = factor necessary for closure of dismantled troops.

(b) Total time required for movement of dismantled troops along a predetermined route (T_{dtime}).

$$T_{dtime} = \left[\sum_{i=1}^{n1} \left(\frac{Dd_i}{Vdtr} + \frac{Dn_i}{Vntr} \right) \right] + Tr + D_{close} \quad (Eq. 9-7)$$

B. The cargo movement section consists of formulas which schedule, screen, load, move, and unload cargo.

(1) Fuel usage for leg 1 of the route. This route is the distance between the load zone and the refueling point.

$$Fuel1 = Routel * Fuelarray/Flightsped \quad (Eq. 9-8)$$

where:

$Fuel1$ = fuel needed for leg 1 of the route.
 $Routel$ = distance in kilometers for the first leg of the route; the distance between the load zone and the refuel point.
 $Fuelarray$ = fuel required to transport the cargo given the helicopter type, altitude, temperature, speed and weight class.
 $Flightsped$ = flight speed.

(2) Fuel usage for leg 2 of the route. This route is the distance between the refueling point and the drop zone.

$$\text{Fuel2} = \text{Route2} * \text{Fuelarray}/\text{Flightspd} \quad (\text{Eq. 9-9})$$

where:

Fuel2 = fuel needed for leg 2 of the route.
Route2 = distance in kilometers for the second leg of the route; the distance between the refueling point and the drop zone.

(3) Fuel needed is the total fuel for both legs (Fuelneed).

$$\text{Fuelneed} = \text{Fuel1} + \text{Fuel2} \quad (\text{Eq. 9-10})$$

(4) The maximum weight of cargo which is transportable by each helicopter is calculated as follows:

$$\text{Mwc}_i = \text{Wta}_i - \text{Wcfrfl}_{ci} \quad (\text{Eq. 9-11})$$

where:

Mwc_i = maximum weight of cargo transportable by the helicopter
where: i = 1 is the CH47D and i = 2 is the UH60A.
Wta_i = the total allowable weight for helicopter i.
Wcfrfl_{ci} = weight of helicopter i + crew + fuel reserve + fuel load + cargo.

(5) Before any item is loaded, the earliest time the event may occur is calculated as:

$$\text{Facilitime} = \text{MAX} (\text{Load_area}, \text{Fac_freed}) \quad (\text{Eq. 9-12})$$

where:

Facilitime = the earliest time the loading of items may occur.
Load_area = the earliest the helicopter can arrive at the loading area.
Fac_freed = the time the load area was last freed for use.

6. "UNITFILE" IMPACT.

The movement program does not impact directly with the "UNITFILE". It is a stand-alone program.

7. CODE.

The DIME movement program consists of a driver and two major phases: troop movement and cargo transport. The driver allows selection of one of the two phases.

A. The troop movement phase depicts dismounted and mounted troop movement.

(1) Both the mounted and dismounted routines follow the same general flow through the code. Figure 9-4 shows this flow.

(2) The program begins by asking the user to indicate whether the ground movement is mounted or dismounted.

(3) Based on the response to the user inputs, the program reads in the appropriate movement rates from an auxiliary data file.

(4) After the proper data is accessed, the program solicits additional information from the gamer concerning the force, march pace, rest periods, column length, and number of tankers available for this march.

(5) At this point, the program combines the movement rates, the gamer responses, and the appropriate formulas to produce the total time required for the movement of troops along the predetermined route.

(6) The mounted and dismounted movement routines produce a printed summary of the total time and the time for closure.

B. The cargo transport phase algorithms consist of routines and formulas which: set up the initial data, establish an event file, schedule, screen, load, move, and unload cargo. See Figure 9-5 for a generalized flow diagram of the cargo transport phase.

(1) Initial setup. The initial setup of the cargo transport phase requires the calling of six subroutines: Datain, Map, Catset, Speedscren, Xfuelcheck, Wtallowed.

(a) Datain is the main data input subroutine. It utilizes the Map, Catset, Speedscren, and Wtallowed routines to check input and set initial parameters. Datain uses a menu procedure for data entry. The operator responses are used to access, build, and load the appropriate data into the Cargo(*), Maxflow(*), and Copter(*) arrays.




Figure 9-4 General flow of troop movement phase.





Figure 9-5. General flow of helicopter cargo movement phase.

1. Map. The Map routine provides the operator with a conceptual map of the seven legs of the route. Figure 9-2 shows this map.

2. Catset. The Catset routine converts the temperature and altitude, input by the operator, into the appropriate temperature and altitude categories.

3. Speedscren. The Speedscren routine checks flight speed fuel usage for two legs within the route and speed/weight restrictions to determine if a specified helicopter can transport the indicated cargo.

a. Speed/weight restrictions. The Speedscren routine checks to see if the flight speed, indicated by the operator, will allow for sufficient fuel to complete the movement of the cargo. The helicopter must be able to go to the load zone from the refuel point, then to the drop zone loaded, and finally to the refuel point empty, or the helicopter must be able to go from the refuel point to the load point empty, then to the refuel point loaded, refuel, then go to the drop zone loaded, and finally back to the refuel point unloaded.

b. If either of the speed/weight restrictions are true, then the Speedscren routine calculates the total allowable weight for each helicopter. The weight in pounds allowable for the CH47D is 4000* weight class + 22000. The weight allowable for the UH60A is 2000* weight class + 10,000.

4. Wtallowed. The Wtallowed routine determines the maximum weight of cargo which is transportable by each helicopter.

(b) Once the three data arrays (Maxflow(*), Cargo(*), Copter(*)) have been established, Datin returns control to the driver.

(c) The driver, in turn, calls the Initl routine to place an event on the schedule array which indicates the helicopters have moved from their place of origin to the loading area.

1. Prior to placing this event onto the schedule array, the Initl routine calls the Dfuelcheck routine to ensure the helicopters have the needed fuel. In addition, the Dfuelcheck routine determines the total time which will be required for the helicopters to move between the point of origin and the loading area. This time will serve as a lease time for the next scheduled event, since one event may not start until the first event has been completed.

a. The Dfuelcheck routine uses the same formula as the Xfuelcheck routine to determine the fuel needed. The Dfuelcheck routine returns the total fuel needed to travel over two legs of the route, as does the Xfuelcheck routine. In addition, the Dfuelcheck routine sets an internal flag (Xstatus) if the fuel needed is greater than the fuel available.

b. Once the fuel needed is determined, the Dfuelcheck routine calculates the total time required to travel over two legs of a route.

2. The Init1 routine uses the total time calculated by the Dfuelcheck routine to build the event array, Schedule(*). The Schedule (I,J) array has dimensions of (100,3) where each I represents a different event and each J is as follows:

<u>J</u>	<u>Description</u>
1	The helicopter type (1 - UH60A, 2 - CH47D) for event I.
2	The mission (1 - load, 3 - drop) assigned to the helicopter for event I.
3	The earliest time the event I may occur.

3. The fuel used to move from the point of origin to the load area is subtracted from the helicopter's available fuel. This updated value is replaced in the Copter(*) array.

(d) The arrival of the helicopters to the loading area indicates the end of the initial setup phase.

(2) Cargo transport. The cargo transport phase includes methodology and formulas which screen, schedule, load, move, and unload cargo between two points.

(a) Screen. The Cargoscren routine is called to determine if the cargo contained within the Cargo array is transportable by the designated helicopter. The Cargoscren routine accesses the Cargo array and searches for any cargo item which may exceed the maximum weight lift capacity of the helicopter. If the cargo exceeds the weight lift capacity, it is removed from the Cargo array. The Cargoscren routine performs a second search of the Cargo array to determine if a cargo item must be moved by an attached sling. If so, it checks to see if a sling has been placed on the copter. If a sling has not been attached to the helicopter, then the Cargoscren routine removes the sling-only cargo from the Cargo array.

(b) Schedule. The Scheduler routine is called to determine the next event on the Schedule(*) array. The Schedule(*) array, established by the initial setup phase, is searched to determine the event with the earliest time. The main driver uses the mission to call the Loader or the Drop routine for this event.

(c) Load. Provided the mission indicated by the Scheduler routine for the next scheduled event is to load cargo, the main driver calls the Loader routine.

1. The Loader routine will access the Cargo(*) array and assign the items to the helicopter to be transported to the drop zone.

2. However, before any item is loaded, the Loader routine sets the earliest time the event may occur and reinitializes the Schedule(*) array to zero for this event.

3. In addition, the Cargo(*) array is searched for any restrictions which would require the cargo be transported by the larger CH47D helicopter. The Loader routine calls the Chneed routine to determine if the cargo is restricted. The Chneed routine checks the cargo items for excessive weight and then checks the Copter(*) array for environmental conditions which might limit the weight allowable. If the restriction is valid, the Chneed routine sets a flag and returns control to the Loader routine.

4. Using the flag set by the Chneed routine, the Loader routine passes control in one of two directions.

a. If the flag indicates the cargo must be transported by the CH47D, then the helicopter type, for this event, is checked. Provided the helicopter type is for the CH47D, the cargo is loaded. Otherwise, the Coptdone routine is called. The cargo remaining to be loaded must be transported by a CH47D helicopter.

b. If the flag indicates the cargo has no helicopter- type restriction, then the cargo is loaded.

5. The Loader routine loads the cargo in a simplistic method of troops first, slingable items next, and items which must be loaded inside the helicopter last.

a. Thirty-three infantry personnel may be loaded on a CH47D helicopter, while only 11 will fit inside the UH60A. However, the actual number of personnel loaded during any trip may vary. The module assigns each person a weight of 250 pounds. This weight is then multiplied by the number awaiting transport to produce a total weight for all the troops awaiting transport. If this total weight is less than the maximum allowable weight for the helicopter, then all the troops are loaded. Otherwise, the number of personnel which can be loaded is the integer value of the maximum allowable weight divided by 250 lbs. If no troops can be moved, then the module outputs a message to the terminal and stops. Otherwise, each helicopter, of the type indicated, is loaded with troops until no helicopters remain or until no infantry personnel remain. When the troop loading is completed, the sling loads are considered next.

b. Slingable items are loaded in two passes: items which must be transported by sling and items which can be transported by sling or

inside the cargo bay. Sling loading is strictly by weight allowance remaining on each helicopter. While there are limitations on the number of slings that each helicopter can employ, the data base as it currently exists ensures the cargo weights preclude violation of these limitations.

c. Following the loading of troops and slings, the interior of the helicopter is loaded. The cargo list is searched for items whose weight and space requirements allow it to be placed inside the helicopter type requested. If there is sufficient weight allowance remaining and the cargo bay has space, then the cargo list is decremented by one for that item. This procedure is repeated until all helicopters, of the type specified, have been used or until all cargo has been loaded.

6. If any item was loaded, a fixed time of 0.25 hours is added to the elapsed time counter to reflect loading time. This time is added to the previously set Facilitime value to reflect the earliest time the facility will be free for the next loading event to occur.

(d) Move. The Uhaul routine is called by the Loader and the Drop routines to calculate the actual movement along the specified routes of travel.

1. Irrespective of which routine calls it, Uhaul checks to see that sufficient fuel exists to travel to the drop area (loaded) and then to the refuel area (unloaded) by calling the Xfuelcheck routine.

a. If there is enough fuel for this direct route, then the fuel needed and the total time for completion of the trip is calculated.

(1) The refuel point computes the time to refuel a helicopter by dividing the amount of fuel needed by 13,320 which is the number of pounds of fuel which may be dispensed in an hour.

(2) This refuel time is added to the travel time to determine the total time for completion of the trip.

b. If insufficient fuel is available for this direct route, then the Xfuelcheck routine returns a flag indicating insufficient fuel.

2. If the direct route is infeasible, Uhaul calls Xfuelcheck a second time to check that sufficient fuel exist to travel to the fuel point (loaded), refuel, travel to the drop area (loaded) and then return to the refuel area.

a. If there is enough fuel for this second route, then the fuel needed and the total time for completion of the trip is calculated. This total time is increased for the refuel time. Uhaul calls the Refuel routine to compute the fueling time and the fuel required.

(1) The Refuel routine computes the time to refuel a helicopter by dividing the amount of fuel needed by 13,320, which is the number of pounds of fuel which may be dispensed in an hour.

(2) This refuel time is added to the travel time to determine the total time for completion of the trip.

(3) The refueling area is not treated as a facility, as are the loading areas and the drop areas. However, a count is kept of the number of times the refuel area is used. Since the refuel area is not treated as a facility, the process is modeled as if both helicopter types are refueled simultaneously.

b. If there is insufficient fuel to complete the trip, a message is generated and the program stops.

3. Finally, the Uhaul routine places the move event onto the Schedule(*) array by assigning the current helicopter type a new mission of load or drop and setting the earliest time for the event to begin. This earliest time is the total time computed to complete either the direct or indirect route.

(e) Unload. Provided the mission indicated by the Scheduler routine for the next scheduled event is to drop cargo, the main driver calls the Drop routine.

1. The Drop routine will unload the cargo passed from the loading area and return the helicopter to either the loading area or to its place of origin.

a. The Drop routine begins the unloading process by resetting the Schedule(*) array for this event to zero.

b. In addition, the Drop routine sets the earliest time the event may occur and begins unloading the cargo.

(1) The unloading process involves resetting the helicopter status to an unloaded state, resetting the cargo space used to zero, and incrementing Faciltime by 0.25 hours.

(2) In addition, the Drop routine determines if a helicopter should be returned to the loading area or to its place of origin by screening the Cargo(*) array for the remaining items.

(a) If cargo remains to be loaded, then the mission for the Schedule(*) array is returning the helicopter to the loading area.

(b) If no cargo remains to be loaded, then the Coptdone routine is called to indicate the helicopter has finished its mission and is returning to its point of origin.

2. If more cargo remains to be transported, the Drop routine returns the helicopters to the loading area. This is accomplished by returning control to the main driver routine.

(3) Summary. When all cargo and troops have been transported to the drop area and all helicopters have arrived at their final destinations, the Schedule(*) array will have been reset to contain only zero entries. The call to Scheduler will find that no events remain to occur. At this point, subroutine Summary is called to provide a screen or hardcopy output of the results of the movement.

(a) Subroutine Summary generates a formatted report giving information about the time required to move the cargo and get the helicopters to their final destinations.

1. Faciltime(3) and Faciltime(4) contain the times the CH47D and the UH60A arrived at their termination points. The greater of these times is chosen as the time for movement termination. Faciltime(2) contains the time the drop area was last free; this is reported as the time until all cargo and troops are delivered to their target area.

2. Summary calculates the number of days needed for the move and creates a string variable to report the 24-hour clock time of the day that the move terminates.

3. Information summarized includes:

- a. Number of helicopters of each type used.
- b. Number of sorties by each helicopter type.
- c. Speed maintained by each helicopter type.
- d. Miles flown by each helicopter type.
- e. Total fuel dispensed.
- f. Number of hours from origin to destination for each helicopter type.
- g. A listing of all cargo left behind as too heavy for conditions.

(b) At this point, the program may be rerun with alterations to the gamer inputs used. The operator will be asked if a rerun is desired. A negative response causes the program to terminate and the DIME menu to be loaded. A positive reply causes a message to be printed giving instruction for rerunning the program using some of the previous inputs, and the program stops.

(c) If the rerun option is chosen, the user is directed to type "RUN RERUNIT". This causes all variables to be re-initialized and execution to begin in subroutine Rerunit. Rerunit causes flag Reprcount to be set to 1 to indicate that a rerun is taking place. Subroutine Fromfile is called to reenter inputs stored in the previous run. The start time, temperature, altitude, CH47D use option, number of each type of helicopter to use, sling options for each helicopter type, refueling option chosen for each type, and finally the cargo list from the last run are reloaded. The user is asked if the cargo series has changed, and if so, to what. Portions of the main program are utilized to reset name strings and header strings, as well as to initialize capacities, etc. Program control resumes in subroutine Databin, with the display of the data entry menu. The gamer may alter any or all of the input parameters; any not chosen for alteration will retain previous values. The only major pieces of information that must be reentered are the speeds to be flown by each helicopter. The program then proceeds as described.

C. The movement program consists of a driver routine and two phases: ground movement and cargo transport. Each phase has its own algorithms and subroutines consisting of local variables which are not common to both phases. These phases, with their accompanying subroutines and primary variables, are contained in Tables 9-1 and 9-2. Table 9-3 contains a listing of the original movement program code and Table 9-3a contains a listing of ADEA's movement program code.

Table 9-1. Troop movement subroutine table.

<u>Functional areas(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable Description</u>
A. Controls flow of troop movement module.	Header	Determines if gamer wishes to move troops which are dismounted or mounted.	Choice	An integer value which indicates the flow of the troop movement module: 1 - Dismounted movement 2 - Mounted movement 3 - Return to main movement menu
B. Movement of dismounted troops.	Dismount	Reads in dismounted movement rates.	Move_rate(i,j)	An 8x5 real array which contains the dismounted movement rates in km/hr, for eight traveling conditions within five geographic/terrain types i = 1 to 8, where: 1 - Blue/normal/day 2 - Blue/forced/day 3 - Blue/normal/night 4 - Blue/forced/night 5 - Red/normal/day 6 - Red/forced/day 7 - Red/normal/night 8 - Red/forced/night j = 1 to 5, where: 1 - Open road/trail 2 - Hilly road/trail 3 - Open cross country 4 - Hilly cross country 5 - Mountainous cross country

Table 9-1. Troop movement subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
B. Movement of dismounted troops (continued).	Start_dis_mov; Zero_gnd_data; Start_up	Establishes dimensions for new dismounted run; resets values input by previous run to zero; reads in new values input by gamer for present run.	a. Describe\$ b. Force; Side	A character string containing header information for run An integer value of 1 or 2 which indicates the force being moved where: 1 = Blue 2 = Red
			c. Mar_pace; Pace	An integer value of 1 or 2 which indicates the march pace, where: 1 = Normal 2 = Forced
			d. Mar_time; March	An integer value which indicates the time, in hours, for march time
			e. Rest_time	A real value which indicates the rest time between moves
			f. St_time	An integer value which indicates the starting time for the move, to the nearest hour...based on a 24 hour clock
			g. Persons	An integer value which indicates the number of persons in a marching column

Table 9-1. Troop movement subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable Description</u>
B. Movement of dismounted troops (continued).	Start_dis_mov; Zero_snd_data; Start_up_ (continued)		h. Ttrs	An integer value which indicates the number of tankers per march column
			i. Legs(n)	A real array which contains the distance in kilometers, and the road condition for 5 legs: Legs(1) = Distance on first leg of march Legs(2) = Road condition on first leg of march Legs(3) = Distance on second leg of march
			j. Day_nite	Legs(10) = Road condition on fifth leg of march An integer value of 0 or 1 which indicates the light conditions based on day (0) or night (1)

Table 9-1. Troop movement subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable Description</u>
b. Movement of dismounted troops (continued).	Walk_start; Walk_over	Calculate the total time needed to move along entire march, where march is equal to total distance + total rest periods during entire march.	a. Leg_now b. Leg_frac	A real value which contains the distance of the leg to be moved in current leg of march A real value which contains the distance remaining on the current leg to use in computing the time required for a move which is less than 1 hour
			c. Rate	A real value which contains the calculated movement rate as a function of side, pace, and day-night status
			d. Time	A real value which contains the elapsed time for march, where time is equal to total movement time + rest time + refueling time for each leg of march
	Err_check_1; Ch_var	Checks for errors entered by gamer through input routine.	Err	A flag value of 0 or 1 which indicates if an error has occurred during the input routine where: 0 = No error 1 = Error

Table 9-1. Troop movement subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable Description</u>
B. Movement of dismounted troops (concluded).	Prt_dis_out	Provides a printed summary of dismounted movement results.	a. Up_time b. Min_time	A real value which contains the start time adjusted to appear as standard 24-hour figure A real value which contains the calculated number of minutes past the hour at which column closure occurs
C. Movement of mounted troops.	Mmount	Reads in mounted movement rates.	C. Close_time Move_rate(*)	A real value which contains the time the final element in the column reaches the final destination on the march An 8x5 real array which contains the mounted movement rates in Km/hr (see detailed discussion in (B) above)
	Start_gnd_mov; Zero_gnd_data; Start_up	Establish dimensions for new mounted run; resets values to zero; reads in new values input by gamer for present run. (Note: Variables discussed under dismounted troops (B) are common to both dismounted and mounted troops.)	a. Refuel_dist b. Refuel_time	A real value which contains the distance remaining until a refueling stop must occur. This value is initially set to 200Km and reset to 200Km each time a refueling occurs. A real value which contains the calculated time required for refueling

Table 4-1. Troop movement subroutine table (concluded).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable Description</u>
C. Movement of mounted troops (concluded).	Gnd_mov_over	Calculates the total time needed to move along entire march.	Time	A real value which contains the total time needed for a column to reach the final destination, where time includes movement, rest, and refueling time enroute.

Table 9-2. Cargo transport subroutine table.

<u>Functional area(s):</u>	<u>A. Controls flow of movement module</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>
<u>Master menu</u>	<u>Primary variables</u>
	<u>Variable descriptions</u>
	A. Opt\$
	Determines if gamer wishes to move cargo or troops.
<u>Functional area(s):</u>	<u>B. Establishes data arrays</u>
<u>Subroutine called</u>	<u>Subroutine function(s)</u>
<u>Datain</u>	<u>Primary variables</u>
	<u>Variable descriptions</u>
	A. Fuelcap(I)
	Initializes cargo, helicopter and fuel use arrays for new runs. Fill new cargo, fuel and helicopter arrays with new data.
	B. Lowwt (I)
	Maximum fuel capacity for helicopter type I. 1 = UH60A 2 = CH47D
	Weight of empty helicopter I and crew. 1 = 22499 lbs (CH47D) 2 = 12165 lbs (UH60A)
	C. Typecargo
	An integer indicating which force's cargo list is to be loaded. 1 = A force cargo loaded 0 = B force cargo loaded.
	D. Cargo (I,J)
	A 71x9 array containing the cargo which is to be moved to the support unit. I = 1-70 - the 70 system elements of the unitfile. = 71 - personnel. J = 1 - integer containing one of the 71 elements carried. = 2 - type of helicopter used = 3 - weight of item = 4 - vacant = 5 - described how item is carried = 6-8 - vacant = 9 - cargo space in helicopter required by item.

Functional area(s): B. Establishes data arrays

Subroutine called Subroutine function(s) Primary variables

Datain
(continued)

E. Maxflow(H,I,J)

Variable descriptions

A 2x6x6 array containing helicopter fuel use (pounds/hour).

H = 1 - UH60A
 = 2 - CH47D

I is altitude above sea level

= 1 - 0 ft.
= 2 - 2000 ft.
= 3 - 4000 ft.
= 4 - 6000 ft.
= 5 - 8000 ft.
= 6 - 10000 ft.

J is temperature (degrees celsius)

= 1 - -10
= 2 - 0
= 3 - +10
= 4 - +20
= 5 - +30
= 6 - +40

F. Fuel_array
(A,B,C,D,E)

A 2x6x6x7x7 array containing fuel use data.

A = 1 - UH60A
 = 2 - CH47D

B = 1-6 (altitude above sea level)

C = 1-6 (temperature (degrees celsius))

D is speed (knots) of helicopter

= 1 - 40
= 2 - 60
= 3 - 80
= 4 - 100
= 5 - 120
= 6 - 140
= 7 - 160

E is 1-7 weight classes for helicopters weight to max. lift weight for each of two helicopters:

CH47D = 1 - 7
UH60A = 1 - 5.

Functional area(s): B. Establishes data arrays

Subroutine called Subroutine function(s) Primary variables

Datain
(continued)

Variable descriptions

An array containing the maximum weight of helicopter I.
I = 1 - 50,000 lbs (CH47D)
 = 2 - 20,500 lbs (UH60A).

G. Wtcap(I)

H. Copter(H,I,J)

A 2x10x10 array containing helicopter characteristics.

H = 1 - UH60A

 = 2 - CH47D

I = 1 - 10 (number of helicopters available)

J = 1-10 and describes dimensions

 = 1 - Vacant

 = 2 - Weight allowable for cargo transport

 = 3 - Weight of crew + fuel reserve + fuel load

 = 4 - Total permitted weight of helicopter

 = 5 - Vacant

 = 6 - Total cargo space (inches) available

 = 7 - Total cargo space (inches) taken up in helicopter

 = 8 - Current weight of fuel on helicopter

 = 9 - Vacant

 =10 - Weight of crew + fuel reserve + fuel load + cargo + helicopter weight.

I. Fuelr(I)

Fuel expenditure in 1/2 hour increments as a function of maximum fuel flow for a specified altitude and temperature for helicopter I.

I = 1 - CH47D

 = 2 - UH60A

Table 9-2. Cargo transport subroutine table.

Functional area(s): B. Establishes data arrays			
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Datain (continued)		J. Wts(I)	An array containing the maximum weight of helicopter I as a function of speed, temperature, altitude and fuel level input by the gamer.
		K. Schedule (*)	A 100x3 array used to schedule cargo movement events. Up to K = 100 events may be queued for execution, where (K,1) = Helicopter type for event (K,2) = Indicates if cargo is to be dropped or loaded (K,3) = Indicates earliest time helicopter will be available to take part in movement.
		L. Hname\$	A character string containing the name of the helicopter moving cargo.
Menu	Provides gamer with input questions and reads responses into cargo, fuel and helicopter arrays.	A. Choice	An integer (1-8) used to choose whether to input all new responses for each run or to change only selected responses for a new run. 1 = change start time only 2 = Change temperature only 3 = Change max. altitude only 4 = Conage1 only # troops to move 5 = Change only helicopter profiles 6 = Change only flight routes 7 = Change only cargo profiles 8 = Change all entries
		B. Starttime	A real number indicating the start time in hours and minutes.
		C. Temp	A real value indicating the ambient air temperature (celsius) from -10 to +40.

Table 9-2. Cargo transport subroutine table.

Functional area(s):	B. Establishes data arrays	Subroutine called	Subroutine function(s)	Primary variables	Variable descriptions
Menu (continued)				D. Altitude	A real value indicating the average altitude flown by each helicopter (0-10000 ft.).
				E. Ncopts(I)	Number of helicopters of type I available for this game turn.
				F. Slng(I)	Flag indicating how cargo may be carried by the helicopter type I. 1 = Load only interior 2 = Load interior and sling as needed.
				G. Fuelstat(I)	Fuel use status for helicopter I. 1 = 1 hr. fuel load 2 = full tank.
				H. Chstat	Integer indicating restrictions on CH47D helicopter use: 1 = use only for cargo that can be lifted by CH47D 2 = no restrictions on CH47D usage.
Map	Provides a conceptual map of the routes for helicopters. Maximum of 7 routes designated.	A. Route(*)			An array containing the distance nautical miles) for 7 routes. 1 = Distance between original location of helicopter 1 and point where cargo is loaded. 2 = Distance between original location of helicopter 2 and point where cargo is loaded. 3 = Distance between load point and drop zone. 4 = Distance between load point and refuel point. 5 = Distance between refuel point and drop zone. 6 = Distance between drop zone and final destination, helicopter 1. 7 = Distance between drop zone and final destination, helicopter 2.

Table 9-2. Cargo transport subroutine table.

Functional area(s):	B. Establishes data arrays		
<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Catset	Sets the altitude and temperature categories for the fuel array.	A. Tcat	An integer (1-6) indicating the temperature categories for the fuel array. Categories 1 - 6 correspond to temperatures -10C to +40C in 10 degree increments.
		B. Altcat	An integer (1-6) indicating the altitude categories for the fuel array. Categories 1 - 6 correspond to altitudes 0 - 10,000 ft. in 2000 foot increments.
Speedscreen	Establishes the flying speed of the helicopters As a function of fuel use and weight lift capacity.	A. Flightsped(I) B. Fteller1 C. Fteller2 D. Fteller3 E. Spokay	The flight speed (knots) of helicopter I. Speed is expressed in increments of 20 knots from 40 - 160 knots. Fuel needed to complete the distance from refuel point to load zone to drop zone and to refuel point. Fuel needed to complete the distance from refuel point to load zone to refuel point. Fuel needed to complete the distance from refuel point to drop point to refuel point. Flag indicating if speed input by games is feasible based on fuel needed to complete the distances indicated by Fteller1, Fteller2 or Fteller3. 0 = not feasible 1 = feasible

Table 9-2. Cargo transport subroutine table.

Functional area(s): B. Establishes data arrays	Subroutine called	Subroutine function(s)	Primary variables	Variable descriptions
Xfuelcheck		Determines how much fuel is required to complete up to 2 legs of the route.	A. Fuelneed	The amount of fuel needed to travel the distance between 2 legs of the route.
Functional area(s): C. Moves the helicopters to the load zone	Subroutine called	Subroutine function(s)	Primary variables	Variable descriptions
Init1		Calculates the time and fuel needed by each helicopter to move from original point to the load point. Establishes initial load/unload queues on the schedule array.	A. Milesflow B. Uptime Ctime C. Uhfuel Chfuel	Total miles flown by each helicopter for each of the 7 routes. Time required to get from the original point to the load point. Uptime for UH60A; Ctime for CH47D. Fuel needed to get from the original point to the load point
Dfuelcheck		Computes fuel and time usage for up to two legs of travel.	A. Xstatus	A flag indicating that a helicopter has sufficient fuel to complete two legs of a route. 1 = sufficient fuel 0 = insufficient fuel
Functional area(s): D. Screens cargo for loading	Subroutine called	Subroutine function(s)	Primary variables	Variable descriptions
Cargpscreen		Screens cargo to determine if it can be transported by a helicopter of specific type.	A. Kill	A flag indicating special cargo transportation requirements. 0 = cargo can be transported by either helicopter type 1 = only transportable by UH60A 2 = only transportable by CH47D 3 = requires a sling for transport.

Functional area(s): E. Loads and transports cargo

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Loader	Assigns cargo to helicopter and moves to drop area.	A. Troops B. Timeused	Total number of troops which can be transported by helicopter type specified. A constant of 15 minutes added to each helicopter's total flight time to represent load time.
Refuel	Calculates the time required to refuel helicopter.	A. Timef B. Kallit	Refuel time (hours). A counter indicating the total number of times a helicopter used the refuel point.
Uhaul	Calculates the time required to move from load zone to drop zone.	A. X	The total time needed to complete a trip, including refuel time (if any).

Functional area(s): F. Unloads cargo and returns helicopter to origin or load zone.

<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable descriptions</u>
Drop	Sets counter for number of sorties used to transport cargo. Returns helicopters to either load zone or origin point.	A. Dropcount(I) B. Qui	A counter holding the total number of type I helicopters used to transport cargo. A flag indicating if helicopter I is needed for loading additional cargo. 0 = not needed, return to origin point 1 = required to transport more cargo, return to load zone.

Table 9-3. Movement code.

```

10 ! "P9" IS THE MOVEMENT PROGRAM FOR THE DIVISION MAP EXERCISE (
DIME)
20 !
60 !MAIN MENU OF MODULE
80 OPTION BASE 1
90 Mastermenu: !
100 PRINT USING "e,#"
110 PRINT TABXY(1,7),TAB(25),"DIME MOVEMENT CALCULATOR"
120 PRINT " "
130 PRINT "THIS PROGRAM CALCULATES MOVEMENT TIME FOR UNITS USIN
G VARIOUS"
140 PRINT " MODES OF TRANSPORT. THESE ARE:"
150 PRINT
160 !
170 PRINT "MOVEMENT MENU: 1-HELICOPTER MOVEMENT OF CARGO"
180 PRINT " 2-GROUND MOVEMENT"
190 PRINT " 3-RETURN TO MASTER MENU"
200 INPUT "SELECT OPTION",Opt$
210 IF Opt$="3" THEN LOAD "DIME:HP9134,701,0"
220 IF Opt$="2" THEN
230 CALL P9
240 GOTO Mastermenu
250 END IF
260 PRINT "THIS PROGRAM REQUIRES A FILE NAMED <LOGDATA> ON YOUR
DISC"
270 PRINT " IT SHOULD BE 1 RECORD OF LENGTH 2400"
280 Reccount=0
290 !DIMENSION ARRAYS NEEDED IN PROGRAM
300 Dimit:DIM Hname$(3)[5],Milesflown(2)
310 DIM Cargo(22,9),Sling(2),Leg(2),Faciltime(4),Schedule(100,3
),Templ(2)
320 DIM Route(7),Ncopts(2),Copter(2,10,10),Fuelarray(2,6,6,7,7)
330 DIM Maxflow(2,6,6),Wtcap(2),Fuelr(2)
340 DIM Fuel(2,2),Headr$(1)[80]
350 DIM Fuelusstat(2),Legwt(2),Dropcount(2)
360 DIM Flightsped(2),Lowwt(2),Wta(2),Fuelcap(2),Totfuelusd(2),
Fhelo(2)
370 DIM Fuelend(2),Dropfuel(2,10),Firer$(2,22)[15],Labels$(7)[4
5]
380 REAL Fuel1,Fuel2
390 Or$=""
400 IF Reccount=1 THEN GOTO Datget
410 !HELICOPTER NAMES
420 Progtop:Hname$(1)="CH47D"
430 Hname$(2)="UH60"
440 Hname$(3)="BOTH "
450 !NAMES OF THE ELEMENTS OF THE CARGO FILES
460 !FORCE 'A' CARGO
470 Firer$(1,1)="descriptive name for system element 1 restrict

```

Table 9-3. Movement code (continued).

ed to 14 char."		
480	Firer\$(1,2)="descriptive name for system element 2 restrict ed to 14 char."	
490	Firer\$(1,3)="	3
500	Firer\$(1,4)="	4
510	Firer\$(1,5)="	5
520	Firer\$(1,6)="	6
530	Firer\$(1,7)="	7
540	Firer\$(1,8)="	8
550	Firer\$(1,9)="	9
560	Firer\$(1,10)="	10
570	Firer\$(1,11)="	11
580	Firer\$(1,12)="	12
590	Firer\$(1,13)="	13
600	Firer\$(1,14)="	14
610	Firer\$(1,15)="	15
620	Firer\$(1,16)="	16
630	Firer\$(1,17)="	17
640	Firer\$(1,18)="	18
650	Firer\$(1,19)="	19
660	Firer\$(1,20)="	20
670	Firer\$(1,21)="	21
680	Firer\$(1,22)="INFANTRY" ! always reserved for infantry	
690	!FORCE 'B' CARGO	
700	Firer\$(2,1)="descriptive name for system element 1 restrict ed to 14 char."	
710	Firer\$(2,2)="descriptive name for system element 2 restrict ed to 14 char."	
720	Firer\$(2,3)="	3
730	Firer\$(2,4)="	4
740	Firer\$(2,5)="	5

Table 9-3. Movement code (continued).

750	Firer\$(2,6)="	6
760	Firer\$(2,7)="	7
770	Firer\$(2,8)="	8
780	Firer\$(2,9)="	9
790	Firer\$(2,10)="	10
800	Firer\$(2,11)="	11
810	Firer\$(2,12)="	12
820	Firer\$(2,13)="	13
830	Firer\$(2,14)="	14
840	Firer\$(2,15)="	15
850	Firer\$(2,16)="	16
860	Firer\$(2,17)="	17
870	Firer\$(2,18)="	18
880	Firer\$(2,19)="	19
890	Firer\$(2,20)="	20
900	Firer\$(2,21)="	21
910	Firer\$(2,22)="INFANTRY" ! always reserved for infantry	
920	!LABELS OF ROUTES 1 - 7	
930	Labels\$(1)="DISTANCE FROM CH ORIGIN TO LOAD ZONE"	
940	Labels\$(2)="DISTANCE FROM UH ORIGIN TO LOAD ZONE"	
950	Labels\$(3)="DISTANCE FROM LOAD ZONE TO DROP ZONE"	
960	Labels\$(4)="DISTANCE FROM LOAD ZONE TO REFUEL POINT"	
970	Labels\$(5)="DISTANCE FROM DROP ZONE TO REFUEL POINT"	
980	Labels\$(6)="DISTANCE FROM DROP ZONE TO CH DESTINATION"	
990	Labels\$(7)="DISTANCE FROM DROP ZONE TO UH DESTINATION"	
1000	Kallit=0	
1010	!NUMBER OF SORTIES MADE BY <1=CH, 2=UH>	
1020	Dropcount(1)=0	
1030	Dropcount(2)=0	
1040	!FUEL USAGE COUNTERS	
1050	Totfuelusd(1)=0	
1060	Totfuelusd(2)=0	
1070	Fuelend(1)=0	
1080	Fuelend(2)=0	
1090	!ARRAY TO RECORD FUEL AVAILABLE AT DROP POINT	

Table 9-3. Movement code (continued).

```

1100 FOR I=1 TO 2
1110   FOR J=1 TO 10
1120     Dropfuel(I,J)=0
1130   NEXT J
1140 NEXT I
1150 Flag=0
1160 GOSUB Datatin      !ENTER DATA
1170 GOSUB Initl       !SEND COPTERS TO LOAD ZONE
1180 GOSUB Cargoscren  !SCREEN OUT UNMOVABLE CARGO
1190 PRINT "PERFORMING CARGO MOVEMENT---WAIT..."
1200 More:GOSUB Scheduler !LOOP AS APT FOR EVENTS
1210 SELECT What !1-READY TO LOAD CARGO 3-READY TO DROP OFF C
ARGO
1220 CASE 1
1230   GOSUB Loader
1240 CASE 3
1250   GOSUB Drop
1260 CASE ELSE
1270   PRINT "SHOULD NOT HAVE GOTTEN HERE!"
1280   LOAD "DIME:HP9134,701,0"
1290 END SELECT
1300 GOTO More
1310 !*****
*****
1320 Xfuelcheck: !
1330           !DETERMINE HOW MUCH FUEL WOULD BE REQUIRED FOR U
P TO 2 LEGS
1340 Fuel1=0.
1350 Fuel2=0.
1360 Tstvlv=INT((Flightspd(Helo)-20)/20)
1370 IF Leg(1)<>0 THEN
1380   Fuel1=Route(Leg(1))*Fuelarray(Helo,Altcat,Tcat,Tstvlv,Leg
wt(1))/Flightspd(Helo)
1390 END IF
1400 IF Leg(2)<>0 THEN
1410   Fuel2=Route(Leg(2))*Fuelarray(Helo,Altcat,Tcat,Tstvlv,Leg
wt(2))/Flightspd(Helo)
1420 END IF
1430 Fuelneed=Fuel1+Fuel2
1440 RETURN
1450 !*****
*****
1460 Speedscren: ! SET WT OF HELO TO 0 INITIALLY
1470 Wta(1)=0
1480 Wta(2)=0
1490 FOR Helo=1 TO 2
1500   IF Ncopts(Helo)=0 THEN GOTO Twohelo
1510   PRINT "ENTER FLIGHT SPEED TO USE FOR HELO ";Hname$(Helo);
" BETWEEN 40 AND 160 KNOTS: ENTER 0 IF NO SPEED HAS WORKED."
1520 Newsp:INPUT Flightspd(Helo)
1530   IF Flightspd(Helo)=0 THEN
1540     Ncopts(Helo)=0

```


Table 9-3. Movement code (continued).

```

1550     PRINT Hname$(Helo);" COULD NOT BE USED UNDER THESE COND
ITIONS"
1560     GOTO Twohelo
1570     END IF
1580     Atstvlu=INT((Flightspd(Helo)-20)/20)
1590     IF Flightspd(Helo)<40 OR Flightspd(Helo)>160 THEN
1600         PRINT "SPEED MUST BE BETWEEN 40 AND 160 KNOTS"
1610         PRINT "RE-ENTER SPEED FOR ";Hname$(Helo)
1620         GOTO Newsp
1630     END IF
1640     Spokay=0
1650     Top=7
1660     IF Helo=2 THEN Top=5
1670     FOR Wcat=Top TO 2 STEP -1
1680         IF Fuelarray(Helo,Altcat,Tcat,Atstvlu,Wcat)>Maxflow(Hel
o,Altcat,Tcat) THEN GOTO Newcat !SCREEN OUT NON-PERMISSABLE WT/
SPEED COMBINATIONS
1690         Leg(1)=4 !COPTER MUST BE ABLE TO GO
TO LOAD
1700         Leg(2)=3 !ZONE FROM REFUEL POINT, TH
EN TO DROP
1710         Legwt(1)=1 !ZONE LOADED, THEN TO REFUE
L
1720         Legwt(2)=Wcat !OR
1730         GOSUB Xfuelcheck !COPTER MUST BE ABLE TO GO
FROM REFUEL
1740         Fteller1=Fuelneed !POINT TO LOAD POINT EMPTY,
THEN TO REFUEL
1750         Leg(1)=5 !POINT LOADED, REFUEL, THEN
GO TO DROP
1760         Leg(2)=0 !ZONE LOADED, THEN BACK TO
REFUEL UNLOADED
1770         GOSUB Xfuelcheck
1780         Fteller1=Fteller1+Fuelneed !IF EITHER CHECK IS PASSED,
THE SPEED/WT
1790         Leg(1)=4 !COMBINATION IS OKAY.
1800         Leg(2)=4
1810         GOSUB Xfuelcheck
1820         Fteller2=Fuelneed
1830         Leg(1)=5
1840         Leg(2)=5
1850         GOSUB Xfuelcheck
1860         Fteller3=Fuelneed
1870         IF Fteller1<=Copter(Helo,1,8) OR (Fteller2<=Copter(Helo
,1,8) AND Fteller3<=Copter(Helo,1,8)) THEN Spokay=1
1880         IF Spokay=1 THEN
1890             Wta(Helo)=Wcat
1900             GOTO Newhelo
1910         END IF
1920     Newcat:NEXT Wcat
1930     PRINT "THAT SPEED NOT FEASIBLE FOR ";Hname$(Helo)
1940     PRINT "ENTER NEW SPEED TO TRY FOR ";Hname$(Helo)

```

Table 9-3. Movement code (continued).

```

1950     GOTO Newsp
1960 Newhelo: !
1970     IF Helo=1 AND Ncopts(Helo)<>0 THEN Wta(1)=Wta(1)*4000+220
00
1980     IF Helo=2 AND Ncopts(Helo)<>0 THEN Wta(2)=Wta(2)*2000+100
00
1990     IF Wta(2)=20000 AND Helo=2 AND Ncopts(Helo)<>0 THEN Wta(2
)=20500
2000 Twohelo:NEXT Helo
2010     RETURN
2020     !*****
*****
2030 Cargoscren: !
2040     FOR I=1 TO 22
2050         Kill=0
2060         IF Cargo(I,1)=0 THEN GOTO Nexone
2070         !MUST BE SLUNG AND CANNOT
2080         IF Sling(1)=0 AND Cargo(I,5)=11 THEN Kill=1
2090         IF Sling(2)=0 AND Cargo(I,5)=21 THEN Kill=2
2100         IF Sling(1)=0 AND Sling(2)=0 AND Cargo(I,5)=1121 THEN Kil
l=3
2110         !TOO HEAVY EVEN FOR CH47D
2120         IF Ncopts(1)<>0 THEN
2130             IF Cargo(I,3)>Copter(1,1,2) THEN Kill=1
2140         END IF
2150         IF Kill>0 THEN
2160             PRINTER IS 702
2170             PRINT "CARGO ITEM # ";I;" CANNOT BE MOVED: REQUIRES SLI
NG ON OR IS TOO HEAVY FOR ";Hname$(Kill)
2180             IF I=16 THEN
2190                 PRINT "MISSILES FOR ITEM 16 ALSO CANNOT BE MOVED"
2200                 PRINT "      AND WILL NOT SHOW IN THE FINAL SUMMARY"
2210                 Cargo(I,1)=0
2220                 PRINTER IS 1
2230             END IF
2240         END IF
2250 Nexone:NEXT I
2260     Kill=0
2270     FOR I=1 TO 22
2280         IF Cargo(I,1)<>0 THEN Kill=1
2290     NEXT I
2300     IF Kill<>1 THEN
2310         PRINT "NO CARGO LEFT TO MOVE; DROPPED OUT IN CARGOSCREN"
2320         PRINT "DONE SCREENING CARGO"
2330         PRINT " "
2340         LOAD "DIME:HP9134,701,0"
2350     END IF
2360     RETURN
2370     !*****
*****
2380 Coptdone: !
2390     Legwt(1)=1

```

Table 9-3. Movement code (continued).

```

2400 Legwt(2)=1
2410 Originl=Point           !RECORD WHERE COMING FROM IN CASE IMP
ROPERLY SENT
2420                         !BACK TO LOAD POINT WHEN NO CARGO WAS
LOADABLE
2430 Leavetime=Faciltime(Point)
2440 IF Dropcount(Helo)>0 THEN
2450   Originl=Point
2460   Point=2
2470 END IF
2480 SELECT Point           !COMING EITHER FROM (1)LOAD ZONE OR (2
)DROP ZONE
2490 CASE 1
2500   Leg(1)=3
2510   Leg(2)=6
2520   IF Helo=1 THEN Leg(2)=7
2530 !   COMPUTE TIME AND FUEL NEEDED TO GET TO DESTINATION
2540   GOSUB Dfuelcheck
2550   X=Tempus
2560   IF Xstatus=0 THEN
2570     Leg(1)=4
2580     Leg(2)=0
2590     GOSUB Dfuelcheck
2600     X=Tempus
2610     Leg(1)=5
2620     Leg(2)=6
2630     IF Helo=2 THEN Leg(2)=7
2640     GOSUB Refuel
2650     GOSUB Dfuelcheck
2660     Tempus=Tempus+X
2670     !ADD IN DISTANCE FROM ENTRY POINT TO DESTINATION
2680     Milesflown(Helo)=Milesflown(Helo)+Route(4)+Route(5)+Rou
te(Leg(2))
2690   ELSE
2700     Milesflown(Helo)=Milesflown(Helo)+Route(3)+Route(Leg(2)
)
2710     GOTO Timer
2720   END IF
2730 CASE 2
2740   SELECT Helo
2750   CASE 1
2760     Leg(1)=6
2770   CASE 2
2780     Leg(1)=7
2790   END SELECT
2800   Leg(2)=0
2810   !IF POINT COMING FROM IS 1, INADVERTANTLY SENT BACK TO
LOAD ZONE
2820   !SO RESET FUEL ON HAND TO WHAT IT WAS WHEN IT WAS AS TH
E DROP ZONE
2830   !ALSO RESET THE TIME IT LEFT FOR IT'S DESTINATION, AND
THE FUEL

```

Table 9-3. Movement code (continued).

```

2840      !USED AS OF THAT TIME
2850      IF Point<>Origin1 THEN
2860          FOR I=1 TO Ncopts(Helo)
2870              Copter(Helo,I,8)=Dropfuel(Helo,I)
2880          NEXT I
2890          Leavetime=Fluelo(Helo)
2900          Totfuelusd(helo)=Fuelend(Helo)
2910      END IF
2920      GOSUB Dfuelcheck
2930      Milesflown(Helo)=Milesflown(Helo)+Route(Leg(1))
2940  END SELECT
2950      !ADD TRIP TIME TO TIME STARTED FOR DESTINATION;RECORD IN
2960      !FACILITY 3 FOR CH, FACILITY 4 FOR UH
2970  Timer:Faciltime(Helo+2)=Leavetime+Tempus
2980      FOR I=1 TO Ncopts(Helo)
2990          Copter(Helo,I,8)=Copter(Helo,I,8)-Fuelneed
3000      NEXT I
3010      !HELICOPTER TYPE HELO IS DONE, SO ENSURE THAT NO EVENTS FO
R IT
3020      !REMAIN IN THE SCHEDULE ARRAY
3030      FOR I=1 TO 100
3040          IF Schedule(I,1)=Helo THEN
3050              FOR J=1 TO 3
3060                  Schedule(I,J)=0
3070              NEXT J
3080          END IF
3090      NEXT I
3100      IF Helo=1 THEN Flaga=1
3110      RETURN
3120 *****
*****
3130  Datin: !
3140      PRINT "ENTER DESCRIPTIVE TITLE FOR THIS RUN"
3150      INPUT Headr$(1)
3160      PRINTER IS 702
3170      PRINT " "
3180      PRINT Headr$(1)
3190      PRINT " "
3200      PRINT " "
3210      PRINTER IS 1
3220      INPUT "ENTER <1> FOR FORCE 'A', <2> FOR FORCE 'B'",Typecarg
o
3230      IF Repcount<>0 THEN
3240          PRINT "YOU WILL NEED TO RE-ENTER CARGO DATA IF YOUR LAST"
3250          PRINT "    RUN WAS NOT WITH THE SAME CARGO SERIES AS THIS
ONE"
3260          INPUT "HAS THE CARGO SERIES CHANGED?",Qr$
3270      END IF
3280      PRINT "LOADING ARRAYS"
3290      !INITIALIZE FACILITY TIMES
3300      FOR I=1 TO 4
3310          Faciltime(I)=0

```

Table 9-3. Movement code (continued).

```

3320 NEXT I
3330 !SET FUEL CAPACITIES OF EACH HELO
3340 Fuelcap(1)=6180
3350 Fuelcap(2)=2172
3360 !SET LOWWEST WEIGHT OF HELOS
3370 Lowwt(1)=22499
3380 Lowwt(2)=12165
3390 !*****
*****
3400 !ENTER CARGO DATA
3410 IF Reccount=1 AND Qr$="N" THEN GOTO Aleph
3420 IF Typecargo=1 THEN
3430     RESTORE 3530     !LOAD FORCE 'A' CARGO
3440 ELSE
3450     RESTORE 3750     !LOAD FORCE 'B' CARGO
3460 END IF
3470 FOR I=1 TO 22
3480     FOR J=1 TO 9
3490         READ Cargo(I,J)
3500     NEXT J
3510 NEXT I
3520 ! FORCE 'A' DATA
3530 DATA           ! THESE DATA STATEMENTS SHOULD CONTAIN
3540 DATA           ! DATA FOR THE ARRAY 'CARGO(I,J)'.
3550 DATA           ! I=1 TO 22; 1-21 ARE THE 21 SYSTEM ELEMEN
TS
3560 DATA           ! OF THE UNITFILE AND 22 IS ADDED TO PRO
VIDE
3570 DATA           ! THE TRANSPORTING OF PERSONNEL.
3580 DATA           ! J=1 TO 9; (1)INTEGER CONTAINING # OF EAC
H OF THE
3590 DATA           ! 22 ELEMENTS BEING CARRIED BY HELO,
3600 DATA           ! (2)REPRESENTS TYPE OF HELO BEING USED-
-1 for
3610 DATA           ! CH47D 2 for UH60 3 for either,
3620 DATA           ! (3)WEIGHT OF ITEM, (4)VACANT
3630 DATA           ! (5)DESCRIBES HOW ITEM IS TO BE CARRIED
:
3640 DATA           ! If item only transportable by one h
elo (xy)
3650 DATA           ! x = helo used y = how item is
transported
3660 DATA           ! If item may be transported by both
helos (wxyz)
3670 DATA           ! w = CH47D x = how item is
transported
3680 DATA           ! y = UH60 z = how item is t
ransported
3690 DATA           ! Items may be transported in the fol
lowing manners:
3700 DATA           ! 1=sling 2=sling or interior
3=interior

```

Table 9-3. Movement code (continued).

```

3710 DATA          ! (6 THRU 8) VACANT
3720 DATA          ! (9)CARGO SPACE REQUIRED FOR TRANSPORTI
NG
3730 DATA          ! OF ITEM BY HELO.
3740 !FORCE 'B' DATA
3750 DATA          ! THESE DATA STATEMENTS SHOULD CONTAIN
3760 DATA          ! DATA FOR THE ARRAY 'CARGO(I,J)'.
3770 DATA          ! USE SAME FORM DESCRIBED ABOVE FOR FORCE
'A'.
3780 !*****
*****
3790 !ENTER MAXFLOW DATA (MAXIMUM FUEL FLOW ALLOWABLE)
3800 Aleph:RESTORE 3900
3810 FOR H=1 TO 2   !HELO TYPE
3820   FOR I=1 TO 6 !ALTITUDE
3830     FOR J=1 TO 6 !TEMPERATURE
3840       READ Maxflow(H,I,J)
3850         Maxflow(H,I,J)=Maxflow(H,I,J)*100
3860       NEXT J
3870     NEXT I
3880   NEXT H
3890 ! THE FOLLOWING DATA CONTAINS MAXIMUM HELO FUEL USAGE IN P
OUNDS PER HOUR
3900 DATA          !MAXFLOW(H,I,J) CONTAINS:
3910 DATA          ! H=1 TO 2--(1)CH47D (2)UH60
3920 DATA          ! I=1 TO 6--ALTITUDE above sea level: (1)0 f
t. (2)2000 ft.
3930 DATA          ! (3)4000 ft. (4)6000 ft. (5)8000 ft.
(6)10000 ft.
3940 DATA          ! J=1 TO 6--TEMP in Centi.: (1)-10 (2)0 (3
)+10
3950 DATA          ! (4)+20 (5)+30 (6)+40
3960 !*****
*****
3970 !ENTER FUEL ARRAY DATA
3980 RESTORE 4520
3990 FOR Helo=1 TO 2
4000 ! IF Helo=1 THEN PRINT "DATA FOR CH47D";TAB(10);" "
4010 ! IF Helo=2 THEN PRINT "DATA FOR UH60";TAB(10);" "
4020   FOR Alt=1 TO 6 !ALTITUDE
4030     FOR T=1 TO 6 !TEMPERATURE
4040       FOR S=1 TO 7 !SPEED
4050         FOR W=1 TO 7!WEIGHT
4060           READ Fuelarray(Helo,Alt,T,S,W)
4070             Fuelarray(Helo,Alt,T,S,W)=Fuelarray(Helo,Alt,T,S,
W)*100
4080           NEXT W
4090         NEXT S
4100       NEXT T
4110     ! PRINT " "
4120     ! PRINT " "
4130     ! PRINT "ALTITUDE: ";Alt*2000-2000

```

Table 9-3. Movement code (continued).

```

4140 ! PRINT " "
4150 ! FOR T=1 TO 6
4160 ! PRINT "TEMPERATURE: ";(T-2)*10;" DEGREES CENTIGRADE"
4170 ! FOR S=1 TO 7
4180 ! FOR W=1 TO 7
4190 ! PRINT TAB(W*8);Fuelarray(Helo,Alt,T,S,W);
4200 ! NEXT W
4210 ! NEXT S
4220 ! PRINT " "
4230 ! PRINT "*****"
*****"
4240 ! NEXT T
4250 BEEP
4260 NEXT Alt
4270 ! PRINT " "
4280 ! PRINT " "
4290 NEXT Helo
4300 PRINTER IS 1
4310 !*****
*****
4320 DATA ! THE FOLLOWING DATA STATEMENTS ARE TO REPRESENT
4330 DATA ! THE ARRAY Fuelarray(I,J,K,L,M) WHICH CONTAINS
4340 DATA ! THE FUEL USAGE UNDER THE FOLLOWING CONDITIONS:
4350 DATA ! NOTE: ** for conditions unable to fly use 1.E+11
4360 DATA ! I=HELICOPTER TYPE
4370 DATA ! (1)CH47
4380 DATA ! (2)UH60
4390 DATA ! J=ALTITUDE(FEET PA)
4400 DATA ! (1)SEA LEVEL (4)6000
4410 DATA ! (2)2000 (5)8000
4420 DATA ! (3)4000 (6)10000
4430 DATA ! K=TEMPERATURE(C)
4440 DATA ! (1)-10 (4)+20
4450 DATA ! (2) 0 (5)+30
4460 DATA ! (3)+10 (6)+40
4470 DATA ! L=SPEED IN KNOTS
4480 DATA ! (1)40 (4)100
4490 DATA ! (2)60 (5)120 (7)160
4500 DATA ! (3)80 (6)140
4510 DATA ! M=WEIGHT CLASS FOR CH47D
4520 DATA ! (1)22000to26000 (4)34000to38000
4530 DATA ! (2)26000to30000 (5)38000to42000 (7)46000to50000
4540 DATA ! (3)30000to34000 (6)42000to46000
4550 DATA ! M=WEIGHT CLASS FOR UH60
4560 DATA ! (1)10000to12000 (3)14000to16000
4570 DATA ! (2)12000to14000 (4)16000to18000 (5)18000to20500
4580 !*****
*****
4590 !ENTER COPTER DATA: FIRST SET MAXIMUM WEIGHT EVER ALLOWABLE
FOR HELO
4600 Wtcap(1)=50000
4610 Wtcap(2)=20500

```

Table 9-3. Movement code (continued).

```

4620 FOR H=1 TO 2 !FOR EACH HELO TYPE
4630   FOR I=1 TO 10!FOR MAX OF 10 HELOS OF THAT TYPE
4640     FOR J=1 TO 10!FOR 10 ELEMENTS FOR EACH HELO
4650       Copter (H,I,J)=0!INITIALIZE ARRAY WITH APT DATA
4660       IF J=4 THEN Copter (H,I,J)=Wtcap (H)
4670       IF J=6 THEN
4680         IF H=1 THEN Copter (H,I,J)=366
4690         IF H=2 THEN Copter (H,I,J)=151
4700       END IF
4710     NEXT J
4720   NEXT I
4730 NEXT H
4740 Menu:PRINT "MENU:";TAB(1);" 1-START TIME";TAB(1);" 2-TEMP";T
AB(1);" 3-MAXIMUM PRESSURE ALTITUDE";TAB(1);" 4-# TROOPS TO MOVE"
;TAB(1);" 5-HELO DATA"
4750 PRINT " 6-FLIGHT ROUTES";TAB(1);" 7-CARGO DATA";TAB(1);" 8-
RUN PROGRAM"
4760 BEEP
4770 INPUT "SELECT MENU ITEM",Choice
4780 Which:ON Choice GOTO L1,L2,L3,L4,L5,L6,L7,L8
4790 La:INPUT "CORRECT? ",A$
4800 IF A$="N" THEN GOTO Which
4810 GOTO Menu
4820 L1:INPUT "ENTER START TIME <HOUR.MINUTES>",Starttime
4830 PRINT "START TIME IS ";Starttime;
4840 Cstarttime=Starttime
4850 Starttime=INT(Starttime)+(Starttime MOD 1)*5/4
4860 GOTO La
4870 L2:INPUT "ENTER TEMPERATURE IN CENTIGRADE (-10 TO 40) ",Temp
4880 PRINT "TEMPERATURE IS: ";Temp;
4890 GOTO La
4900 L3:INPUT "ENTER MAXIMUM PRESSURE ALTITUDE TO BE FLOWN (<=10,
000 FEET)",Altitude
4910 PRINT "ALTITUDE IS: ";Altitude;
4920 GOTO La
4930 L4:INPUT "ENTER NUMBER OF INFANTRY TO MOVE: INCLUDE WEAPON C
REMEMBERS",Cargo(22,1)
4940 PRINT Cargo(22,1);" TROOPS TO MOVE,CORRECT? <WILL BE STORED
AS CARGO ITEM 22>";
4950 GOTO La
4960 L5:FOR Helo=1 TO 2
4970 L51:PRINT "ENTER # OF ";Hname$(Helo);" AVAILABLE "
4980   INPUT Ncopts(Helo)
4990   PRINT Ncopts(Helo);
5000   INPUT "CORRECT?",A$
5010   IF A$="N" THEN GOTO L51
5020   IF Ncopts(Helo)=0 THEN
5030     Sling(Helo)=0
5040     GOTO Anhelo
5050   END IF
5060 L52:PRINT "ENTER LOAD PROFILE FOR ";Hname$(Helo);TAB(5);"HOW
SHOULD HELO BE LOADED?";TAB(5);"0-INTERIOR ONLY";TAB(5);"1-INTER

```


Table 9-3. Movement code (continued).

```

IOR OR EXTERIOR"
5070 INPUT Sling(Helo)
5080 PRINT "LOAD PROFILE FOR ";Hname$(Helo);" IS ";Sling(Helo)
5090 INPUT "CORRECT?",A$
5100 IF A$="N" THEN GOTO L52
5110 L53:INPUT "ENTER FUEL LOAD TO USE: 1-ONE HOUR RANGE 2-FULL
TANKS",Fuelusstat(Helo)
5120 PRINT "FUEL USE FOR ";Hname$(Helo);" IS ",Fuelusstat(Helo
)
5130 INPUT "CORRECT?",A$
5140 IF A$="N" THEN GOTO L53
5150 L54:IF Helo=1 THEN
5160 PRINT "ENTER CH47D USAGE CODE HERE. 'AS NEEDED' MEANS U
SE IT"
5170 PRINT "ONLY AS LONG AS THERE ARE ITEMS THAT ONLY IT CAN
MOVE. "
5180 PRINT "'FULLY' MEANS USE IT AS LONG AS THERE IS CARGO T
O MOVE."
5190 INPUT "ENTER CH47D UTILIZATION: 1-AS NEEDED ONLY 2-F
ULLY",Chstat
5200 PRINT "CH47D UTILIZATION IS: ";Chstat
5210 INPUT "CORRECT?",A$
5220 IF A$="N" THEN GOTO L54
5230 END IF
5240 Anhelo:NEXT Helo
5250 GOTO Menu
5260 L6:GOSUB Map !PRINT CONCEPTUAL MAP OF ROUTES
5270 PRINT "ENTER DATA FOR THE 7 MAP ROUTES: ENTER A <0> IF THAT
ROUTE WON'T BE USED"
5280 PRINT "ENTER THE DATA AS FOLLOWS:"
5290 PRINT "ENTER THE DISTANCE IN STATUTE MILES FOR EACH ROUTE:"
5300 FOR I=1 TO 7
5310 PRINT TABXY(0,23);"FOR ROUTE: ";I;" ,ENTER THE ";Labels$(
I)
5320 INPUT Route(I)
5330 NEXT I
5340 L61:FOR I=1 TO 7
5350 PRINT "ROUTE ";I;" DISTANCE: ";Route(I)
5360 NEXT I
5370 INPUT "ANY CHANGES",A$
5380 IF A$="Y" THEN
5390 L62:INPUT "ENTER <ROUTE,DISTANCE>: 0,0 TO CEASE CHANGE",I1,I
2
5400 IF I1=0 THEN GOTO L61
5410 Route(I1)=I2
5420 GOTO L62
5430 END IF
5440 !CONVERT MILES TO NAUTICAL MILES
5450 FOR I=1 TO 7
5460 Route(I)=Route(I)/1.1
5470 NEXT I
5480 GOTO Menu

```

Table 9-3. Movement code (continued).

```

5490 L7:PRINT "ENTER CARGO DATA AS FOLLOWS:"
5500 L71:INPUT "ENTER ELEMENT # OF ITEM, HOW MANY TO MOVE: ENTER
0,0 TO CEASE DATA INPUT",I1,I2
5510 IF I1=0 THEN GOTO L72
5520 IF Typecargo=1 THEN
5530     !FORCE 'A'
5540     IF I1=1 OR I1=6 OR I1=8 OR I1=9 OR I1=9 OR I1=13 THEN
5550         PRINT "ITEM ";I1;" CANNOT BE MOVED BY HELICOPTER"
5560         GOTO L71
5570     END IF
5580 ELSE
5590     !FORCE 'B'
5600     IF I1=1 OR I1=2 OR I1=3 OR I1=10 OR I1=12 OR I1=13 THEN
5610         PRINT "ITEM ";I1;" CANNOT BE MOVED BY HELICOPTER"
5620         GOTO L71
5630     END IF
5640 END IF
5650 PRINT I2;" OF ITEM ";I1;" ARE TO BE MOVED"
5660 INPUT "CORRECT",A$
5670 IF A$="N" THEN GOTO L71
5680 Cargo(I1,1)=I2
5690 IF I1=16 THEN                                !SEPERATE OUT MIS
SILES
5700     Cargo(1,1)=6*I2
5710     PRINT "MISSILES FOR ITEM 16 WILL BE STORED IN CARGO ITEM
1"
5720 END IF
5730 GOTO L71
5740 L72:PRINT "ELEMENT    NUMBER OF ITEMS TO MOVE"
5750 FOR I=1 TO 22
5760     PRINT TAB(4);I;TAB(22);Cargo(I,1)
5770 NEXT I
5780 INPUT "ANY CHANGES?",A$
5790 IF A$="Y" THEN GOTO L71
5800 GOTO Menu
5810 L8: ASSIGN @P TO "LOGDATA:HP9134,701,0"!RECORD SELECTED DATA
FOR RERUNS
5820 OUTPUT @P,1;Starttime,Temp,Altitude,Chstat,Ncopts(*),Sling(
*),Fuelusstat(*),Route(*),Cargo(*),Cstarttime
5830 ASSIGN @P TO *
5840 PRINTER IS 702
5850 PRINT " "
5860 PRINT " "
5870 IF Typecargo=1 THEN
5880     PRINT "FORCE 'A' CARGO TO MOVE:"
5890 ELSE
5900     PRINT "FORCE 'B' CARGO TO MOVE:"
5910 END IF
5920 PRINT "SUMMARY OF CARGO TO BE MOVED:"
5930 PRINT "          NOTES: 1- ITEM 1 IS MISSILES FOR ITEM 16"
5940 PRINT "          2- ITEM 22 IS TROOPS INCLUDING WEAPON C
REWS"

```

Table 9-3. Movement code (continued).

```

5950 PRINT " "
5960 PRINT "ITEM: "; TAB(20); "# TO MOVE"; TAB(35); "ITEM: "; TAB(55); "
# TO MOVE"
5970 FOR I=1 TO 11
5980 PRINT I; "-"; Firer$(Typecargo, I); TAB(20); Cargo(I, 1); TAB(35
); I+11; "-"; Firer$(Typecargo, I+11); TAB(55); Cargo(I+11, 1)
5990 NEXT I
6000 PRINT " "
6010 PRINT "ROUTE"; TAB(13); "DISTANCE"
6020 FOR I=1 TO 7
6030 PRINT TAB(3); I; TAB(13); INT((Route(I)*1.1)*100.)/100.; TAB(
25); Labels$(I)
6040 NEXT I
6050 PRINT " "
6060 PRINT " "
6070 PRINTER IS 1
6080 GOSUB Catset !SET ALTITUDE, TEMP CATEGORIES FOR ARRAY USE
6090 !
6100 !DETERMINE HOW MUCH FUEL CAN BE CARRIED ON HELO'S
6110 FOR H=1 TO 2
6120 IF Ncopts(H)=0 THEN GOTO Newh1
6130 Fuelr(H)=.5*(Maxflow(H, Altcat, Tcat))
6140 FOR I=1 TO Ncopts(H)
6150 Copter(H, I, 3)=Fuelr(H)+Lowwt(H)
6160 NEXT I
6170 IF Fuelstat(H)=1 THEN !1 HOUR FUEL
6180 FOR I=1 TO Ncopts(H)
6190 IF Copter(H, I, 3)+2*Fuelr(H)<Copter(H, I, 3)+Fuelcap(H)
THEN
6200 Copter(H, I, 3)=Copter(H, I, 3)+2*Fuelr(H)
6210 ELSE
6220 Copter(H, I, 3)=Copter(H, I, 3)+Fuelcap(H)
6230 END IF
6240 IF Copter(H, I, 3)+2*Fuelr(H)>Copter(H, I, 3)+Fuelcap(H)
THEN
6250 Copter(H, I, 8)=Fuelcap(H)-Fuelr(H)
6260 ELSE
6270 Copter(H, I, 8)=2*Fuelr(H)
6280 Fuel(H, 1)=Copter(H, I, 8)
6290 END IF
6300 NEXT I
6310 ELSE !FULL FUEL
6320 FOR I=1 TO Ncopts(H)
6330 Copter(H, I, 3)=Copter(H, I, 3)+Fuelcap(H)-Fuelr(H)
6340 Copter(H, I, 8)=Fuelcap(H)-Fuelr(H)
6350 Fuel(H, 2)=Copter(H, I, 8)
6360 NEXT I
6370 END IF
6380 Newh1:NEXT H
6390 GOSUB Speedscren !SET SPEED TO FLY AT
6400 FOR I=1 TO 2
6410 IF Wta(I)>Wtcap(I) THEN Wta(I)=Wtcap(I)

```

Table 9-3. Movement code (continued).

```

6420     IF Copter(I,1,3)>Wta(I) THEN
6430       PRINT "FUEL LOAD ON ";Hname$(I);" TOO HEAVY"
6440       PRINT "RERUN WITH NEW ALT/TEMP/SPEED OR FUEL USE"
6450       STOP
6460     END IF
6470   NEXT I
6480   GOSUB Wtallowed    !SET HELO WT ELEMENT IN ARRAY, AND INITIA
LIZE OTHERS
6490   !INITIALIZE SCHEDULE ARRAY
6500   FOR I=1 TO 100    !INITIALIZE SCHEDULE ARRAY TO 0
6510     Schedule(I,1)=0
6520     Schedule(I,2)=0
6530     Schedule(I,3)=0
6540   NEXT I
6550   RETURN
6560 !*****
*****
6570 Dfuelcheck:      ! SAME AS XFUELCHECK EXCEPT TIME COMPUTED AND
PUT IN TEMPUS
6580                  ! AND A STATUS VARIABLE IS SET IF ANY HELO HAS
INSUFFICIENT
6590                  ! FUEL TO MAKE THE TRIP INDICATED
6600   Xstatus=1
6610   Fuel1=0
6620   Fuel2=0
6630   Temp1(1)=0
6640   Temp1(2)=0
6650   FOR I=1 TO 2
6660     IF Leg(I)<>0 THEN Temp1(I)=Route(Leg(I))/Flightspd(Helo)
6670   NEXT I
6680   Oh1=(Flightspd(Helo)-20)/20
6690   IF Leg(2)<>0 THEN Fuel2=Temp1(2)*Fuelarray(Helo,Altcat,Tcat
,Oh1,Legwt(2))
6700   IF Leg(1)<>0 THEN Fuel1=Temp1(1)*Fuelarray(Helo,Altcat,Tcat
,Oh1,Legwt(1))
6710   Tempus=Temp1(1)+Temp1(2)
6720   Fuelneed=Fuel1+Fuel2
6730   FOR I=1 TO Ncopts(Helo)
6740     IF Copter(Helo,I,8)<Fuelneed THEN Xstatus=0
6750   NEXT I
6760   RETURN
6770 !*****
*****
6780 Findwt:         ! DETERMINE THE MAX WEIGHT OF HELO'S IN THE GROU
P
6790   Maxwt(Helo)=0
6800   FOR I=1 TO Ncopts(Helo)
6810     IF Maxwt(Helo)<Copter(Helo,I,10) THEN Maxwt(Helo)=Copter(
Helo,I,10)
6820   NEXT I
6830   RETURN
6840 !*****
*****

```

Table 9-3. Movement code (continued).

```

*****
6850 Catset: ! SET TEMP AND ALT CATEGORIES TO USE IN ARRAYS
6860 Tempuse=INT((Temp+.5)/10)*10
6870 IF Tempuse>40 THEN Tempuse=40
6880 IF Tempuse<-10 THEN Tempuse=-10
6890 Tcat=INT((Tempuse+20)/10)
6900 Altcat=INT((Altitude)/2000)+1
6910 IF Altcat<1 THEN Altcat=1
6920 IF Altcat>6 THEN Altcat=6
6930 RETURN
6940 !*****
*****
6950 Drop: !
6960 Dropcount(Helo)=Dropcount(Helo)+1 !COUNT # OF SORT
IES
6970 !SET BEGINNING TIME OF EVENT TO GREATER OF WHEN FACILIT
Y LAST
6980 !FREED OR WHEN HELOS CAN ARRIVE, AND ZERO THE EVENT FRO
M THE SCHEDULE
6990 IF Faciltme(2)<Schedule(Which,3) THEN Faciltme(2)=Schedul
e(Which,3)
7000 Schedule(Which,1)=0
7010 Schedule(Which,2)=0
7020 Schedule(Which,3)=0
7030 GOSUB Wtallowed
7040 FOR I=1 TO Ncopts(Helo)
7050 Copter(Helo,I,7)=0
7060 !CARGO SPACE USED RESET TO ZERO
7070 NEXT I
7080 Faciltme(2)=Faciltme(2)+.25 !FLAT 15 MIN. TO UNLOAD C
ARGO
7090 Fhelo(Helo)=Faciltme(2)
7100 IF Helo=1 AND Flaga=0 AND Chstat=1 THEN !CH47D USED AS
NEEDED AND
7110 GOSUB Chneed !NOT ALREADY SE
NT HOME
7120 IF Flag=0 THEN
7130 Point=2
7140 GOSUB Coptdone ! NOT NEEDED, SEND HOME
7150 Flaga=1
7160 GOTO Outit
7170 END IF
7180 END IF
7190 Qui=0
7200 FOR I=1 TO 22
7210 IF Cargo(I,1)=0 THEN GOTO Nexi !SCREEN OUT BY DON'T NEE
D REASONS
7220 IF Cargo(I,2)<>Helo AND Cargo(I,2)<>3 THEN GOTO Nexi
7230 IF Cargo(I,2)=Helo AND Sling(Helo)=0 AND (Cargo(I,5) MOD
10=1) THEN GOTO Nexi
7240 IF Cargo(I,3)>Copter(Helo,1,2) THEN GOTO Nexi
7250 IF Cargo(I,2)=3 THEN

```

Table 9-3. Movement code (continued).

```

7260     IF Helo=1 AND Sling(1)=0 AND INT(Cargo(I,5)/100)=11 THE
N GOTO Nexi
7270     IF Helo=2 AND Sling(2)=0 AND (Cargo(I,5) MOD 100)=21 TH
EN GOTO Nexi
7280     END IF
7290     Qui=1      !GETS HERE IF THIS HELO NEEDED TO CARRY IT
7300 Nexi:NEXT I
7310     IF Qui=0 OR Cargoflag=0 THEN      !NOT NEEDED, SEND HOME
7320     Point=2
7330     GOSUB Coptdone
7340     GOTO Outit
7350     END IF
7360     What=4      !SET WHAT=4 FOR UHAUL TO COMPUTE TRIP BACK FR
OM DROP ZONE
7370     Fuelend(Helo)=Totfuelusd(Helo)
7380     FOR I=1 TO Ncopts(Helo)
7390     Dropfuel(Helo,I)=Copter(Helo,I,8)
7400     NEXT I
7410     GOSUB Uhaul
7420 Outit:RETURN
7430     !*****
*****
7440 Loader:  !
7450 Check=1
7460 Check1=0
7470     !SET TIME FACILITY CAN BE ENGAGED TO BE MAX(TIME FACILITY
LAST FREED,
7480     !TIME HELO'S ARRIVE), THEN ZERO EVENT FROM SCHEDULE ARRAY
7490     IF Faciltime(1)<Schedule(Which,3) THEN Faciltime(1)=Schedul
e(Which,3)
7500     Schedule(Which,1)=0
7510     Schedule(Which,2)=0
7520     Schedule(Which,3)=0
7530     !SCREEN FOR CH NEED
7540     !FLAGA=1 IF CH'S FINISHED ALREADY
7550     IF Flag=0 AND Helo=1 AND Chstat=1 THEN
7560     GOSUB Chneed
7570     IF Flag=0 THEN
7580 Outit5:Point=1
7590     GOSUB Coptdone
7600     IF Helo=1 THEN Flag=1
7610     GOTO Quit10
7620     END IF
7630     END IF
7640     Check=0
7650     FOR I=1 TO 22      !SEE IF CARGO LEFT
TO MOVE
7660     IF Cargo(I,1)<>0 THEN Check=Check+1
7670     NEXT I
7680     IF Check=0 THEN GOTO Outit5
7690     ! LOAD INFANTRY
7700     IF Cargo(22,1)<>0 THEN

```

Table 9-3. Movement code (continued).

```

7710   Check1=1
7720   FOR I=1 TO Ncopts(Helo)
7730     IF Helo=1 THEN
7740       Troops=33
7750       IF Troops>Cargo(22,1) THEN Troops=Cargo(22,1)
7760     ELSE
7770       Troops=11
7780       IF Troops>Cargo(22,1) THEN Troops=Cargo(22,1)
7790     END IF
7800     IF (Copter(Helo,I,10)+Troops*250)>Wta(Helo) THEN
7810       Troops=INT((Wta(Helo)-Copter(Helo,I,10))/250)
7820     END IF
7830     IF (Troops<=0) THEN
7840       PRINT "NO WEIGHT ALLOWANCE FOR TROOPS---STOPPING"
7850       STOP
7860     END IF
7870     Cargo(22,1)=Cargo(22,1)-Troops
7880     Copter(Helo,I,10)=Copter(Helo,I,10)+Troops*250
7890     IF (Troops=33 AND Helo=1) OR (Troops=11 AND Helo=2) THE
N
7900       Copter(Helo,I,7)=Copter(Helo,I,6)
7910     ELSE
7920       IF Helo=1 THEN
7930         Copter(Helo,I,7)=Copter(Helo,I,6)-Troops*(366/33)
7940       ELSE
7950         Copter(Helo,I,7)=Copter(Helo,I,6)-Troops*(151/11)
7960       END IF
7970     END IF
7980     PRINTER IS 1
7990     IF Cargo(22,1)<=0 THEN GOTO Loadsling
8000   Anotheri:NEXT I
8010   END IF
8020
!LOAD S
LINGS
8030   Loadsling:!
8040   FOR Copt=1 TO Ncopts(Helo)
8050     FOR Q=1 TO 2
8060       FOR I=1 TO 21
8070         IF Cargo(I,1)<=0 THEN GOTO Newi1
8080         IF Cargo(I,2)<>Helo AND Cargo(I,2)<>3 THEN GOTO Newi1
8090         IF Q=1 THEN !SLING ONLY ITEMS
ON PASS 1
8100           IF Cargo(I,2)=3 THEN
8110             IF INT(Cargo(I,5)/100) MOD 10<>1 AND Helo=1 THEN
GOTO Newi1
8120             IF Cargo(I,5) MOD 10<>1 AND Helo=2 THEN GOTO Newi
1
8130           ELSE
8140             IF Cargo(I,5) MOD 10<>1 THEN GOTO Newi1
8150           END IF
8160         END IF
8170       IF Cargo(I,2)=3 THEN !SCREEN NON-SLINGABLES; LOAD I

```

Table 9-3. Movement code (continued).

```

INTERIOR LAST
8180         IF (INT(Cargo(I,5)/100) MOD 10)=3 AND Helo=1 THEN G
OTO Newi1
8190         IF (Cargo(I,5) MOD 10)=3 AND Helo=2 THEN GOTO Newi1
8200         ELSE
8210         IF (Cargo(I,5) MOD 10)=3 THEN GOTO Newi1
8220         END IF
8230 Reload: !
8240         IF Copter(Helo,Copt,10)+Cargo(I,3)>Wta(Helo) THEN GOT
O Newi1
8250         Copter(Helo,Copt,10)=Copter(Helo,Copt,10)+Cargo(I,3)
8260         Cargo(I,1)=Cargo(I,1)-1
8270         Check1=1
8280         IF Cargo(I,1)<=0 THEN GOTO Newi1
8290         GOTO Reload
8300 Newi1:NEXT I
8310     NEXT Q
8320 NEXT Copt
8330                                             !LO
AD INTERIOR
8340 Loadinside: !
8350 FOR Copt=1 TO Ncopts(Helo)
8360     IF Copter(Helo,Copt,7)>=Copter(Helo,Copt,6) THEN GOTO Get
acoptr
8370     FOR Q=1 TO 2
8380         FOR I=1 TO 21
8390             IF Cargo(I,1)<=0 THEN GOTO Nexi1
8400             IF Cargo(I,2)<>Helo AND Cargo(I,2)<>3 THEN GOTO Nexi1
8410             IF Q=1 THEN ! LOAD INTERIOR ONLY ITEMS
ON PASS 1
8420                 IF Cargo(I,2)=3 THEN
8430                     IF INT(Cargo(I,5)/100) MOD 10<>3 AND Helo=1 THEN
GOTO Nexi1
8440                     IF Cargo(I,5) MOD 10<>3 AND Helo=2 THEN GOTO Nexi
1
8450                 ELSE
8460                     IF Cargo(I,5) MOD 10<>3 THEN GOTO Nexi1
8470                 END IF
8480             END IF
8490             IF Cargo(I,2)=3 THEN
8500                 IF INT(Cargo(I,5)/100)=11 AND Helo=1 THEN GOTO Nexi
1
8510                 IF Cargo(I,5) MOD 10=1 AND Helo=2 THEN GOTO Nexi1
8520             ELSE
8530                 IF Cargo(I,5) MOD 10=1 THEN GOTO Nexi1
8540             END IF
8550 Morein: ! IF IT GETS HERE, ITEM CAN GO INSIDE
8560         IF Wta(Helo)<Copter(Helo,Copt,10)+Cargo(I,3) THEN GOT
O Nexi1
8570         Sizex=Cargo(I,9)
8580         IF Copter(Helo,Copt,6)<Copter(Helo,Copt,7)+Sizex THEN
GOTO Nexi1

```


Table 9-3. Movement code (continued).

```

8590      Copter (Helo,Copt,7)=Copter (Helo,Copt,7)+Sizex
8600      Copter (Helo,Copt,10)=Copter (Helo,Copt,10)+Cargo(I,3)
8610      Cargo(I,1)=Cargo(I,1)-1
8620      Check1=1
8630      IF Cargo(I,1)<=0 THEN GOTO Nexi1
8640      GOTO Morein
8650 Nexi1:NEXT I
8660      NEXT Q
8670 Getacopt: NEXT Copt
8680 IF Check1=0 THEN          !NO CARGO COULD BE LOADED THIS TIM
E
8690      Point=1
8700      GOSUB Coptdone
8710      PRINTER IS 1
8720      PRINT " "
8730      PRINT " "
8740      PRINT "NO CARGO COULD BE LOADED ON: ";Hname$(Helo);" THIS
TIME . HELO SENT TO DESTINATION."
8750      PRINT " "
8760      PRINT " "
8770      GOTO Quit10
8780 END IF
8790      !ALL COPTERS OF TYPE HELO ARE LOADED
8800 Timeused=.25
8810 Faciltime(1)=Faciltime(1)+Timeused          !ADD IN FLAT 15 MIN.
TO LOAD CARGO
8820 What=2          !SET WHAT=2 FOR UHAUL TO COMPUTE TRIP FROM LOAD
POINT
8830 GOSUB Uhaul
8840      !TRIP COMPLETED, READY TO GOTO DROP:  SEE WHAT WAS CARRIE
D"
8850 Cargoflag=0
8860 FOR I=1 TO 22
8870     IF Cargo(I,1)<>0 THEN
8880         Cargoflag=1
8890!         PRINT Cargo(I,1);" OF ITEM ";I;" LEFT"
8900     END IF
8910 NEXT I
8920 Quit10:RETURN
8930      !*****
*****
8940 Scheduler:      !
8950 Minx=1.E+6
8960 What=0          !INITIALLY, NOTHING TO BE DONE
8970 Which=0
8980 Helo=0
8990 FOR I=1 TO 100
9000     IF Schedule(I,1)=0 THEN GOTO Loopit
9010     IF Schedule(I,3)<Minx THEN
9020         Minx=Schedule(I,3)
9030         What=Schedule(I,2)          !SET WHAT TO NEXT EVENT TO OCCUR
<1 OR 3>

```

Table 9-3. Movement code (continued).

```

9040     Which=I
9050     END IF
9060 Loopit:NEXT I
9070     IF What=0 THEN           !NOTHING LEFT IN SCHEDULE ARRAY, PRI
NT SUMMARY
9080     GOSUB Summary
9090     END IF
9100     When=Minx
9110     Helo=Schedule(Which,1)
9120     RETURN
9130 *****
*****
9140 Refuel: !
9150     Lowf=500000
9160     FOR I=1 TO Ncopts(Helo)
9170         IF Copter(Helo,I,8)<Lowf THEN Lowf=Copter(Helo,I,8) !FIND
GREATEST
9171                                     !FUEL
NEEDED
9180     NEXT I
9190     Fuelin=Fuel(Helo,Fuelusstat(Helo))-Lowf
9200     Timef=Fuelin/(37*6*60) !REFUEL TIME IN HOURS
9210     X=X+Timef
9220     FOR I=1 TO Ncopts(Helo)
9230         Copter(Helo,I,8)=Fuel(Helo,Fuelusstat(Helo))
9240         Totfuelusd(Helo)=Totfuelusd(Helo)+Fuelin
9250     NEXT I
9260     Kallit=Kallit+1 !COUNT NUMBER OF TIMES REFUEL POINT USED
9270     RETURN
9280 *****
*****
9290 Uhaul: !
9300     X=0
9310     IF What=2 THEN           !WORKING ON TRIP TO DROP ZONE
9320         GOSUB Findwt
9330         IF Helo=2 THEN       !SET MAXIMUM WEIGHT CLASS OF HELO
9340             Legwt(1)=INT(((Maxwt(Helo)-Lowwt(Helo))/2000)+1)
9350         ELSE
9360             Legwt(1)=INT(((Maxwt(Helo)-Lowwt(Helo))/4000)+1)
9370         END IF
9380         IF Legwt(1)<1 THEN
9390             PRINT "ERROR IN LEG WT IN UHAUL ROUTINE"
9400             LOAD "DIME:HP9134,701,0"
9410         END IF
9420         IF Legwt(1)<1 THEN Legwt(1)=1
9430         Tleg1=Legwt(1) !STORE LEG 1 WEIGHT
9440         Legwt(2)=1 !LEG WEIGHT OF SECOND LEG=LOWEST CLASS
9450         Leg(1)=3 !AT LOAD, SEE IF CAN GO LEG3 LOADED AND L
EG5 UNLOADED
9460         Leg(2)=5
9470         GOSUB Xfuelcheck
9480         Till1=Fuelneed

```

Table 9-3. Movement code (continued).

```

9490     IF Till1<=Copter (Helo,1,8) THEN           !CAN DROP CARGO AND R
EFUEL
9500         Legwt(1)=Tleg1
9510         GOTO Trip
9520     END IF
9530     Leg(1)=4
9540     Leg(2)=0
9550     GOSUB Xfuelcheck
9560     Till2=Fuelneed
9570     Leg(1)=5
9580     Leg(2)=5
9590     GOSUB Xfuelcheck
9600     Till3=Fuelneed
9610     Spokay=0
9620     IF Till2<=Copter (Helo,1,8) AND Till3<=Fuel (Helo,Fuelussta
t(Helo)) THEN
9630         Leg(1)=4
9640         Leg(2)=0
9650         GOSUB Dfuelcheck
9660         IF Xstatus=0 THEN LOAD "DIME:HP9134,701,0"
9670         X=Tempus
9680         GOSUB Refuel
9690         Leg(1)=5
9700         Leg(2)=0
9710         GOSUB Dfuelcheck
9720         IF Xstatus=0 THEN LOAD "DIME:HP9134,701,0"
9730         Milesflown(Helo)=Milesflown(Helo)+Route(4)+Route(5)
9740         GOTO Checker
9750     END IF
9760     PRINT "OHBOY SOMETHINGWRONGHASGONE"
9770     LOAD "DIME:HP9134,701,0"
9780     END IF
9790     IF What=4 THEN                               !WORKING ON TRIP FROM DROP ZONE TO LOAD
POINT
9800     IF Helo=2 THEN
9810         Legwt(1)=INT(((Wta(Helo)-Lowwt(Helo))/2000)+1)
9820     ELSE
9830         Legwt(1)=INT(((Wta(Helo)-Lowwt(Helo))/4000)+1)
9840     END IF
9850     Legwt(2)=1
9860     Leg(1)=4
9870     Leg(2)=3
9880     GOSUB Xfuelcheck
9890     IF Fuelneed<=Copter (Helo,1,8) THEN
9900         Legwt(1)=1
9910         GOTO Trip
9920     END IF
9930     Leg(1)=0
9940     Leg(2)=5
9950     GOSUB Xfuelcheck
9960     Till1=Fuelneed
9970     Leg(1)=0

```

Table 9-3. Movement code (continued).

```

9980     Leg(2)=4
9990     GOSUB Xfuelcheck
10000    Till2=Fuelneed
10010    Leg(1)=4
10020    Leg(2)=0
10030    GOSUB Xfuelcheck
10040    Till3=Fuelneed+Till2
10050    IF Till1<=Copter(Helo,1,8) AND Till3<=Fuel(Helo,Fuelussta
t(Helo)) THEN
10060        Leg(1)=0
10070        Leg(2)=5
10080        GOSUB Dfuelcheck
10090        X=Tempus
10100        GOSUB Refuel
10110        Leg(2)=4
10120        GOSUB Dfuelcheck
10130        Milesflown(Helo)=Milesflown(Helo)+Route(4)+Route(5)
10140        GOTO Checker
10150    END IF
10160    PRINT "MYOHMY YOUBLEWITAGAIN"
10170    LOAD "DIME:HP9134,701,0"
10180    END IF
10190    Trip: !
10200    Leg(1)=3
10210    Leg(2)=0
10220    Milesflown(Helo)=Milesflown(Helo)+Route(3)
10230    GOSUB Dfuelcheck
10240    Checker: X=X+Tempus
10250    FOR I=1 TO Ncopts(Helo)
10260        Copter(Helo,I,8)=Copter(Helo,I,8)-Fuelneed
10270    NEXT I
10280    IF What=2 THEN That=3      !TRIP TO DROP COMPUTED, SCHEDULE
CARGO DROP
10290    IF What=4 THEN That=1      !TRIP TO LOAD COMPUTED, SCHEDULE
LOADING
10300    FOR I=1 TO 100
10310        IF Schedule(I,1)=0 THEN
10320            Schedule(I,1)=Helo
10330            Schedule(I,2)=That
10340            Schedule(I,3)=Faciltime(What/2)+X !RECORD EARLIEST HELO
'S CAN ARRIVE
10341                !AT <WHAT=2,LOAD> <WHAT=4,DROP> FACILITY=TIME
LEFT+TRIP TIME
10350            GOTO Outit1
10360        END IF
10370    NEXT I
10380    Outit1:RETURN
10390    !*****
*****
10400    Chneed: ! CHECK ALL REASONS WHY CH47D MAY STILL BE NEEDED
10410    Flag=0
10420    FOR I=1 TO 22

```

Table 9-3. Movement code (continued).

```

10430 IF Cargo(I,1)=0 THEN GOTO Ani10
10440 IF Cargo(I,2)=1 AND Copter(1,1,2)>=Cargo(I,3) THEN Flag=1
10450 IF Copter(2,1,2)<Cargo(I,3) AND Copter(1,1,2)>=Cargo(I,3)
AND NOT (Sling(1)=0 AND INT(Cargo(I,5)/100)=11) THEN Flag=1
10460 IF Sling(2)=0 AND Sling(1)<>0 AND Cargo(I,5)=1121. AND Co
pter(1,1,2)>=Cargo(I,3) THEN Flag=1
10470 IF Cargo(I,2)=3 THEN
10480 IF Sling(1)=0 AND INT(Cargo(I,5)/100)=11 THEN GOTO Ani1
0
10490 IF Sling(2)=0 AND (Cargo(I,5) MOD 100)=21 AND Copter(1,
1,2)>=Cargo(I,3) THEN Flag=1
10500 END IF
10510 Ani10:NEXT I
10520 RETURN
10530!*****
*****
10540 Wtallowed:! SET WT ELEMENTS OF COPTER ARRAY
10550 FOR Xhelo=1 TO 2
10560 FOR I=1 TO Ncopts(Xhelo) !WTA=MAX WT OF HELO (1) AND (2)
10570 IF Ncopts(Xhelo)=0 THEN GOTO Getanewi
10580 Copter(Xhelo,I,4)=Wta(Xhelo) !MAX WT ALLOWED AT THIS
TEMP,ALT,SPD
10590 Copter(Xhelo,I,2)=Wta(Xhelo)-Copter(Xhelo,I,3) !MAX CA
RGO WT ALLOWED
10600 Copter(Xhelo,I,10)=Copter(Xhelo,I,3) !CURRENT HELO WT
COUNTER
10610 Getanewi:NEXT I
10620 NEXT Xhelo
10630 RETURN
10640!*****
*****
10650 Summary:!
10660 INPUT "SCREEN (S) OR PRINTER (P) SUMMARY?";C$
10670 PRINT "PRINTING SUMMARY"
10680 IF C$="P" THEN PRINTER IS 702
10690 Timedone=Faciltime(3)
10700 IF Timedone<Faciltime(4) THEN Timedone=Faciltime(4)
10710 FOR I=1 TO 8
10720 PRINT " "
10730 NEXT I
10740 Daystaken=INT(Timedone/24)
10750 Clockdone=(Timedone+Starttime) MOD 24
10760 Clockhr=INT(Clockdone)
10770 IF Clockhr<10 THEN
10780 Clockhr$="0"&VAL$(Clockhr)
10790 ELSE
10800 Clockhr$=VAL$(Clockhr)
10810 END IF
10820 Clockmin=INT(DROUND((Clockdone MOD 1)*60,2))
10830 PRINT "START TIME WAS: ";Cstarttime
10840 IF Chstat=1 THEN
10850 PRINT "CH47D USED ONLY AS NEEDED"

```

Table 9-3. Movement code (continued).

```

10860 ELSE
10870 PRINT "CH47D USED FULLY"
10880 END IF
10890 PRINT "TIME REQUIRED (IN HOURS) UNTIL ALL CARGO HAS BEEN DE
LIVERED: ";
10900 PRINT INT(Faciltime(2)*100)/100
10910 PRINT " "
10920 PRINT "LAST COPTER AT DESTINATION AT ";Clockhr$;":";
10930 IF Clockmin<10 THEN
10940 PRINT "0"&VAL$(Clockmin)
10950 ELSE
10960 PRINT VAL$(Clockmin)
10970 END IF
10980 PRINT " "
10990 PRINT " "
11000 PRINT TAB(20);Hname$(1);TAB(30);Hname$(2)
11010 PRINT " "
11020 PRINT "# OF HELOS USED";TAB(20);Ncopts(1);TAB(30);Ncopts(2)
11030 PRINT "NUMBER OF SORTIES";TAB(20);Dropcount(1);TAB(30);Drop
count(2)
11040 PRINT "SPEED FLOWN";TAB(20);Flightspd(1);TAB(30);Flightspe
d(2)
11050 PRINT "MILES FLOWN";TAB(20);1.1*Milesflown(1);TAB(30);1.1*M
ilesflown(2)
11060 PRINT "FUEL DISPENSED";TAB(20);INT(Totfuelusd(1)*100/6)/100
;TAB(30);INT(Totfuelusd(2)*100/6)/100
11070 FOR I=3 TO 4
11080 Xqr=Faciltime(I)*10.
11090 IF Xqr MOD 1>=.5 THEN Xqr=Xqr+1.
11100 Faciltime(I)=Xqr/10.
11110 NEXT I
11120 PRINT "HOURS TILL DONE";TAB(20);INT(Faciltime(3)*10)/10;TAB
(30);INT(Faciltime(4)*10)/10
11130 PRINT " "
11140 PRINT TAB(15);"TOTAL SORTIES FLOWN: ";Dropcount(1)+Dropcoun
t(2)
11150 PRINT TAB(15);"TOTAL FUEL DISPENSED: ";INT((Totfuelusd(1)+T
otfuelusd(2))*100/6)/100;" GALLONS"
11160 PRINT TAB(15);"TOTAL MILES FLOWN: ";1.1*(Milesflown(1)+Mile
sflown(2))
11170 PRINT TAB(15);"REFUELING POINT USED ";Kallit;" TIMES"
11180 PRINT " "
11190 PRINT " "
11200 PRINT " "
11210 PRINT " "
11220 Checklate=0
11230 FOR I=1 TO 22
11240 IF Cargo(I,1)<>0 THEN Checklate=1
11250 NEXT I
11260 IF Checklate=1 THEN
11270 PRINT "CARGO ITEMS LEFT BEHIND: TOO HEAVY FOR CONDITIONS
OR CANNOT BE SLUNG ON APPROPRIATE HELICOPTER"

```

Table 9-3. Movement code (continued).

```

11280 PRINT " "
11290 FOR I=1 TO 22
11300     IF Cargo(I,1)<>0 THEN PRINT Cargo(I,1);" OF THE ";Firer
$(Typecargo,I)
11310     NEXT I
11320 END IF
11330 PRINT " "
11340 PRINT " "
11350 PRINTER IS 1
11360 PRINT "IF THESE RESULTS ARE UNSATISFACTORY, YOU MAY MAKE CH
ANGES TO"
11370 PRINT "YOUR INITIAL SET-UP"
11380 INPUT "RERUN WITH NEW SET-UP?",A$
11390 IF A$="N" THEN GOTO Whoopee
11400 PRINT "ENTER <RUN RERUNIT> AND FOLLOW DIRECTIONS"
11410 Whoopee:PRINT "PROGRAM DONE"
11420 STOP
11430 LOAD "DIME:HP9134,701,0"
11440 RETURN
11450!*****
*****
11460 Init1:!
11470 IF Ncopts(1)=0 AND Ncopts(2)=0 THEN
11480     PRINT "YOU DIDN'T GIVE ME ANY HELICOPTERS--STOPPING!"
11490     LOAD "DIME:HP9134,701,0"
11500 END IF
11510 FOR Helo=1 TO 2
11520     Milesflown(Helo)=0
11530     IF Ncopts(Helo)<>0 THEN Milesflown(Helo)=Milesflown(Helo)
+Route(Helo)
11540 NEXT Helo
11550 Helo=2
11560 Legwt(1)=1      !SET INITIAL TRIP LEGS TO BE AT MINIMUM WEIGH
T
11570 Legwt(2)=1
11580 Leg(1)=2      !UH TRIP ON LEG 2
11590 Leg(2)=0
11600 IF Ncopts(2)=0 THEN GOTO Aleph1
11610 GOSUB Dfuelcheck      !COMPUTE TRIP TIME, FUEL USED TO LOA
D POINT
11620 IF Xstatus=0 THEN GOTO Ops
11630 Uhtime=Tempus      !TIME TO GET TO LOAD POINT
11640 Uhfuel=Fuelneed
11650 FOR I=1 TO Ncopts(2)
11660     Copter(2,I,8)=Copter(2,I,8)-Uhfuel  !DECRIMENT FUEL ON HA
ND BY TRIP USE
11670 NEXT I
11680 Schedule(2,1)=2      !SCHEDULE THE UH
11690 Schedule(2,2)=1      !TO LOAD CARGO
11700 Schedule(2,3)=Uhtime !NO EARLIER THAN IT'S ARRIVAL AT LOAD
POINT
11710 Aleph1:IF Ncopts(1)=0 THEN GOTO Outer

```

Table 9-3. Movement code (continued).

```

11720 Helo=1
11730 Leg(1)=1           !CH TRIP LEG 1 TO LOAD POINT
11740 GOSUB Dfuelcheck
11750 IF Xstatus=0 THEN GOTO Ops
11760 Chtime=Tempus     !TIME FOR UH TO GET TO LOAD POINT
11770 Chfuel=Fuelneed
11780 Schedule(1,1)=1   !SCHEDULE THE CH
11790 Schedule(1,2)=1   !TO LOAD CARGO
11800 Schedule(1,3)=Chtime !NO EARLIER THAN IT'S ARRIVAL AT LOAD
POINT
11810 FOR I=1 TO Ncopts(1)
11820   Copter(1,I,8)=Copter(1,I,8)-Chfuel !DECREDIT FUEL BY TRIP
USE
11830 NEXT I
11840 GOTO Outer
11850 Ops:PRINT "BOMBED OFF AT START; CAN'T GET TO LOAD POINT."
11860 LOAD "DIME:HP9134,701,0"
11870 Outer:RETURN
11880 !*****
11890 Fromfile:! RE-ENTER DATA FROM LOGFILE FOR RERUN
11900 PRINT "ENTERING DATA FROM DISC"
11910 ASSIGN @P TO "LOGDATA:HP9134,701,0"
11920 ENTER @P,1;Starttime,Temp,Altitude,Chstat,Ncopts(*),Sling(*
),Fuelusstat(*),Route(*),Cargo(*),Cstarttime
11930 ASSIGN @P TO *
11940 RETURN
11950 !*****
11960 !RERUN PROGRAM WITH SOME CHANGES
11970 Rerunit:!
11980 Reprcount=1      !SET FLAG INDICATING IT'S A RERUN
11990 GOTO Dimit      !REDIMENSION ARRAYS AND REINITIALIZE WHERE AP
T
12000 Datget:GOSUB Fromfile !RELOAD DATA FROM LAST RUN
12010 GOTO Progtop !RUN PROGRAM
12020 !*****
12030 Map:! CONCEPTUAL MAP OF ROUTES TO FLY
12040 PRINT USING "e"
12050 PRINT "      CH47D      REFUEL      CH47D"
12060 PRINT "      ORIGIN      POINT      DESTINATION"
12070 PRINT "      X          X          X"
12080 PRINT "      -          -          -"
12090 PRINT "      -          -          -"
12100 PRINT "      1          4          5          6"
12110 PRINT "      -          -          -          -"
12120 PRINT "      -          -          -          -"
12130 PRINT "LOAD POINT X-----3-----X DROP ZONE"
12140 PRINT "      -          -          -          -"
12150 PRINT "      -          -          -          -"
12160 PRINT "      2          7"

```


Table 9-3. Movement code (continued).

```

12170 PRINT "          -          -"
12180 PRINT "          -          -"
12190 PRINT "          X          X"
12200 PRINT "          UH60          UH60"
12210 PRINT "          ORIGIN          DESTINATION"
12220 RETURN
12230 END
12240 !*****
*****
*****
12250 SUB P9
12260 REM "P9" IS THE MOVEMENT CALCULATOR PROGRAM FOR DIME. CO
DED BY
12270 ! MAJ T. REISCHL, OAB, CAORA, A/V 552-4613/5122. THIS PRO
GRAM
12280 ! LAST CHANGED ON 12 JUNE 1983. HELD PORTION CODED BY
12290 ! TERRY D. BRASHLEY <SAME ADDRESS>, LAST CHANGED ON 30DEC
83.
12300 OPTION BASE 1
12310 DIM Move_rate(8,5),Leg(10),P1$(4),P2$(6),Describe$(40)
12320 INTEGER I,J,K
12330 !
12340 ! PRINT OPTION PAGE
12350 Header:PRINT USING "e"
12360 PRINTER IS 702
12370 PRINT USING "e,#"
12380 PRINTER IS 1
12390 PRINT TABXY(1,7),TAB(25),"GROUND MOVEMENT CALCULATOR"
12400 PRINT " "
12410 PRINT "THIS PROGRAM CALCULATES MOVEMENT TIME FOR UNITS US
ING VARIOUS"
12420 PRINT " MODES OF TRANSPORT. THESE ARE:"
12430 PRINT
12440 PRINT "          1. DISMOUNTED"
12450 PRINT "          2. GROUND (WHEEL/TRACK VEHICLE)"
12460 PRINT "          3. RETURN TO MOVEMENT MENU"
12470 INPUT "ENTER DESIRED OPTION:",Choice
12480 IF Choice<>1 AND Choice<>2 AND Choice<>3 THEN Header
12490 IF Choice=3 THEN
12500     GOTO Backuptop
12510 END IF
12520 ON Choice GOSUB Dismount,Ground
12530 GOTO Header
12540 !
12550 ! ***** END OF MAIN PROGRAM *****
*****
12560 !
12570 Dismount: !SBR DISMOUNT CALCULATES DISMOUNTED MOVEMENT TIME
S
12580 !
12590 RESTORE 12610
12600 READ Move_rate(*)

```

Table 9-3. Movement code (continued).

```

12610 DATA      ! THE FOLLOWING IS THE DISMOUNTED MOVEMENT RATE
VELOCITIES
12620 DATA      ! (Km/Hr) IN NONCOMBAT CONDITIONS FOR 1 BLUE AND
1 RED FORCE.
12630 DATA      ! Move_rate(I,J) CONTAINS:
12640 DATA      ! I=GEOGRAPHIC AREA                J=TRAVEL CONDI
TIONS
12650 DATA      ! (1)open road/trail                (1)blue norma
1 day
12660 DATA      ! (2)hilly road/trail                (2)blue force
d day
12670 DATA      ! (3)open cross-country            (3)blue norma
1 night
12680 DATA      ! (4)hilly cross-country            (4)blue force
d night
12690 DATA      ! (5)mountainous x-country          (5-8)same as
above for red
12700 !
12710 !
12720 Start_dis_mov:PRINT USING "@"
12730 PRINT TABXY(26,17),"DISMOUNTED MOVEMENT MODULE"
12740 Move_type=1
12750 GOSUB Start_up
12760 GOTO Walk_start
12770 Start_up:GOSUB Zero_gnd_data
12780 INPUT "ENTER DESCRIPTION: ",Describe$
12790 PRINT "MARCH FACTORS ARE:"
12800 PRINT "FORCE (1,2), MARCH PACE(1,2), MARCH TIME, REST TIM
E, START TIME"
12810 PRINT "NUMBER OF PERSONS, NUMBER OF TANKERS"
12820 INPUT "ENTER MARCH FACTORS: ",Force,Mar_pace,Mar_time,Res
t_time,St_time,Persons,Tkrs
12830 INPUT "ENTER TERRAIN PROFILE FOR 5 LEGS: DIST(km) AND LE
G TYPE ",Leg($ )
12840 Type_bound=5
12850 IF Choice=2 THEN Type_bound=4
12860 FOR Ck_loop=1 TO 9 STEP 2
12870 CALL Ck_var("TERRAIN PROFILE DIST(km)", "THRU",Leg(Ck_lo
op),0,40)
12880 NEXT Ck_loop
12890 FOR Ck_loop=2 TO 10 STEP 2
12900 CALL Ck_var("TERRAIN PROFILE LEG TYPE","TO",Leg(Ck_loop
),1,Type_bound)
12910 NEXT Ck_loop
12920 !
12930 GOSUB Err_check_1
12940 IF Err=1 THEN 12820
12950 ! SET LIGHT CONDITIONS
12960 IF St_time>=6 AND St_time<=18 THEN
12970 Day_nite=0
AY=0
12980 Vis_left=18-St_time
!D

```

Table 9-3. Movement code (continued).

```

12990 ELSE
13000     Day_nite=1
13010     IF St_time>18 THEN
13020         Vis_left=St_time-12
13030     ELSE
13040         Vis_left=St_time+6
13050     END IF
13060 END IF
13070 Pace=Mar_pace
13080 Side=4*(Force-1)
13090 March=Mar_time
13100 RETURN
13110 !
13120 ! *****
*****
13130 !
13140 Walk_start:FOR I=1 TO 9 STEP 2           ! BEGIN MOVEME
NT CALCULATION
13150     IF Leg(I)=0 OR Leg(I+1)=0 THEN Walk_over
13160 !     DETERMINE MOVEMENT TIME
13170     Leg_now=Leg(I)
13180     LOOP
13190         Rate=Side+Pace+Day_nite*2
13200         Leg_frac=Leg_now
13210         Leg_now=Leg_now-Move_rate(Rate,Leg(I+1))
13220         IF Leg_now<0 THEN Time=Time+Leg_frac/Move_rate(Rate,L
eg(I+1))
13230     EXIT IF Leg_now<=0
13240     Time=Time+1
13250     Vis_left=Vis_left-1
13260     March=March-1
13270     IF March=0 THEN
13280         Time=Time+Rest_time
13290         March=Mar_time
13300     END IF
13310     IF Vis_left<=0 THEN
13320         Vis_left=12
13330         IF Day_nite=0 THEN
13340             Day_nite=1
13350         ELSE
13360             Day_nite=0
13370         END IF
13380     END IF
13390 END LOOP
13400 NEXT I
13410 Walk_over: ! ADD IN COLUMN CLOSURE TIME
13420     Time=Time+(Persons/360)
13430 !PRINT RESULTS OF MOVEMENT
13440     Prt=1
13450     GOSUB Prt_dis_out
13460     INPUT "DO YOU WANT HARD COPY OUTPUT? (Y OR N)",Q$

```

Table 9-3. Movement code (continued).

```

13470 IF Q$<>"Y" AND Q$<>"N" THEN 13460
13480 IF Q$="Y" THEN
13490   Prt=702
13500   GOSUB Prt_dis_out
13510 END IF
13520 PRINTER IS 1
13530 INPUT "MORE DISMOUNTED MOVEMENT TO CALCULATE? (Y OR N)",
Q$
13540 IF Q$<>"Y" AND Q$<>"N" THEN 13530
13550 IF Q$="Y" THEN Start_dis_mov
13560 RETURN
13570 !
13580 ! *****
*****
13590 !
13600 Zero_gnd_data: ! THIS SBR ZEROES VARIABLES FOR THE GND/DSM
TD MODULES
13610 FOR I=1 TO 10
13620   Leg(I)=0
13630 NEXT I
13640 Pace=1
13650 Force=1
13660 Mar_pace=0
13670 Mar_time=8
13680 Rest_time=0
13690 St_time=0
13700 Persons=0
13710 Time=0
13720 Tkrs=1
13730 Day_nite=0
13740 Close_time=0
13750 Describe$="
13760 Refuel_dist=200
13770 RETURN
13780 !
13790 ! *****
*****
13800 !
13810 Err_check_1:! THIS SBR CHECKS FOR ERRORS IN DISMOUNTED/GR
OUND INPUT
13820 Err=0
13830 IF Force<>1 AND Force<>2 THEN
13840   PRINT "FORCE INPUT ERROR"
13850   Err=1
13860 END IF
13870 IF Mar_pace<>1 AND Mar_pace<>2 THEN
13880   Err=1
13890   PRINT "MARCH CYCLE INPUT ERROR"
13900 END IF
13910 IF St_time>24 OR St_time<0 THEN
13920   Err=1
13930   PRINT "START TIME INPUT ERROR"

```

Table 9-3. Movement code (continued).

```

13940 END IF
13950 FOR I=2 TO 10 STEP 2
13960     IF Leg(I)<0 OR Leg(I)>5 THEN
13970         Err=1
13980         PRINT "TERRAIN PROFILE INPUT ERROR"
13990     END IF
14000 NEXT I
14010 RETURN
14020 !
14030 ! *****
*****
14040 !
14050 Prt_dis_out: ! THIS SBR PRINTS OUT DISMOUNTED MOVEMENT RE
SULTS
14060 !
14070 PRINTER IS Prt
14080 IF Prt=1 THEN PRINT USING "@"
14090 PRINT " "
14100 PRINT " "
14110 PRINT " "
14120 IF Move_type=1 THEN
14130     PRINT TAB(10),"DISMOUNTED MOVEMENT RESULTS"
14140 ELSE
14150     PRINT TAB(10),"GROUND MOVEMENT RESULTS"
14160 END IF
14170 PRINT " "
14180 PRINT USING "40A";Describe$
14190 PRINT " "
14200 IF Force=1 THEN
14210     P1$="BLUE"
14220 ELSE
14230     P1$="RED "
14240 END IF
14250 IF Mar_pace=1 THEN
14260     P2$="NORMAL"
14270 ELSE
14280     P2$="FORCED"
14290 END IF
14300 PRINT USING "7A,4A,13X,6A,6A";"FORCE: ",P1$,"PACE: ",P2$
14310 Up_time=St_time#100
14320 PRINT USING "13A,2D,3A,2D,4X,12A,4Z,4A";"MARCH CYCLE: ",M
ar_time," - ",Rest_time,"START TIME: ",Up_time," HRS"
14330 PRINT USING "15A,4D,5X,13A,3D";"COLUMN LENGTH: ",Persons,
"NO. TANKERS: ",Tkr$
14340 PRINT USING "9A, 5(3D,1X,1D,3X)";"PROFILE: ",Leg(1)
14350 PRINT " "
14360 PRINT " "
14370 PRINT USING "18A,3D,2D,1X,3A";"TOTAL MARCH TIME: ",Time,"
HRS"
14380 ! CALCULATE CLOSURE TIME
14390 I_time=St_time+INT(Time)
14400 Min_time=(Time-INT(Time))*60

```

Table 9-3. Movement code (continued).

```

14410 Min_time=INT(Min_time)
14420 IF I_time>23 THEN
14430     I_time=I_time MOD 24
14440     Close_time=(I_time*100)+Min_time
14450 ELSE
14460     Close_time=(I_time*100)+Min_time
14470 END IF
14480 PRINT " "
14490 PRINT USING "14A,4Z,1X,3A";"CLOSURE TIME: ",Close_time,"H
RS"
14500 RETURN
14510 !
14520 ! *****
*****
14530 !
14540 Ground:! SBR GROUND CALCULATES GROUND MOVEMENT TIMES
14550 !
14560 RESTORE 14580
14570 READ Move_rate(*)
14580 DATA      ! CONTAINS SAME DATA FORMAT FOR THESE MOUNTED MO
VEMENT RATES
14590 DATA      ! AS THE DISMOUNTED MOVEMENT RATES PREVIOUSLY DE
SCRIBED.
14600 Start_gnd_mov:PRINT USING "e"
14610 PRINT TABXY(26,17),"GROUND MOVEMENT MODULE"
14620 Move_type=2
14630 GOSUB Start_up
14640 !
14650 !     BEGIN MOVEMENT TIME CALCULATION
14660 FOR I=1 TO 9 STEP 2
14670     IF Leg(I)=0 OR Leg(I+1)=0 THEN Gnd_mov_over
14680 !
14690 !     DETERMINE MOVEMENT TIME
14700 Leg_now=Leg(I)
14710 LOOP
14720     Rate=Side+Pace+Day_nite*2
14730     Leg_frac=Leg_now
14740     Leg_now=Leg_now-Move_rate(Rate,Leg(I+1))
14750     IF Leg_now<0 THEN
14760         Time=Time+Leg_frac/Move_rate(Rate,Leg(I+1))
14770         Refuel_dist=Refuel_dist-Move_rate(Rate,Leg(I+1))
14780     END IF
14790 EXIT IF Leg_now<=0
14800 Refuel_dist=Refuel_dist-Move_rate(Rate,Leg(I+1))
14810 Time=Time+1
14820 Vis_left=Vis_left-1
14830 March=March-1
14840 IF March=0 THEN
14850     March=Mar_time
14860     Refuel_time=0
14870     IF Refuel_dist<=30 THEN
14880         Refuel_dist=200

```

Table 9-3. Movement code (continued).

```

14890         Refuel_time=Persons/Tkrs/4*8
14900         END IF
14910         IF Refuel_time>Rest_time THEN
14920             Time=Time+Refuel_time
14930         ELSE
14940             Time=Time+Rest_time
14950         END IF
14960     END IF
14970     IF Refuel_dist<=0 AND March>0 THEN
14980         Refuel_dist=200
14990         Refuel_time=Persons/Tkrs/4*8
15000         Time=Time+Refuel_time
15010         IF Refuel_time>=Rest_time THEN March=Mar_time
15020     END IF
15030     IF Vis_left<=0 THEN
15040         Vis_left=12
15050         IF Day_nite=0 THEN
15060             Day_nite=1
15070         ELSE
15080             Day_nite=0
15090         END IF
15100     END IF
15110 END LOOP
15120 NEXT I                                     ! GOTO NEXT LEG
15130 Gnd_mov_over:!! ADD IN CLOSURE TIME
15140     Time=Time+Persons/180
15150 !
15160 ! PRINT RESULTS OF MOVEMENT
15170     Prt=1
15180     GOSUB Prt_dis_out
15190     INPUT "DO YOU WANT HARDCOPY OUTPUT? (Y OR N)",Q$
15200     IF Q$<>"Y" AND Q$<>"N" THEN 15190
15210     IF Q$="Y" THEN
15220         Prt=702
15230         GOSUB Prt_dis_out
15240     END IF
15250     PRINTER IS 1
15260     INPUT "MORE GROUND MOVEMENT TO CALCULATE? (Y OR N)",Q$
15270     IF Q$<>"Y" AND Q$<>"N" THEN 15260
15280     IF Q$="Y" THEN Start_gnd_mov
15290 Backup_top:PRINT USING "e"
15300 SUBEND
15310 SUB Ck_var (Var_name$,T$,Variable,Min_value,Max_value)
15320     SELECT T$
15330     CASE "THRU"
15340         WHILE Variable<Min_value OR Variable>Max_value
15350             GOSUB Print_error
15360         END WHILE
15370     CASE "OR"
15380         GOTO Case_to
15390     CASE "TO"
15400 Case_to:FOR M=Min_value TO Max_value

```

Table 9-3. Movement code (concluded).

```
15410     IF Variable=M THEN GOTO End_select
15420     NEXT M
15430     GOSUB Print_error
15440     GOTO Case_to
15450 End_select:
15460     END SELECT
15470     GOTO Rtrn
15480 Print_error:
15490     PRINT
15500     PRINT "## ERROR: ";Variable;" IS INVALID FOR ";Var_name$
15510     PRINT "INPUT: ";Min_value;" ";T$;" ";Max_value;" ONLY"
15520     INPUT Variable
15530     RETURN
15540 Rtrn:
15550 SUBEND
```


Table 9-3a. ADEA movement code.

```

10  ! PROGRAM MOVEPLAN -- a unit movement planning aid
20  Frtr=702 'Frtr is the printer
30  PRINTER IS 1
40  OPTION BASE 1
50  DIM Spd(22),Flm(22),Dut(21,100),Dun(21,100),Lc(100),Hlt(21)
60  DIM Back(100) ' used in control move
70  DIM Bran(10),Vehs_in_mu(100),Mus_in_serial(10),Avg_spd(20,100)
80  INTEGER Pf,Id,A,An,I,J
90  ! title routine
100 Home ! clear the screen
110 PRINT TABXY(26,6);"UNIT PLANNING AID FOR MOVEMENT"
120 PRINT TAB(24);"COMMAND CONTROL ANALYSIS DIVISION"
130 PRINT TAB(37);"CAORA"
140 PRINT TAB(27);"FT LEAVENWORTH, KANSAS 66027"
150 PRINT TAB(33);"AUTOVON 552-3595"
160 WAIT 3
161 PRINT
162 PRINT
164 PRINT "THIS PROGRAM HAS BEEN SUBSTITUED FOR THE ORIGINAL P9"
165 PRINT "MOVEMENT CALCULATOR BY ROB BELFLOWER, BDM"
166 PRINT
167 PRINT "THIS PROGRAM REQUIRES A DATA FILE ON THE DEFAULT MASS"
168 PRINT "STORAGE DEVICE. IF THAT IS NOT YOUR HARD DISK, INSERT"
169 PRINT "A FORMATTED MICROFLOPPY DISK INTO YOUR DEFAULT DRIVE"
170 PRINT
171 PRINT "PRESS ENTER TO CONTINUE"
172 INPUT A$
173 Menu:Home
180 Flag=0 ' flag for creating files
190 Flag1=0 ' flag for changing file names
200 Flag2=0 ' flag for changing files
210 PRINT
220 PRINT TAB(1);"THE FOLLOWING CHOICES CAN BE MADE FROM THE MAIN MENU:"
230 PRINT
240 PRINT TAB(1);"1. RUN PROBLEM "
250 PRINT TAB(1);"2. GENERAL PROGRAM INFORMATION"
260 PRINT TAB(1);"3. QUIT"
270 PRINT TAB(1);"4. CREATE A DATA FILE"
280 PRINT TAB(1);"5. CHANGE A DATA FILE"
290 PRINT TAB(1);"6. GET INPUT SHEET"
300 PRINT TAB(1);"7. DELETE A DATA FILE"
310 PRINT TAB(1);"8. LISTING OF FILES"
320 PRINT
330 DISP "( ENTER 1,2,3,4,5,6,7,OR 8 )"
340 ENTER 2:A
350 IF A<1 OR A>8 THEN GOTO 330
360 ON A GOTO Run_problem,Help,Finish,Run_problem,Change_file,Sheet,Delete_+
e,File_list
370 Help:CALL Information
380 GOTO Menu
390 Sheet:CALL Input_sheet

```

Table 9-3a. ADEA movement code (continued).

```

400 GOTO Menu
410 Finish:Home
420 PRINT TABXY(1,15);"THE END"
421 LOAD "DIME:HF913X,701"
430 STOP
440 Run_problem: ! get inputs and calculate results
450 Home
460 IF A=1 THEN ! if menu choice is #1
470 DISP "IS DATA ON A DISK(1) OR IS DATA KEYBOARD INPUT(2) (ENTER 1 OR 2)
480 ENTER 2;An
490 IF An<1 OR An>2 THEN GOTO 470
500 IF An=1 THEN
510 GOSUB Read_file ! read data from disk
520 GOTO 790
530 END IF
540 Home
550 END IF
560 DISP "NEED A DATA INPUT SHEET ? ENTER Y TO GET INPUT SHEET OTHERWISE PRE
ENTER"
570 GOSUB Answer
580 IF Yes THEN CALL Input_sheet
590 Home
600 GOSUB Data_input
610 IF A=4 THEN ! if creating a data file
620 GOTO Create_file
630 ASSIGN @Path TO File$
640 OUTPUT @Path,1;Spd(*),Klm(*),Hlt(*),Bran(*),Vehs_in_mu(*),Lc(*),Face,V
_int,Veh_length,Unint,Nunit,Slint,Nseg,Lenng,Colng,Nser1,Mus_in_serial(*),Vehs
650 ASSIGN @Path TO *
660 GOTO Menu
670 END IF
680 IF An=2 THEN ! if keyboard input
690 DISP "WANT TO SAVE INPUT DATA TO A FILE ? ENTER Y TO SAVE OTHERWISE FF
S ENTER"
700 GOSUB Answer
710 IF Yes THEN
720 Flag=1
730 GOTO Create_file
740 ASSIGN @Path TO File$
750 OUTPUT @Path,1;Spd(*),Klm(*),Hlt(*),Bran(*),Vehs_in_mu(*),Lc(*),Face
eh_int,Veh_length,Unint,Nunit,Slint,Nseg,Lenng,Colng,Nser1,Mus_in_serial(*),Ve
760 ASSIGN @Path TO *
770 END IF
780 END IF
790 Home
800 PRINT "RESULTS FROM WHICH MARCH DISCIPLINE?"
810 PRINT "1. HASTY WITH SPEED CHANGES"
820 PRINT "2. HASTY WITH ROLLBACK"
830 PRINT "3. CONTROLLED MOVE"
840 PRINT
850 DISP " ENTER 1 OR 2 OR 3 OR 4 (TO RETURN TO MAIN MENU)"
860 ENTER 2;P#

```

Table 9-3a. ADEA movement code (continued).

```

870 IF Pf<1 OR Pf>4 THEN GOTO 850
880 SELECT Pf
890 CASE <=2 ! if choice is 1 or 2
900 CALL Hasty(Dun(*),Dut(*),Lc(*),K1m(*),Nseg,Spd(*),Face,Unint,Slint,Bra
*),Nunit,Pf)
910 CASE =3 ! if choice is 3
920 CALL Control_move(Unint,Slint,Spd(*),K1m(*),Colng,Dun(*),Dut(*),Face,f
g,Nser1,Bran(*),Lc(*),Back(*),Nunit)
930 CASE =4 ! if choice is 4
940 GOTO Menu
950 END SELECT
960 GOSUB Choose_time
970 GOSUB Output
980 Home
990 GOTO Menu
1000!***** SUBROUTINES *****
1010!
1020!***** this routine prints the results *****
1030 Output:
1040 PRINTER IS Prtr
1050 IF Pf=1 THEN PRINT "HASTYMOVE "
1060 IF Pf=2 THEN PRINT "HASTYMOVE WITH TIMES ROLLBACKED"
1070 IF Pf=3 THEN PRINT "CONTROL MOVE"
1080 PRINT
1090 PRINT
1100 FOR I=1 TO Nunit
1110 FOR J=1 TO Nseg
1120 Tim=Dun(J+1,I)-Dun(J,I)
1130 Avg_spd(J,I)=(60*K1m(J))/Tim ' calculate avg speed
1140 NEXT J
1150 NEXT I
1160 Ttime=Dut(Nseg+1,1)-Dun(1,1)
1170 GOSUB Resting
1180 PRINT TAB(10);"ROAD MOVEMENT TABLE"
1190 PRINT
1200 PRINT "PACE (KMPH)=";FNRound(Face);TAB(39);"VEHICLE INTERVAL (METERS)=";Ve
int
1210 PRINT "AVG SPEED FOR 1ST UNIT (KMPH)=";FNRound((Lenng*60)/Ttime);TAB(39):
ARCH UNIT INTERVAL (KILOMETERS)=";Unint
1220 Img1:IMAGE "LENGTH OF COLUMN(KM)= ",DDDD.DD,# ' print format
1230 PRINT USING Img1:Colng
1240 PRINT TAB(39);"SERIAL INTERVAL (KILOMETERS)=";Slint
1250 PRINT "AVG VEHICLE LENGTH (METERS)=";FNRound(Veh_length)
1260 Img2:IMAGE "VEHICLE DENSITY (VPKM)=",DDDD.D,# ' print format
1270 PRINT USING Img2:Vehs/Colng
1280 PRINT
1290 PRINT
1300 PRINT TAB(8);"MARCH";TAB(14);"NUMBER"
1310 PRINT TAB(1);"SERIAL";TAB(8);"UNIT";TAB(14);" OF";TAB(23);"CHECK";TAB
);"DUE IN";TAB(38);"RELEASE"
1320 PRINT TAB(1);" NO";TAB(8);" NO";TAB(14);"VEHICLES";TAB(23);"POINT";TAB
);"TIME";TAB(37);" TIME REMARKS";TAB(71);"CAST"

```

Table 9-3a. ADEA movement code (continued).

```

1330 PRINT TAB(28);"(HHMM DD)";TAB(37);"(HHMM DD)";TAB(67);"(KMPH) (MPH)"
1340 PRINT
1350 Id=1
1360 FOR I=1 TO Nunit
1370   IF I=Bran(Id) THEN
1380     PRINT TAB(1);" ";Id; ! print serial number
1390     IF Id<Nser1 THEN Id=Id+1
1400   END IF
1410   PRINT TAB(8);I;TAB(14);Vehs_in_mu(I); ! print march unit # and number
1420                                     ! of vehicles in that unit
1430   FOR J=1 TO Nseg+1
1440     PRINT TAB(23);
1450     IF J=1 THEN
1460       A$="SP"
1470     ELSE
1480       IF J=Nseg+1 THEN
1490         A$="RP"
1500       ELSE
1510         A$=VAL$(J-1)
1520       END IF
1530     END IF
1540     Hrsmindays(Dun(J,I),Hours_in,Mins_in,Days_in) ! convert to military
ime
1550     Hrsmindays(Dut(J,I),Hours_out,Mins_out,Days_out)
1560     PRINT USING Img3;A$,Hours_in,Mins_in,Days_in,Hours_out,Mins_out,Days
ut ! print CP,due in and due out time
1570 Img3:IMAGE AA,4X,ZZ,ZZ,"+",ZZ,2X,ZZ,ZZ,"+",ZZ,X,# ! print format
1580     IF Hit(J)>0 THEN
1590       PRINT Hit(J);"-MINUTE REST";TAB(68):
1600     ELSE
1610       PRINT TAB(68);
1620     END IF
1630     IF J<Nseg+1 THEN
1640       PRINT USING Img4;Avg_spd(J,I),Avg_spd(J,I)*.62 ! print speed in k
h and mph
1650 Img4: IMAGE DD.D,2X,DD.D ! print format
1660     ELSE
1670       PRINT
1680     END IF
1690   NEXT J
1700   PRINT
1710 NEXT I
1720 Ff
1730 PRINT TAB(7);"TIME ANALYSIS--FULL COLUMN"
1740 PRINT
1750 PRINT
1760 PRINT "START TIME = ";
1770 Hrsmindays(Dun(1,1),Hrs,Mins,Days)
1780 PRINT USING Img5;Hrs,Mins,Days
1790 PRINT "COMPLETION TIME = ";
1800 Hrsmindays(Dut(Nseg+1,Nunit),Hrs,Mins,Days)
1810 PRINT USING Img5;Hrs,Mins,Days

```

Table 9-3a. ADEA movement code (continued).

```

1820 Img5:IMAGE ZZ,ZZ,"+",ZZ ' print format
1830 Img6:IMAGE DDDD,":",ZZ ' print format
1840 PRINT "MARCH TIME (INCLUDING HALTS) = ";
1850 Hrsmindays(Dut(Nseg+1,Nunit)-Dun(1,1).Hrs,Mins,Days)
1860 PRINT USING Img6;Hrs+Days*24,Mins
1870 PRINT
1880 PRINT
1890 PRINT TAB(8);"TIME";TAB(16);" TIME";TAB(24);" TIME";TAB(32);" TIME";TAB
);" PASSTIME"
1900 PRINT TAB(1);"SERIAL";TAB(8);"LEFT";TAB(16);"CLEARED";TAB(24);"ARRIVED";
B(32);"CLEARED";TAB(39);" AT"
1910 PRINT TAB(1);" NO";TAB(8);" SP";TAB(16);" SP";TAB(24);" RP";TAB(32);
RP";TAB(39);" RP"
1920 PRINT
1930 PRINT
1940 FOR J=1 TO Nser1
1950 PRINT TAB(1);" ";J;
1960 Id=Bran(J)
1970 IF J<Nser1 THEN
1980 Mark=Bran(J+1)-1
1990 ELSE
2000 Mark=Nunit
2010 END IF
2020 Hrsmindays(Dun(1,Id),Hours_in,Mins_in,Days_in) ! time arrive SP
2030 Hrsmindays(Dut(1,Mark),Hours_out,Mins_out,Days_out) ! time cleared SP
2040 Hrsmindays(Dun(Nseg+1,Id),Hrs_inrp,Mins_inrp,Days_inrp) ! arrive RP
2050 Hrsmindays(Dut(Nseg+1,Mark),Hrs_outrp,Mins_outrp,Days_outrp) ! clear
2060 Hrsmindays(Dut(Nseg+1,Mark)-Dun(Nseg+1,Id),Hrs,Mins,Days) !passtime at
2070 PRINT USING Img7;Hours_in,Mins_in,Days_in,Hours_out,Mins_out,Days_out,
s_inrp,Mins_inrp,Days_inrp,Hrs_outrp,Mins_outrp,Days_outrp,Hrs+Days*24,Mins
2080 Img7:IMAGE ZZ,ZZ,"+",ZZ,2X,ZZ,ZZ,"+",ZZ,2X,ZZ,ZZ,"+",ZZ,2X,ZZ,ZZ,"+",ZZ,
D,":",ZZ ' print format
2090 NEXT J
2100 Ff
2110 PRINT TAB(17);"ROUTE"
2120 PRINT TAB(14);"DESCRIPTION"
2130 PRINT
2140 PRINT
2150 PRINT "ROAD";TAB(20);"MAX RATE"
2160 PRINT "SEGMENT";TAB(9);"DISTANCE";TAB(20);"OF TRAVEL"
2170 PRINT TAB(9);" (KM)";TAB(14);" (MI)";TAB(21);" (KMPH) "
2180 PRINT
2190 FOR I=1 TO Nseg
2200 PRINT TAB(4);I;TAB(9);
2210 IF K1m(I)<1 THEN PRINT USING Img8;K1m(I),K1m(I)*.62
2220 IF K1m(I)>1 THEN PRINT FNRound(K1m(I));TAB(14);FNRound(K1m(I)*.62);
2230 PRINT TAB(22);FNRound(Spd(I))
2240 NEXT I
2250 Img8:IMAGE .DD,2X,.DD,# 'print format
2260 Ff
2270 Ff
2280 PRINTER IS 1

```

Table 9-3a. ADEA movement code (continued).

```

2290 RETURN
2300 !***** this routine adds on halt times *****
2310 Resting: !
2320 FOR I=1 TO Nseg+1
2330 IF Hlt(I)>0 THEN
2340 FOR J=I TO Nseg+1
2350 FOR K=1 TO Nunit
2360 IF J<>I THEN Dun(J,K)=Dun(J,K)+Hlt(I)
2370 Dut(J,K)=Dut(J,K)+Hlt(I)
2380 NEXT K
2390 NEXT J
2400 END IF
2410 NEXT I
2420 RETURN
2430 !***** this routine allows user to define start or arrival time *****
2440 Choose_time: !
2450 MAT Dun= (60)*Dun ! change from hours to minutes
2460 MAT Dut= (60)*Dut
2470 Halt_total=0
2480 FOR I=1 TO Nseg+1
2490 Halt_total=Halt_total+Hlt(I) ! total time of all halts
2500 NEXT I
2510 Totaltime=Dut(Nseg+1,Nunit)+Halt_total
2520 Hours=INT(Totaltime/60)
2530 Mins=FNRound(Totaltime MOD 60)
2540 Home
2550 PRINT TABXY(1,12);"THE MOVE TAKES";
2560 PRINT " ";Hours;" ";"HOURS AND ";Mins;" MINUTES"
2570 PRINT
2580 Id=99
2590 PRINT TABXY(1,19);"[1]DO YOU WANT TO COMPUTE A START TIME BASED ON AN ARRIVAL
VAL DEFINED BY YOU ?"
2600 PRINT TAB(1);"[2]DO YOU WANT TO COMPUTE AN ARRIVAL TIME BASED ON A START
IME DEFINED BY YOU ?"
2610 INPUT "ENTER 1 OR 2 OR 0(TO RETURN TO MAIN MENU)",Id
2620 IF Id<0 OR Id>2 THEN GOTO 2610
2630 SELECT Id
2640 CASE =0
2650 GOTO Menu
2660 CASE =1
2670 Time_input("DUE TIME","TO THE DUE DATE",Alfa)
2680 Home
2690 PRINT TABXY(1,23);"ENTER THE CURRENT TIME IN MILITARY CLOCK"
2700 DISP "HOUR(S) (0-24) : "
2710 ENTER 2;A
2720 IF A<0 OR A>24 THEN GOTO 2700
2730 DISP "MINUTE(S) (0-59) : "
2740 ENTER 2;B
2750 IF B<0 OR B>59 THEN GOTO 2730
2760 IF A=0 AND B=0 THEN GOTO 2700
2770 IF A=24 AND B<>0 THEN GOTO 2700
2780 Now=B+(60*A)

```

Table 9-3a. ADEA movement code (continued).

```

2790     IF Alfa>=Totaltime+Now THEN
2800         Alfa=Alfa-Totaltime
2810         MAT Dun= Dun+(Alfa)
2820         MAT Dut= Dut+(Alfa)
2830     ELSE
2840         Home
2850         PRINT TABXY(1,12):"THERE IS NOT ENOUGH TIME TO EXECUTE THE MOVE"
2860         PRINT
2870         PRINT
2880         PRINT "ENTER C TO CHANGE EITHER THE DUE TIME OR THE CURRENT TIME OR"
2890         PRINT "ENTER R TO RETURN TO MAIN MENU "
2900         ENTER 2;An$
2910         IF An$="R" THEN GOTO Menu
2920         IF An$="C" THEN GOTO 2670
2930         Home
2940         GOTO 2880
2950     END IF
2960     Id=0
2970     CASE =2
2980     Time_input("STARTING TIME","FROM TODAY
TO THE DEPARTURE DATE",Alfa)
2990     MAT Dun= Dun+(Alfa)
3000     MAT Dut= Dut+(Alfa)
3010     END SELECT
3020     RETURN
3030     !***** file routines *****!
3040     !
3050     !**** this routine prints a listing of files ****
3060     File_list:Home
3070     ON ERROR GOTO Err3
3080     CAT
3090     DISP "PRESS ENTER TO RETURN TO MENU"
3100     ENTER 2;C$
3110     OFF ERROR
3120     GOTO Menu
3130     !**** this routine deletes files ****
3140     Delete_file:Home
3150     DISP "ENTER FILE NAME TO BE DELETED"
3160     ENTER 2;File$
3170     IF File$[1,8]<>"MOVEPLAN" THEN ! don't delete main program file
3180         ON ERROR GOTO Err3
3190         PURGE File$
3200     ELSE
3210         Home
3220         PRINT TABXY(1,15):"ERROR--YOU TRIED TO DELETE MAIN PROGRAM"
3230         WAIT 3
3240         DISP "ENTER Y TO TRY AGAIN OTHERWISE PRESS RETURN"
3250         GOSUB Answer
3260         IF Yes THEN GOTO Delete_file
3270         GOTO Menu
3280     END IF
3290     OFF ERROR

```

Table 9-3a. ADEA movement code (continued).

```

3300 GOTO Menu
3310 !***** this routine allows changes to made to data files *****
3320 Change_file:Home
3330 Flag2=1
3340 GOSUB Open_file
3350 ENTER @Path,1;Spd(*),K1m(*),Hlt(*),Bran(*),Vehs_in_mu(*),Lc(*),Face,Veh_
t,Veh_length,Unint,Nunit,Slint,Nseq,Lenng,Colng,Nser1,Mus_in_serial(*),Vehs
3360 ASSIGN @Path TO *
3370 GOSUB Data_input
3380 Home
3390 WAIT 2
3400 DISP "TO SAVE THIS DATA ON A DIFFERENT FILE THAN ";File$;" ENTER Y OTH
WISE PRESS ENTER"
3410 GOSUB Answer
3420 IF Yes THEN
3430     Flag1=1
3440     GOSUB Open_file
3450     ON ERROR GOTO Err2
3460     CREATE BDAT File$,1,4500
3470 END IF
3480 ASSIGN @Path TO File$
3490 OUTPUT @Path,1;Spd(*),K1m(*),Hlt(*),Bran(*),Vehs_in_mu(*),Lc(*),Face,Veh_
nt,Veh_length,Unint,Nunit,Slint,Nseq,Lenng,Colng,Nser1,Mus_in_serial(*),Vehs
3500 ASSIGN @Path TO *
3510 OFF ERROR
3520 GOTO Menu
3530 !***** this routine opens files *****
3540 Open_file:ON ERROR GOTO Err1
3550 Home
3560 DISP "ENTER FILE NAME (10 ALPHANUMERIC CHARACTERS IS MAX)"
3570 ENTER 2;File$
3580 IF LEN(File$)>10 THEN GOTO 3560
3590 ASSIGN @Path TO File$
3600 OFF ERROR
3610 RETURN
3620 !***** this routine creates data files *****
3630 Create_file:Home
3640 GOSUB Open_file
3650 ON ERROR GOTO Err2
3660 CREATE BDAT File$,1,4500
3670 OFF ERROR
3680 IF A=4 THEN
3690     GOTO 630
3700 ELSE
3710     GOTO 740
3720 END IF
3730 !***** this routine reads data from files *****
3740 Read_file:!
3750 GOSUB Open_file
3760 OFF ERROR
3770 ENTER @Path,1;Spd(*),K1m(*),Hlt(*),Bran(*),Vehs_in_mu(*),Lc(*),Face,Veh_
t,Veh_length,Unint,Nunit,Slint,Nseq,Lenng,Colng,Nser1,Mus_in_serial(*),Vehs

```


Table 9-3a. ADEA movement code (continued).

```

3780 ASSIGN @Path TO *
3790 RETURN
3800 '***** error routines *****'
3810 Err1:OFF ERROR
3820 IF ERRN=80 THEN
3830   Home
3840   PRINT TABXY(1,15);"ERROR--DISK IS NOT IN CORRECT DRIVE"
3850   WAIT 3
3860   GOTO 3540
3870 END IF
3880 IF ERRN=53 THEN
3890   Home
3900   PRINT TABXY(1,15);"ERROR--INVALID FILE NAME"
3910   WAIT 3
3920   GOTO 3540
3930 END IF
3940 IF ERRN=56 THEN
3950   IF NOT Flag AND A<>4 AND NOT Flag1 THEN
3960     Home
3970     PRINT TABXY(1,15);"ERROR--FILE DOESN'T EXIST"
3980     WAIT 3
3990     DISP "ENTER Y TO TRY AGAIN OTHERWISE PRESS ENTER"
4000     GOSUB Answer
4010     IF Yes THEN
4020       GOTO 3540
4030     ELSE
4040       GOTO Menu
4050     END IF
4060   END IF
4070 END IF
4080 GOTO 3610
4090 Err2:OFF ERROR
4100 Home
4110 PRINT TABXY(1,15);"ERROR--FILE ALREADY EXISTS"
4120 WAIT 3
4130 IF Flag1 THEN
4140   GOTO 3440
4150 ELSE
4160   GOTO 3630
4170 END IF
4180 Err3:OFF ERROR
4190 Home
4200 IF ERRN=80 THEN
4210   PRINT TABXY(1,15);"ERROR--DISK IS NOT IN DRIVE"
4220   WAIT 2
4230   IF A=7 THEN GOTO Delete_file
4240   GOTO Menu
4250 END IF
4260 PRINT TABXY(1,15);"ERROR--FILE DOESN'T EXIST"
4270 WAIT 3
4280 DISP "ENTER Y TO TRY AGAIN OTHERWISE PRESS RETURN"
4290 GOSUB Answer

```

Table 9-3a. ADEA movement code (continued).

```

4300 IF Yes THEN GOTO Delete_file
4310 GOTO Menu
4320 !***** MORE SUBROUTINES *****
4330 !
4340 !***** this routine inputs and changes data *****
4350 Data_input:!
4360 IF Flag2 THEN
4370     DISP "PACE =";Pace;" ENTER Y TO CHANGE OTHERWISE PRESS ENTER"
4380     GOSUB Answer
4390 END IF
4400 IF Yes OR NOT Flag2 THEN
4410     DISP "ENTER THE PACE (THE MAX SPEED OF THE SLOWEST VEHICLE)"
4420     ENTER 2;Pace
4430     IF Pace<=0 OR Pace>76 THEN GOTO 4410
4440 END IF
4450 IF Flag2 THEN
4460     DISP "VEHICLE INTERVAL =";Veh_int;" ENTER Y TO CHANGE OTHERWISE PRESS
ENTER"
4470     GOSUB Answer
4480 END IF
4490 IF Yes OR NOT Flag2 THEN
4500     DISP "ENTER VEHICLE INTERVAL IN METERS"
4510     ENTER 2;Veh_int
4520     IF Veh_int<=0 OR Veh_int>999 THEN GOTO 4500
4530 END IF
4540 IF Flag2 THEN
4550     DISP "AVG VEHICLE LENGTH =";Veh_length;" ENTER Y TO CHANGE OTHERWISE P
ESS ENTER"
4560     GOSUB Answer
4570 END IF
4580 IF Yes OR NOT Flag2 THEN
4590     DISP "ENTER THE AVG VEHICLE LENGTH IN METERS"
4600     ENTER 2;Veh_length
4610     IF Veh_length<=0 OR Veh_length>99 THEN GOTO 4590
4620 END IF
4630 IF Flag2 THEN
4640     DISP "MARCH UNIT INTERVAL=";Unint;" ENTER Y TO CHANGE OTHERWISE PRESS
ENTER"
4650     GOSUB Answer
4660 END IF
4670 IF Yes OR NOT Flag2 THEN
4680     DISP "ENTER MARCH UNIT INTERVAL IN KM"
4690     ENTER 2;Unint
4700     IF Unint<=0 OR Unint>9 THEN GOTO 4680
4710 END IF
4720 IF Flag2 THEN
4730     DISP "SERIAL INTERVAL IN KM =";Sint;" ENTER Y TO CHANGE OTHERWISE PRE
S ENTER"
4740     GOSUB Answer
4750 END IF
4760 IF Yes OR NOT Flag2 THEN
4770     DISP "ENTER SERIAL INTERVAL IN KILOMETERS"

```

Table 9-3a. ADEA movement code (continued).

```

4780   ENTER 2;Slint
4790   IF Slint<=0 OR Slint>25 THEN GOTO 4770
4800   END IF
4810   IF Flag2 THEN
4820     DISP "NUMBER OF ROAD SEGMENTS =";Nseg;" ENTER Y TO CHANGE OTHERWISE F
SS ENTER"
4830     GOSUB Answer
4840   END IF
4850   IF Yes OR NOT Flag2 THEN
4860     DISP "A MAX OF 20 ROAD SEGMENTS CAN BE USED ";
4870     DISP "FOR A GIVEN ROUTE. ENTER # OF SEGMENTS"
4880     ENTER 2;Nseg
4890     Nseg=INT(Nseg)
4900     IF Nseg<=0 OR Nseg>20 THEN GOTO 820
4910     Home
4920   END IF
4930   FOR I=1 TO Nseg
4940     IF Flag2 THEN
4950       IF Spd(I)=0 THEN GOTO 5000
4960       DISP "FOR SEGMENT";I;" SPEED =";Spd(I);" ENTER Y TO CHANGE OTHERWISE
PRESS ENTER"
4970       GOSUB Answer
4980     END IF
4990     IF Yes OR NOT Flag2 THEN
5000       DISP "ENTER MAX SPEED IN KMPH FOR ROAD SEGMENT";I
5010       ENTER 2;Spd(I)
5020       IF Spd(I)<=0 OR Spd(I)>100 THEN GOTO 5000
5030     END IF
5040     IF Flag2 THEN
5050       IF K1m(I)=0 THEN GOTO 5100
5060       DISP "FOR SEGMENT";I;" DISTANCE=";K1m(I);" ENTER Y TO CHANGE OTHERW
E PRESS ENTER"
5070       GOSUB Answer
5080     END IF
5090     IF Yes OR NOT Flag2 THEN
5100       DISP "ENTER DISTANCE IN KM FOR ROAD SEGMENT";I
5110       ENTER 2;K1m(I)
5120       IF K1m(I)<=0 THEN GOTO 5100
5130     END IF
5140   NEXT I
5150   Lenng=0
5160   FOR I=1 TO Nseg
5170     Lenng=Lenng+K1m(I) ! total length of route
5180   NEXT I
5190   IF Flag2 THEN
5200     DISP "NUMBER OF SERIALS =";Nser1;" ENTER Y TO CHANGE OTHERWISE PRESS
TER"
5210     GOSUB Answer
5220   END IF
5230   IF Yes OR NOT Flag2 THEN
5240     DISP "ENTER THE NUMBER OF SERIALS ";
5250     DISP "(MAX IS 10)"

```

Table 9-3a. ADEA movement code (continued).

```

5260   ENTER 2;Nser1
5270   Nser1=INT(Nser1)
5280   IF Nser1<=0 OR Nser1>10 THEN GOTO 5240
5290   END IF
5300   Vehs=0
5310   Nunit=0
5320   FOR I=1 TO Nser1
5330     Home
5340     IF Flag2 THEN
5350       IF Mus_in_serial(I)=0 THEN GOTO 5400
5360       DISP "# OF MARCH UNITS IN SERIAL";I;"=";Mus_in_serial(I);" ENTER Y T
CHANGE OTHERWISE PRESS ENTER"
5370       GOSUB Answer
5380     END IF
5390     IF Yes OR NOT Flag2 THEN
5400       DISP "ENTER THE # OF MARCH UNITS IN SERIAL";I;
5410       DISP " (MAX IS 10)"
5420       ENTER 2;Mus_in_serial(I)
5430       Mus_in_serial(I)=INT(Mus_in_serial(I))
5440       IF Mus_in_serial(I)<=0 OR Mus_in_serial(I)>10 THEN GOTO 5400
5450     END IF
5460     Munit=Mus_in_serial(I)
5470     Nunit=Nunit+Munit ! total number of march units
5480     Bran(I)=Nunit-Munit+1 ! marks head of a serial
5490     FOR J=Bran(I) TO Bran(I)+Munit-1
5500       Count=J-Bran(I)+1
5510       IF Flag2 THEN
5520         IF Vehs_in_mu(J)=0 THEN GOTO 5570
5530         DISP "# OF VEHICLES IN MU";Count;"=";Vehs_in_mu(J);" ENTER Y TO CH
GE OTHERWISE PRESS ENTER"
5540         GOSUB Answer
5550       END IF
5560       IF Yes OR NOT Flag2 THEN
5570         DISP "ENTER THE # OF VEHICLES IN MU";Count
5580         ENTER 2;Vehs_in_mu(J)
5590         Vehs_in_mu(J)=INT(Vehs_in_mu(J))
5600         IF Vehs_in_mu(J)<=0 OR Vehs_in_mu(J)>999 THEN GOTO 5570
5610       END IF
5620       Mveh=Vehs_in_mu(J)
5630       Lc(J)=(Veh_length*Mveh)/1000
5640       Lc(J)=Lc(J)+((Veh_int*(Mveh-1))/1000) ! length of march unit
5650       Vehs=Vehs+Mveh ! total number of vehicles
5660     NEXT J
5670   NEXT I
5680   K1m(Nseg+1)=2999
5690   Spd(Nseg+1)=Spd(Nseg)
5700   FOR I=1 TO Nseg+1
5710     Home
5720     IF I=1 THEN I$="SP"
5730     IF I=Nseg+1 THEN I$="RP"
5740     IF I<>Nseg+1 AND I<>1 THEN I$=VAL$(I-1)
5750     IF Flag2 THEN

```

Table 9-3a. ADEA movement code (continued).

```

5760     DISP "HALT AT CP-";I$;"="";Hit(I):"  ENTER Y TO CHANGE OTHERWISE PF
        ENTER"
5770     GOSUB Answer
5780     END IF
5790     IF Yes OR NOT Flag2 THEN
5800     DISP "ENTER HALT TIME (IN MINUTES) FOR CP-";I$
5810     ENTER 2;Hit(I)
5820     IF Hit(I)<0 OR Hit(I)>1440 THEN GOTO 5800
5830     END IF
5840     NEXT I
5850     Home
5860     Colng=0
5870     FOR I=1 TO Nunit
5880     Colng=Colng+Lc(I)
5890     NEXT I
5900     Colng=Colng+((Nser1-1)*Slint)
5910     Colng=Colng+((Nunit-Nser1)*Unint)  ! total column length
5920     RETURN
5930     !***** this routine prompts for yes/no answer *****
5940     Answer: !
5950     ENTER 2;B$
5960     IF B$="Y" THEN
5970     Yes=1
5980     ELSE
5990     Yes=0
6000     END IF
6010     RETURN
6020     END
6030     !***** SUB PROGRAMS *****
6040     !
6050     !***** this routine clears the screen *****
6060     SUB Home
6070     DISP "
6080     PRINT CHR$(12)
6090     SUBEND
6100     !***** this routine sets up the nodes for calculations *****
6110     SUB Calculate_nodes(Node(*),Length_segment(*),Key_node(*),Length_serial
eg)
6120     INTEGER I
6130     Node(0)=0
6140     FOR I=0 TO Nseg
6150     Node(I+1)=Node(I)+Length_segment(I)
6160     Node(Nseg+I+1)=Node(I)+Length_serial
6170     NEXT I
6180     MAT SORT Node TO Key_node
6190     MAT SORT Node
6200     SUBEND
6210     !***** this routine calculates speeds over road segments *****
6220     SUB Control_speeds(Speed(*),Maxnode,Segment_speed(*),Length_serial,Face
y_node(*),Nseg)
6230     INTEGER I
6240     DIM Speedlist(40)

```

Table 9-3a. ADEA movement code (continued).

```

6250 MAT Speedlist= (1000.1)
6260 Segment_speed(Nseg)=Segment_speed(Nseg-1)
6270 Speedlist(0)=Pace
6280 Speed_del=1
6290 Speed_add=1
6300 FOR I=0 TO Maxnode
6310     IF Key_node(I)>Nseg THEN
6320         Speedlist(Speed_del)=1000.1 ' node is artificial
6330         Speed_del=Speed_del+1
6340     ELSE ' node is check point
6350         Speedlist(Speed_add)=Segment_speed(Speed_add-1)
6360         Speed_add=Speed_add+1
6370     END IF
6380     Speed(I)=MIN(Speedlist,*)
6390 NEXT I
6400 SUBEND
6410 !***** this routine calculates distance between nodes *****
6420 SUB Calculate_length(Length(*),Node(*),Maxnode)
6430     INTEGER I
6440     FOR I=1 TO Maxnode
6450         Length(I-1)=Node(I)-Node(I-1)
6460     NEXT I
6470 SUBEND
6480 !***** this routine calculates time to travel to node *****
6490 SUB Calculate_times(Maxnode,Speed(*),Length(*),Time(*))
6500     INTEGER I
6510     Time(0)=0
6520     FOR I=1 TO Maxnode
6530         Time(I)=Time(I-1)+Length(I-1)/Speed(I-1)
6540     NEXT I
6550 SUBEND
6560 !***** this function returns the time that the head of the ser- *****
6570 !***** ial crosses the point a distance x from the start point *****
6580 DEF FNCross(X,Time(*),Nodes(*),Speed(*))
6590     N1=1
6600     LOOP
6610     EXIT IF X<Nodes(N1)
6620     N1=N1+1
6630     END LOOP
6640     N1=N1-1
6650     T=Time(N1)+(X-Nodes(N1))/Speed(N1)
6660     RETURN T
6670 FNEND
6680 !***** this routine calculates a controlled move *****
6690 SUB Control_move(Mu_int,Ser_int,Speeds(*),Length_seg(*),Length_serial,Dut
*),Dut(*),Pace,Nseg,Nser,Bran(*),Lc(*),Back(*),Nunit)
6700     DIM Nodes(41),Key_nodes(41),Speed(21),Length_segment(21),Length(41),Ti
(41),Speed_art(41)
6710     REDIM Nodes(2*Nseg+1),Key_nodes(2*Nseg+1)
6720     INTEGER I,J
6730     MAT Speed= Speeds
6740     MAT Length_segment= Length_seg

```

Table 9-3a. ADEA movement code (continued).

```

6750     Maxnode=2*Nseg+1
6760     CALL Calculate_nodes(Nodes(*),Length_segment(*),Fev_nodes(*),Length_ser-
al,Nseg)
6770     CALL Control_speeds(Speed_art(*),Maxnode,Speed(*),Length_serial,Face_
_nodes(*),Nseg)
6780     CALL Calculate_lengt(Length(*),Nodes(*),Maxnode)
6790     CALL Calculate_times(Maxnode,Speed_art(*),Length(*),Time(*))
6800     FOR I=2 TO Nunit
6810         Back(I)=Back(I-1)+Mu_int+Lc(I-1)
6820     NEXT I
6830     FOR I=2 TO Nser
6840         FOR L=Bran(I) TO Nunit
6850             Back(L)=Back(L)-Mu_int+Ser_int
6860         NEXT L
6870     NEXT I
6880     MAT SORT Key_nodes TO key_nodes
6890     FOR I=1 TO Nunit
6900         FOR J=1 TO Nseg+1
6910             X1=Nodes(Key_nodes(J-1))+Back(I)
6920             X2=X1+Lc(I)
6930             Dun(J,I)=FNCross(X1,Time(*),Nodes(*),Speed_art(*))
6940             Dut(J,I)=FNCross(X2,Time(*),Nodes(*),Speed_art(*))
6950         NEXT J
6960     NEXT I
6970     SUBEND
6980     '***** this function rounds to nearest integer
6990     DEF FNRound(X)
7000         RETURN INT(X+.5)
7010     FNEND
7020     '***** this routine tab feeds the page in the printer *****
7030     SUB Ff
7040         PRINT CHR$(12)
7050     SUBEND
7060     '***** this routine prints a data input sheet *****
7070     SUB Input_sheet
7080         INTEGER C,D
7090         PRINTER IS 702
7100         PRINT TAB(32):"DATA INPUT SHEET"
7110         PRINT
7120         PRINT "FACE SPEED _____ KMPH  "
7130         PRINT "VEHICLE INTERVAL _____ METERS      AVG VEHICLE LENGTH _____ MET
S"
7140         PRINT "MARCH UNIT INTERVAL _____ KM      SERIAL INTERVAL _____ FM"
7150         PRINT
7160         PRINT "# OF ROAD SEGMENTS IN ROUTE ____"
7170         PRINT
7180         PRINT "SEGMENT#  MAX RATE (KMPH)  DISTANCE (FM)  SEGMENT#  MAX RATE (KMPH)
DISTANCE (FM)"
7190         FOR D=1 TO 10
7200             PRINT TAB(3):D;TAB(13):"_____"
7210         NEXT D

```

Table 9-3a. ADEA movement code (continued).

```

7220 PRINT
7230 PRINT "# OF SERIALS ____"
7240 PRINT
7250 FOR D=1 TO 5
7260 PRINT "SERIAL NUMBER";D;TAB(40);"SERIAL NUMBER";D+5
7270 PRINT "# OF MARCH UNITS IN SERIAL";D;"____";TAB(40);"# OF MARCH UNIT
IN SERIAL";D+5;"____"
7280 PRINT "MU# # OF VEHICLES";TAB(40);"MU# # OF VEHICLES"
7290 FOR C=1 TO 10
7300 PRINT TAB(1);C;TAB(11);"____";TAB(40);C;TAB(50);"____"
7310 NEXT C
7320 PRINT
7330 NEXT D
7340 PRINT
7350 PRINT " CP HALT TIME(MINS) CP HALT TIME(MINS) CP HALT T
E(MINS)"
7360 FOR D=1 TO 7
7370 IF D=1 THEN
7380 PRINT TAB(2);"SP";
7390 ELSE
7400 PRINT TAB(1);D-1;
7410 END IF
7420 PRINT TAB(10);"____";TAB(26);D+6;TAB(35);"____";
7430 IF D=7 THEN
7440 PRINT TAB(52);"RP";TAB(60);"____"
7450 ELSE
7460 PRINT TAB(51);D+13;TAB(60);"____"
7470 END IF
7480 NEXT D
7490 PRINT
7500 PRINT "RESULTS FROM WHICH MARCH DISCIPLINE (CIRCLE ONE)"
7510 PRINT
7520 PRINT "1. HASTY WITH SPEED CHANGES"
7530 PRINT "2. HASTY WITH ROLLBACK"
7540 PRINT "3. CONTROLLED MOVE"
7550 PRINT
7560 PRINT
7570 PRINT "DESIRED START TIME _____ OR DESIRED ARRIVAL TIME _____"
7580 PRINT "NUMBER OF DAYS TO DEPARTURE _____"
7590 PRINT CHR$(12)
7600 PRINT CHR$(12)
7610 PRINTER IS 1
7620 SUBEND
7630 !***** this routine converts time to military clock *****
7640 SUB Hrsmindays(Minutes,Hrs,Mins,Days)
7650 M=FNRound(Minutes)
7660 Days=M DIV 1440
7670 Hrs=(M MOD 1440) DIV 60
7680 Mins=FNRound((M MOD 1440) MOD 60)
7690 IF (Hrs=0 AND Mins=0 AND M<>0) THEN
7700 Hrs=24
7710 Days=Days-1

```


Table 9-3a. ADEA movement code (continued).

```

7720     END IF
7730     SUBEND
7740     !***** this routine prompts for a start time or due time *****
7750     SUB Time_input(A1$,A2$,Alfa)
7760         INTEGER A,B
7770         Home
7780         PRINT TABXY(1,23);"ENTER THE ";A1$;" IN MILITARY CLOCK"!A1$ IS STARTING
TIME OR DUE TIME
7790         DISP "HOUR(S)    (0-24) : "
7800         ENTER 2;A
7810         IF A<0 OR A>24 THEN GOTO 7790
7820         DISP "MINUTE(S) (0-59) : "
7830         ENTER 2;B
7840         IF B<0 OR B>59 THEN GOTO 7820
7850         IF A=0 AND B=0 THEN GOTO 7790
7860         IF A=24 AND B<>0 THEN GOTO 7790
7870         Zorro=B+(60*A)
7880         Home
7890         PRINT TABXY(1,23);"ENTER THE NUMBER OF DAYS ";A2$
7900         PRINT "(e.g. ENTER 2 FOR THE DAY AFTER TOMMOROW)"
7910         ENTER 2;Mark
7920         IF Mark<0 OR Mark>365 THEN GOTO 7890
7930         Alfa=Zorro+(Mark*1440)
7940     SUBEND
7950     !***** this routine provides general information to the user *****
7960     SUB Information
7970         Home
7980         PRINT TABXY(1,6);"STEP ONE-ORGANIZE ROUTE INFORMATION"
7990         PRINT
8000         PRINT TAB(4);"LIST ON THE INPUT SHEET, BY ROAD"
8010         PRINT TAB(4);"SEGMENT, THE LENGTH AND MAXIMUM"
8020         PRINT TAB(4);"TRAVEL RATE FOR EACH SEGMENT."
8030         PRINT TAB(4);"LIST ON THE INPUT SHEET, ANY"
8040         PRINT TAB(4);"HALT TIMES FOR ANY CHECK POINT."
8050         PRINT
8060         PRINT
8070         INPUT "PRESS ENTER TO CONTINUE",An$
8080         Home
8090         PRINT TABXY(1,6);"STEP TWO-ORGANIZE SERIAL INFORMATION"
8100         PRINT
8110         PRINT
8120         PRINT TAB(1);"LIST ON THE INPUT SHEET, BY SERIAL, THE"
8130         PRINT TAB(1);"NUMBER OF MARCH UNITS IN EACH SERIAL AND"
8140         PRINT TAB(1);"THEN NUMBER OF VEHICLES IN EACH MARCH"
8150         PRINT TAB(1);"UNIT.          ENTER IN SERIAL ORDER"
8160         PRINT TAB(1);"IE. (SERIAL1,MU1), (SERIAL1,MU2),...."
8170         PRINT TAB(1);"(SERIALN,MU1),.... (SERIALN,MUQ)."

```

Table 9-3a. ADEA movement code (continued).

```

8230 PRINT
8240 PRINT
8250 PRINT TAB(1): "THE FOLLOWING CONSTANTS ARE REQUIRED:"
8260 PRINT TAB(1): "MAXIMUM SPEED FOR LEAD VEHICLE (PACE)"
8270 PRINT TAB(1): "VEHICLE INTERVAL"
8280 PRINT TAB(1): "AVERAGE VEHICLE LENGTH"
8290 PRINT TAB(1): "MARCH UNIT INTERVAL"
8300 PRINT TAB(1): "SERIAL INTERVAL"
8310 PRINT TAB(1): "MARCH DISCIPLINE"
8320 PRINT TAB(1): "START TIME OR ARRIVAL TIME"
8330 PRINT TAB(1): "NUMBER OF DAYS TO DEPARTURE"
8340 PRINT
8350 PRINT
8360 INPUT "PRESS ENTER TO CONTINUE", An$
8370 PRINT
8380 PRINT
8390 PRINT TAB(25): "MOVEMENT RATE GUIDE (UNOPPOSED)"
8400 PRINT TAB(37): "(KMPH)"
8410 PRINT
8420 PRINT TAB(44): "WEATHER CONDITIONS"
8430 PRINT TAB(40): "(DAY/N-LIGHTS/N-BLACKOUT)"
8440 PRINT TAB(8): "
                                LIGHT          F
/HVY"
8450 PRINT TAB(8): "TERRAIN    UNIT TYPE    GOOD    PRECIPITATION  PREC
ITATION"
8460 PRINT TAB(8): "ROAD      FOOT TRPS   4/3.2/3.2   3.2/2.5/2.5   2.4
.9/1.9"
8470 PRINT TAB(8): "          TRK, GENRL   40/40/16    32/32/12.8    2
24/9.6"
8480 PRINT TAB(8): "          TRCKD VEH   24/24/16    16.8/16.8/11.2  1
12/8"
8490 PRINT TAB(8): "          ARTY, TRCK  40/40/16    32/32/16      2
24/9.6"
8500 PRINT TAB(8): "          ARTY, TRCTR  32/32/16    22.4/22.4/11.2  1
16/8"
8510 PRINT
8520 PRINT TAB(8): "X-COUNTRY FOOT TRPS   2.4/1.6/1.6   1.9/1.2/1.2   1.4
.9/0.9"
8530 PRINT TAB(8): "          TRK, GENRL   12/12/8     9.6/6.4/6.4   7.5
.8/4.8"
8540 PRINT TAB(8): "          TRCKD VEH   14/8/8      11.2/5.6/5.6
/8/4"
8550 PRINT TAB(8): "          ARTY, TRCK  12/8/8      9.6/6.4/6.4   7.5
.8/4.8"
8560 PRINT TAB(8): "          ARTY, TRCTR  16/8/8      11.2/5.5/5.6
8/4"
8570 DISP "PRESS ENTER TO CONTINUE"
8580 ENTER 2: An$
8590 SUBEND
8600 !***** this routine calculates a hasty move with speed *****
8610 !***** changes or a hasty move with times rolledback *****
8620 SUB Hasty(Dun(*), Dut(*), Lc(*), Flm(*), Nseq, Spd(*), Pace, Mu_int, Ser_int, Rr-

```

Table 9-3a. ADEA movement code (concluded).

```

*) , Nunit, INTEGER Pf)
8630 DIM Nodes(41), Key_nodes(41), Speed(21), Length_segment(21), Length(41), Time
(41), Speed_art(41), Due_diff(20)
8640 REDIM Nodes(2*Nseg+1), Key_nodes(2*Nseg+1)
8650 INTEGER I, J
8660 MAT Speed= Spd
8670 MAT Length_segment= Klm
8680 Maxnode=2*Nseg+1
8690 FOR I=1 TO Nunit
8700 CALL Calculate_nodes(Nodes(*), Length_segment(*), Key_nodes(*), Lc(I), N
g)
8710 Control_speeds(Speed_art(*), Maxnode, Speed(*), Lc(I), Face, Key_nodes(*
seg)
8720 Calculate_lengt(Length(*), Nodes(*), Maxnode)
8730 Calculate_times(Maxnode, Speed_art(*), Length(*), Time(*))
8740 MAT SORT Key_nodes TO Key_nodes
8750 FOR J=1 TO Nseg+1
8760 X1=Nodes(Key_nodes(J-1))
8770 X2=X1+Lc(I)
8780 Dun(J, I)=FNCross(X1, Time(*), Nodes(*), Speed_art(*))
8790 Dut(J, I)=FNCross(X2, Time(*), Nodes(*), Speed_art(*))
8800 NEXT J
8810 NEXT I
8820 FOR I=2 TO Nunit
8830 FOR J=1 TO Nseg+1
8840 Gap=Mu_int
8850 FOR k=2 TO SIZE(Bran, 1)
8860 IF I=Bran(k) THEN Gap=Ser_int
8870 NEXT k
8880 Gap=Gap/Face
8890 IF Pf=1 THEN ! if hasty with speed changes
8900 IF J<Nseg+1 THEN Due_diff(J)=Dun(J+1, I)-Dun(J, I)
8910 Diff=Dut(J, I)-Dun(J, I)
8920 IF J>1 THEN
8930 Dun(J, I)=Dun(J-1, I)+Due_diff(J-1)
8940 IF Dun(J, I)<Dut(J, I-1)+Gap THEN Dun(J, I)=Dut(J, I-1)+Gap
8950 ELSE
8960 Dun(J, I)=Dut(J, I-1)+Gap
8970 END IF
8980 Dut(J, I)=Dun(J, I)+Diff
8990 END IF
9000 IF Pf=2 THEN ! if hasty with rollback
9010 IF Dun(J, I)<Dut(J, I-1)+Gap THEN
9020 Delay=Dut(J, I-1)+Gap-Dun(J, I)
9030 FOR k=1 TO Nseg+1
9040 Dun(k, I)=Dun(k, I)+Delay
9050 Dut(k, I)=Dut(k, I)+Delay
9060 NEXT k
9070 END IF
9080 END IF
9090 NEXT J
9100 NEXT I
9110 SUREND

```

CHAPTER 10

UNIT STATUS REPORT

1. PURPOSE.

The purpose of the DIME unit status report (P8) is to generate reports summarizing divisional activities for a six-hour period.

2. GENERAL.

A. Unit history. The unit history is a cumulative display of ammunition levels remaining after the six-hour critical incident (CI). These values, along with current mission, combat effectiveness, and ammunition/fuel (AMMO/POL) logistics data, are given for each active unit in the "UNITFILE." (See Figure 10-1.)

B. Killer/victim summary. The killer/victim (K/V) segment of the DIME unit status report (P8) generates two reports: a killer/victim scoreboard and attack helicopter results. The K/V scoreboard shows both Blue vs. Red and Red vs. Blue. (See Figure 10-2.)

C. Gamer/staff worksheets. Gamer/staff worksheets are printed for each active unit in the CI. Information from the unit history is used to calculate resupply values which are input from the worksheets in the game initialization program (P1). (See Figure 10-3.)

3. DATA FLOW.

Data used in P8 consist of interactive question/answer information and external data files.

A. Operator input.

(1) It is possible to enter P8 anytime during a game turn in order to obtain a current K/V scoreboard. By answering "Y" to the question "Killer/victim table listing only?", calculations or updates are made to the "UNITFILE." The questions concerning attrition and game turn identification which follow must then be answered. The K/V summary is the only portion printed before control returns to the DIME menu.

UNIT HISTORY FOR GAME 1 TURN 2

RED UNITS:

UNIT: 66 111HTB TYPE: 2.0 ACTIVE CBT-EFF: .80 MISSION: 2.0

SYSTEMS REMAINING:

1: 17.4 2: 11.5 3: .8 4: 0.0 5: 4.0 6: 0.0 7: 9.1
 8: .6 9: 8.8 10: 100.9 11: 0.0 12: .4 13: 0.0 14: 3.8
 15: 0.0 16: 0.0 17: 1.9 18: .1 19: 5.0 20: 43.0 21: 9.0

DETECTION: NOT DET SENS STATUS (Z/G): 4.4 FRA CVG: .50 KM MOVED: 0

AIR DEFENSE: SUPPRESSION: 0.00 CORPS SUPPORT ADA: 71

LOGISTICS:

TYPE	STATUS	PROFILE	CONSUMED	RESUPPLY	ON-TRK	ON-GND	DISPND	ON-VEH	CURRNT	USD/DT
DF	1.00	2	9	0	181	749	0	92	1011	9
IF	1.00	2	10	0	16	67	0	3	86	11
AD	1.00	2	1	0	18	76	0	1	95	2
FU	.26	2	3826	0	0	0	0	3193	3193	12641

EQUIVALENT EMPTY AMMO TRUCKS 0

UNIT: 67 112HTB TYPE: 2.0 ACTIVE CBT-EFF: .80 MISSION: 2.0

SYSTEMS REMAINING:

1: 25.7 2: 11.5 3: .8 4: 0.0 5: 4.0 6: 0.0 7: 9.1
 8: .6 9: 0.0 10: 100.9 11: 0.0 12: .4 13: 0.0 14: 3.8
 15: 0.0 16: 0.0 17: 1.9 18: .1 19: 5.0 20: 43.0 21: 9.0

DETECTION: NOT DET SENS STATUS (Z/G): 3.4 FRA CVG: .50 KM MOVED: 0

AIR DEFENSE: SUPPRESSION: 0.00 CORPS SUPPORT ADA: 71

LOGISTICS:

TYPE	STATUS	PROFILE	CONSUMED	RESUPPLY	ON-TRK	ON-GND	DISPND	ON-VEH	CURRNT	USD/DT
DF	1.00	2	9	0	182	800	0	80	1063	10
IF	1.00	2	10	0	15	68	0	3	86	11
AD	1.00	2	1	0	18	77	0	1	95	2
FU	.24	2	4866	0	0	0	0	2885	2885	14721

EQUIVALENT EMPTY AMMO TRUCKS 0

UNIT: 68 113HTB TYPE: 2.0 ACTIVE CBT-EFF: .80 MISSION: 2.0

SYSTEMS REMAINING:

1: 25.7 2: 11.5 3: .8 4: 0.0 5: 4.0 6: 0.0 7: 9.1
 8: .6 9: 0.0 10: 100.9 11: 0.0 12: .4 13: 0.0 14: 3.8
 15: 0.0 16: 0.0 17: 1.9 18: .1 19: 5.0 20: 43.0 21: 9.0

Figure 10-1. Unit history output.

RED KILLER--BLUE VICTIM FILE FOR GAME 1 TURN 2

VICTIM	KILLER									T/KILL
	D/F	I/F	PGM	A/H	INF	MIN	CHM	AIR		
LAV25	7.5	3.1	0.0	2.1	0.0	.1	0.0	3.6	21.4	
FAV-T	10.6	2.1	0.0	1.8	0.0	0.0	0.0	3.9	18.4	
HMM-T	4.2	.9	0.0	.8	0.0	.1	0.0	3.5	9.5	
FAV40	2.5	1.0	0.0	1.8	0.0	0.0	0.0	2.0	7.3	
HMM40	19.3	4.4	0.0	10.0	0.0	.1	0.0	23.8	57.6	
PGATH	0.0	0.0	0.0	0.0	0.0	0.0	0.0	1.7	1.7	
DRAGN	39.7	32.3	0.0	.1	0.0	.6	0.0	5.6	78.3	
	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	
	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	
INFTY	0.0	294.4	0.0	.1	36.9	1.2	0.0	25.2	377.8	
ARTY	0.0	3.4	0.0	21.9	0.0	0.0	0.0	4.4	29.7	
VULCN	0.0	1.1	0.0	1.4	0.0	0.0	0.0	.3	2.8	
MLRS	0.0	.7	0.0	0.0	0.0	0.0	0.0	0.0	.7	
MORTR	0.0	10.9	0.0	0.0	0.0	0.0	0.0	1.2	12.1	
ICHAP	0.0	.5	0.0	.8	0.0	0.0	0.0	.1	1.4	
IHAWK	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	
STING	2.0	7.0	0.0	0.0	0.0	0.0	0.0	.3	9.3	
CMD-V	14.5	5.8	0.0	15.7	0.0	.2	0.0	.3	36.5	
F-TRK	0.0	.1	0.0	0.0	0.0	0.0	0.0	1.6	1.7	
A-TRK	0.0	.6	0.0	.1	0.0	0.0	0.0	14.9	15.6	
SP-VE	12.3	.2	0.0	0.0	0.0	.2	0.0	9.3	22.0	

BLUE KILLER--RED VICTIM FILE FOR GAME 1 TURN 2

VICTIM	KILLER									T/KILL
	D/F	I/F	PGM	A/H	INF	MIN	CHM	AIR		
T80	13.3	3.6	0.0	4.9	0.0	.4	0.0	12.5	34.7	
BMP	7.5	11.4	0.0	2.9	0.0	.4	0.0	2.5	24.7	
BMPB1	1.5	.5	0.0	.5	0.0	0.0	0.0	2.7	5.2	
BTR	7.1	5.6	0.0	13.2	0.0	1.1	0.0	17.5	44.5	
BRDM2	1.9	2.4	0.0	2.7	0.0	.2	0.0	2.7	9.9	
SPAT	.4	.2	0.0	.8	0.0	.1	0.0	.5	2.0	
AT-4	1.2	3.0	0.0	0.0	0.0	.2	0.0	1.3	5.7	
ASUB5	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	0.0	
BMD	0.0	0.0	0.0	0.0	0.0	0.0	0.0	9.5	9.5	
INFTY	104.3	119.4	0.0	118.8	98.0	11.1	0.0	233.8	665.4	
ARTY	0.0	3.4	0.0	9.5	0.0	0.0	0.0	60.8	73.7	
ZSU-X	.4	1.0	0.0	.4	0.0	0.0	0.0	1.8	3.6	
MRL	0.0	2.7	0.0	4.8	0.0	0.0	0.0	19.7	27.2	
MORTR	2.2	26.5	0.0	0.0	0.0	.3	0.0	6.4	35.4	
SA-13	0.0	1.7	0.0	.2	0.0	0.0	0.0	2.3	4.2	
SA-8	0.0	0.0	0.0	0.0	0.0	0.0	0.0	.2	.2	
SA-14	2.5	15.4	0.0	0.0	0.0	0.0	0.0	8.5	26.4	
CMD-V	5.7	7.5	0.0	13.6	0.0	1.3	0.0	32.5	60.6	
F-TRK	0.0	0.0	0.0	.1	0.0	0.0	0.0	5.3	5.4	
A-TRK	0.0	0.0	0.0	.2	0.0	0.0	0.0	40.1	40.3	
SP-VE	15.6	0.0	0.0	.3	0.0	4.0	0.0	32.5	52.4	

ATTACK HELICOPTER RESULTS

TYPE	#KILLED	#SORTIES
AH64	1.9	52.4
LCH	0.0	0.0
AHIP	1.2	4.5
HIND	17.4	49.5

Figure 10-2. Killer/victim scoreboard.

GAMER STAFF WORK SHEET FOR TURN 3

BLUE UNITS:

UNIT 1 LIDTEST TYPE: 1.6
LINE 1: ACTIVITY: 1 HOPP LEVEL: 1 MISSION: 8.0 KM MOVED: 0
LINE 2: SENSOR GP: 4 ZONE: 4 PCT COVERED: 50
LINE 3: PCT ADA SUPPRESSION: VEH: 0 HAND: 0 CORPS ADA: 6
LINE 4: RESUPPLY: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL(gal): __
LINE 5: DISPENSED: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL:(gal) __

UNIT 2 LID1-DRD TYPE: 1.6
LINE 1: ACTIVITY: 1 HOPP LEVEL: 1 MISSION: 8.0 KM MOVED: 0
LINE 2: SENSOR GP: 4 ZONE: 4 PCT COVERED: 50
LINE 3: PCT ADA SUPPRESSION: VEH: 0 HAND: 0 CORPS ADA: 6
LINE 4: RESUPPLY: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL(gal): __
LINE 5: DISPENSED: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL:(gal) __

UNIT 3 CRDEHQTR TYPE: 1.6
LINE 1: ACTIVITY: 1 HOPP LEVEL: 1 MISSION: 8.0 KM MOVED: 0
LINE 2: SENSOR GP: 4 ZONE: 4 PCT COVERED: 50
LINE 3: PCT ADA SUPPRESSION: VEH: 0 HAND: 0 CORPS ADA: 6
LINE 4: RESUPPLY: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL(gal): __
LINE 5: DISPENSED: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL:(gal) __

UNIT 4 CBAHQTR TYPE: 1.6
LINE 1: ACTIVITY: 1 HOPP LEVEL: 1 MISSION: 8.0 KM MOVED: 0
LINE 2: SENSOR GP: 4 ZONE: 4 PCT COVERED: 50
LINE 3: PCT ADA SUPPRESSION: VEH: 0 HAND: 0 CORPS ADA: 5
LINE 4: RESUPPLY: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL(gal): __
LINE 5: DISPENSED: %DF: __ %IF: __ %AD: __ AMMO(tons): __ FUEL:(gal) __

Figure 10-3. Gamer/staff worksheet.

(2) If game turn updates are wanted (answer the first question with "N"), more information is needed before the process may continue. It is important to know what attrition programs (P3, P4, P5 or P6) have been run during the CI.

(3) After answering correctly about the attrition programs, enter characters to identify the game and the turn (CI). A final abort of P8 is then offered before irreversible changes are made during the running of this program.

B. Outputs consist of the unit history, K/V summary, and gamer/staff worksheets discussed in paragraph 2. For necessary file outputs of P8, refer to paragraph 6 of this chapter.

C. A data flow chart is shown in Figure 10-4.

D. Information about the external data files may be found in the following paragraph.

4. FILE STRUCTURE.

A. "UNITFILE". The unit status file is a 400-record file which holds 150 elements of information for each of the 400 units. A complete description may be found in Chapter 1, Table 1-1.

B. "TOEFILE". The "TOEFILE" holds the beginning 70 weapon systems from the "UNITFILE", an effectiveness number, side, and mission data.

C. "NAMEFILE". The "NAMEFILE" holds the name of each of the 400 units in the "UNITFILE".


D. "KVFILE". Holds killer/victim data for Blue and Red.

E. "HELOFILE". Holds attack helicopter data.

F. "BL/RDCHMVCTM". Holds Blue and Red chemical victim data.

G. "B/RAIR IN". Holds Red and Blue air losses. The "BAIR_IN" file holds the number of kills by the Blue aircraft (number of Red system losses) and the "RAIR_IN" files contains the number of kills by Red aircraft (Blue system losses).

H. All P1 Files. See Chapter 2 for greater detail.



5. ALGORITHMS.

The logic flow of the unit status report is shown in Figure 10-5. Most of the calculations in P8 are done through loss assessment files that have been accumulated over the preceding six-hour game turn. The main algorithms are as follows:

A. Current ammunition on cargo vehicles.

$$\text{New_N123} = \text{N123} * \text{N58} / \text{N84} \quad (\text{Eq. 10-1})$$

where:

New_N123 = current ammunition on cargo vehicles in short tons.
 N123 = preceding ammunition on cargo vehicles in short tons.
 N58 = current number of ammo trucks.
 N84 = cargo trucks alive at start of preceding game turn.

B. Current fuel on fuel vehicles.

$$\text{New_N103} = \text{N103} * \text{N55} / \text{N85} \quad (\text{Eq. 10-2})$$

where:

New_N103 = current fuel on fuel vehicles in gallons.
 N103 = preceding fuel on fuel trucks in gallons.
 N55 = current number of fuel trucks.
 N85 = fuel trucks alive at start of preceding game turn.




Figure 10-5. Unit status report logic flow.

C. Calculation of the total amount of ammunition on vehicles for each of the three weapon types (DF, IF, AD) is done as follows:

$$\text{Tra}_i = \sum_{j=1}^{70} (N_{ij} * \text{Ac}_{ij}) \quad (\text{Eq. 10-3})$$

where:

Tra_i = total amount of ammunition on vehicles of type i (DF, IF, AD) in short tons.

N_{ij} = number of "UNITFILE" system elements (j) which are of type i .

Ac_{ij} = ammunition capacity for system element (j) which is of type i in short tons.

D. The total amount of ammunition per weapon type (DF, IF, AD) is:

$$\text{Ta}_i = \sum_{j=1}^{70} (\text{Ac}_{ij} * N_{ij} * \text{As}_i) \quad (\text{Eq. 10-4})$$

where:

Ta_i = total amount of ammunition per weapon type i (DF, IF, AD) (short tons).

As_i = ammunition status for weapon type i ; the percentage of total ammunition capacity the vehicles are actually holding.

E. Total fuel for all system elements is calculated as follows:

$$\text{Tf} = \sum_{j=1}^{70} (N_j * \text{Fc}_j * \text{N101}) \quad (\text{Eq. 10-5})$$

where:

Tf = total fuel (gallons) for all system elements.

N_j = number of "UNITFILE" system elements (j).

Fc_j = fuel capacity (gallons) for system element j .

N101 = fuel status of unit vehicles; the percentage of total fuel capacity the vehicles are actually holding.

6. FILE EFFECTS.

P8 affects various files used in DIME, some in such a way that the only way they can be recovered is by rerunning a CI.

A. "UNITFILE" impact. Updates the fuel status, ammunition status, and combat effectiveness of each unit.

B. "KVFILE". Zeros out all entries in the K/V file after it has printed the worksheets.

C. "HELOFILE". Zeroes the helicopter file at the end of processing.

D. Chem files. Zeroes chemical files at the end of processing.

E. Air files. Zeroes air loss files at the end of processing.

7. CODE.

A. This section contains information on the unit status report program code. For a generalized flow of this program, refer to Figure 10-5.

B. The program begins by entering data necessary to open the appropriate files. Once the files have been accessed, the following areas are done for each of the 400 units:

(1) The appropriate data is read for each unit.

(2) If the unit is active, the current fuel and ammunition on the cargo vehicles is calculated. The number of ammunition and fuel trucks that will begin in the following critical incident (CI) are saved within the "UNITFILE". Finally, for each active unit, the combat effectiveness is recalculated.

(3) All units, active or inactive, go through the following process:

(a) The total amount of ammunition on vehicles for each of the three weapon types (DF, IF, AD) is calculated.

(b) Ammunition status for each weapon type (DF, IF, AD) is recalculated. Ammunition available to be consumed is set to zero and the ammunition which remained after the CI is placed in entirety on the ground.

(c) The new distribution of ammunition on the ground for DF, IF, and AD is figured.

(d) Calculations for the total fuel over all systems and the total ammunition for each weapon type (DF, IF, AD) then occur.

(e) Resupply and dispensation information is zeroed out to prepare for new resupply information to be entered in P1 (game initialization).

(f) The status report for each unit is printed and information is updated to the "UNITFILE".

(4) The killer/victim scoreboard and helicopter information are printed. Following these are the gamer/staff worksheets.

(5) All cumulative kill files are zeroed to prepare for the following CI.

C. A subroutine and variable listing is shown in Table 10-1. A code listing appears in Table 10-2.

Table 10-1. Unit status report subroutine table.

<u>functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary Variables</u>	<u>Variable description</u>
A. Read data and determines which reports will be produced.	Main program	Opens and enters required files and calls subroutines.	a. N(*) b. U(*)	75 dimensional array holding data provided by the "UNIFFILE" 23 dimensional array holding data provided by the "JOEFILE"
	Blue_data	Reads Blue unit arrays.	a. Wpn_type(*)	Array containing the weapon type of each element. Weapon types are: 1 = Indirect fire 2 = Direct fire 3 = Air defense.
			b. Ammo_cap(*)	Array containing amount of ammo capacity for a particular element from 1 to 21
			c. Fuel_cap(*)	Array containing amount of fuel capacity for a particular element from 1 to 21
	Red_data	Reads Red unit arrays.	See Blue_data subroutine variable list.	
B. Killer/victim output.	Zero	Zeros chemical and air loss variables.	a. R_air_loss(*) b. B_air_loss(*) c. R_chem_loss(*) d. B_chem_loss(*)	Array containing losses of Red targets due to Blue air fire Array containing losses of Blue targets due to Red air fire Array containing losses of Red targets due to Blue chemicals Array containing losses of Blue targets due to Red chemicals

Table 10-1. Unit status report subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
B. Killer/victim output (concluded).	Print_kvfile; Zero_lost; List_kv	<p>Calls the sub-routines. Zero list and list kv; zeroes variables for kv print; prints kv table.</p>	<p>a. Kv(1,J)</p>	<p>Array containing losses to target element J due to weapon type I where:</p> <ul style="list-style-type: none"> I = 1 Direct fire = 2 Indirect fire = 3 PGM = 4 Attack helicopter = 5 Infantry = 6 Mines = 7 Chemicals = 8 Air defense <p>J = 1 to 21 elements</p>
			b. Kv_tot(*)	Array containing total number of losses to target elements due to all weapon types
	Print_helo_file	Prints helicopter data.	C1_helo_b(1,J)	Array containing blue type I Helicopter data where:
				<ul style="list-style-type: none"> I = 1 HIND J = 2 # killed J = 6 # sorties
C. Unit history and game input worksheet portion.	Update_fuel	Reconciles truck losses with cargo loads.	a. New_ammo	Current ammo truck loads in tons
			b. New_fuel	Current fuel truck loads in gallons

Table 10-1. Unit status report subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
c. Unit history and gamer input worksheet portion (continued).	Update_cbt_eff	Updates unit combat effectiveness.	a. Eff	Systems effectiveness
	Print_unit_stat	Prints individual unit history.	b. Cbt_eff a. Df_stat(1)	Unit combat effectiveness Array containing direct fire supply status where: 1 = 1 ammo resupply profile 1 = 2 distribution of ammo in cargo vehicles 1 = 3 distribution of ground ammo 1 = 4 ammo dispensed to other vehicles
			b. lf_stat(1)	Array containing indirect fire supply status 1 = same as above
			c. Ad_stat(1)	Array containing air defense supply status 1 = same as above
			d. ldf	Current level of direct fire ammo in tons
			e. lff	Current level of indirect fire ammo in tons
			f. fad	Current level of air defense ammo in tons
			g. Uf_used	Direct fire ammo consumed in tons

Table 10-1. Unit status report subroutine table (continued).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
c. Unit history and gamer input worksheet portion (continued).	Print_unit_stat (concluded)		h. If_used	Indirect fire ammo consumed in tons
			i. Ad_used	Air defense ammo consumed in tons
			j. C_fuel	Unused fuel in gallons
			k. Gnd_amao	Total direct fire, indirect fire, and air defense ammo on the ground
			l. Trk_cap	Combined fuel capacity of trucks
	Print_sup_out	Prints required systems lists.	N(*)	75 dimensional array for holding data provided by the "UNIFFILE"
	Update_ammo	"Loads trucks" after calculating Dr, IF and AD ammo capacities.	a. Tot_veh_ammol(*)	Array containing total amount of ammo capacity by vehicles for each weapon type 1 to 3
			b. Anno_left(*)	Array containing ammo available to be consumed for each weapon type 1 to 3
			c. Pdf	% direct fire ammo on ground in tons
			d. Plf	% indirect fire ammo on ground in tons
			e. Atrk_cap	Combined ammo capacity of trucks in tons

Table 10-1. Unit status report subroutine table (concluded).

<u>Functional area(s)</u>	<u>Subroutine called</u>	<u>Subroutine function(s)</u>	<u>Primary variables</u>	<u>Variable description</u>
c. Unit history and gamer input worksheet portion (concluded).	Update_ammo (concluded)		f. fk_emp g. fk_ammo(*)	Number of empty trucks Array containing capacity of trucks for resupplying weapon types 1 to 3
			h. fk_perc(*)	Array containing weapon type 1 percent of ground ammo for weapon types 1 to 3
	Veh_ammo	Calculates total levels of ammo and fuel as related to weapon systems.	a. Tot_ammo(*)	Array containing total ammo capacity of weapon types from 1 to 3
			b. I_fuel	Fuel level of weapon systems combined

Table 10-2. Unit status report code.

```

10  REM  "P8" DOES THE END OF GAMER TURN UPDATES, PRINTS GAME RECORDS
20  !   AND THE GAMER COMBAT SUPPORT INPUT SHEET.
30  !   DATA CHANGED FEBRUARY 3, 1986, ROB BELFLOWER, BDM
40  ! *****
50  !   EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
51  !   DECLASSIFIED -- AUG 7, 1986 -- BY OAO CORP.  ** DC **
60  OPTION BASE 1
70  DIM N(150),S(70),U(72),A(2,70),F(2,70),W(2,70),Sys_eff(2,70),Helo(3,6)
80  DIM Ci_kv_b(8,70),Ci_kv_r(8,70),Fil1$(10),Fil2$(10),Fil3$(10),Fil4$(10)
90  DIM Turn$(3),Game$(2),Msus$(13),Id$(4),M$(16),M1$(9),T$(7)
100 DIM B_veh$(350),R_veh$(350),Veh$(350)
110 DIM R_air_loss(72),B_air_loss(72),R_chem_loss(70),B_chem_loss(70)
120 DIM Df_stat(4),If_stat(4),Ad_stat(4),Kv(8,70),Kv_tot(70)
130 DIM Ci_helo_b(3,6),Ci_helo_r(3,6),Tot_ammo(3),Fuel_cap(70)
140 DIM Ammo_cap(70),Wpn_type(70),Tot_veh_ammo(3),Ammo_left(3)
150 DIM T1(28),Tk_ammo(3),Tk_perc(3),Truck_cap(7)
151 DIM Dummyrec(70) ! ** DC **
160 INTEGER I,J,K,T
170 !
180 ! READ REQUIRED DATA ARRAYS
190 Dist$=":9134,704,0"
191 Dcdisk$=":9134,704,0" ! ** DC **
200 GOSUB Read_data
210 !
220 ! PRINT HEADERS
230 PRINTER IS 1
240 PRINT USING "@,#"
250 PRINT TABXY(28,8),"DIME GAME TURN PROCESSOR"
260 PRINT USING "////"
270 PRINT "          BE SURE THAT ALL PROCESSING PROGRAMS HAVE BEEN COMPLETED
280 PRINT "          BEFORE RUNNING THIS PROGRAM"
290 PRINT USING "/////"
300 PRINT "PLEASE ANSWER THE FOLLOWING:"
310 REPEAT
320   INPUT "KILLER VICTIM TABLE LISTING ONLY?(Y/N)",Kvans$
330   UNTIL Kvans$="Y" OR Kvans$="N"
340   GOTO Open
350   REPEAT
360     INPUT "HAVE YOU RUN P3 AIRSTRIKE (Y/N)",P3$
370     UNTIL P3$="Y" OR P3$="N"
380     REPEAT
390       INPUT "HAVE YOU RUN P4 COMBAT (Y/N)",P4$
400       UNTIL P4$="Y" OR P4$="N"
410       REPEAT
420         INPUT "HAVE YOU RUN P5 CHEMICAL (Y/N)",P5$
430         UNTIL P5$="Y" OR P5$="N"
440         REPEAT
450           INPUT "HAVE YOU RUN P6 LOSS ASSESSMENT (Y/N)",P6$
460           UNTIL P6$="Y" OR P6$="N"
470           INPUT "ENTER GAME NUMBER:",Game$,"ENTER TURN NUMBER:",Turn$
480           T=VAL(Turn$)
490           ! OPEN REQUIRED FILES

```

Table 10-2. Unit status report code (continued).

```

500 ASSIGN @Punit TO "UNITFILE"&Disk$
510 ASSIGN @Ptoe TO "TOEFILE"&Disk$
520 ASSIGN @Pname TO "NAMEFILE"&Disk$
530 IF P4$="Y" OR P6$="Y" THEN
540     ASSIGN @Pkv TO "KVFILE"&Disk$
550     ASSIGN @Phelo TO "HELOFILE"&Disk$
560 END IF
570 IF P5$="Y" OR P6$="Y" THEN
580     ASSIGN @Pbchem TO "ELCHMVCTM"&Disk$
590     ASSIGN @Prchem TO "RDCHMVCTM"&Disk$
600 END IF
610 IF P3$="Y" OR P6$="Y" THEN
620     ASSIGN @Bair TO "EL_AIR_INF"&Disk$
630     ASSIGN @Rair TO "RD_AIR_INF"&Disk$
640 END IF
650 Open:      ! ASSIGNS ANSWERS TO EXTRANEIOUS QUESTIONS ABOVE.
660 P3$="Y"
670 P4$="Y"
680 P5$="N"
690 P6$="Y"
700 INPUT "ENTER GAME NUMBER:",Game$,"ENTER TURN NUMBER: ".Turn$
710 INPUT "ENTER THE GAME TIME",T$
720 T=VAL(Turn$)
730 ! OPEN REQUIRED FILES
740 ASSIGN @Punit TO "UNITFILE"&Disk$
750 ASSIGN @Ptoe TO "TOEFILE"&Disk$
760 ASSIGN @Pname TO "NAMEFILE"&Disk$
770 ASSIGN @Pkv TO "KVFILE"&Disk$
780 ASSIGN @Phelo TO "HELOFILE"&Disk$
790 ASSIGN @Bair TO "EL_AIR_INF"&Disk$
800 ASSIGN @Rair TO "RD_AIR_INF"&Disk$
810 ASSIGN @Pbchem TO "ELCHMVCTM"&Disk$
820 ASSIGN @Prchem TO "RDCHMVCTM"&Disk$
830 IF Kvang$="Y" THEN Kv_only
840 !
850 REPEAT
860     INPUT "DO YOU WISH TO RUN P8? (Y/N)",Y_n_$
870 UNTIL Y_n_$="Y" OR Y_n_$="N"
880 IF Y_n_$="N" THEN GOTO Halt
890 !
900 !
910 ! PRINT HEADERS FOR UNIT HISTORY FILE
920 PRINT USING "@.#"
930 PRINTER IS 702
940 PRINT USING "@.#,10X,22A,2A,7A,3A,2X,4A,1X,7A,//";"UNIT HISTORY FOR GAME
,Game$," TURN ",Turn$,"TIME",T$
950 PRINT USING "11A.//":"BLUE UNITS:"
960 PRINTER IS 1
970 !
980 ! BEGIN INDIVIDUAL UNIT PROCESSING
990 !
1000 Tdf_used=0

```

Table 10-2. Unit status report code (continued).

```

1010 Tif_used=0
1020 Tad_used=0
1030 Totaldf=0
1040 Totalif=0
1050 Totalad=0
1060 Totalfuel=0
1070 Currentfuel=0
1080 GOSUB Blue_data
1090 !
1100 FOR I=1 TO 400
1110   IF I=192 THEN
1120     PRINTER IS 702
1130     PRINT USING "@.#,10X,22A,1A,7A,3A,2X,4A,1X,7A,///<";"UNIT HISTORY FOR G-
ME ",Game$, " TURN ",Turn$, "TIME",T$
1140     PRINT USING "11A,///<";"RED UNITS:"
1150     PRINTER IS 1
1160     Tdf_used=0
1170     Tif_used=0
1180     Tad_used=0
1190     Totaldf=0
1200     Totalif=0
1210     Totalad=0
1220     Totalfuel=0
1230     Currentfuel=0
1240     GOSUB Red_data
1250   END IF
1260   ENTER @Punit,I;N(*)
1270   ENTER @Ptoe,I;U(*)
1280   ENTER @Pname,I;M$
1290   PRINTER IS 1
1300   IF M$="UNUSED" THEN GOTO Print_out
1310   PRINT USING "/,16A,3D,///<";"PROCESSING UNIT ";I
1320   IF I<192 THEN
1330     Side=1
1340   ELSE
1350     Side=2
1360   END IF
1370   !
1380   ! DO UNIT UPDATES
1390   GOSUB Update_fuel
1400   GOSUB Update_cbt_eff
1410   !
1420   !
1430   Print_out:GOSUB Print_unit_stat
1440   GOSUB Print_work_sht
1450   OUTPUT @Punit,I;N(*)
1460   IF I=191 OR I=400 THEN
1470     PRINT
1480     PRINT
1490     PRINT ! ROB
1500     PRINT USING "40A,2X,8D,1X,4A";"TOTAL DF USED DURING THE LAST SIX HOURS
";Tdf_used;"TONS"

```

Table 10-2. Unit status report code (continued).

```

1510     PRINT USING "40A,2X,8D,1X,4A";"TOTAL IF USED DURING THE LAST SIX HOUR
: ";Tif_used;"TONS"
1520     PRINT USING "40A,2X,8D,1X,4A";"TOTAL AD USED DURING THE LAST SIX HOUR
: ";Tad_used;"TONS"
1530     PRINT USING "46A,2X,14D,1X,7A";"TOTAL FUEL CONSUMED DURING THE LAST S
X HOURS:";Totalfuel;"GALLONS"
1540     PRINT
1550     PRINT USING "18A,8D,1X,4A";"TOTAL DF REMAINING";Totaldf;"TONS"
1560     PRINT USING "18A,8D,1X,4A";"TOTAL IF REMAINING";Totalif;"TONS"
1570     PRINT USING "18A,8D,1X,4A";"TOTAL AD REMAINING";Totalad;"TONS"
1580     PRINT USING "20A,10D,1X,7A";"TOTAL FUEL REMAINING";Currentfuel;"GALLO
S"
1590     END IF
1600     NEXT I
1610     !
1620     Kv_only: !
1630     PRINTER IS 1
1640     PRINT USING "@,#"
1650     PRINT TABXY(26,12),"PRINTING KILLER-VICTIM TABLE"
1660     PRINTER IS 702
1670     !PRINT USING "@,#"
1680     GOSUB Zero
1690     !
1700     IF P4$="Y" OR P6$="Y" THEN
1710         ENTER @Pkv,1;Ci_kv_b(*)
1720         ENTER @Pkv,2;Ci_kv_r(*)
1730     END IF
1740     !
1750     ! READ IN AND ENTER IN CHEMICAL/CLOSE AIR KILLS
1760     IF P5$="Y" OR P6$="Y" THEN
1770         ENTER @Pbchem,1;B_chem_loss(*)
1780         ENTER @Prchem,1;R_chem_loss(*)
1790     END IF
1800     IF P3$="Y" OR P6$="Y" THEN
1810         ENTER @Bair,1;T1(*),R_air_loss(*)
1820         ENTER @Rair,1;T1(*),B_air_loss(*)
1830     END IF
1840     FOR I=1 TO 70
1850         IF P3$="Y" OR P6$="Y" THEN
1860             Ci_kv_r(8,I)=R_air_loss(I)+Ci_kv_r(8,I)
1870             Ci_kv_b(8,I)=B_air_loss(I)+Ci_kv_b(8,I)
1880         END IF
1890         IF P5$="Y" OR P6$="Y" THEN
1900             Ci_kv_b(7,I)=B_chem_loss(I)+Ci_kv_b(7,I)
1910             Ci_kv_r(7,I)=R_chem_loss(I)+Ci_kv_r(7,I)
1920         END IF
1930     NEXT I
1940     !
1950     ! PRINT OUT KILLER-VICTIM SUMMARY FILE
1960     GOSUB Print_kvfile
1970     !
1980     ! PRINT OUT HELICOPTER FILE

```

Table 10-2. Unit status report code (continued).

```

1990 IF P4$="Y" THEN GOSUB Print_helo_file
2000 IF Kvals$="Y" THEN Halt
2010 IF Kvals$="N" THEN Zero_files
2020 !
2030 ! PRINT OUT GAMER INPUT WORKSHEET HEADER
2040 T1=T+1
2050 PRINTER IS 1
2060 PRINT USING "@,#"
2070 PRINT TABXY(24,12),"PRINTING GAMER STAFF WORK SHEETS"
2080 PRINTER IS 702
2090 PRINT USING "@, #,32A,2D";"GAMER STAFF WORK SHEET FOR TURN ",T1
2100 PRINT USING "//,13A";"BLUE UNITS:"
2110 !
2120 ! PRINT INDIVIDUAL UNITS
2130 FOR I=1 TO 400
2140     ENTER @Punit,I;N(*)
2150     ENTER @Pname,I;M$
2160     GOSUB Print_work_sht
2170 NEXT I
2180 !
2190 !
2200 Zero_files: !STAFF WORK SHEETS ARE PRINTED WITH UNIT STATUS
2210 ! ZERO GAME TURN FILES FOR USE IN NEXT GAME TURN
2220 IF P4$="Y" OR P6$="Y" THEN
2230     FOR I=1 TO 8
2240         FOR J=1 TO 70
2250             Ci_kv_b(I,J)=0
2260         NEXT J
2270     NEXT I
2280     FOR I=1 TO 2
2290         OUTPUT @Pkv,I;Ci_kv_b(*)
2300     NEXT I
2310 !ZERO HELICOPTER FILES
2320     FOR I=1 TO 3
2330         FOR J=1 TO 6
2340             Helo(I,J)=0
2350         NEXT J
2360     NEXT I
2370     OUTPUT @Phelo,1;Helo(*)
2380     OUTPUT @Phelo,2;Helo(*)
2390 END IF
2400 !
2410 IF P5$="Y" OR P6$="Y" THEN
2420 !ZERO CHEMICAL FILE
2430     FOR I=1 TO 70
2440         R_chem_loss(I)=0
2450     NEXT I
2460     OUTPUT @Pbchem,1;R_chem_loss(*)
2470     OUTPUT @Prchem,1;R_chem_loss(*)
2480 END IF
2490 !
2500 IF P3$="Y" OR P6$="Y" THEN

```

Tabke 10-2. Unit status report code (continued).

```

2510 ZERO AIR LOSS FILES
2520 FOR I=1 TO 72
2530     B_air_loss(I)=0
2540 NEXT I
2550 FOR I=1 TO 28
2560     T1(I)=0
2570 NEXT I
2580     OUTPUT @Rair,1:T1(*),B_air_loss(*)
2590     OUTPUT @Bair,1:T1(*),B_air_loss(*)
2600 END IF
2610 !
2620 ! CLOSE ALL FILES AND RETURN TO MENU PROGRAM
2630 ASSIGN @Punit TO *
2640 ASSIGN @Ptoe TO *
2650 ASSIGN @Pname TO *
2660 IF P4$="Y" OR P6$="Y" THEN ASSIGN @PkV TO *
2670 IF P4$="Y" OR P6$="Y" THEN ASSIGN @Phelo TO *
2680 IF P3$="Y" OR P6$="Y" THEN ASSIGN @Bair TO *
2690 IF P3$="Y" OR P6$="Y" THEN ASSIGN @Rair TO *
2700 IF P5$="Y" OR P6$="Y" THEN ASSIGN @Pbchem TO *
2710 IF P5$="Y" OR P6$="Y" THEN ASSIGN @Prchem TO *
2720 GOTO Halt
2730 !
2740 !
2750 ! ***** END OF MAIN PROGRAM *****
2760 !
2770 !
2780 Read_data: ! THIS SBR READS REQUIRED DATA
2790 !
2800 ! ** DC **
2810 !
2820 ASSIGN @Psyseff TO "SYS_EFF"&Dcdisk$
2830 ENTER @Psyseff,1:Sys_eff(*)
2840 ASSIGN @Psyseff TO *
2850 ! ** END DC **
2960 B_veh$[1,125]="DF FAV-TM551 FAV40HMV-GDF DRAGNLAW DF CMD-VDF DF
DF DF DF HMV40DF-ICDF-ICDF-ICDF-ICARTY ARTY ARTY ARTY ARTY "
2970 B_veh$[126,250]="ARTY ARTY MORTRMORTRMORTRMORTRMRLRSTMLRSTMLRSTMLRSTINF I
F INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSARMSSVULCNAVNGRIHAWK"
2980 B_veh$[251,350]="ADA ADA STINGADAHF-TRKJ4TRK:WATERCGO-TNATRF:EWTRF:EWTRF:
GR OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
2990 R_veh$[1,125]="T55 DF BMP73DF BRDM3BRDM5AT-75AGS17T12 CMD-VDF DF
DF DF DF BMPATBTR DF-ICDF-ICDF-ICARTY ARTY ARTY ARTY ARTY "
3000 R_veh$[126,250]="ARTY ARTY MORTRMORTRMORTRMORTRMRL MRL MRL MRL INF I
F INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSARMSSZSU-XSA-13SA-6 "
3010 R_veh$[251,350]="ADA ADA SA-14ADAHF-TRKJ4TRK:WATERCGO-TNATRF:EWTRF:EWTRF:
GR OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
3020 RETURN
3030 Print_sys_out: ! THIS SBR PRINTS OUT THE REQUIRED SYSTEMS LISTS
3040 FOR X=7 TO 70 STEP 7
3050 PRINT USING Fmt1:X-6,":",N(X-6),X-5,":",N(X-5),X-4,":",N(X-4),X-3,":",N
X-3),X-2,":",N(X-2),X-1,":",N(X-1),X,":",N(X)

```


Table 10-2. Unit status report code (continued)

```

3060 NEXT X
3070 Fmt1:IMAGE 7(2D,1A,4D,1D,2X)
3080 !
3090 RETURN
3100 !
3110 !*****
3120 !
3130 Zero: !
3140 FOR I=1 TO 8
3150   FOR J=1 TO 70
3160     Ci_kv_b(I,J)=0
3170     Ci_kv_r(I,J)=0
3180   NEXT J
3190 NEXT I
3200 FOR I=1 TO 70
3210   E_chem_loss(I)=0
3220   R_chem_loss(I)=0
3230   E_air_loss(I)=0
3240   R_air_loss(I)=0
3250 NEXT I
3260 E_air_loss(71)=0
3270 E_air_loss(72)=0
3280 R_air_loss(71)=0
3290 R_air_loss(72)=0
3300 RETURN
3310 !
3320 ! *****
3330 !
3340 Update_fuel: THIS SBR RECONCILES TRUCK LOSSES WITH CARGE LOADS
3350 !
3360 Ammo=N(123)
3370 Ammog=N(125)
3380 IF N(84)<=0 THEN
3390   N(123)=0
3400   N(125)=0
3410   GOTO 3480
3420 END IF
3430 New_ammo=Ammo*N(58)/N(84)
3440 N(123)=New_ammo
3450 New_ammog=Ammog*N(58)/N(84)
3460 N(125)=New_ammog
3470 !
3480 Fuel=N(103)
3490 Fuelg=N(105)
3500 IF N(85)<=0 THEN
3510   N(103)=0
3520   N(105)=0
3530   GOTO 3590
3540 END IF
3550 New_fuel=Fuel*N(55)/N(85)
3560 N(103)=New_fuel
3570 N(105)=Fuelg*N(55)/N(85)

```

Table 10-2. Unit status report code (continued).

```

3580 !
3590 N(85)=N(55)
3600 N(84)=N(58)
3610 !
3620 RETURN
3630 !
3640 ! *****
3650 !
3660 Update_cbt_eff: ! THIS SBR UPDATES UNIT COMBAT EFFECTIVENESS
3670 !
3680 Eff=0
3690 FOR J=1 TO 70
3700   Eff=Eff+Sys_eff(Side,J)*N(J)
3710 NEXT J
3720 IF U(71)=0 THEN 3760
3730 Cbt_eff=Eff/U(71)
3740 N(79)=Cbt_eff
3750 !
3760 RETURN
3770 !
3780 ! *****
3790 !
3800 Print_unit_stat: ! THIS SBR PRINTS OUT THE INDIVIDUAL UNIT HISTORY
3810 !
3820 PRINTER IS 702
3830 IF N(82)=0 THEN M1$="INACTIVE"
3840 IF N(82)=1 THEN M1$="ACTIVE  "
3850 IF N(82)=2 THEN M1$="DESTROYED"
3860 ! PRINT USING Fmt2:"UNIT: ",I,M$,"TYPE: ",N(78),M1$,"CBT-EFF: ",N(79),"M:
SION: ",N(83)
3870 ! Fmt2: IMAGE /.6A,3D,3X,8A,3X,6A,1D,1D,3X,8A,3X,9A,3D,2D,3X,9A,1D,1D
3880 PRINT USING Fmt2:"UNIT: ",I,M$,"TYPE: ",N(78),M1$,"CBT-EFF: ",N(79)
3890 Fmt2: IMAGE /.6A,3D,3X,16A,3X,6A,1D,1D,3X,9A,3X,9A,3D,2D,3X
3900 IF N(82)=0 OR N(82)=2 THEN End_stat_print
3910 FOR J=1 TO 70
3920   S(J)=N(J)
3930 NEXT J
3940 PRINT USING "/.26A";"SYSTEMS REMAINING:"
3950 GOSUB Print_sys_out
3960 GOTO Log
3970 SELECT N(91)
3980 CASE =0
3990   M1$="NOT DET "
4000 CASE =1
4010   M1$="DETECTED"
4020 CASE =2
4030   M1$="VERIFIED"
4040 CASE =3
4050   M1$="LOST  "
4060 END SELECT
4070 PRINT USING Fmt3:"DETECTION: ",M1$,"SENS STATUS (Z/G): ",N(89),"FRA CVG:
,N(90),"KM MOVED: ",N(146)

```

Table 10-2. Unit status report code (continued).

```

4080 Fmt3: IMAGE /, 11A, 8A, 3X, 19A, 1D, 1D, 4X, 9A, 1D, 2D, 6X, 10A, 3D
4090 PRINT USING Fmt4: "AIR DEFENSE:", "SUPPRESSION:", ".N(80)." "CORPS SUPPORT ADG:
".N(81)
4100 Fmt4: IMAGE /, 12A, 4X, 13A, 2D, 2D, 4X, 19A, 3D
4110 Log: !LOGISTICS
4120 PRINT USING "/, 10A": "LOGISTICS:"
4130 PRINT USING Fmt5: "TYPE", "STATUS", "PROFILE", "CONSUMED", "RESUPPLY", "ON-TRE",
"ON-GND", "DISPND", "ON-VEH", "CURRNT", "USD/DT"
4140 Fmt5: IMAGE 4A, 1X, 6A, 1X, 7A, 1X, 8A, 1X, 8A, 6(1X, 6A)
4150 !
4160 Df_used=N(116)-N(131)
4170 If_used=N(117)-N(132)
4180 Ad_used=N(118)-N(133)
4190 Tdf_used=Tdf_used+Df_used
4200 Tif_used=Tif_used+If_used
4210 Tad_used=Tad_used+Ad_used
4220 !
4230 N135_sv=N(135)
4240 GOSUB Update_ammo
4250 !
4260 ! FILL IN SUPPLY STATUS MATRICES
4270 Df_stat(1)=INT(N(136))/1000*N135_sv
4280 Df_stat(2)=INT(N(124))/1000*N(123)
4290 Df_stat(3)=INT(N(126))/1000*N(125)
4300 Df_stat(4)=INT(N(138))/1000*N(137)
4310 !
4320 If_stat(1)=(N(136)-INT(N(136)))*N135_sv
4330 If_stat(2)=(N(124)-INT(N(124)))*N(123)
4340 If_stat(3)=(N(126)-INT(N(126)))*N(125)
4350 If_stat(4)=(N(138)-INT(N(138)))*N(137)
4360 !
4370 Ad_stat(1)=N135_sv-(Df_stat(1)+If_stat(1))
4380 Ad_stat(2)=N(123)-(Df_stat(2)+If_stat(2))
4390 Ad_stat(3)=N(125)-(Df_stat(3)+If_stat(3))
4400 Ad_stat(4)=N(137)-(Df_stat(4)+If_stat(4))
4410 !
4420 GOSUB Veh_ammo
4430 C_fuel=T_fuel+N(105)+N(103)
4440 Totalfuel=Totalfuel+N(108)
4450 Currentfuel=Currentfuel+C_fuel
4460 !
4470 Tdf=Df_stat(2)+Df_stat(3)+Tot_ammo(1)
4480 Tif=If_stat(2)+If_stat(3)+Tot_ammo(2)
4490 Tad=Ad_stat(2)+Ad_stat(3)+Tot_ammo(3)
4500 Totaldf=Totaldf+Tdf
4510 Totalif=Totalif+Tif
4520 Totalad=Totalad+Tad
4530 Tdf_used=Tdf_used-Df_stat(4)
4540 Tif_used=Tif_used-If_stat(4) !TEST
4550 Tad_used=Tad_used-Ad_stat(4)
4560 !
4570 Gnd_ammo=Df_stat(3)+If_stat(3)+Ad_stat(3)

```

Table 10-2. Unit status report code (continued).

```

4580 Ftrk_cap=N(55)*Truck_cap(1)
4590 Ft4=0
4600 IF Tk_emp<0 THEN Tk_emp=0
4610 IF N(103)<N(55)*Truck_cap(1) THEN
4620   Ft1=N(103)/(N(55)*Truck_cap(1))
4630   Ft2=N(55)*(1-Ft1)
4640   Ft4=INT(Ft2)
4650 END IF
4660 PRINT USING Fmt6;"DF",N(119),N(127),Df_used,Df_stat(*),Tot_ammo(1),Tdf,N(
39)
4670 PRINT USING Fmt6;"IF",N(120),N(128),If_used,If_stat(*),Tot_ammo(2),Tif,N(
40)
4680 PRINT USING Fmt6;"AD",N(121),N(129),Ad_used,Ad_stat(*),Tot_ammo(3),Tad,N(
41)
4690 PRINT USING Fmt6;"FU",N(101),N(107),N(108),N(110),N(103),N(105),N(112),T_
uel,C_fuel,N(143)
4700 Fmt6:IMAGE 1X,2A,1X,4D,2D,1X,7D,1X,8D,1X,8D,6(1X,6D)
4710 !
4720 PRINT
4730 Tk_emp=INT(Tk_emp)
4740 PRINT "EMPTY AMMO TRUCKS ":Tk_emp;"      EMPTY FUEL TRUCKS ":Ft4
4750 !PRINT " EQUIVALENT EMPTY FUEL TRUCKS ":Ft4
4760 !PRINT USING "///"
4770 N(110)=0
4780 N(135)=0
4790 N(136)=0
4800 N(112)=0
4810 N(137)=0
4820 N(138)=0
4830 End_stat_print:RETURN
4840 !
4850 ! *****
4860 !
4870 Print_kvfile: ! THIS SBR PRINTS OUT THE SUMMARY KV FILE
4880 !
4890 GOSUB Zero_list
4900 FOR I=1 TO 8
4910   FOR J=1 TO 70
4920     Kv(I,J)=Ci_kv_b(I,J)
4930     Kv_tot(J)=Kv_tot(J)+Ci_kv_b(I,J)
4940   NEXT J
4950 NEXT I
4960 Veh$=B_veh$
4970 PRINT USING "@,38A,1A,7A,3A,2X,4A,1X,7A, /": "RED KILLER--BLUE VICTIM FILE
OR GAME ",Game$,"  TURN ",Turn$,"TIME",T$
4980 GOSUB List_kv
4990 !
5000 ! PRINT OUT RED KV LIST
5010 GOSUB Zero_list
5020 FOR I=1 TO 8
5030   FOR J=1 TO 70
5040     kv(I,J)=Ci_kv_r(I,J)

```

Table 10-2. Unit status report code (continued).

```

5050     kv_tot(J)=Kv_tot(J)+Ci_kv_r(I,J)
5060     NEXT J
5070     NEXT I
5080     Veh$=R_veh$
5090     PRINT USING "@,3BA,1A,7A,3A,2X,4A,1X,7A,/" ; "BLUE KILLER--RED VICTIM FILE F
OR GAME ",Game$,"  TURN ",Turn$,"TIME",T$
5100     GOSUB List_kv
5110     !
5120     RETURN
5130     !
5140     ! *****
5150     !
5160     Zero_list: ! ZERO VARIABLES FOR KV PRINT
5170     !
5180     FOR I=1 TO 8
5190         FOR J=1 TO 70
5200             Kv(I,J)=0
5210             Kv_tot(J)=0
5220         NEXT J
5230     NEXT I
5240     !
5250     RETURN
5260     !
5270     ! *****
5280     !
5290     List_kv: ! THIS SBR PRINTS THE KV TABLE
5300     PRINT USING "//,6A,13X,49A"; "VICTIM", "<----- KILLER -----
----->"
5310     PRINT USING Fmt10; "          ", "D/F", "I/F", "FGM", "A/H", "INF", "MIN", "CHM", "AI
R", "T/KILL"
5320     Fmt10: IMAGE /,8A,3X,7(3A,5X),3A,4X,6A,/
5330     FOR I=1 TO 70
5340         PRINT USING Fmt11; Veh$( (I-1)*5+1, I*5), Kv(1, I), Kv(2, I), Kv(3, I), Kv(4, I), Kv
(5, I), Kv(6, I), Kv(7, I), Kv(8, I), Kv_tot(I)
5350         IF I=55 THEN
5360             PRINT USING "@"
5370         END IF
5380     NEXT I
5390     Fmt11: IMAGE 5A,4X,8(4D,1D,2X),1X,4D,1D
5400     !
5410     RETURN
5420     !
5430     ! *****
5440     !
5450     Print_helo_file: ! THIS SBR PRINTS OUT BLUE HELICOPTER DATA
5460     !
5470     ENTER @Phelo,1;Ci_helo_b(*)
5480     ENTER @Phelo,2;Ci_helo_r(*)
5490     PRINT USING "@,#.27A"; "ATTACK HELICOPTER RESULTS"
5500     PRINT USING Fmt32; "TYPE", "#KILLED", "#SORTIES"
5510     PRINT USING Fmt33; "LCH ", Ci_helo_b(1,2), Ci_helo_b(1,6)
5520     PRINT USING Fmt33; "AH-1", Ci_helo_b(2,2), Ci_helo_b(2,6)

```

Table 10-2. Unit status report code (continued).

```

5530 PRINT USING Fmt33;"OH58",Ci_helo_b(3,2),Ci_helo_b(3,6)
5540 PRINT USING "/"
5550 PRINT USING Fmt33;"HIP",Ci_helo_r(2,2),Ci_helo_r(2,6)
5560 PRINT USING Fmt33;"HIND",Ci_helo_r(1,2),Ci_helo_r(1,6)
5570 Fmt32:IMAGE ///,4A,4X,7A,3(4X,8A),//
5580 Fmt33:IMAGE 4A, 5X,3(3D.1D,7X),5D
5590 !
5600 RETURN
5610 !
5620 ! *****
5630 !
5640 Print_work_sht: ! THIS SBR PRINTS GAMER WORK SHEETS
5650 !
5660 !IF I=192 THEN
5670 ! PRINT USING "@,#,32A,2D";"GAMER STAFF WORK SHEET FOR TURN ",T1
5680 ! PRINT USING "/",13A";"RED UNITS:"
5690 !END IF
5700 !IF N(82)=0 OR N(82)=2 THEN End_print
5710 !PRINT USING Fmt20;"UNIT ",I,M$,"TYPE: ",N(78)
5720 !Fmt20:IMAGE ///,5A,3D,5X,8A,4X,6A,1D.1D
5730 !PRINT USING Fmt21;"LINE 1: ACTIVITY: ",N(82),"MOPP LEVEL: ",N(77),"MISS:
N: ",N(83),"KM MOVED: ",N(146)
5740 Fmt21:IMAGE /,19A,1D,7X,12A,1D.6X,9A,1D.1D.4X,10A,3D
5750 N2=INT(N(89))
5760 N1=INT((N(89)-N2)*10+.5)
5770 N3=INT(N(90)*100)
5780 PRINT USING Fmt22;"LINE 2: SENSOR GP: ",N1,"ZONE: ",N2,"PCT COVERED: ".
5790 Fmt22:IMAGE /,20A,1D,8X,6A,1D,10X,13A,3D
5800 N1=INT(N(80))
5810 N2=INT(((N(80)-N1)*100))
5820 PRINT USING Fmt23;"LINE 3: PCT ADA SUPPRESSION: VEH: ",N1,"HAND: ",N2,"
ORPS ADA: ",N(81)
5830 Fmt23:IMAGE /,36A,3D,7X,6A,3D,8X,11A,3D
5840 !
5850 PRINT
5860 PRINT "LINE 4: RESUPPLY: DF(Tons)___IF(Tons)___AD(Tons)___ FUEL(gal):
"
5870 PRINT
5880 PRINT "LINE 5: DISPENSED: DF(Tons)___IF(Tons)___AD(Tons)___ FUEL:(ga:
"
5890 PRINT
5900 IF I<192 THEN
5910 PRINT "LINE 6: GDRADAR___":N(95);"ARTRADAR___":N(96);"LRRP___":N(97)
"RPV___":N(98);"SLAR___":N(99);"FO___":N(100)
5920 ELSE
5930 PRINT "LINE 6: GDRADAR___":N(95);"ARTRADAR___":N(96);"LRRP___":N(97)
"SLAR___":N(98);"RPV___":N(99);"FO___":N(100)
5940 END IF
5950 PRINT
5960 PRINT "CURRENT LOCATION _____ PROPOSED LOCATION _____
"
5970 PRINT

```

Table 10-2. Unit status report code (continued).

```

5980 PRINT "ACTUAL LOCATION ARRIVED AT _____"
5990 PRINT
6000 PRINT "ACTION TO BE TAKEN AT THE OBJECTIVE:"
6010 PRINT
6020 PRINT "_____
6030 End_print: !
6040 RETURN
6050 !
6060 ! *****
6070 !
6080 Blue_data: !
6090 !
6091 ! ** DC **
6092 !
6100 ASSIGN @Pwpntyp TO "WPN_TYP"&Dcdisk$
6110 ENTER @Pwpntyp,1;Wpn_type(*)
6120 ASSIGN @Pwpntyp TO *
6130 !
6180 ASSIGN @Pammocap TO "AMMO_CAP"&Dcdisk$
6190 ENTER @Pammocap,1;Ammo_cap(*)
6200 ASSIGN @Pammocap TO *
6210 !
6270 ASSIGN @Pfuelcap TO "FUEL_CAP"&Dcdisk$
6280 ENTER @Pfuelcap,1;Fuel_cap(*)
6290 ASSIGN @Pfuelcap TO *
6300 !
6310 ASSIGN @Ptrkcap TO "BL_TRK_CAP"&Dcdisk$
6320 ENTER @Ptrkcap,1;Truck_cap(*)
6330 ASSIGN @Ptrkcap TO *
6360 !Truck_cap(4)=6.5
6370 !Truck_cap(1)=1800
6380 RETURN
6390 !
6400 ! *****
6410 !
6420 Red_data: !
6430 ASSIGN @Pwpntyp TO "WPN_TYP"&Dcdisk$
6440 ENTER @Pwpntyp,1;Dummyrec(*),Wpn_type(*)
6441 ASSIGN @Pwpntyp TO *
6450 !
6520 ASSIGN @Pammocap TO "AMMO_CAP"&Dcdisk$
6530 ENTER @Pammocap,1;Dummyrec(*),Ammo_cap(*)
6540 ASSIGN @Pammocap TO *
6550 !
6610 ASSIGN @Pfuelcap TO "FUEL_CAP"&Dcdisk$
6620 ENTER @Pfuelcap,1;Dummyrec(*),Fuel_cap(*)
6630 ASSIGN @Pfuelcap TO *
6640 !
6650 ASSIGN @Ptrkcap TO "RD_TRK_CAP"&Dcdisk$
6660 ENTER @Ptrkcap,1;Truck_cap(*)
6670 ASSIGN @Ptrkcap TO *
6700 !Truck_cap(4)=4.5

```

Table 10-2. Unit status report code (continued).

```

6710 !Truck_cap(1)=1288
6711 ! ** END DC **
6720 RETURN
6730 !
6740 !*****
6750 !
6760 Update_ammo: !CALCULATE TOTAL CAPACITY
6770 FOR Ikp=1 TO 3
6780 Tot_veh_ammo(Ikp)=0
6790 NEXT Ikp
6800 FOR J=1 TO 70
6810 Tot_veh_ammo(Wpn_type(J))=Tot_veh_ammo(Wpn_type(J))+N(J)*Ammo_cap(J)
6820 NEXT J
6830 N(125)=0
6840 FOR Ikp=1 TO 3
6850 IF N(130+Ikp)<0 THEN N(130+Ikp)=0
6860 IF Tot_veh_ammo(Ikp)<=0 THEN
6870 Ammo_left(Ikp)=N(130+Ikp)
6880 N(118+Ikp)=0
6890 N(130+Ikp)=0
6900 GOTO Ec1
6910 END IF
6920 IF N(130+Ikp)>Tot_veh_ammo(Ikp) THEN
6930 N(118+Ikp)=1
6940 Ammo_left(Ikp)=N(130+Ikp)-Tot_veh_ammo(Ikp)
6950 N(130+Ikp)=0
6960 ELSE
6970 N(118+Ikp)=N(130+Ikp)/Tot_veh_ammo(Ikp)
6980 N(130+Ikp)=0
6990 Ammo_left(Ikp)=0
7000 END IF
7010 Ec1:N(125)=N(125)+Ammo_left(Ikp)
7020 NEXT Ikp
7030 !
7040 IF N(125)=0 THEN
7050 N(126)=0
7060 ELSE
7070 Pdf=Ammo_left(1)/N(125)
7080 Pif=Ammo_left(2)/N(125)
7090 N(126)=INT(Pdf*1000)+Pif
7100 END IF
7110 ! CALC PROPER TRUCK CAPACITY
7120 Atrk_cap=N(58)*Truck_cap(4)
7130 ! TAKE AMMO FROM PILES IN SAME RATIO AS AVAILABLE TRUCKS
7140 Tk_emp=0
7150 ! ZERO AMOUNT IN TRUCKS
7160 FOR Ikp=1 TO 3
7170 Tk_ammo(Ikp)=0
7180 NEXT Ikp
7190 N(123)=0
7200 IF N(125)<=0 OR Atrk_cap<=0 THEN No_trks
7210 ! AMMO IS ON GROUND AND TRUCKS HAVE A CAPACITY LOAD ON EMPTY TRUCKS

```


Table 10-2. Unit status report code (concluded).

```

7220 Tk_perc(1)=INT(N(126))/1000
7230 Tk_perc(2)=N(126)-INT(N(126))
7240 Tk_perc(3)=1-(Tk_perc(1)+Tk_perc(2))
7250 IF Atrk_cap<N(125) THEN
7260   Tk_ammo(1)=Atrk_cap*Tk_perc(1)
7270   Tk_ammo(2)=Atrk_cap*Tk_perc(2)
7280   Tk_ammo(3)=Atrk_cap*Tk_perc(3)
7290   N(123)=Atrk_cap
7300   N(124)=N(126)
7310   N(125)=N(125)-N(123)
7320   Tk_emp=0
7330 ELSE
7340   !MORE TRUCKS THAN ON GROUND AVAILABLE
7350   Tk_ammo(1)=N(125)*Tk_perc(1)
7360   Tk_ammo(2)=N(125)*Tk_perc(2)
7370   Tk_ammo(3)=N(125)*Tk_perc(3)
7380   N(123)=Tk_ammo(1)+Tk_ammo(2)+Tk_ammo(3)
7390   N(124)=N(126)
7400   Tk_emp=(Atrk_cap-N(125))/Truck_cap(4)
7410   N(125)=0
7420 END IF
7430 N(131)=0
7440 N(132)=0
7450 N(133)=0
7460 N(135)=0
7470 No_trks: !
7480 !IF Ammog=0 THEN N(125)=0
7490 !IF N(146)>0 THEN N(125)=0
7500 !IF N(146)>0 THEN N(105)=0
7510 !IF Fuelg=0 THEN N(105)=0
7520 RETURN
7530 !
7540 !*****
7550 !
7560 Veh_ammo: !
7570 FOR J=1 TO 3
7580   Tot_ammo(J)=0
7590 NEXT J
7600 T_fuel=0
7610 FOR J=1 TO 70
7620   Tot_ammo(Wpn_type(J))=Tot_ammo(Wpn_type(J))+Ammo_cap(J)*N(J)*N(118+Wpn_
ypn_
ype(J))
7630   T_fuel=T_fuel+N(J)*Fuel_cap(J)*N(101)
7640 NEXT J
7650 RETURN
7660 !
7670 !*****
7680 !
7690 Halt: !
7700 LOAD "DIME"%:Disk$
7710 END

```

CHAPTER 11

UTILITY ROUTINES

1. PURPOSE.

DIME utility routines are available to assist in the creation of needed files, in listing files and in some cases, changing data values.

2. CREATE ROUTINES.

The following routines are used preceding the use of game initialization (P1). These are necessary before any DIME game operations may be done.

A. "CR_NAME". Initially creates and blanks the unit name file, "NAMEFILE".

B. "CR_TOE". Initially creates and zeros the table of organization/equipment (TOE) file, "TOEFILE".

C. "CR_UNIT". Initially creates and zeros the unit status file, "UNITFILE".

3. "UNITFILE" UTILITIES.

The following routines may be used to list and check the "UNITFILE", "NAMEFILE" and "TOEFILE" after they have been built in P1.

A. "NAMEDUMP". This routine lists the names ("NAMEFILE") of the 400 possible units created.

B. "STRENGTH". This routine lists the total of each 21 systems in the 191 Blue units and 209 Red units. These totals are listed from both the "UNITFILE" and "TOEFILE".

C. "EFFECTIVE". This routine recalculates effectiveness totals and percentages. The internal system effectiveness data may be changed and recalculated in both the "TOEFILE" and "UNITFILE".

4. CREATE/ZEROING ROUTINES.

These routines may be used when initially creating the game's cumulative kill files, when zeroing is necessary before the beginning of a game or when the unit status report (P8) is not run to completion. The following routines create and/or zero files which contain accumulated kills for one complete game turn.

- A. "CR_KV". Creates and/or zeros the killer/victim file, "KVFILE".
- B. "CR_HELO". Creates and/or zeros the helicopter file, "HELOFILE".
- C. "AIRPLANE". Creates and/or zeros the air defense victim files. This is the same routine which is used to create the entire air defense (P3) data base. The two files consist of:
 - (1) The "RAIR_INF" contains the number of Blue victims.
 - (2) The "BAIR_INF" contains the number of Red victims.
- D. "CR_CHEM". Creates and/or zeros both chemical files which consist of:
 - (1) "BLCHMVCTM" which contains the number of Blue victims.
 - (2) "RDCHMVCTM" which contains the number of Red victims.

5. "OMNI" DATA FILE UTILITIES

The following routines are primarily used to alter the data values in files used by DIME. In addition, they may be used to create new data files and/or list the values in these files. All "OMNI" routines may be executed from the "OMNI" menu. The routines are described below.

A. Ground Combat Files.

- (1) "OMNI_ECF" processes the expected number of completed firing files.
- (2) "OMNI_SSKP" processes the probability of kill files.
- (3) "OMNI_CAT" processes the pointer to the P(K) files.
- (4) "OMNI_AMMO" processes the ammunition weight files.
- (5) "OMNI_FIRE" processes the fire distribution files.

B. Helicopter Files

- (1) "HELOCREATE" creates helicopter files.
- (2) "HELOTGTPRG" creates helicopter target preference files.
- (3) "HELOFORM" lists helicopter files.

C. Main Driver Files.

- (1) "OPERATION" processes operational mission template files.
- (2) "AMMO"

D. Artillery Files

- (1) "LETHALAREA" processes lethal area files.
- (2) "FIREDELVRY" processes fire delivery files.

E. Infantry Files.

- (1) "FIREPOWER" processes firepower scores files.

F. Projectile Guided Missile (PGM) Files.

- (1) "PGMDATAPRG" processes PGM files.

G. Air Attack/Air Defense Files.

- (1) "AIRPLANE" processes the following:
 - (a) Air ingress/egress profile files.
 - (b) Air strike profile files.
 - (c) Unit area template files.
 - (d) Weapon load template files.
 - (e) Air mission/target priority files.
 - (f) Initializes air and target loss files.

H. Declassification Files. In previous versions of the DIME model, data was contained in data statements. These data are now contained in data files. The following utility programs are used to process these files.

- (1) "AMMOCAPdc" processes ammunition capacity files.
- (2) "FUELCAPdc" processes fuel capacity files.
- (3) "SYSEFFdc" processes system effectiveness files.
- (4) "WPNTYPdc" processes weapon type files.
- (5) "AMMOUSEdc" processes ammunition use files.
- (6) "FUELUSEdc" processes fuel use files.

- (7) "TRUCKCAPdc" processes truck capacity files.
- (8) "TOTPLOSSdc" processes total probability of loss files.
- (9) "FRACDISMdc" processes dismounted fraction files.
- (10) "AMMOWTdc" processes ammunition weight files.
- (11) "BASICLDdc" processes basic load files.
- (12) "ARTYRATEdc" processes artillery rate files.
- (13) "ARTYWTdc" processes artillery weight files.
- (14) "FMASKdc" processes indirect fire mask files.
- (15) "DFMASKdc" processes direct fire mask files.
- (16) "DSSTARTdc" processes start range for direct fire files.
- (17) "ARTYALOCdc" processes artillery allocation files.
- (18) "MINEFRCTdc" processes mine fraction files.
- (19) "CONVERTDdc" processes defender loss coefficient files.
- (20) "CONVERTAdc" processes attacker loss coefficient files.
- (21) "AREABANDdc" processes area band files.
- (22) "DISPMASKdc" processes dispersion mask files.
- (23) "TGTMASKdc" processes target mask files.
- (24) "PSNLPOSTdc" processes personnel pasture files.
- (25) "TLEdc" processes target location error files.
- (26) "ROUNDWTdc" processes round weight files.
- (27) "AMWTPPdc" processes ammunition weight per round files.
- (28) "IROFdc" processes integer rate of fire files.
- (29) "SENSORdc" processes sensor files.
- (30) "TGTVALSdc" processes target values files.
- (31) "SSKPdc" processes single shot kill probability files.
- (32) "TGTMASK1dc" processes target mask files.

- (33) "DUSTABRTdc" processes probability of dust abort files.
- (34) "CLGPMASKdc" processes cannon loaded guided projectile files.
- (35) "PROBDESGdc" processes probability designator files.
- (36) "SSKPCLGPdc" processes single shot kill probabilities for cannon loaded guided projectile files.

6. OFF-LINE LOSS ASSESSMENT (P6).

A. This routine, available through the DIME menu, may be used to create losses to units separate from the attrition calculations of air attack/air defense (P3), ground combat (P4), and chemical (P5).

B. In order to cause attrition through this off-line loss assessment, the following items must be identified:

- (1) The unit number being assessed.
- (2) The killing category (direct fire, indirect fire, precision guided munitions, attack helicopters, infantry, mines, chemical, and air attack/air defense).
- (3) The system number (1-70).
- (4) The amount of losses to the particular system in a specific unit.

C. Included in the loss with the systems, ammunition and fuel losses are calculated for the systems.

7. CODE.

Listings for the utility routines (except OMNI) may be found in Tables 11-1 through 11-10. A listing of the P6 code appears in Table 11-11.

Table 11-1. "CR_NAME" program.

```

10      :
20      : PROGRAM : CR_NAME                                DIME V5.0 - MAR 1986
30      :
40      OPTION BASE 1
50      DIM M$(16)
60      PRINT CHR$(12)
70      REPEAT
80          INPUT "(CR)CREATE OR (IN)INITIALIZE 'NAMEFILE'?.A$
90      UNTIL A$="CR" OR A$="IN"
100     IF A$="CR" THEN
110         CREATE BDAT "NAMEFILE:HP9134,701.0",400,20
120         PRINT TABXY(2,2):"NAMEFILE CREATED."
130     END IF
140     PRINT TABXY(2,4):"INITIALIZING NAMEFILE (400 RECORDS)"
150     ASSIGN @Pname TO "NAMEFILE:HP9134,701.0"
160     M$="UNUSED"
170     FOR Recnum=1 TO 400
180         OUTPUT @Pname,Recnum;M$
190         IF Recnum MOD 10=0 THEN PRINT TABXY(2,7):Recnum:" . . . "
200     NEXT Recnum
210     PRINT TABXY(2,10):"NAMEFILE INITIALIZED."
220     ASSIGN @Pname TO *
230     PRINT TABXY(2,17):CHR$(130):"INSERT":CHR$(128):" OMNI MENU DISK. THEN P
PRESS ENTER..."
240     INPUT ".A$
250     LOAD "OMNI_MENU"
260     END!

```

Table 11-2. "CR_TOE program.

```

10
20 PROGRAM : CR_TOE                                DIME V5.0 - MAR 1986
30
40 OPTION BASE 1
50 DIM U(72)
60 PRINT CHR$(12)
70 REPEAT
80     INPUT "(CR)CREATE OR (IN)INITIALIZE 'TOEFILE'?.A$
90     UNTIL A$="CR" OR A$="IN"
100    IF A$="CR" THEN
110        CREATE BDAT "TOEFILE:HP9134,701,0",400,576
120        PRINT TABXY(2,2);"TOEFILE CREATED. "
130    END IF
140    PRINT TABXY(2,4);"INITIALIZING TOEFILE (400 RECORDS)"
150    ASSIGN @Ptoe TO "TOEFILE:HP9134,701.0"
160    FOR I=1 TO 72
170        U(I)=0
180    NEXT I
190    FOR Recnum=1 TO 400
200        OUTPUT @Ptoe,Recnum;U(*)
210        IF Recnum MOD 10=0 THEN PRINT TABXY(2,7);Recnum;" . . . "
220    NEXT Recnum
230    PRINT TABXY(2,10);"TOEFILE INITIALIZED."
240    ASSIGN @Ptoe TO *
250    PRINT TABXY(2,17);CHR$(130);"INSERT";CHR$(128);" OMNI MENU DISK. THEN
RESS ENTER..."
260    INPUT "",A$
270    LOAD "OMNI_MENU"
280    END!

```


Table 11-3. CR_UNIT program.

```

10
20      PROGRAM : CR_UNIT                                DIME V5.0 - MAR 1986
30
40      OPTION BASE 1
50      DIM N(150)
60      PRINT CHR$(12)
70      REPEAT
80          INPUT "(CR)CREATE OR (IN)INITIALIZE 'UNITFILE'?",A$
90      UNTIL A$="CR" OR A$="IN"
100     IF A$="CR" THEN
110         CREATE BDAT "UNITFILE:HP9134,701,0",400,1200
120         PRINT TABXY(2,2);"UNITFILE CREATED. "
130     END IF
140     PRINT TABXY(2,4);"INITIALIZING UNITFILE (400 RECORDS)"
150     ASSIGN @Punit TO "UNITFILE:HP9134,701,0"
160     FOR I=1 TO 150
170         N(I)=0
180     NEXT I
190     FOR Recnum=1 TO 400
200         OUTPUT @Punit,Recnum;N(*)
210         IF Recnum MOD 10=0 THEN PRINT TABXY(2,7);Recnum;" . . . "
220     NEXT Recnum
230     PRINT TABXY(2,10);"UNITFILE INITIALIZED."
240     ASSIGN @Punit TO *
250     PRINT TABXY(2,17);CHR$(130);"INSERT":CHR$(128);" OMNI MENU DISP. THEN P
RESS ENTER..."
260     INPUT "",A$
270     LOAD "OMNI_MENU"
280     END!

```

Table 11-4. "NAMEDUMP" program.

```
10      !
20      ! PROGRAM : NAMEDUMP                                DIME V5.0 - MAR 1986
30      !
40      OPTION BASE 1
50      DIM A$(400)[16]
60      PRINT CHR$(12)
70      PRINT TABXY(2,2);"READING NAMEFILE"
80      ASSIGN @Pname TO "NAMEFILE:HP9134,701,0"
90      FOR Recnum=1 TO 400
100     ENTER @Pname,Recnum;A$(Recnum)
110     NEXT Recnum
120     ASSIGN @Pname TO *
130     !
140     PRINT TABXY(2,4);"PRINTING NAMEFILE"
150     PRINTER IS 702
160     !
170     PRINT CHR$(10)
180     PRINT TAB(10);"NAMEFILE VALUES (400 RECORDS) :"
190     PRINT CHR$(10)
200     FOR I=1 TO 400
210         IF I MOD 50=1 AND I>1 THEN
220             PRINT CHR$(12)
230             PRINT CHR$(10)
240             PRINT TAB(10);"NAMEFILE VALUES (continued) "
250             PRINT CHR$(10)
260         END IF
270         PRINT TAB(15):
280         PRINT USING "DDD,4A,.#":I: " - "
290         PRINT A$(I)
300     NEXT I
310     PRINT CHR$(12)
320     PRINTER IS 1
330     PRINT TABXY(2,10);" DONE PRINTING."
340     STOP
350     END'
```

Table 11-5. "STRENGTH" program.

```

10      !
20      ! PROGRAM : STRENGTH                                DIME 5.0 - 1986
30      !
40      OPTION BASE 1
50      DIM U(150),T(72),W(70),N(70),D(70),Sys$(350),Rsys$(350),T$(7)
60      Sys$(1,125)="DF FAV-TM551 FAV40HNV-GDF DRAGNLAW DF CMD-VDF DF
F DF DF HMV40DF-ICDF-ICDF-ICDF-ICARTY ARTY ARTY ARTY ARTY "
70      Sys$(126,250)="ARTY ARTY MORTMORTMORTMORTMORTMRLRSTMLRSTMLRSTMLRSTINF INF
INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSARMSSARMSSVULCNAVNGRIHAWK"
80      Sys$(251,350)="ADA ADA STINGADAHHF-TRKJ4TRKWATERCGO-TNATRKEWTRKEWTRKENG
OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
90      Rsys$(1,125)="T55 DF BMP73DF BRDM3BRDMSAT-75AGS17T12 CMD-VDF DF
DF DF DF BMPATBTR DF-ICDF-ICDF-ICARTY ARTY ARTY ARTY ARTY "
100     Rsys$(126,250)="ARTY ARTY MORTMORTMORTMORTMORTMRL MRL MRL MRL INF INF
INF INF INF SARMSSARMSSARMSSARMSSARMSSARMSSARMSSARMSSZSU-XSA-13SA-6 "
110     Rsys$(251,350)="ADA ADA SA-14ADAHHF-TRKJ4TRKWATERCGO-TNATRKEWTRKEWTRKENG
R OBSCEAVLB PONBRENGEQENGEQMATHEMATHEAATHE"
120     ASSIGN @Pu TO "UNITFILE:HP9134,701"
130     ASSIGN @Pt TO "TOEFILE:HP9134,701"
140     INPUT "ENTER GAME TIME",T$
150     PRINTER IS 702
160     RESTORE 180
170     READ W(*)
180     DATA -, -, -, -, -, -, -, -, -, -
190     DATA -, -, -, -, -, -, -, -, -, -
200     DATA -, -, -, -, -, -, -, -, -, -
210     DATA -, -, -, -, -, -, -, -, -, -
220     DATA -, -, -, -, -, -, -, -, -, -
230     DATA -, -, -, -, -, -, -, -, -, -
240     DATA -, -, -, -, -, -, -, -, -, -
250     Side$="BLUE"
260     GOSUB Prt_pg_hdrs
270     FOR I=1 TO 191
280         ENTER @Pu,I;U(*)
290         ENTER @Pt,I;T(*)
300         IF U(82)=0 THEN 350
310         FOR J=1 TO 70
320             D(J)=D(J)+T(J)
330             IF U(79)>.3999 THEN N(J)=N(J)+U(J)
340         NEXT J
350     NEXT I
360     FOR J=1 TO 70
370         IF J=55 THEN GOSUB Prt_pg_hdrs
380         Num=Num+N(J)*W(J)
390         Den=Den+D(J)*W(J)
400         PRINT USING "20X,3D,5X,5A,5X,7D,5X,7D":J, Sys$( (J-1)*5+1, J*5), N(J), D(J)
410         N(J)=0
420         D(J)=0
430     NEXT J
440     IF Den<>0 THEN Beff=Num/Den
450     X=Num
460     PRINT USING "18X,15A,3X,9D,3X,9D": "WEIGHTED TOTALS", Num, Den

```


Table 11-6. "EFFECTIVE" program.

```

1      |
2      | PROGRAM : EFFECTIVE                                DIME 5.0 - MAR 1986
3      |
10     | OPTION BASE 1
20     | ! THIS PROGRAM WILL LOOK AT THE UNIT'S EFFECTIVENESS AND PRINT
30     | ! OUT THE PERCENTAGE.
40     | DIM U(150),T(72),M$(16)
50     | ASSIGN @Pu TO "UNITFILE:HP9134,701"
60     | ASSIGN @Pt TO "TOEFILE:HP9134,701"
70     | ASSIGN @Pname TO "NAMEFILE:HP9134,701"
80     | INPUT "WHAT IS THE GAME TIME ",X
90     | INPUT "PRINT TO SCREEN OR PRINTER(S/P)",S$
100    | PRINTER IS 1
110    | IF S$="P" THEN
120        | PRINTER IS 702
130        | PRINT USING "@,#"
140        | GOTO 170
150    | END IF
160    | IF S$<>"S" THEN GOTO 90
170    | PRINT "***** BLUE UNIT EFFECTIVENESS ***** TIME ":X:"*"
180    | PRINT " "
190    | PRINT "          ACTIVE                                INACTIVE"
200    | PRINT " "
210    | FOR I=1 TO 191
220        | ENTER @Pu,I;U(*)
230        | ENTER @Pt,I;T(*)
240        | ENTER @Pname,I;M$
250        | IF M$="UNUSED" OR M$=" " THEN 440
260        | IF U(82)=1 OR U(82)=2 THEN
270            | U_790=DROUND(U(79),2)
280            | IF U_790>=.8 THEN
290                | PRINT USING "3D,5X,16A,3X,D.2D":I,M$,U_790
300                | GOTO 440
310            | END IF
320            | IF U_790>=.6 THEN
330                | PRINT USING "3D,5X,16A,10X,D.2D":I,M$,U_790
340                | GOTO 440
350            | END IF
360            | IF U_790>=.4 THEN
370                | PRINT USING "3D,5X,16A,20X,D.2D":I,M$,U_790
380                | GOTO 440
390            | END IF
400            | IF U_790<.4 THEN
410                | PRINT USING "3D,5X,16A,30X,D.2D,3A":I,M$,U_790,"***"
420            | END IF
430        | END IF
440    | NEXT I
450    | PRINT " "
460    | PRINT CHR$(12)
470    | PRINT " "
480    | PRINT "***** RED UNIT EFFECTIVENESS ***** TIME ":X:"*"
490    | PRINT " "

```

Table 11-6. "EFFECTIVE" program.

```

500 PRINT "          ACTIVE          INACTIVE"
510 PRINT "          "
520 FOR I=192 TO 400
530   ENTER @Pu,I;U(*)
540   ENTER @Pt,I;T(*)
550   ENTER @Pname,I;M$
560   IF M$="UNUSED" OR M$="          " THEN 750
570   IF U(82)=1 OR U(82)=2 THEN
580     U_790=DROUND(U(79),2)
590     IF U_790>=.8 THEN
600       PRINT USING "3D,5X,16A,3X,D.2D":I,M$,U_790
610       GOTO 750
620     END IF
630     IF U_790>=.6 THEN
640       PRINT USING "3D,5X,16A,10X,D.2D":I,M$,U_790
650       GOTO 750
660     END IF
670     IF U_790>=.4 THEN
680       PRINT USING "3D,5X,16A,20X,D.2D":I,M$,U_790
690       GOTO 750
700     END IF
710     IF U_790<.4 THEN
720       PRINT USING "3D,5X,16A,30X,D.2D,3A":I,M$,U_790."***"
730     END IF
740   END IF
750 NEXT I
760 PRINTER IS 1
770 PRINT USING "@"
780 PRINT "DO YOU WANT TO RUN 1)ARMY?"
790 PRINT "          2)STRENGTH?"
800 PRINT "          3)DIME?"
810 INPUT X
820 IF X=1 THEN LOAD "ARMY:HP9134.701"
830 IF X=2 THEN LOAD "STRENGTH:HP9134.701"
840 IF X=3 THEN LOAD "DIME:HP9134.701"
850 END

```

Table 11-7. "CR_KV" program.

```

10  !
20  ! PROGRAM : CR_KV                                OMNI V5.0 - MAR 1986
30  !
40  OPTION BASE 1
50  DIM Kv_data(8,70)
60  PRINT CHR$(12)
70  REPEAT
80      INPUT "CREATE OR INIT THE KV FILE(CR/IN)?",A$
90  UNTIL A$="CR" OR A$="IN"
100 IF A$="CR" THEN
110     CREATE BDAT "KVFILE:HP9134,701,0",2,1360
120     PRINT TABXY(2,2);"CREATING KVFILE (2 RECORDS)"
130 END IF
140 PRINT TABXY(2,4);"INITIALIZING KVFILE"
150 ASSIGN @Path TO "KVFILE:HP9134,701,0"
160 FOR I=1 TO 8
170     FOR J=1 TO 70
180         Kv_data(I,J)=0
190     NEXT J
200 NEXT I
210 FOR Recnum=1 TO 2
220     OUTPUT @Path,Recnum;Kv_data(*),END
230     PRINT TABXY(2,7);Recnum;" . . . "
240 NEXT Recnum
250 PRINT TABXY(2,10);"KVFILE INITIALIZED."
260 ASSIGN @Path TO *
270 PRINT TABXY(2,17);CHR$(130);"INSERT";CHR$(128);" OMNI MENU DISK, THEN
RESS ENTER..."
280 INPUT "",A$
290 LOAD "OMNI_MENU"
300 END

```

Table 11-8. "CR_HELO" program.

```

10  :
20  : PROGRAM : CR_HELO                                DIME V5.0 - MAR 1986
30  :
40  OPTION BASE 1
50  DIM Helo_data(3,6)
60  PRINT CHR$(12)
70  REPEAT
80      INPUT "(CR)CREATE OR (IN)INITIALIZE 'HELOFILE'?.A$
90  UNTIL A$="CR" OR A$="IN"
100 IF A$="CR" THEN
110     CREATE BDAT "HELOFILE:HP9134,701,0".2,144
120     PRINT TABXY(2,2);"CREATING HELOFILE (2 RECORDS)"
130 END IF
140 PRINT TABXY(2,4);"INITIALIZING HELOFILE"
150 ASSIGN @Phelo TO "HELOFILE:HP9134,701,0"
160 FOR I=1 TO 3
170     FOR J=1 TO 6
180         Helo_data(I,J)=0
190     NEXT J
200 NEXT I
210 FOR Recnum=1 TO 2
220     OUTPUT @Phelo,Recnum;Helo_data(*)
230     PRINT TABXY(2,7);Recnum;" . . . "
240 NEXT Recnum
250 PRINT TABXY(2,10);"HELOFILE INITIALIZE."
260 ASSIGN @Phelo TO *
270 PRINT TABXY(2,17);CHR$(130);"INSERT";CHR$(128);" OMNI MENU DISK. THEN
RESS ENTER..."
280 INPUT "",A$
290 LOAD "OMNI_MENU"
300 END!

```


Table 11-9 "AIRPLANE" program.

```

10 !
20 ! PROGRAM : AIRPLANE                                OMNI V5.0 - MAR 1986
30 !
40 ! THIS IS THE UTILITY PROGRAM FOR BUILDING AND MAINTAINING THE AIR ATTACK /
50 ! AIR DEFENSE DATABASE. THIS PROGRAM WAS CODED BY STEVE ARRINGTON AND CINDY
60 ! JAHNKE AND LAST CHANGED BY JIM LUNN ON 09 AUG 84.
70 !
80 ! NOTE: THIS DOCUMENT IS PROTECTED BY PROVISIONS UNDER AR 600-50
90 ! UNTIL PUBLICATION IN THE PUBLIC DOMAIN - "All DA Personnel will
100 ! refrain from releasing to an individual or business concern or
110 ! its representatives any knowledge such persons may possess or
120 ! have acquired in any way concerning proposed acquisition or
130 ! purchases by any contracting activity of DA . . . . Such
140 ! information will be released to all potential contractors as
150 ! nearly simultaneous as possible . . . . Such information will
160 ! be provided in accordance with existing authorized procedures
170 ! and only in connection with the necessary and proper discharge
180 ! of official duties."
190 !
191 ! -----
192 ! THIS CODE LISTING ONLY CONTAINS THE PART NECESSARY TO INITIALIZE
193 ! THE ACCUMULATIVE KILL FILES. THE REST OF THE CODE DEALING WITH
194 ! THE ENTIRE DATABASE CAN BE FOUND IN VOLUME III OF THE DIME
195 ! DOCUMENTATION.
196 ! -----
200 ! OPTION BASE 1
210 ! DIM Area(10,4) ! CONTAINS UNIT AREAS BASED ON 10 UNIT TYPES AND
220 ! ! 4 MISSION POSTURES
230 ! DIM Flt(7,8) ! CONTAINS INGRESS/EGRESS PROFILE DATA
240 ! DIM Flt_info(56) ! CONTAINS INGRESS/EGRESS PROFILE DATA
250 ! DIM Load$(3)[14] ! CONTAINS FILE NAME OF STRIKE PROFILES (MAX 3)
260 ! DIM Stk(28,8) ! CONTAINS STRIKE PROFILE DATA
270 ! DIM Stk_info(224) ! CONTAINS STRIKE PROFILE DATA
280 ! DIM Totals(51) ! CONTAINS ACCUMULATION LOSSES FOR AIR ATTACK/AIR
290 ! ! DEFENSE MODULE
300 ! DIM Wts(72,5) ! CONTAINS MISSION/TARGET WEIGHT VALUES BASED ON
310 ! ! 23 TARGET ELEMENTS AND 5 MISSION TYPES
320 !
330 ! *****
340 !
350 Main_program: ! UTILITY PROGRAM MENU
360 !
370 REPEAT
380 PRINT CHR$(12)
390 PRINT "AIRPLANE - AIR DEFENSE DATA PROGRAM"
400 INPUT "SELECT (D)DISKETTE OR (W)WINCHESTER ?".An$
410 UNTIL An$="W" OR An$="D"
420 IF An$="W" THEN
430 Disk$=":HP913X.701"
440 ELSE
450 Disk$=""
460 END IF

```

Table 11-9 "AIRPLANE" program.

```

470 !
480 Repeat_main$="Y"
490 WHILE Repeat_main$="Y"
500     PRINT CHR$(12)
510     PRINT "        DIME AIR ATTACK/AIR DEFENSE UTILITY PROGRAM"
520     PRINT
530     PRINT " MENU : "
540     PRINT
550     PRINT "     1 - PROCESS AIR INGRESS/EGRESS PROFILE"
560     PRINT "     2 - PROCESS AIR STRIKE PROFILE"
570     PRINT "     3 - PROCESS UNIT AREA TEMPLATE"
580     PRINT "     4 - PROCESS WEAPON LOAD TEMPLATE"
590     PRINT "     5 - PROCESS AIR MISSION/TARGET PRIORITIES"
600     PRINT "     6 - INITIALIZE AIR AND TARGET LOSSES"
610     PRINT "     7 - EXIT"
620     INPUT "SELECT OPTION : ",Main_option
630     SELECT Main_option
640     CASE 1
650         GOSUB Prcs_ing_egr
660     CASE 2
670         GOSUB Prcs_air_stk
680     CASE 3
690         GOSUB Prcs_area_tmp
700     CASE 4
710         GOSUB Prcs_wpn_load
720     CASE 5
730         GOSUB Prcs_tgt_wt
740     CASE 6
750         GOSUB Init_losses
760     CASE 7
770         PRINT
780         PRINT " EXIT UTILITY PROGRAM."
790         STOP
800     END SELECT
810 END WHILE
820 !
830 !
840 !*****
850 !
860 Init_losses: ! REINITIALIZES AIR/TARGET LOSS FILES TO ZERO
870 !
880     GOSUB Slct_color
890     File$=Color$&"_AIR_INF"
900     PURGE File$&":HP913X,701"
910     CREATE BDAT File$&":HP913X,701",1,408
920     FOR I=1 TO 51
930         Totals(I)=0
940     NEXT I
950     ASSIGN @Path TO File$&":HP913X,701"
960     OUTPUT @Path,1;Totals(*)
970     ASSIGN @Path TO *
980     PRINT

```

Table 11-9 "AIRPLANE" program.

```
990     PRINT "FILE ";File$&":HF913X,701": " HAS BEEN INITIALIZED TO ZERO"
1000  !
1010     RETURN
1020  !
1030  !*****
1040  !
1050 Slct_color:  ! SELECTS BLUE OR RED FORCE
1060  !
1070     REPEAT
1080         PRINT
1090         PRINT "SELECT (BL)BLUE OR (RD)RED FORCE  : ";
1100         INPUT Color$
1110         UNTIL Color$="BL" OR Color$="RD"
1120         PRINT Color$
1130  !
1140     RETURN
1150  !
1160  !*****
1170 END
```

Table 11-10. CR_CHEM program.

```

10      !
20      !   PROGRAM : CR_CHEM                               DIME V5.0 - MAR 1986
30      !
40      OPTION BASE 1
50      DIM Chem(70)
60      PRINT CHR$(12)
70      REPEAT
80          INPUT "(CR)CREATE OR (IN)INITIALIZE CHEMICAL FILES?".A$
90      UNTIL A$="CR" OR A$="IN"
100     IF A$="CR" THEN
110         CREATE BDAT "BLCHMVCTM:HF9134,701,0".1,560
120         CREATE BDAT "RDCHMVCTM:HF9134,701,0".1,560
130         PRINT TABXY(2,2);"CHEMICAL FILES CREATED."
140     END IF
150     PRINT TABXY(2,4);"INITIALIZING CHEMICAL FILES (1 RECORD/FILE)"
160     FOR I=1 TO 70
170         Chem(I)=0
180     NEXT I
190     ASSIGN @Pchem TO "BLCHMVCTM:HF9134,701,0"
200     OUTPUT @Pchem,1;Chem(*)
210     ASSIGN @Pchem TO "RDCHMVCTM:HF9134,701,0"
220     OUTPUT @Pchem,1;Chem(*)
230     ASSIGN @Pchem TO *
240     PRINT TABXY(2,10);"CHEMICAL FILES INITIALIZED."
250     PRINT TABXY(2,17);CHR$(130);"INSERT":CHR$(128);" OMNI MENU DISP. THEN
RESS ENTER..."
260     INPUT "",A$
270     LOAD "OMNI_MENU"
280     END!

```

Table 11-11. Off-line assessment program code.

```

10      !!! "P6" ALLOWS OFF-LINE INPUT OF LOSSES TO UNITS BY SEPARATE KILLER
20      !     CATEGORY. CODED BY MAJ REISCHL, DPNS ANAL BR. CAORA (A/V 552-4617).
30      !     THIS PROGRAM WAS LAST UPDATED ON 11 JAN 1984 BY CINDY JAHNKE.
40      !*****
50      ! EXPANDED VERSION -- JUNE 9, 1986 -- BY OAO CORP.
51      !     DECLASSIFIED -- AUG 7, 1986 -- BY OAO CORP.  ** DC **
60      OPTION BASE 1
70      DIM Kv_data(8,70),Loss(70),Sys(70),N(150),Loss_allowed(70),S(150)
80      DIM Sys_eff(2,70),T1(28),Air_loss(72)
90      INTEGER I,J,K,System,Killer
91      Dcdisk$=":HP9134,701,0" ! ** DC **
100     ASSIGN @Unitpath TO "UNITFILE:HP9134,701"
110     ASSIGN @Kvpath TO "KVFILE:HP9134,701"
120     '
121     ' ** DC **
122     '
130     ASSIGN @Psyseff TO "SYS_EFF"&Dcdisk$
140     ENTER @Psyseff,1;Sys_eff(*)
150     ASSIGN @Psyseff TO *
160     ' ** END DC **
290     PRINTER IS 1
300     '
310     ' START INPUT PORTION
320 Start_assess:PRINT USING "@ .25X,26A";"OFF-LINE UNIT ASSESSMENT"
330     INPUT "ENTER # OF UNIT TO BE ASSESSED (999=STOP): ",I
340     IF I=999 THEN Units_all_done
350     IF I<0 OR I>400 THEN 320
360     '
370     ' READ IN UNIT TO BE CHANGED
380     ENTER @Unitpath,I;N(*)
390     '
400     ' READ IN RED OR BLUE KV MATRIX
410     IF I<192 THEN
420         ENTER @Kvpath,1;Kv_data(*)
430         Side=1
440     ELSE
450         ENTER @Kvpath,2;Kv_data(*)
460         Side=2
470     END IF
480     FOR J=1 TO 70
490         Sys(J)=N(J)
500         S(J)=N(J)
510     NEXT J
520     '
530     ' PRINT OUT CURRENT LIST AND ASK FOR CHANGES
540 Start_input:PRINT " "
550     PRINT "UNIT: ",I
560     PRINT " "
570     PRINT "SYSTEMS AVAILABLE: "
580     GOSUB Print_sys_out
590     INPUT "# KILLER CAT: 1-D/F 2-I/F 3-PGM 4-A/H 5-INF 6-MIN 7-CHM 8-A
R 999=STOP",Killer

```

Table 11-11. Off-line assessment program code.

```

600 IF Killer=999 THEN Unit_done
610 IF Killer<1 OR Killer>8 THEN 590
620 FOR J=1 TO 70
630 Loss(J)=0
640 NEXT J
650 Put_in_loss:INPUT "ENTER LOSS BY SYS#, #LOST (999.999=STOP): ".System,No_1
st
660 IF System=999 THEN Stop_losses
670 IF System<1 OR System>70 OR No_lost<0 THEN 650
680 Loss(System)=No_lost
690 GOTO Put_in_loss
700 !
710 Stop_losses: ! SUBTRACT LOSSES AND CHECK FOR ERRORS
720 FOR J=1 TO 70
730 Temp_loss=0
740 Temp_loss=Sys(J)-Loss(J)
750 IF Temp_loss<0 THEN
760 Loss(J)=Sys(J)
770 Loss_allowed(J)=Sys(J)
780 Sys(J)=0
790 ELSE
800 Sys(J)=Temp_loss
810 Loss_allowed(J)=Loss(J)
820 END IF
830 NEXT J
840 FOR J=1 TO 70
850 S(J)=Loss_allowed(J)
860 NEXT J
870 !
880 ! PRINT OUT CURRENT FORCE LEVEL AND UPDATE KV FILE
890 PRINT " "
900 PRINT "LOSSES ALLOWED:"
910 GOSUB Print_sys_out
920 FOR J=1 TO 70
930 S(J)=Sys(J)
940 NEXT J
950 FOR J=71 TO 150
960 S(J)=N(J)
970 NEXT J
980 PRINT " "
990 PRINT "SYSTEMS REMAINING:"
1000 GOSUB Print_sys_out
1010 FOR J=1 TO 70
1020 Kv_data(Killer,J)=Kv_data(Killer,J)+Loss_allowed(J)
1030 NEXT J
1040 Unit_done:INPUT "DO YOU WISH UNIT ASSESSMENT POSTED TO UNITFILE? (Y or N)
",Q$
1050 IF Q$<>"Y" AND Q$<>"N" THEN 1040
1060 IF Q$="N" THEN
1070 GOTO Start_assess
1080 ELSE
1090 OUTPUT @Kvpath,Side;Kv_data(*)

```

Table 11-11. Off-line assessment program code.

```

1100     OUTPUT @Unitpath,I;S(*)
1110     ENTER @Unitpath,I;S(*)
1120     GOSUB Upd_ammo_fuel
1130     GOSUB Upd_cbt_eff
1140     OUTPUT @Unitpath,I;S(*)
1150     END IF
1160     PRINT USING "@,#"
1170     GOTO Start_assess
1180     !
1190     !
1200 Units_all_done:      ! UNIT ENTRY COMPLETED
1210     INPUT "DO YOU WANT AN UPDATED KILLER-VICTIM MATRIX? (Y or N) ".Q$
1220     IF Q$<>"Y" AND Q$<>"N" THEN 1210
1230     IF Q$="Y" THEN GOSUB Print_kv_matrix
1240     ASSIGN @Unitpath TO *
1250     ASSIGN @Kvpath TO *
1260     GOTO Halt
1270     !
1280     !
1290     ! ***** END OF MAIN PROGRAM *****
1300     !
1310     !
1320 !*****
1330 !
1340 Upd_ammo_fuel: !
1350     ! UPDATE CARGO TRUCKS
1360     IF S(58)<N(58) AND N(58)>0 THEN
1370         Tons_on_truck=N(123)/N(58)
1380         S(123)=S(58)*Tons_on_truck
1390         IF S(123)<0 THEN S(123)=0
1400         S(84)=S(58)
1410     END IF
1420     !
1430     !UPDATE FUEL
1440     IF S(55)<N(55) AND N(55)>0 THEN
1450         Gal_on_truck=N(103)/N(55)
1460         S(105)=Gal_on_truck*S(55)
1470         IF S(105)<0 THEN S(105)=0
1480         S(85)=S(55)
1490     END IF
1500     !
1510     RETURN
1520     !
1530     !*****
1540     !
1550 Upd_cbt_eff: !
1560     Neff=0
1570     Seff=0
1580     FOR Ieff=1 TO 70
1590         Seff=Seff+S(Ieff)*Svs_eff(Side,Ieff)
1600         Neff=Neff+N(Ieff)*Sys_eff(Side,Ieff)
1610     NEXT Ieff

```

Table 11-11. Off-line assessment program code.

```

1620 S(79)=(Seff/Neff)*N(79)
1630 !
1640 RETURN
1650 !
1660 !*****
1670 !
1680 Print_sys_out: ! THIS SBR PRINTS OUT THE SYSTEMS LIST
1690 !
1700 FOR X=7 TO 70 STEP 7
1710 PRINT USING Fmt1:X-6,"":S(X-6),X-5,"":S(X-5),X-4,"":S(X-4),X-3,"":S(X-3),X-2,"":S(X-2),X-1,"":S(X-1),X,"":S(X)
1720 NEXT X
1730 Fmt1:IMAGE 7(2D,1A,4D,1D,2X)
1740 !
1750 RETURN
1760 !
1770 !*****
1780 !
1790 Print_kv_matrix: ! THIS SBR PRINTS OUT THE CURRENT KV MATRIX
1800 !
1810 PRINT USING "/////////"
1820 PRINT " TO OBTAIN AN UPDATED "
1830 PRINT " "
1840 PRINT " KILLER-VICTIM MATRIX "
1850 PRINT
1860 PRINT " PRINT-OUT "
1870 PRINT
1880 PRINT " RUN OPTION 8 IN DIME MENU, THEN USE THE KV-FILE ONLY OPTION "
1890 PRINT " "
1900 PRINT USING " ///"
1910 PRINT " PRESS CONT TO RETURN TO THE DIME MENU"
1920 PAUSE
1930 RETURN
1940 !
1950 !*****
1960 !
1970 Halt:LOAD "DIME:HP9134,701"
1980 END

```


APPENDIX A

BIBLIOGRAPHY

1. Bunch, John H., Jr. and Strater, Felix R., Jr. Information Systems. Santa Barbara: Hamilton Publishing Co., 1974.
2. Couger, J. Daniel and Kapp, Robert W. Systems Analysis Techniques. New York: John Wiley & Sons, 1974.
3. Defense Intelligence Agency. DDB-1100-333-82: Soviet Divisional Organizational Guide. July, 1982.
4. _____ . DDB-1110-1-79: The Soviet Motorized Rifle Division. September, 1979.
5. _____ . DDB-1120-10-80: Soviet Tabk Battalion Tactics. November, 1980.
6. _____ . DST-1120F-015-81: Soviet Tank/Antiarmor Threat 1981-2000 (U). August, 1981. (SECRET/REL FRG, FR, UK, AUS & CAN).
7. _____ . DST-1120S-114-890: Soviet Close Combat Technical Capabilities Assessment (U). March, 1980.
8. _____ . DST-13405-224-81: Hind Helicopter System (U). DST-13405-224-81. June 1981. (SECRET/NOFORN/WNINTEL)
9. Department of the Army. Field Manual FM 3-10-1: Employment of Chemical Agents. Washington, DC: 15 December 1978. (CONFIDENTIAL)
10. _____ . Field Manual FM 5-35: Engineer's Reference and Logistical Data. Washington, DC: 30 September 1975.
11. _____ . Field Manual FM 6-20: Fire Support in Combined Arms Operation. Washington, DC: 30 September 1977.
12. _____ . Field Manual FM 7-20: The Infantry Battalion. Washington, DC: 3 April 1978.
13. _____ . Field Manual FM 11-50: Combat Communications Within the Division. Washington, DC: 31 March 1977.
14. _____ . Field Manual FM 17-12: Tank Gunnery. Washington, DC: 21 March 1977.
15. _____ . Field Manual FM 17-47: Air Cavalry Combat Brigade. Washington, DC: 29 April 1977.

16. _____ . Field Manual FM 17-50: Attack Helicopter Operation. Washington, DC: 1 July 1977.
17. _____ . Field Manual FM 17-95: US Cavalry. Washington, DC: 1 July 1977.
18. _____ . Field Manual FM 21-30: Military Symbols. Washington, DC: 31 March 1980.
19. _____ . Field Manual FM-21-1: Combat Communications. Washington, DC: 30 September 1976.
20. _____ . Field Manual FM 24-22: Communications - Electronic Management Systems. Washington, DC: 1 July 1978.
21. _____ . Field Manual FM 24-22: Communications - Electronic Management Systems. Washington, DC: 1 July 1978.
22. _____ . Field Manual FM 30-5: Combat Intelligence. Washington, DC: 30 October 1973.
23. _____ . Field Manual FM 32-30: Electronic Warfare. Washington, DC: 31 March 1975.
24. _____ . Field Manual FM 44-1: Air Defense Artillery Employment. Washington, DC: 30 September, 1977.
25. _____ . Field Manual FM 44-3: Air Defense Artillery Employment, Chaparral/Vulcan. Washington, DC: 30 September, 1977.
26. _____ . Field Manual FM 44-23: Air Defense Artillery Employment, Redeye. Washington, DC: 30 September 1977.
27. _____ . Field Manual FM 54-2: Division/ Brigade Support Command. Washington, DC: 1 July 1976.
28. _____ . Field Manual FM 54-7: Theater Army Logistics. Washington, DC: 31 March 1975.
29. _____ . Field Manual FM 54-9: Corps Support Command. Washington, DC: 1 July 1978.
30. _____ . Field Manual FM 71-1: Tank and Mechanized Infantry Company Team. Washington, DC: 30 June 1977.
31. _____ . Field Manual FM 71-2: Tank and Mechanized Infantry Battalion Task Force. Washington, DC: 30 June 1977.
32. _____ . Field Manual FM 71-100: Armored and Mechanized Division Operations. Washington, DC: 30 September 1977.

33. _____ . Field Manual FM 90-1: Aviation Units in a High Threat Environment. Washington, DC: 20 May 1977.
34. _____ . Field Manual FM 90-3: Desert Operations. Washington, DC: 19 August 1977.
35. _____ . Field Manual FM 100-2-1: Soviet Army Operations and Tactics (draft). USACACDA Threats Division, Fort Leavenworth, KS: 1 July 1982.
36. _____ . Field Manual FM 100-2-2: Soviet Army Specialized Warfare and Rear Area Support (draft). USACACDA Threats Division, Fort Leavenworth, KS: 1 July 1982.
37. _____ . Field Manual FM 100-5: Operations. Washington, DC: 20 August 1982.
38. _____ . Field Manual FM 100-15: Corps Operations (draft). Fort Leavenworth, KS: 27 June 1980.
39. _____ . Field Manual FM 100-16: Support Operations - Echelons Above Corps (draft). Fort Leavenworth, KS: June 1982.
40. _____ . Field Manual FM 105-5: Maneuver Control. Washington, DC: 10 May 1976.
41. _____ . Field Manual FM 101-10-1: Staff Officer's Field Manual. Washington, DC: 1 July, 1976.
42. _____ . Training Circular TC 7-24: Antiarmor Tactics for Mechanized Infantry. Fort Benning, GA: (not dated).
43. _____ . Training Circular TC 24-18: Communications. Washington, DC: (not dated).
44. _____ . Training Circular TC 101-5: Control and Coordinating Division Operations. Washington, DC: (not dated).
45. Department of Defense. Joint Munitions Effectiveness Manual FM 101-60-3: Effectiveness Data for 155mm Howitzer. Washington, DC: November 1980. (CONFIDENTIAL)
46. _____ . Joint Munitions Effectiveness Manual FM 101-60-4: Effectiveness Data for 8-inch Howitzer. Washington, DC: July 1980. (CONFIDENTIAL)
47. _____ . Joint Munitions Effectiveness Manual FM 101-60-17: Basic Effectiveness Manual. Washington, DC: September, 1976. (CONFIDENTIAL)
48. Department of Defense, Australia. Water Buffalo Land Component. 1 April 1982

49. Hembold, Robert L. "Solution of a General, Nonadaptive, Many-VS-Many Duel Model." Operations Research. May/June 1968.
50. Huber, Reiner K., Jones, Lynn F., and Reine, Egile. Military Strategy and Tactics. New York: Plenum Press, 1975.
51. Isbey, David C. Weapons and Tactics of the Soviet Army. London: Jane's, 1981.
52. Department of the Army. CACDA SCORES European Scenario III, Sequence 2A (U). October 1980. (SECRET/NOFORN/WNINTEL)
53. _____ . Combined Arms Combat Developments Activity. CAS Army Force Planning Data and Assumptions FY 1982-1991 (U). July 1981. (SECRET/NOFORN/WNINTEL)
54. _____ . Combined Arms Combat Developments Activity Letter, ATCD-AN-R "Mission Area Analysis (MAA)". Fort Leavenworth, KS: 18 October 1978.
55. _____ . Combined Arms Combat Developments Activity Letter, ATZL-CA-DL "Logistic Planning Factors, Division 86", Change 1(U). Fort Leavenworth, KS: 3 May 1979.
56. _____ . Combined Arms Combat Developments Activity Letter, ATZL-CAS-FS, "Ammunition Expenditure Rates." Fort Leavenworth, KS: 26 April 1982.
57. _____ . Combined Arms Combat Developments Activity Technical Report 6-80: Jiffy III War Game Methodology, Vols. II, III, Fort Leavenworth, KS: September, 1980.
58. _____ . Combined Arms Combat Developments Activity Technical Report 4-78: CACDA Ground Combat Model. Fort Leavenworth, KS: August, 1978.
59. _____ . Combined Arms Combat Developments Activity Technical Report 5-83: Deep Attack Map Exercise (DAME) Game Rules and Operation Procedures. Fort Leavenworth, KS: February, 1983.
60. Department of the Army. USACGSC Reference Book RB 3-1: NBC Operations (draft). Fort Leavenworth, KS: 31 July 1973.
61. Department of the Army. USACGSC Reference Book RB 32-20: Electronic Warfare (draft). Fort Leavenworth, KS: 31 March 1980.
62. Department of the Army. USACGSC Reference Book RB 100-1: Organization Data for the Army in the Field. Fort Leavenworth, KS: 9 January 1980.

63. Department of the Army. USACGSC Reference Book RB 100-5: Command and Control of Combat Operation. Fort Leavenworth, KS: 28 November 1977.
64. Department of the Army. USACGSC Reference Book RB 100-8: Reference Data for Heavy Maneuver Forces. Fort Leavenworth, KS: 1 August 1980.
65. Department of the Army. USACGSC Reference Book RB 100-33: Electronic Leavenworth, KS: 1 June 1979.
66. U.S. Army Concepts Analysis Agency. Target Acquisition Study II. Washington, D.C: August 1979. (SECRET)
67. Department of the Army. Field Artillery School, Director of Combat Developments, Programmable Calculator (TI-58 or TI-59) Manual for Evaluating Effectiveness of Non-nuclear Surface-to-Surface Indirect-Fire Weapons Against Area Targets. Fort Sill, OK: 02 June 1981.
68. Wagner, Harvey M. Principles of Operations Research. New York: Prentice - Hall, 1975.